

# MYSQL主从配置

## 1.1 部署环境

主(master\_mysql): 192.168.1.200 OS:CentOS 6.5

从(slave\_mysql): 192.168.1.201 OS:CentOS 6.5

## 1.2 安装mysql

主和从: yum install mysql-server

## 1.3 配置

### 1.3.1 主配置 (master\_mysql配置)

vim etcmy.cnf

server-id=200 #设置主服务器的ID

innodb\_flush\_log\_at\_trx\_commit=2

#操作系统崩溃或者系统断电的情况下，上一秒钟所有事务数据才可能丢失

sync\_binlog=1 #开启binlog日志同步功能

log-bin=mysql-bin-200 #binlog日志文件名

binlog-do-db=xxxx # 这个表示只同步某个库（如果没有此项，表示同步所有的库）

### 1.3.2 配置完后，重启主库的mysql

service mysqld restart

mysql -uroot -p ##登录mysql

mysql>grant replication slave on . to 'mark'@'192.168.1.201' identified by '123456'; ##授权给从数据库服务器192.168.1.201，用户名mark，密码123456

mysql>show master status ; ##查看主库的状态

```
mysql> show master status ;
+-----+-----+-----+-----+
| File           | Position | Binlog_Do_DB | Binlog_Ignore_DB |
+-----+-----+-----+-----+
| mysql-bin-200.000002 |      1167 |              |                  |
+-----+-----+-----+-----+
1 row in set (0.00 sec)
```

### 1.3.3 配置从库服务器

vim etcmy.cnf

server-id=201

innodb\_flush\_log\_at\_trx\_commit=2

sync\_binlog=1

log-bin=mysql-bin-201

### 1.3.4 配置完后，重启从库的mysql

service mysqld restart

mysql -uroot -p

mysql> change master to master\_host='192.168.1.200',

master\_user='mark',master\_password='123456',master\_log\_file='mysql-  
bin-200.000002',master\_log\_pos=1167;

mysql> start slave; ##开启从库 (stop slave: 关闭从库)

mysql> show slave status; ###Slave\_IO\_Running,Slave\_SQL\_Running 都为Yes的时候表示配置成功

```
mysql> show slave status \G;
***** 1. row *****
      Slave_IO_State: Waiting for master to send event
        Master_Host: 192.168.1.200
        Master_User: mark
        Master_Port: 3306
        Connect_Retry: 60
        Master_Log_File: mysql-bin-200.000002
        Read_Master_Log_Pos: 1167
        Relay_Log_File: mysqld-relay-bin.000003
        Relay_Log_Pos: 255
        Relay_Master_Log_File: mysql-bin-200.000002
        Slave_IO_Running: Yes
        Slave_SQL_Running: Yes
        Replicate_Do_DB:
        Replicate_Ignore_DB:
        Replicate_Do_Table:
        Replicate_Ignore_Table:
        Replicate_Wild_Do_Table:
        Replicate_Wild_Ignore_Table:
          Last_Errno: 0
          Last_Error:
          Skip_Counter: 0
        Exec_Master_Log_Pos: 1167
        Relay_Log_Space: 691
        Until_Condition: None
        Until_Log_File:
        Until_Log_Pos: 0
        Master_SSL_Allowed: No
        Master_SSL_CA_File:
        Master_SSL_CA_Path:
        Master_SSL_Cert:
        Master_SSL_Cipher:
        Master_SSL_Key:
      Seconds_Behind_Master: 0
Master_SSL_Verify_Server_Cert: No
```

### 1.4: 验证主从

可以在主库上创建一个库，再在从库上刷新查看是否同步

二、读写分离配置 (mysql\_proxy, master, sl