

# Remote controlled client-side log collection

## Overview

Logging is the instrumentation of source code that uses API calls to record messages in order to facilitate diagnostics and debugging. Example: `java.util.logging` in Java.

Logging libraries typically have verbosity controls, that are frequently called *levels*. From least to most verbose: ERROR, WARN, INFO, LOG, DEBUG

- Developers can filter by level in their log viewer.
- Capture tools can filter by level in their configurations.

This tutorial covers the following topics:

- Log capture
- Server preparation (in production)
- Admin control for client logs
- Crash capture
- For more information
- API calls for specific environments

## Log capture

Log capture is the ability to persistently record messages that are passed to the logging API. Capture is on by default but can be turned off.

Logging defaults to DEBUG level in development, and to FATAL in production. You can control levels, and therefore verbosity, with API calls that are specific to your environment.

## Server preparation (in production)

It is useless to persistently capture log output in browsers and devices in production unless that captured data can be sent for diagnostic inspection. You can send captured data by calling the `send` method explicitly in your application.

You can turn the automatic behavior on or off with API calls that are specific to your environment, or by calling the `send` method explicitly in your application.

## How to receive and process logs at the server?

There are two ways to receive client logs on MobileFirst Server:

1. Install the IBM MobileFirst Platform Operational Analytics (MobileFirst Operational Analytics for short).
2. Develop and deploy an adapter that is named `WLClientLogReceiver` with a function (procedure) that is named `log`.

The MobileFirst Operational Analytics is available by default in the embedded Liberty server in the MobileFirst Studio development environment. You can open the Analytics Console from the

MobileFirst Operations Console. When MobileFirst Operational Analytics is properly installed and configured, client logs that are sent to MobileFirst Server are automatically forwarded to MobileFirst Operational Analytics.

For more information about installing MobileFirst Operational Analytics in a production environment, see the topic about installing MobileFirst Operational Analytics, in the user documentation.

If you do not wish to use MobileFirst Operational Analytics, you can still collect and process client logs by creating an adapter. By default, MobileFirst Platform Foundation is configured to forward client logs to an adapter named `WLClientLogReceiver`, which exposes a method called `log`.

If MobileFirst Operational Analytics and the adapter have both been configured, MobileFirst Platform Foundation sends logs to both endpoints. Using both may be useful if you want to take benefit of MobileFirst Operational Analytics log searching capabilities AND do some custom operations on client logs by using your own adapter.

**Note:** Installation and configuration of MobileFirst Operational Analytics and development of adapters is beyond the scope of this Getting Started tutorial. For more information, see the topic about installing MobileFirst Operational Analytics, in the user documentation, and the Adapters overview tutorial

([file:///home/travis/build/MFPSamples/DevCenter/\\_site/tutorials/en/foundation/7.0/server-side-development/adapter-framework-overview/](file:///home/travis/build/MFPSamples/DevCenter/_site/tutorials/en/foundation/7.0/server-side-development/adapter-framework-overview/)).

## Admin control of client log capture

The screenshot shows the MobileFirst Operations Console interface. The top navigation bar includes 'MobileFirst Operations Console', 'Analytics Console', and 'Hello, admin'. The left sidebar shows 'Runtimes' with 'HelloWorldProject' selected. The main content area is titled 'HelloWorldProject' and features a tabbed interface with 'Client Log Profiles' selected. Below the tabs, there is a 'Client Log Profiles' section with a blue circular arrow icon and a 'View more...' link. A blue button 'Add new app or adapter' is located in the top right corner of the main content area.

The screenshot shows the MobileFirst Operations Console interface, specifically the 'Client Log Profiles' section. The top navigation bar includes 'MobileFirst Operations Console', 'Analytics Console', and 'Hello, admin'. The left sidebar shows 'Runtimes' with 'HelloWorldProject' selected. The main content area is titled 'HelloWorldProject > Client Log Profiles' and features a blue button 'Add a profile...'. Below the title, there is a table with the following columns: Application, Version, Operating system, Model, OS version, and Priority. The table contains one row: 'HelloWorld', '1.0', 'Android', 'All', 'All', and 'All'. Below the table, there is a 'Packages' section with a table containing two columns: 'Name' and 'Level'. The table contains one row: 'All packages' and 'Fatal'. A blue circular arrow icon is located to the left of the table.

Application	Version	Operating system	Model	OS version	Priority
HelloWorld	1.0	Android	All	All	All

Name	Level
All packages	Fatal

To configure log capture preferences for applications in production, use the MobileFirst Operations Console. Administrators can control the MobileFirst client SDK log capture and levels from the MobileFirst Operations Console.

## **Crash capture**

The MobileFirst client SDK, on Android and iOS, captures a stack trace upon application crash and logs it at FATAL level. This type of crash is a true crash where the UI disappears from the user's view.

The MobileFirst client SDK, in JavaScript, captures JavaScript global errors and if possible, a JavaScript call stack, and logs it at FATAL level. This type of crash is not a crash event, and might or might not have any adverse consequences to the user experience at run time.

Crash, uncaught exceptions, and global errors are caught and logged automatically.

## **For more information**

For more information about logging and log capture, see the user documentation.