

KRC planetary surface temperatures: Helplist

Hugh H. Kieffer File=-/krc/Doc/helplist.tex Version 3.5.4 2017oct01

October 1, 2017

Contents

1	Introduction	2
1.1	Notation use here	2
2	METHOD	3
2.1	Convergence Notes	3
3	INPUT FILE	4
4	PARAMETER CHANGES	8
5	Contents of COMMOMS	9
6	Error Returns	10
6.1	Tday Blowup	10
6.2	Other errors: INCOMPLETE	10
7	DISK BINARY FILES	10
7.1	Items which control file I/O	10
7.2	Maximum sizes	12
7.2.1	Direct access files	12
7.2.2	Type 52 files	12
8	Optional input files	12
8.1	Text	12
8.1.1	Zone depth table	12
8.1.2	Seasonal albedo table	13
8.1.3	Seasonal opacity table	13
8.2	Binary: Seasonal climate table	13
9	Handy things	13
9.1	ASCII Output Files	14
9.2	To run two material types	14
9.3	Setting temperature-dependant properties	14
10	RUNNING THE "ONE-POINT" MODE	15

10.0.1	Comments on the One-point model	15
11	DEBUG OPTIONS	16
12	Accessing KRC output in IDL	17
13	Special tabular output; routine tun8.f	18
14	Notes on how some aspects of the code work	19
14.1	New file name	19
14.2	End of a case and end of a run	19
14.3	Setting one-point mode	19
14.3.1	How one-point converts Ls to date	19
14.4	Starting conditions and date	20
14.5	Changing parameters within a seasonal run = Continue from memory.	20
14.6	Use of common PORBCM	20
14.7	Lower boundary condition and resetting (jumping) layer temperatures.	20
14.8	Temperature scaling for KofT	20
14.9	No atmosphere flag	20
14.10	Far-field temperatures 2016jun30	21
14.11	Seasonal variation of albedo or opacity or “climate”	21
14.12	Cap-dependent pressure	21
14.13	When parameter and layer tables appear	21
15	Non-standard FORTRAN	22
A	Map of type 52 file	22
B	Time-step doubling	24
B.1	Version 343	24

1 Introduction

This document is intended to help the expert user of KRC set up an input file that addresses their goals and will generate the kind of output they desire. It is assumed that the user is familiar with the KRC journal article: H.H. Kieffer, Thermal model for analysis of Mars infrared mapping, J. Geophys. Res.: Planets, v.118, 451-570 (2013) [Ref. 1]

The evolution of KRC code is contained in: evolve.txt

A crude diagram of the call architecture is in: flow.txt

Capabilites new in version 3.4.x are decribed in: V34UG.tex (or .dvi or .pdf versions)

Eclipse capabilites (V3.5) are described in: eclipse.tex (“

[[Development for thermal beaming of asteroids is described in: Beaming.tex (“)]]

1.1 Notation use here

The following fonts styles have been partially implemented:

File names are shown as *file*.

Program and routine names are shown as **PROGRM** [,N]

where **N** indicates a major control index.

Code variable names are shown as **variab** and within equations as **variab**.

Input parameters are shown as **INPUT** and within equations as **INPUT**

When KRC was made double-precision, an '8' was added to many routine names, both as the source-code file and as they are called; this 8 is commonly omitted in this documentation.

2 METHOD

The program is designed to compute surface and subsurface temperatures for a global set of latitudes at a full set of seasons, with enough depth to capture the annual thermal wave, and to compute seasonal condensation mass. For historic reasons, the code has substantial optimization. Although developed for Mars, there are generalities that allow this code set to be used for any solid body with any spin vector, in any orbit (around any star), with or without an atmosphere; this is also the source of some of the complexity.

Method is explicit forward finite differences with exponentially increasing layer thickness and binary time increase with depth where allowed by stability. Depth parameter is scaled to the diurnal thermal skin depth. Initially starts at 18 hours with the mean temperature of a perfect conductor. Second degree perturbation is applied at the end (midnight) of the (third) day; this jumps the mean temperature of all layers and the lower boundary to equal the mean surface temperature.

Boundary condition treatment:

Perturbation solution of quartic equation at surface for each iteration; temperature gradient assumed uniform in top interval.

Lower boundary may be insulating or constant-temperature.

Atmospheric Radiation: KRC uses a one-layer atmosphere that is grey in both the solar and infra-red regions. The default atmospheric parameters are based on estimates of Mars' gas and aerosol properties.

Two-stream Delta-Eddington model for insolation; direct onto sloped surface and diffuse, with possible twilight extension. The atmosphere temperature is based on Delta-Eddington solar absorption and IR opacity

Keplerian orbital motion; seasons are at uniform increments of time. Mean orbital elements are pre-calculated for any epoch (all planets and several comets and asteroids) by the PORB code set.

Units are SI, except for use of days for orbital motion and rotation period

Options:

Different Physical properties below a set layer (IC).

May define many zones via an input table

Regional slope. Self- or far-field heating

Three (for Mars) ways to handle seasonal global pressure variation .

Up to two zones of temperature-dependent conductivity and specific heat

Non-Lambertian solar absorption.

Global geothermal heat flow.

Atmosphere condensation:

Global integral of frost-gas budget can control surface pressure.

Can have virtually any single condensing gas desired.

Allows different surface elevation for each latitude zone.

Zonal frost saturation temperature tracks local surface pressure.

Option for cap albedo to depend upon mean daily insolation.

Frost albedo can vary continuously with frost amount

2.1 Convergence Notes

Convergence prediction routine can't jump more than one time constant ($\text{TAU} = X^{**2}/2$) $\tau = x^2/2$ for the total thickness. Therefore, if $X(N1)$ is small, make DDT smaller than usual. If DELJUL is much smaller than $(X(N1))^{**2}/2 - X_{N1}^2/2$, then DDT can be as large as 0.3. Otherwise DDT must be about 0 for the prediction routine to work well (it assumes the 3rd derivative to be 0).

3 INPUT FILE

KRC asks for the name of an input file, default is *krc.inp*, and an output file, default is *krc.prt*. If the desired file is not in the current directory, then its name must be surrounded by single quotes.

All parameters for KRC are set by a formatted text file. An example is *master.inp*, which has default values for a 19 latitude set for a run of three martian years, with the last output to disk. Parameter values are listed below their titles, which are in many cases identical to the code name, and last character of the title is above the last location in the field. Thus, integer values MUST be aligned. Titles with a leading "[]" indicate that the value is not used. The recommended procedure is to copy *master.inp* and edit only the values you wish to change. The number of lines of Latitudes and Elevations must match the value of N4, e.g., 2 lines for N4=11:20, entries beyond the N4 position may be left blank or contain the end of the line. The 7 lines following Elevations are a geometry matrix for Mars orientation and orbit in 2010, and should not be touched; they could be replaced by running PORBMN carefully.

The parameter title lines are skipped, so that you may put comments there carefully.

The first input line is always KOLD,KEEP [I*], which sets file usage; these are described in §7. If KOLD=0, then a full set of input values is read.

If and only if there is a third non-zero integer, then KRC will read the next card as 6 debug flags, IDB1 to IBD6, which are normally zero. See §11 below

The next (normally second) line is free text where you can outline the purpose of your run; up to 84 characters.

Change lines may follow immediately after the geometry matrix (see §4). The end of definition of a "case" is indicated by a "0/" line. Two successive "0/" lines ends the run.

The source code for 'krcc8m.f' indicates which subroutine sets many of the parameters; as the routine name in lowercase just below the parameter name.

```
-----
Type 1 Real parameters  (8F10.2) =====
  Surface Properties
1  ALB      Surface albedo
2  EMIS      Surface emissivity
3  SKRC      Surface thermal inertia [J m^-2 s^-1/2 K^-1] { cal cm * 4.184e4}
4  COND2     Lower material conductivity (IC>0)
5  DENS2     Lower material density (IC>0)
6  PERIOD    Length of solar day in days (of 86400 seconds)
7  SPHT      Surface specific heat [J/(kg K)] {cal/(g K) * 4184.}
8  DENS      Surface density [kg/m^3] {g/cubic cm. *1000}
-----
  Atmospheric Properties
9  CABR      IR opacity of dust-free atmosphere of PTOTAL surface pressure
10 AMW       Molecular weight of the atmosphere
11 ABRPHA    First Clausius-Clapeyron coefficient  SatPrA
12 PTOTAL    Global annual mean surface pressure at 0 elev., Pascal[=.01mb]
              If <=1.; no atmosphere at all.
              If KPREF=2, global average of atmosphere plus cap system.
13 FANON     Mass-fraction of mean atmosphere that is non-condensing
14 TATM      Atm temp for scale-height calculations
-----
15 TDEEP     Fixed bottom temperature. Used if IIB>=1.
16 SPHT2     Lower material specific heat (IC2>0)
-----
  Dust & Slope Properties
17 TAUD      Mean visible opacity of dust, solar wavelengths
18 DUSTA     Single scattering albedo of dust
19 TAURAT    Ratio of thermal to visible opacity of dust
20 TWILI     Twilight extension angle [deg]
21 ARC2      Henyey-Greenstein asymmetry factor      ARC2/Pho
              If no atmosphere, this is photometric function control
              0=Lambert <-1=Lommel-Seeliger +=Kheim-Vasavada
              else (-1< x <0) Minnaert with exponent -x (is positive)
```

```

22  ARC3      Minimum allowable numerical convergence factor   Theory is 1.
23  SLOPE     Ground slope, degrees dip. Only pit may slope beyond pole.
24  SLOAZI    Slope azimuth, degrees east from north. <-360 is a pit
-- -- -- -- --
      Frost Properties
25  TFROST    Minimum Frost saturation temperature
                may be overridden by local saturation temperature (LVFT)
26  CFROST    Frost latent heat [J/kg] {cal/gm*4184. [ Not used if
27  AFROST    Frost albedo, may be overridden (LVFA) [ TFROST never
28  FEMIS     Frost emissivity                                [ reached
29  AF1       constant term in linear relation of albedo to solar flux
30  AF2       linear term in relation of albedo to solar flux units=1/flux
                Afrst = AF1 + AF2 * <cos incidence> SOLCON / DAU^2
31  FROEXT    Frost required for unity scattering attenuation coeff. [kg/m^2]
                the greater of this and 0.01 is always used.
32  fd32     Second Clausius-Clapeyron coefficient      SatPrB
-- -- -- -- --
      Thermal Solution Parameters
33  RLAY      Layer thickness ratio
34  FLAY      First physical layer thickness (in skin depths)
35  CONV      Safety factor for classical numerical convergence
                0 for no binary time division of lower layers
                >0.8 for binary time division. Larger is more conservative
36  DEPTH     Total model depth (scaled) (overrides FLAY if not 0.)
37  DRSET     Perturbation factor in jump convergence. If = 0., then
                all layers reset to same average as surface layer. Else,
                does quadratic curve between surface and bottom averages
38  DDT       Convergence limit of temperature RMS 2nd differences
39  GGT       Surface boundary condition iteration test on temperature
40  DTMAX     Convergence test: RMS layer T changes in a day
-- -- -- -- --
      Orbit Geometry & Constants
41  DJUL      Starting Julian date of run -2451545 (J2000.0) (N5>0)
                If LKEY (logical item 12) is set True, this is desired Ls of
                first disk output date (set by JDISK: integer item 12)
42  DELJUL    Increment between seasons in Julian days (if N5>1)
43  SDEC      Solar declination in degrees. (if Not LPROB)
44  DAU       Distance from Sun in astronomical units (if Not LPROB)
45  SUBS      Aerocentric longitude of Sun, in degrees. For printout
                only. Computed from date unless N5=0 (for printout only)
46  SOLCON    Solar constant. Total stellar irradiance at 1 AU [W/m^2]
47  GRAV      Surface gravity. MKS-units
48  AtmCp     Specific heat at constant pressure of the atmosphere [J/kg/K]
-- -- -- -- --
      Temperature dependent conductivity. Ignored unless LKOFT set.
49  ConUp0    Constant coef for upper material
50  ConUp1    Linear   in k=c0+c1x+c2x^2+c3x^3 where x=(T-220)*0.01
51  ConUp2    Quadratic   "
52  ConUp3    Cubic coeff. "
53  ConLo0    Constant coef for lower material
54  ConLo1    Linear   as for ConUp above
55  ConLo2    Quadratic   "
56  ConLo3    Cubic coeff. "
      Temperature dependent specific heat. Ignored unless LKOFT set.
57  SphUp0    Constant coef for upper material
58  SphUp1    Linear   in k=c0+c1x+c2x^2+c3x^3 where x=(T-220)*0.01
59  SphUp2    Quadratic   "

```

```

60 SphUp3 Cubic coeff. "
61 SphLo0 Constant coef for lower material
62 SphLo1 Linear      as for   SphUp above
63 SphLo2 Quadratic   "
64 SphLo3 Cubic coeff. "
-----
    Computed REAL values
65 HUGE    = 3.3E38   nearly largest REAL*4 value
66 TINY     = 2.0E-38 nearly smallest REAL*4 value
67 EXPMIN   = 86.80   neg exponent that would almost cause underflow
68 FSPARE   Spare
69 FLOST    Atm frost 'lost' in the atm. in last day at current lat./season
70 RGAS     = 8.3145  ideal gas constant (MKS=J/mol/K)
71 TATMIN   Atmosphere saturation temperature
72 PRES     Local surface pressure at current season
73 OPACITY  Solar opacity for current elevation and season
74 TAUIR    current thermal opacity at the zenith
75 TAU EFF  effective current thermal opacity
76 TATMJ    One-layer atmosphere temperature
77 SKYFAC   fraction of upper hemisphere that is sky
78 TFNOW    frost condensation temperature at current latitude
79 AFNOW    frost albedo at current latitude
80 PZREF     Current surface pressure at 0 elevation, [Pascal]
81 SUMF      Global average columnar mass of frost [MKS]
82 TEQUIL   Equilibrium temperature (no diurnal variation)
83 TBLOW     Numerical limit (Blowup) temperature
84 HOURO     Output Hour requested for "one-point" model
85 SCALEH    Atmospheric scale height
86 BETA      Atmospheric IR absorption
87 DJU5      Current Julian date (offset J2000.0 ala PORB convention)
88 DAM       Half length of daylight in degrees
89 EFROST    Frost on the ground at current latitude [kg/m^2] {g/cm^2 * 10.}
90 DLAT      Current latitude
91 COND      Top material Thermal conductivity (for printout only)
92 DIFFU     Top material Thermal diffusivity (for printout only)
93 SCALE     Top material Diurnal skin depth (for printout only)
94 PIVAL     pi
95 SIGSB     Stephan-Boltzman constant (set in KRC)
96 RADC      Degrees/radian

```

Type 2 Integer Parameters (8I10) =====

To simplify coding logic, some may be input as 0, meaning none or never,
but will be modified automatically to very large, Indicate by: -->never

```

1  N1      # layers (including fake first layer) (lim MAXN1)
2  N2      # 'times' per day (lim MAXN2). Must be an even number,
           should be a multiple of N24 and NMHA.
3  N3      Maximum # days to iterate for solution (lim MAXN3)
           This can be 1, but then must use DELJUL ~= PERIOD
           If N3 lt 3, first day starts on midnight. else at 18H
4  N4      # latitudes (lim MAXN4). Global integrations done for N4>8
5  N5      # 'seasons' total for this run. If 0, then DAU and SDEC will be
           used as entered for a single season.
6  N24     # 'hours' per day stored, should be divisor of N2 (lim MAXNH)
7  IIB     Bottom control: 0=insulating, -1=constant temperature
           -2=start all layers =TDEEP & constant temperature
           += geothermal heat flow in milliwatts/m^2

```

```

8   IC2      First layer (remember that 1 is virtual) of changed properties.
          <3 will be changed to 999 =homogeneous
-----
9   NRSET    # days before reset of lower layers first season; >N3=no reset
10  NMHA     # 'hour angles' per day for printout (no limit)
11  NRUN     Run #; appears in some printout. Initalized as 0 and
          auto-increment whenever disk file opened. May be modified
12  JDISK    Season count that disk output is to begin. <1 -->never
13  IDOWN    Season at which to read change cards
14  I14      Index in FD of flexible print
15  I15      "" and >100 is code for special output to fort.77 via tun.f
16  KPREF    Mean global pressure control. 0=constant
          1= follows Viking Lander curve 2=reduced by global frost, but
          then N4 must be >8, and latitudes must be monotonic increasing
          and must include both polar regions (no warning for your failure)
-----
17  K4OUT    Disk output control: See details in DISK BINARY FILES section
          Three modes of direct access Fortran files; one case per file.
          --KRCCOM(once), then TSF [,TPF [,TAF]]
          -1 saves TST, the surface kinetic temperature
          -2 also saves TPF, the top-of-atmosphere bolometric temperature
          -3 also saves TAF, the 1-layer atmosphere kinetic temperature
          0=KRCCOM,LATCOM each season
          1:49=KRCCOM,DAYCOM for the last latitude; each season
          Modes of bin5 file for multiple cases. ONLY 52 IS STILL SUPPORTED
          x51=(Hours, 2 min/max, lat, seasons, cases)
          52=(hours, 7 items, lat, seasons, cases)
          x54=(many seasons, 5 items,lats, cases)
          x55=(many seasons,9 items, cases)
          x56=(packed T hour and depth, latitude,season,case)
18  JBARE    J5 season count at end of which to set frost amount to 0. 0-->never
19  NMOD     Spacing of season for notification. minimum of 1
20  IDISK2   Last season to disk for which TDISK prints notice
          Note: Special routines MKRC,KRCA and TYEARP use TDISK differently
-----

```

Computed Integer values

```

21  KOLD     Season index for reading starting conditions
22  KVALB    Flag: to use seasonal surface albedo ALB
23  KVTAU    Flag: 1:TAUD=SEASTAU(SUBS) 2:CLIMTAU opacities for dust and ice
24  ID24(4)  spare
28  NFD      Number of real items read in
39  NID      Number of integer items read in
30  NLD      Number of logical items read in
31  N1M1     Temperature vrs depth printout limit (N1-1)
32  NLW      Temperature vrs depth printout increment
33  JJ0      Index of starting time of first day
34  KKK      Total # separately timed layers
35  N1PIB    N1+IB Used to control reset of lowest layer
36  NCASE    Count of input parameter sets in one run
37  J2       Index of current time of day
38  J3       Index of current day of iteration
39  J4       Index of current latitude
40  J5       Index of current "season"

```

Type 3 Logical Parameters (10L7) =====

```

1   LP1      Print program description. TPRINT(1)

```

```

2  LP2      Print all parameters and change cards (2) for current case
3  LP3      Print hourly conditions on last day (3), every lat, every season
4  LP4      Print daily convergence summary (4)
5  LP5      Print latitude summary (5)
6  LP6      Print TMIN and TMAX versus latitude and layer (6)
7  LPGLOB   Print global parameters each season
8  LVFA     Use variable frost albedo. Uses AF1 & AF2 (real # 29,30)
9  LVFT     Use variable frost temperatures
10 LKOFT    Use temperature-dependent conductivity and specific heat
- - - - -
11 LPORB    Call PORB1 just after full input set
12 LKEY     Treat DJUL (real item 41) as the Ls of the first output
           season, set by JDISK [the 12'th integer input]
13 LSC      Read change cards from input file at start of each season
14 LZONE    Use a zone depth table file to set layers.
15 LOCAL    Use each layer for scaling depth
16 LD16     Print hourly table to fort.76 [TLATS]
           SUBS,DLAT,ALB,SKRC,TAUD,PRES at end of every latitude
           and every hour: Hour  T_K  IR_Inc  Solar  T_Planet
17 LD17     Print temperatures at end of last day of each season
18 LD18     Print of parameters and layers was done after last change
19 LD19     Output to fort.79 [TLATS] insolation and atm.rad. arrays
           for every time-step for every latitude, every time tlats is called.
20 LONE     (Computed) Set TRUE if KRC is in the "one-point" mode
=====

```

followed in 'krccom' by:

84 character KITLE Description/purpose of this run.

20 character DAYTIM run date and time

```

Latitude(s) (10F7.2)  N4 latitudes in degrees
Latitudes to be in order; south to north. [[If last latitude is
.LE. 0, will assume symmetric results for global integrations]]

```

Elevation(s) (10F7.2) N4 values in Km corresponding to latitudes

Orbital Parameters (LPORB=T) Format identical to that produced by PORB program set ASCII file output. So these can be directly pasted with an editor. see porbc8m.f

4 PARAMETER CHANGES

Fortran list-directed. Change the values in KRCCOM. Lines of four (or more) white-separated values, a "/" terminates the read and leaves remaining values unchanged. The 4 required items are:

- 1: Type (integer): see table below
- 2: Index in array (integer): as listed in Input File table above
- 3: New value, numeric: 0.=false. Will read as real and convert as needed.
- 4: File name or a reason: Text string within single quotes; or a /
Missing quote may cause run failure.
[after a / (forward slash) nothing is read, so you can use for comments]

The print file will list each change as read, followed by the title of the changed item. It is a good idea to look at this print to be sure you changed what you intended.

Type	Meaning	Valid Index
------	---------	-------------


```

0   End of Current Changes                                any
1   Real Parameter                                       1:NFDR=64
2   Integer Parameter                                   1:NIDR=20
3   Logical Parameter                                    1:NLDR=20
4   New Latitude Card(s) Follow                          any
5   New Elevation Card(s) Follow                        any
6   New Orbital Parm Cards Follow (LPORB Must be True)  any
7   Text becomes new Title                              any
8   Text becomes new  output or input file name
    if index=3, name of far-field temperature file to read
        value 0/1 sets report of each read off/on
    if index=5, is name of type 5x (52) packed output file
    if index=21, this is name of direct-access file
    if index=22, call SEASALB to read variable ALBEDO
    if index=23, call SEASTAU to read variable TAUD
    if index=24, call CLIMTAU to read Mars climate
    if index=25, name of new zone table
9   Complete new set of input follows                    any
10  Text becomes new One-Point input file name
11  This is a set of parameters for "one-point" model
    For this type, 9 values must appear in a rigid format
12  Set of 2*4 coefficients for T-dep. conductivity. List-directed IO
13  Set of 2*4 coefficients for T-dep. specific heat. List-directed IO
14  Set of 10 values for eclipse. See -/Doc/v35/eclipse.pdf sec. 4.4
e.g. 14  1 5.2026 71492. 0.6711D6 3121.6 3.551 0.01 6000. 12. 2 / Europa
15  Set of 7 values for flux load from primary body (planet). " sec. 6.1
e.g. 15  0.62 0. 0. 0.21 0.21 0. 12. / Jupiter heat load on Europa, nearside center
16  Latitude and name for high-time-resolution surface temperature file
    See eclipse.pdf section. 7

```

For Type 12 and 13, 8 white-space-separated coefficients must follow after the type on the same line, with no intervening index or text

For Type 8, SEASALB and SEASTAU read 2-column, white-separated text files.

To start variable albedo, use input card:

```
8 22 0 'AlbedoFileName' / Variable albedo text file name
```

Can revert to constant albedo by using a non-existent file name. E.g.,

```
8 22 0 'badName' / turn variable albedo off
```

Text table files of value versus season will be read at the start of a run. These will apply to ALL latitudes. See example *valb1.tab*

Variable dust opacity done the same way, with 22 being replaced with 23

CLIMTAU files have dust and ice opacity over season and latitude. Uses BINF5 to read a binary array (72 seasons, 36 latitudes, 2=dust/ice) of opacities. The sample file *THEMIS1yearDustIce.bin5* is described in section [159] of Ref 1.

5 Contents of COMMOMS

```

COMMON /KRCCOM/ Input and transfer variables. See krcc8m.f
COMMON /DAYCOM/ Layer and time-of-day items. See dayc8m.f
COMMON /FILCOM/ File names. See filc8m.f
COMMON /HATCOM/ Store post-2003 items. See hatc8m.f
COMMON /LATCOM/ Latitude-dependent items. See latc8m.f
COMMON /PORBCM/ PORB system geometry matrix. See porbc8m.f
COMMON /UNITS/ Logical units for I/O and errors. See unic8m.f

```

Because the binding routines to IDL are intolerant of any errors, changes to KRCCOM, DAYCOM and LATCOM are avoided if possible. Rather, in 2004July HATCOM was added as a "catch-all" for any new items.

A listing of all Fortran commons can be generated by these Linux commands:

```
cd /home/hkieffer/krc/src [replace top part of path with local installation]
rm allinc.txt
cat *c8m.f > allinc.txt
```

6 Error Returns

6.1 Tday Blowup

There are two triggers:

(ADELN.GT.0.8): $\frac{|\Delta T|}{T} > 0.8$

(TSUR.GT.TBLOW): $t_{\text{blow}} = \frac{\langle S \rangle}{\epsilon \sigma}$

In either case, control goes to 340 in TDAY; iteration is terminated and several values are sent to the print file. TDISK is called to output the current season and to close the file. TPRINT is called to print out the full input set and the latest daily convergence.

6.2 Other errors: INCOMPLETE

Case had FATAL error= 41 ... Running with atmosphere but FFF has none

If you run into errors that are not related to blunders in the input file, please contact the author.

"Parameter error in TDAY(1)" : Convergence factor < .8 classic.

Instability anticipated.

"UNSTABLE; Layer..... TDAY(1):

```
DRSET: 0=>      Reset by delta_average_T for each layer:
                else: reset by {linear + DRSET*quadratic}*{<surf>-<botm>}
TDAY: LRESET    Reset midnight T's for all but top layer.
LDAY           Last day computations
```

7 DISK BINARY FILES

The routine TDISK is used to read or write seasonal/global direct-access binary files and to write multi-case bin5 files. The first season to write is specified by JDISK, all following seasons will go to the same file. For direct-access files, each file record consists of KRCCOM plus LATCOM or KRCCOM plus DAYCOM. Writing of bin5 and direct-access files are independent of each other and may be simultaneous.

Disk output is largely controlled by the KRC and TSEAS routines.

7.1 Items which control file I/O

KOLD & KEEP on first input line

KOLD: 0= input card set follows; else=disk record number to start from, then will read any change cards.

If LPORB in old file was True, then there must be a PORB card set as the set of lines following the KEEP,KOLD line

KEEP: 0= close disk file after reading seasonal record KOLD;

>0= value of JJJJJ at which to start saving seasons in same disk file [overrides JDISK].

To start from a prior seasonal run, need to determine the record corresponding to the desired season;

KOLD=J5_target - JDISK(old) ; >0

set KEEP=1, change card J5=number of new seasons, set K4OUT.

JDISK sets the first season to save results

N5 sets the last season to run

K4OUT sets the direct-access record content: (ignored for Type 52)

-1:-3 Will output first record of KRCCOM,ALAT,ELEV, then records of TSF & TPF

0 Will output records of KRCCOM+LATCOM. Usual for large data-base.

+n<=50 Will output records of KRCCOM+DAYCOM for the last computed latitude.

If a change ' 8 5 0 <filename> ' has been set, then will write a type 52 bin5 file at the end of a run, with dimensionality of 5. This allows multiple cases, each with a "prefix" for each case consisting of 4 size integers (converted to Float) followed by KRCCOM; after this may come vectors of parameters versus season. The next-to-last dimension is increased to allow room for the prefix to be embedded in the bin5 array. Each dimension is adjusted to the necessary size. Each case has the same structure; this simplifies coding although some items are then present redundantly.

KRC input items that would increase any of the bin5 dimensions are not allowed to change between cases in a file. Decrease in these sizes are allowed, however this will leave regions of the file undefined and the only clue will be the values in krccom that are stored for each case. Increases to larger than the value for the first case will cause an error and closing of the file. This restriction is on:

N5-JDISK: number of output seasons

N4: number of latitudes

N24: number of hours output

Although KRC allows the N1, the number of layers, to change between cases the IDL type 52 reader **readkrc52** will only extract the number in the first case, so N1 should not increase between cases.

The first 4 words of the prefix, and thus of the bin5 array, are:

(1)=FLOAT(NWKRC) ! Number of words in KRCCOM

(2)=FLOAT(IDX) ! 1-based index of dimension with extra values

(3)=FLOAT(NDX) ! Number of those extra

(4)=FLOAT(NSOUT) ! [Available of other use]

See also Appendix A for a detailed description and how it is unpacked.

52=(N24 hours, 7 items, N4 lats, NDX+ seasons, cases)

The prefix section contains: sub_array(seasons,5)(0-based index)

0)=DJU5 1)=SUBS 2)=PZREF 3)=TAUD 4)=SUMF

The 7 items are: 1)=TSF 2)=TPF 3)=TAF 4)=DOWNVIS 5)=DOWNIR

6) packed with [NDJ4,DTM4,TTA4, followed by TIN(2+

7) packed with [FROST4,AFRO4,HEATMM, followed by TAX(2+

The number of layers for TIN and TAX is the smaller of: the number computed and that fit here.

----- The other type 5x listed below are no longer supported -----

51=(N24 hours, 2: TSF TPF, N4 lats, NDX+ seasons, cases)

The prefix is identical to Type 52

0)=DJU5 1)=SUBS 2)=PZREF 3)=TAUD 4)=SUMF

54= (seasons, 5 items, NDX +nlat, cases)

Items are (0-based index):

0= TSF=surface temperature at 1 am, 1= TSF at 13 hours,

2= HEATMM=heat flow, 3= FROST4=frost amount,

4= TTB4 = predicted mean bottom temperature

The prefix contains DJU5

55= (seasons,NDX+ items,cases). For seasonal studies at one latitude

ITEMS intended to be recoded as needed. Initial version is 9 items:

```
[Tsur@ 1am,3am,1pm, spare, Tplan @1am,1pm, Surface heat flow,
frost budget, T_bottom]
The prefix contains DJU5
Can hold very large number of seasons and cases.
THIS MODE DOES NOT SUPPORT CONTINUATION RUNS
```

```
56= [vectors&items, latitudes, NDX+ seasons, cases]
The first dimension is: TSF for all hours, TPF at all hours,
T4 for all layers at midnight, then FROST4,HEATMM,TTA4
The prefix is identical to Type 52
```

Once a disk file is opened, any records written will go into that file until a new filename is specified (Type 8 Change line), which closes the current file. It is best to ensure that output file does not already exist. If the file already exists, new output may be written in same area, even if the old file was larger than needed.

7.2 Maximum sizes

Values for latest version of KRC in this section are in square brackets. All are firm-coded in krcc8m.f

For any run, even without recorded output, there are three limits:

```
maximum number of layers, N1 [50]
maximum number of times of day, N2 [393216]
maximum number of iteration days, N3 [16]
```

For all file output types, there are two more limits:

```
The number of latitudes N4 [37]
Number of stored hours N24 [96].
```

All of these are checked and limited in TCARD before a run starts.

MAXN5 and MAXN6 are not limits for standard KRC.

7.2.1 Direct access files

For type 0, -1, -2 and -3 files, each recorded season is a logical record, so there is no limit to the number of seasons allowed.

7.2.2 Type 52 files

For type 52, the primary limit is the total words available to accumulate results into a bin5 array; this is the parameter KOMMON in krcc8m.f, currently set at 10,000,000. The size needed for one case is approximately: $N24 * 7 * N4 * (N5 - JDISK + 3)$.

All five limits mentioned above are in effect.

The number of cases allowed is set by the size of case one, and printed as MASE at the end of the first case in the print output. Cases beyond the maximum that can be stored will be executed, but not saved.

8 Optional input files

8.1 Text

8.1.1 Zone depth table

Name is defined by a change card: 8 25 x 'fileName' / . May have up to 20 lines of comments before a "C_END" line. Then each row define a zone and must contain 4 columns:

```
Col 1: thickness, m
Col 2: density, kg/m³          But: -1=use DENS, -2=use DENS2
Col 3: Conductivity, SI Units. [ If negative then col 4 is a pointer
Col 4: Specific heat, SI Units. [ 1=upper material, 2=lower material
```

Must be at least 3 zones; otherwise could use two layers within input parameters.

The thickness of the last zone is ignored; KRC will fill out to N1 geometric layers.
Must not be any trailing blank lines

The file name is read in by TCARD; TDAY will call READZONE to read the file. Then the zones will be expanded into an appropriate number of layers. If the zone definitions violate the convergence stability requirements or the number of layers assigned, the case will be skipped with a warning.

MAXN1 [firm-coded as 50 in KRCCOM] zones are allowed, any beyond this will be ignored.

If the number of layers generated exceeds N1, a warning is printed and the case is skipped.

8.1.2 Seasonal albedo table

Name is defined by a change card: " 8 22 x 'fileName' / " and stored as FVALB in FILCOM. May have up to 20 lines of comments before a "C.END" line. Then each row must contain 2 columns.

Col 1: L_S in degrees

Col 2: surface albedo

Values of Col 1 must be within 0:360 and monotonically increasing.

Must not be any trailing blank lines

Values apply to all latitudes. Active flag is KVALB

The file name is read in by TCARD; TLATS will call SEASALB to initiate or to get a values for a specific season. SEASALB calls READTXT360 to read the file. SEASALB will do linear interpolation in season and handle wrap-around.

Example: *-/krc/tes/valb1.tab*

8.1.3 Seasonal opacity table

Similar to the albedo table with these exceptions:

primary routine is SEASTAU.

Name is defined by a change card: 8 23 x 'fileName' and stored as FVTAU in FILCOM

Col 2: visual dust opacity

Active flag is KVTAU=1

Example: *-/krc/tes/SmithTau.tab*

8.2 Binary: Seasonal climate table

Name is defined by a change card: 8 25 x 'fileName' / and stored as FVTAU in FILCOM; name is shared with variable tau as cannot be active at once. The active flag is KVTAU=2.

A binary file of .bin5 format. [Seasons,latitude,item] assumes Seasons and latitude on a rectangular, uniformly-spaced, grid. Item 1 is visual opacity. Item 2 is ice-cloud opacity [could be optional, but coded to be present].

File is read and bi-linear interpolated by CLIMTAU; which is called by TLATS.

Firm-coded for 72 seasons and 36 latitudes, both uniformly spaced.

Example: */work1/mars/opacity/THEMIS1yearDustIce.bin5*

9 Handy things

The first "hour" in printout and output arrays is 1/N24 of a sol after midnight. E.g., the last time is midnight, not the first.

Atmospheric scale height, SCALEH, depends upon physical constants GRAV [input] and TATMAVE which (2007nov) is TATM [input] for the first season and thereafter the diurnal average of the prior season.

To run and save various cases for a single season, set N5 and JDISK to 1.

To extract a detailed day by saving DAYCOM to disk, set JDISK=N5, set a new file name, and set K4OUT to desired latitude index (normally 1):

To run continuously with output every K (1-3) days, set DELJUL=K*PERIOD This will force prediction terms to near 0.
setting N3=1 will turn off all prediction.

set GGT large (to avoid iteration for convergence)
 set NRSET=999 (to avoid reset of layers)

To continue a run with new parameters (e.g., DELJUL)

3 21 1 'flag set to continue'

Note: changing DELJUL will cause reset of DJUL

Must increase the value of N5: e.g., 2 5 [bigger] 'Increase stopping season'

Reset will not occur because J5 continues incrementing

9.1 ASCII Output Files

Reconstructed 2017oct01

----.prt General results. Things in output are controlled by LP1:6 & LPGLOB

eLog---.---- Error Log, named for time as yyyyymmddThhmmss.fff

fort.75 tlats8.f: Debug geometry details

fort.76 tlats.f: mimic Mike Mellon ASCII files

fort.77 tun8.f: Special items, firmcoded

fort.43. 44 and 47. tfin8.f , Usually only if eclipse case. see eclipse.tex

9.2 To run two material types

Set IC2 to the first layer to have the lower material properties (≥ 3)

Set COND2 to the lower material conductivity

Set DENS2 to the lower material density

Set SPHT2 to the lower material specific heat

If LOCAL is False, then initial setting of all layer thicknesses is based upon the scale of the upper material; if it is set True, the thickness of the lower layers is set by their scale.

TDAY no longer allows unstable (thin) layers, and will increase the thickness of the layer IC2 to satisfy the convergence safety factor FCONV if needed. However, the code to check on convergence was retained.

9.3 Setting temperature-dependant properties

Basic Flag is L10=LKOFT . If this is true, then the 8 input parameters ConUp0 to ConLo3 must be set to yield thermal conductivity as a function of temperature for the upper and lower materials. $k = c_0 + c_1x + c_2x^2 + c_3x^3$ where $x = (T - 200.) * 0.01$

Correspondingly, the 8 input parameters SphUp0 to SphLo3 must be set for specific heat

One way to generate the coefficients is to run for each of the upper and lower materials the IDL procedure KOFTOP, which can call all of the temperature-dependant routines. KOFTOP allows change of its parameters, including grain radius and pressure, and will print the required parameters ready for input to KRC.

Below are sample coefficients for thermal conductivity based on Sylvain Piqueux's numerical model for un-cemented soils; the fit error is $< 0.1\%$ over 120-320K. Left column is grain radius in micrometers, then the four normalized coefficients ready for inclusion in a KRC input file, followed by the thermal inertia at 220K for nominal density and specific heat.

R(mu)	c0	c1	c2	c3	Iner
10.	0.008274	0.000735	-0.000376	0.000148	89.8
20.	0.012379	0.001280	-0.000629	0.000250	109.9
50.	0.021485	0.002647	-0.001201	0.000483	144.7
100.	0.032051	0.004528	-0.001874	0.000761	176.8
200.	0.046023	0.007569	-0.002743	0.001129	211.8
500.	0.068387	0.014075	-0.003874	0.001687	258.2
1000.	0.086303	0.021288	-0.004146	0.002099	290.1
2000.	0.103743	0.030909	-0.003141	0.002535	318.0

5000.	0.127172	0.049907	0.002019	0.003469	352.1
10000.	0.149810	0.074734	0.011546	0.004939	382.2
20000.	0.185706	0.119913	0.030938	0.007877	425.5
50000.	0.283361	0.250283	0.089327	0.016714	525.6

10 RUNNING THE "ONE-POINT" MODE

A parameter initialization file *Mone.inp* is provided. It sets the KRC system into a reasonable mode for one-point calculations. Do not change that file unless you have read this entire file; caveat plastis (modeler beware).

A line near the end of that file points to a file 'oneA.one' which can contain any number of one-point conditions. You can replace that name with your own; the named file is intended to be edited to contain the cases you want; however, it must maintain the input format of the sample file.

First Line is any title you wish. It must be present.

The second line is an alignment guide for the location lines. It must be there.

Each following line must start with an '11'; this is a code that tells the full-up KRC that is a one-point line. The next 9 fields are read with a fixed format, and each item should be aligned with the last character of the Column title. All items must be present, each line must extend at least to the m in Azim; comments may extend beyond that, but they will not appear in the output file. Be sure to have a <CR> at the end of the last input line; i.e., no blank lines!

The fields (after the 11) in the one-point input are:

Ls	L_sub_S season, in degrees
Lat	Aerographic latitude in degrees
Hour	Local time, in 1/24'ths of a Martian Day
Elev	Surface elevation (relative to a mean surface Geoid), in Km
Alb	Bolometric Albedo, dimensionless
Inerti	Thermal Inertia, in SI units
Opac	Atmospheric dust opacity in the Solar wavelength region
Slop_	Regional slope, in degrees from horizontal
Azim	Azimuth of the down-slope direction, Degrees East of North.
Title	From 1 to 20 characters, must not be entirely blank

The two additional columns in the output file are:

TkSur	Surface kinetic temperature
TbPla	Planetary bolometric brightness temperature

Try running the binary file first. If that fails, a Makefile is provided to compile and link the program; simply enter "make krc" and pray. If this fails, have your local guru look over the Makefile for local dependancies. Suggestions of making the Makefile more universal are welcome.

To run the program, change to the directory where the program was built, and enter "krc". You should get a prompt:

?* Input file name or / for default = Mone.inp

If the initialization file still has this name and is in the same directory, enter a single "/" and <CR>. Otherwise, enter the full pathname to the initialization file, with no quotes and no blanks.

A second prompt is for the name of the output file:

?* Print file name or / for default = krc.prt

Again, if this is satisfactory, simply enter / <CR> , else enter the desired file path-name.

10.0.1 Comments on the One-point model

The initialization file *Mone.inp* is a compromise between the secular trend being reached (less layers) and the annual variation being damped (more layers). The version after KRC v2.2.4 was tested over a large grid of non-polar-cap points against a model twice as deep and run for 6 years; the average absolute difference was 0.05 K. Execution time on a circa 2013 PC is about 30 cases/second.

The underlying model is the full version of KRC. By modifying the initialization file, you can compute almost anything you might want. If you choose to try this, best to read all of this document.

11 DEBUG OPTIONS

If the first input line has a no-zero third number, then the second line is 6 white-separated debug-control integers: IDB1 to IDB6

```

2017sep30   ]$ grep -in IDB *8.f
krc8.f:141:   IF (IDB6.GT.6 .AND. IDB6.LE.99) THEN
krc8.f:142:     WRITE (IOPM,*) 'Switching IOPM output to  fort.',idb6
krc8.f:143:     IOPM=IDB6
porb08.f:16:   LOP=IDB1.GT.3
tcard8.f:97:   IF (IDB2.GE.5) WRITE(IOSP,*) 'TCARD-A',IQ
tcard8.f:112:   Set all IDB to 0, read and write them
tcard8.f:145:   IF (IDB1.GE.1) WRITE(IOPM,*)'Before PORBO'
tcard8.f:147:   IF (IDB1.GE.1) WRITE(IOPM,*)'AFTER PORBO'
tcard8.f:421:   IF (IDB1.NE.0) WRITE(IOSP,*)'TCARD Exit: IRET=',IRET,NFD,ID(1) !< dbug
tday8.f:84:   IF (IDB2.GE.5) WRITE(IOSP,*) 'TDAY IQ,J4=',IQ,J4,JJO
tday8.f:157:   IF (IDB2.GE.3) WRITE(IOSP,*)'Zlay K J  DSCAL  DDZ'
tday8.f:230:   IF (IDB2.GE.3) WRITE(IOSP, '(a,2i3,6f8.3,i3,f8.4)')
tday8.f:386:   IF (IDB4.GE.2) WRITE(*, '(a,2i4,2f8.5,f10.3,e12.5)')
tday8.f:404:   IF (IDB4.GE.2) WRITE(IOSP, '(i3,2f12.3)') J,SCONVG(J),ZDZ(J)
tday8.f:596:   IF (IDB2.EQ.2) WRITE(IOSP,119) LZONE,LALCON,j5,IK1,IK2,IK3,IK4
tday8.f:651:   IF (IDB5.GE.4)WRITE(47,22)(TTJ(I),I=1,N1) ! coarse T
tday8.f:778:   IF (J7.GT.0 .AND. IDB5.GE.7) WRITE(46,244)
tday8.f:853:   IF (IDB2.EQ.2) WRITE(IOSP,119) LZONE,LALCON,j5,IK1,IK2,IK3,IK4
tday8.f:873: 9   IF (IDB2.GE.6) WRITE(IOSP,*) 'TDAYx'
tdisk8.f:115:   IF (IDB3.GE.3) WRITE(IOSP,*)'TDISKa ',KODE,KREC,NCASE,J5,K4OUT
tdisk8.f:116:   IF (IDB3.GE.4) WRITE(IOSP,31)'TDISKa N3,N4+',N3,N4,N5,J5,MASE !<dbug
tdisk8.f:117:   IF (IDB3.GE.5) WRITE(* ,31)'TDISKa N3,N4+',N3,N4,N5,J5,MASE !<dbug
tdisk8.f:282:   IF (IDB3.GE.3) WRITE(IOSP,*)'TDISKc KREC=',KREC,LOPN2,IOD2,I
tdisk8.f:341:   IRET=IDB3 ! +1=report many values +2 report progress
tdisk8.f:358:   IF (IDB3.GE.7) WRITE(IOSP,*)'TDISKx KREC=',KREC
tfar8.f:67:   IF (IDB3.EQ.2) WRITE(IOSP,*)'TFAR:0 ',KODE,KREC
tfar8.f:82:   IF (IDB3.GE.3) WRITE(IOSP,*)'TFARc KREC=',KREC,LOPN3,IOD3
tfar8.f:191:   IF (IDB3.GE.7) WRITE(IOSP,*)'TFARx: KODE,KREC=',KODE,KREC
tfine8.f:93:   IF (IDB5.GE.1) WRITE(IOSP,*) 'TFINE IQ,J4=',IQ,J4
tfine8.f:123:   IF (IDB5.GE.1) PRINT *,'QB..',QB,RLAY,RLAF,BF1,N1F,JLOW
tfine8.f:139:   IF (IDB5.GE.6) WRITE(IOPM,30),'I,j..',I,J,QB,DIFFI(I)
tfine8.f:184:   IF (IDB5.GE.1) WRITE(IOSP, '(a,i3,f12.3)')
tfine8.f:208:   IF (IRET.LT.1 .OR. IDB5.GE.2) WRITE(42, '(A,I4,2G12.5,F8.1)') !
tfine8.f:302:   IF (IDB5.GE.4) THEN
tfine8.f:318:   IF (IDB5.GE.3) WRITE(IOSP, '(a,2f12.4,g13.5)')
tfine8.f:334:   IF (IDB5.GE.2) WRITE(IOSP,119) LZONE,LALCON,j5,IK1,IK2,IK3,IK4
tfine8.f:451:   IF (IDB5.GE.4) THEN
tfine8.f:476:   I=IDB3 ! +1=report many values +2 report progress
tfine8.f:492: 9   IF (IDB5.GE.1) WRITE(IOSP,*) 'TFINE exit'
tlats8.f:52:C 2016sep09 HK Do not print T-equilb unless IDB2.ge.5
tlats8.f:128:   LQ1=IDB2.GE.5 ! once per season or latitude
tlats8.f:129:   LQ2=IDB2.GE.9 ! each time of day
tlats8.f:130:   IF (IDB2.NE.0) WRITE(IOSP,*)'TLATSa',N3,N4,J5,LATM,LQ1,LQ2
tlats8.f:179:   IF (IDB2.GT.0 .AND. J5.EQ.1) WRITE(IOPM,*)'SKYFAC,FAC5X=',
tlats8.f:265:   IF (IDB2.GE. 5) then
tlats8.f:282:   IF (IDB2.GE. 5) then
tlats8.f:651:   IF (IDB2.EQ.4) WRITE(IOPM,*)'J4,5 +',J4,J5,TEQUIL,TATMJ
tlats8.f:754:   I=IDB3 ! +1=report many values +2 report progress
tlats8.f:766: 9   IF (IDB2.GE.3) WRITE(IOSP,*)'TLATSx',N1,N1PIB,N2,N24,J3

```



```

tseas8.f:62:      IF (IDB1.NE.0) WRITE(IOSP,*) 'TSEASa',IQ,J5,LSC,N5,LONE
tseas8.f:88:      IF (IDB1.EQ.3) WRITE(*,132)'DELP1:40',(DELP(I),I=1,40)
tseas8.f:95:      IF (IDB3.GE.3) WRITE(IOSP,'(a,3i5,f9.3,f9.4)')
tseas8.f:159:     IF (IDB3.GE.3) WRITE(IOSP,'(a,f8.4,2f9.3,f9.5,2i4)')
      grep -in lq tlats33.f
128:      LQ1=IDB2.GE.5          ! once per season or latitude
129:      LQ2=IDB2.GE.9          ! each time of day
130:      IF (IDB2.NE.0) WRITE(IOSP,*)'TLATSa',N3,N4,J5,LATM,LQ1,LQ2
131:D      WRITE(IOPM,*)'TLATSa',N3,N4,J5,LATM,LQ1,LQ2 !<debug
175:      IF (LQ1) I=3
197:      IF (LQ1) THEN
      WRITE(75,*) 'J5+',J5,SUBS,SDEC,DAU,SLOPE,SLOAZI
      WRITE(75,*) 'MXX+',MXX,SKYFAC,FAC5X
241:      IF (LQ1) WRITE(IOPM,*)'TLAT1 J5,TBLOW=',J5,TBLOW
243:top of Lat loop
247:      LQ3=LD19 .AND. (J5.EQ.JDISK) .AND. (J4.EQ.1) ! first recorded season
270:      IF (LQ1) KODE=4 ! do debug print in CUBUTERP8
325:      IF (LQ1 .AND. J5.EQ.1) THEN
      WRITE(75,*)'FXX+',FXX,J4,DLAT
      WRITE(75,*)'QXX=',QXX
      WRITE(75,*)'TXX=',TXX
      WRITE(75,*)'PXX+',PXX,LPH,PARW(7),COSP
409:      IF (LQ1) WRITE(IOPM,*)'TLATS: J4+',J4,SOLR,ACOSLIM,COSIAM(1)
411:C3      IF (LQ3) WRITE(IOSP,701)'LQ3',NCASE,J5,J4,TATMAVE,PRES,OPACITY
431 top of time loop
529:      IF (LQ2.AND.(MOD(JJ,24).EQ.1)) THEN
      WRITE(75,*)'HXX+',HXX,JJ
      WRITE(75,*)'ANG:',ANGLE,COSI,COS2,DIRECT,QI
533:      IF (LQ2) WRITE(IOSP,*)', 'TLatc',JJ,COSI,COS3,DIRECT,DIFFUSE
548:C3      IF (LQ3) WRITE(88,777)JJ,COSI,COLL,HUV,QI,DIRECT,DIFFUSE,BOUNCE
551:      IF (LQ3) WRITE(88,777)JJ,COSI,COS2,AVET,HALB,DIRECT,ATMHEAT
559: end time loop
582:      IF (LQ1) WRITE (IOPM,*) 'QS, small tau=',QA,QS
602:      IF (LQ1) then
      WRITE(IOPM,*)'AVEA...',AVEA,AVEE,AVEI,AVEH
      WRITE(IOPM,*)'CABR...',CABR,TAUD,TAUIR,FACTOR,TAUEFF
      WRITE(IOPM,*)'BETA...',BETA,QS,SIGSB
      WRITE(IOPM,*)'TAEQ4,TSEQ4,TEQUIL',TAEQ4,TSEQ4,TEQUIL
618:      IF (LQ1) WRITE(IOPM,*)'TSUR,TBOT',TEQUIL,TSUR,TBOT
620:      IF (LQ1) WRITE(IOPM,*)'XCEN',XCEN
634:      IF (LQ1) WRITE(IOPM,*)'Radiation time, sec',QA
652:      IF (LQ1) WRITE(IOPM,*)'TTJ',TTJ
759: end of lat loop
761:      IF (LQ1 .AND.(.NOT. LONE) .AND. (J5.LE.1)) ! avoid line in OnePoint output
      & WRITE(IOSP,*)'TLATS: TEQQ',(TEQQ(I),I=1,N4) ! starting Tequil
end lat loop

```

12 Accessing KRC output in IDL

IDL routines do not access files directly unless specifically listed.

DEFINEKRC Define structures in IDL that correspond for Fortran commons

Calls: None == None other than IDL library

Firm code of common definitions. Must be recoded if a Fortran *.inc changes

KRCSIZES Compute array and common sizes for KRC Fortran

Test procedure to compute array sizes or hours.

Must recode if any size in *.inc changes

Calls: None

READKRCCOM Read a KRCCOM structure from a bin5 file

Uses 3-element HOLD array. Returns a structure of krccom

Options to open or close bin5 file or read one case

Calls: DEFINEKRC

Files: bin5

HOLD is: 0]=logical unit 1]=number of words in a case 2]=# cases in the file

READKRC1 Read KRC direct access filesC

Calls: DEFINEKRCC

Read type -1,-2 or -3 files. Caller sets the KRC version that wrote the file.

READKRC52 Reads a KRC type 52 bin5 file

Calls: BIN5read READKRCCOM

Reads and unpacks type 52 file, returning 5 multi-dimensional arrays

KRCHANGE Find changes in KRC input values in common KRCCOM

Calls: READKRCCOM MAKEKRCVAL

Reads and stores krccom for first case. For each additional case, makes a list of any changes in the float, integer or logical input values.

KRCCOMLAB Print KRC common input items

all items via arguments

Calls: None

MAKEKRCVAL Make string of selected KRC inputs: Key=val

Calls: DEFINEKRC

KRCLAYER Compute center depth of KRC layers

all items via arguments

Calls: None

13 Special tabular output; routine tun8.f

Beginning with version 3.2.1, the user can request tabular output of items not in the type 52 files. This output is triggered by setting I15 to a value of 100+N where N is an option coded in the subroutine TUN8 (T unique). For each output case, there is a header line of 8 integers:

- 1: the number of dimensions to the data, Ndim, currently always 4
- 2: total number of columns in the table, 3 larger than the data columns
- 3: number of times per day output
- 4: number of latitudes
- 5: number of seasons output
- 6: IDL-style type of data for conversion, currently always 4 (single-precision floating point)
- 7: The run number in the KRC run
- 8: the case number

Thus, the first Ndim+2 values can be used to construct a storage array

This is followed by a line for every hour, latitude and season: the first 3 columns are those values as integers. The rest of the columns are [normally] floating-point values for that instant on the final convergence day of each season.

The three options coded as of 2017 Mar 2 are:

N=1: Temperatures for each layer at each hour, layer number increases to the right
the virtual layer is omitted

N=2: Down-going solar fluxes, atmosphere and apparent sky temperatures
floating-point columns are:

- 1: collimated insolation
- 2: diffuse and 'Bounce' insolation
- 3: Atmosphere kinetic temperature (redundant with Type 52)
- 4: Apparent zenith sky temperature: ${}^4\sqrt{\beta} T_a$, see [40] in the JGR KRC paper.
- 5: Effective hemispheric sky temperature: ${}^4\sqrt{1 - e^{-\tau_r}} T_a$, see [42]

N=3: Photometric albedoes

floating-point columns are:

- 1: time index
- 2: collimated insolation onto slope surface
- 3: all downward insolation except collimated
- 4: solar heating of atm. H_v
- 5: cos of incidence angle on horizontal
- 6: current hemispheric albedo

Output is always to a file 'fort.77' in the directory where KRC was invoked, so for preservation it must be renamed before the next KRC run.

Output will be for the same set of seasons as written by TDISK. Output can be for any subset of cases in a run (single TDISK output file) or multiple runs in one input file. Output is turned on by a change line, e.g.,

```
2 15 101 'I15' / values to fort77
```

and it is turned for by, e.g.,

```
2 15 75 'I15' / RESET to no fort77
```

However, the current IDL routine to read a TUN8 output file does not accomodate cases with different sized tables.

Additional options can be coded into tun8.f .

14 Notes on how some aspects of the code work

14.1 New file name

TCARD reads a card of Type 8, (and index is not 22 or 23)

it calls TDISK(4,0), which closes current file and sets LOPN2=.FALSE.

TCARD then moves new file name into common

KRC checks if current (new) values of N5 and JDISK call for file output;

with LOPN2=.FALSE., KRC calls CALL TDISK (1,0) to open new file.

14.2 End of a case and end of a run

TCARD sets KOUNT=0 at entry; this is incremented for every card except those of type 0 (or less) or type 11 (one-point mode). When type 0 is encountered, if KOUNT is positive, does normal check of changes before return with IR=1 to indicate start of a new case; if KOUNT is zero, returns with IR=5 and prints 'END OF DATA ON INPUT UNIT'

14.3 Setting one-point mode

This can be done only in the first case, and there is no way to leave the one-point mode except to end the run.

TCARD encounters: " 10 * filename" as change card in the initial case.

sets this as new input file name, then returns with IRET=4

[Thus, nothing following this change card in initial file is read]

KRC closes prior input file, opens the new one, and reads past first two lines

then calls TCARD to read first one-point line and sets LONE=true

and drops into the top of the "case" loop.

The master one-point should have a single latitude, no binary output file.

The small number of layers, days to converge, and seasons ignores the seasonal effect.

One-point request values are read by TCARD @ 310, which computes starting DJUL

TPRINT does linear interpolation of TOUT, which has N2 points be sol. To get Tp, does interpolation of Tp-Ts at the hour points, and adds to interpolated Ts.

14.3.1 How one-point converts Ls to date

Ver 212: XREAD is the 2nd column in the OnePoint file, i.e., Ls.

In TCARD 310: calls PORBIT to get the date of the desired Ls, then backs up (N5-1)*DELJUL to the starting date.

14.4 Starting conditions and date

Initial N5-JDISK sets the size of output files. There could be any number of interior seasons where parameter changes are made; based on successive values of IDOWN.

KRC initially calls TCARD(1

For each case loop, sets IQ=TCARD_return. If one-point mode, sets IQ=1

TSEAS uses IQ as key. If this is 1, then sets J5=0 and sets DJU5 to season -1., else, increments J5 and increments DJU5 with current DELDUL. This allows use of variable resolution dates. (so J5 never 0 when TCARD(2 called)

TLATS uses J5 as the key; if it is ≤ 1 , then starts from equilibrium conditions, else uses predictions from prior season

The default is that change cards cause a fresh calculation of starting conditions. Exceptions are when J5=IDOWN > 0 at TCARD entry

14.5 Changing parameters within a seasonal run = Continue from memory.

When J5 reaches IDOWN, TSEAS calls TCARD, which will set IRET=3 before reading the new parameters. May change DELJUL to get finer seasonal resolution, but must NOT change N5

Use: Normal restrictions for what may not change for Type 52 files apply.

Set N5 to be the total number of seasons desired, including those after any number of parameter changes; it must NOT be changed later.

Set IDOWN to the season at the beginning of which wish to (first) change parameters. The next set of changes could include a revised (larger) IDOWN.

14.6 Use of common PORBCM

Contents are described in porbcm8.f

PORBCM is filled by TCARD calling PORB0, which reads the first 30 items in 5G15.7 from the input file and sets the value of π and radians-to-degrees.

TSEAS call PORBIT to get Ls, the heliocentric range and the sub-solar latitude.

14.7 Lower boundary condition and resetting (jumping) layer temperatures.

At the start of a case, TLATS sets the temperature profile linear with depth in one of three ways:

IIB=0: top and bottom at equilibrium temperature

IIB=1: top at equilibrium temperature, the bottom at TDEEP

IIB=2: top and bottom at TDEEP

The kind of resetting is controlled by IB. In TCARD, if IB>0, then N1PIB=N1+1, else N1PIB=N1. T(N1+1) is not reset in the time calculations. In TDAY, for each time step, the temperature of the lower boundary is set equal to T(N1PIB), which results in either zero heat flow (IB=0) or a constant temperature.

14.8 Temperature scaling for KofT

TOFF and TMUL are firm-coded in *tday* as 220 and 0.01. These are appropriate for Mars. They may be made input parameters in later versions to address Mercury-like planets

14.9 No atmosphere flag

tseas.f contains: LATM=PTOTAL.GT.1. so a pressure of 1.0Pa or less is treated as zero atmosphere. The LATM flag is used only in **tlats** and **tday**

14.10 Far-field temperatures 2016jun30

FFAR initially set by KRC to be 'no'; this is less than 4 characters, so far-field is considered turned off.

An input card ' 8 3 x text': TCARD loads <text> into FFAR. For each case, KRC then checks length of FFAR; if 4 or more, will call TFAR(1 to open a FAR file for read. If successful, TFAR sets LOPN3=.true.

LOPN3 is used in TDAY as the flag that the far-field calculation is active (as opposed to self heating)

14.11 Seasonal variation of albedo or opacity or “climate”

When TCARD encounters a type of 8 and an index of 23(tau) [or 22(albedo)], it transfers the text item into FVTAU (which is in COMMON /FILCOM/) and then calls SEASTAU with an Ls of -999 . SEASTAU when called with LSUB LT -90 calls (providing IOD3) READTXT360, which reads file. Maximum number of rows is 360, more will be ignored. First and last entry read are wrapped with ± 360 to Ls to ensure no interpolation faults later. TCARD sets the variable Tau flag, KVTAU, true if table-read was successful, else it is set false. If KVTAU is set, TSEAS calls SEASTAU at start of each season, resetting TAUD.

If type 8 and index 23, the same as above except names are -ALB rather than -TAU

If type 8 and index 24, then TCARD calls CLIMTAU to open and read a .bin5 climate file, and sets KVTAU=2

CLIMTAU expects to read a .bin5 file (season,latitude,2) with dust and ice infrared opacities; this file is normally made by the IDL routine mopacity.pro . Season is assumed to be uniform in Ls from 0 to 360-delta and latitude assumes to be uniform from -90+delta/2 to +90-delta/2. CLIMTAU has firm-coded sizes, 72 seasons and 36 latitudes, and stores the file. Upon later calls from TLATS, it returns the two opacities at a requested Ls and latitude, using bi-linear interpolation.

14.12 Cap-dependent pressure

```
TSEAS:  BUF(1)=0.          ! flag for TINT to compute areas
IF (N4.GT.8) CALL TINT (FROST4, BUF, SUMF)
```

Tlats

```
IF (N4.GT.8) THEN          ! use global integrations
  PCAP = SUMF*GRAV         ! cap_frost equivalent surface pressure
```

```
KPREF.EQ.2
```

```
PZREF = PTOTAL - PCAP
```

```
PCO2G = PCO2M -PCAP ! all changes are pure CO2
```

14.13 When parameter and layer tables appear

The flag LD18 means: a value has changed after the parameter and layer tables were last are printed. It is set: initially and by TCARD. It is cleared when the tabel are printed,

Can tell if zones are active by length of FZONE in common

These two table are printed: initially, before TSEAS for each case if LP2 is set, or after TSEAS if an error occurs or if LD15

When to print.

first case

if LP2 true

if an error and prints are out of date.

Something is out-of-date: initially, or if TCARD was called

but not for each season, LSC true.

What to print

parameters

layers

zones if active.

If all the prints were at the same place, or controlled from the same place, that could set the “current” flag.

As of 3.3.1,

parameters printed by TPRINT(2

layers printed in TDAY(3)
zones printed by READZONE in TDAY(1 or 3, if active)

Because case change is done in KRC8, and errors return there with a code, the top control logic could be there.

15 Non-standard FORTRAN

All thought to be removed in Version 3+

A Map of type 52 file

Type 52 is a "bin5" file; this has an ASCII header followed by a N-dimensional binary array whose dimensions and word-type are defined in the header; for type 52, the number of dimensions is 5 and the type is REAL*4 or REAL*8. The 4th dimension is increased to allow room for a "prefix" to be embedded in the binary array for each case.

The array is written by the `tdisk[8]` routine, which stores values for each season for each case in the large buffer FFF.

Type 52 = (N24 hours, 7 items, N4 latitudes, NDX+seasons, cases)

The 7 items are:

- 1)=TSF Final hourly surface temperature
- 2)=TPF Final hourly planetary temperature
- 3)=TAF Final hourly atmosphere temperature, not predicted
- 4)=DOWNVIS Hourly net downward solar flux [W/m²]
- 5)=DOWNNIR Hourly net downward thermal flux [W/m²]
- 6) packed with:
 - NDJ4 Number of days to compute solution
 - DTM4 RMS temperature change on last day
 - TTA4 Predicted final atmosphere temperature
 - TIN(2:n) Minimum hourly layer temperature, starting with first real layer
 n is the smaller of: N1 (the number KRC computed
 N24-2 (limit of what fits in this file)
- 7) packed with:
 - FROST4 Predicted frost amount, [kg/m²]
 - AFR04 Frost albedo (at the last time step)
 - HEATMM Mean upward heat flow into soil surface on last day, [W/m²]
 This would have contributed to sublime frost-cap if it were present
 - TAX(2:n) Maximum hourly layer temperature. Parallel to TIN

Type 52 allows multiple cases, each with a "prefix" for each case stored in the NDX leading extra seasons. This region contains:

4 integers (converted to Real) that define sizes

- (1)=FLOAT(NWKRC) Number of 4-byte words in KRCCOM, currently 255
- (2)=FLOAT(IDX) 1-based index of the dimension with extra values
- (3)=FLOAT(NDX) Number of those extra
- (4)=FLOAT(NSOUT) Number of output seasons (Not used; could be redefined)

followed by KRCCOM, defined in `krccom.inc` or `krccom8.f`

followed by a sub-array (seasons,5) (0-based index)

- 0]=DJU5 Current Julian date (offset from J2000.0)
- 1]=SUBS Seasonal longitude of Sun, in degrees
- 2]=PZREF Current surface pressure at 0 elevation, [Pascal]
- 3]=TAUD Mean visible opacity of dust, solar wavelengths
 If a climate model is used, value if for the last latitude.
- 4]=SUMF Global average columnar mass of frost [kg /m²] (If computed)

Thus the prefix requires NPREF = [255 or 426]+4 +5*nseas words;
 where nseas is the number of seasons output: NJ5-JDISK+1

Each season contains N24*7*N4 words, the number of leading pseudo-seasons is
 $NDX = \text{Ceil} (NPREF / (N24*7*N4))$

For Type 52, the size of a case is set by the first case. The number of cases allowed is set by this size and printed as MASE at the end of the first case in the print output.

KRC input items that would change any of the bin5 dimensions are not allowed to increase between cases; i.e., N24, N4 and nseas=N5-JDISK. An invalid change of these will be detected in tdisk.f; a note will go to the print file and the error file, the output file will be written with any cases completed up to this point and the file closed. All remaining cases will be computed but not saved.

The number of cases that can be stored is dynamic and fairly liberal; recent versions of KRC reserve 10 M words for the bin5 array. So, for example, with N24=24, 19 latitudes and 50 stored seasons, up to 61 cases can be saved in one run.

In the IDL readkrc52 routine, these are expanded into 5 arrays and a structure. The dimensions here are typical; produced in krcvtest @188

```
TTT          FLOAT      = Array[24, 5, 3, 120, 8]
(hour,item,latitude,season,case)
itemt = Tsurf, Tplan, Tatm, DownVIS, DownIR
```

```
DDD          FLOAT      = Array[21, 2, 3, 120, 8]
(layer,item,latitude,season,case)
itemd = Tmin, Tmax
```

```
GGG          FLOAT      = Array[6, 3, 120, 8]
(item,latitude,season,case)
itemg = NDJ4, DTM4, TTA4, FROST4, AFRO4,, HEATMM
```

```
UUU          FLOAT      = Array[3, 2, 8]
(nlat,item,case)      Values often the same for each case
itemu = Lat., elev
```

```
VVV          FLOAT      = Array[120, 5, 8]
(season,item,case)    First 2 item values often the same for each case
itemv = DJU5, SUBS, PZREF, TAUD, SUMF
```

KRCCOM is in kcom: readkrc52 returns values for the first case
 ** Structure <cdcab8>, 7 tags, length=1020, data length=1020, refs=1:

```
FD          FLOAT      Array[96]
ID          LONG       Array[40]
LD          LONG       Array[20]
TIT         BYTE       Array[80]
DAYTIM      BYTE       Array[20]
ALAT        FLOAT      Array[37]
ELEV        FLOAT      Array[37]
```

For the REAL*8 version, the order is changed
 FD REAL*8 Array[96]

ALAT	REAL*8	Array[37]
ELEV	REAL*8	Array[37]
ID	LONG	Array[40]
LD	LONG	Array[20]
TIT	BYTE	Array[80]
DAYTIM	BYTE	Array[20]

B Time-step doubling

In the JGR article, a convergence safety factor is defined as $B_i/\sqrt{2\Delta t_i \cdot \kappa_i}$; KRC[103]. In the code, the square of this, $B_i^2/(2\Delta t_i \cdot \kappa_i)$ is defined as SCONVG and printed.

Proceeding from the top, if SCONVG is more than twice CONVF for a layer, then the time-step can be doubled for that layer.

Code changed significantly when layer tables added; between

v321: layer thickness BLAY set by FLAY (virtual) and RLAY

and 331: BLAY set by FLAY (top physical) and RLAY

With zone table, at each layer must know the minimum pre-doubling safty factor at all lower layer

For same layer thicknesses, after first time doubling, 321 and 341 converg. factor disagree!

B.1 Version 343

Code includes several loops for setting layer parameters, starting at the indicated line number (2016 sept 5 source code):

Set the thermophysical properties for each layer. Seperate exclusive loops for

156: zone table or not.

278: no zone table

327: Print temperature-dependent properties for up to two zones

369: If not a zone table, check lower material stabilty and increase layer thickness if needed.

379: LOOP 1 compute safety factor for each layer before any doubling SCONVG(J)

387: LOOP 2. Find the minimum safety factor at or below each layer before any time doubling; ZDZ (temporary)

406 LOOP 3 Assign time doubling, from top to depth. In English:

IF: have not yet reach maximum number of time doublings allowed

AND at least 2 physical layers already

AND number of time steps now is even

AND new time-step would be acceptably stable for all lower layers

THEN, do doubling at current layer and update forecast factor.

436: Generate the last-layer versus time comb KJ

480: Print the layer table