

MOUNT CEPH FS IN YOUR FILE SYSTEMS TABLE

If you mount Ceph FS in your file systems table, the Ceph file system will mount automatically on startup.

KERNEL DRIVER

To mount Ceph FS in your file systems table as a kernel driver, add the following to `/etc/fstab`:

```
{ipaddress}:{port}:/ {mount}/{mountpoint} {filesystem-name} [name=username,secret=secretkey]
```

For example:

```
10.10.10.10:6789:/ /mnt/ceph ceph name=admin,secretfile=/etc/ceph/secret.key,noatime
```

Important: The name and secret or secretfile options are mandatory when you have Ceph authentication running.

See [Authentication](#) for details.

FUSE

To mount Ceph FS in your file systems table as a filesystem in user space, add the following to `/etc/fstab`:

#DEVICE	PATH	TYPE	OPTIONS
id={user-ID}[,conf={path/to/conf.conf}]	/mount/path	fuse.ceph	defaults 0 0

For example:

```
id=admin /mnt/ceph fuse.ceph defaults 0 0
id=myuser,conf=/etc/ceph/cluster.conf /mnt/ceph2 fuse.ceph defaults 0 0
```

The DEVICE field is a comma-delimited list of options to pass to the command line. Ensure you use the ID (e.g., admin, not client.admin). You can pass any valid ceph-fuse option to the command line this way.

See [Authentication](#) for details.