

Volume Drivers

1 List out Docker plugins on host

```
$ docker plugin ls
```

2 Install a Docker Plugin

```
$ docker plugin install  
tiborvass/sample-volume-plugin
```

3 List out Docker plugins on host

```
$ docker plugin ls
```

4 Create volume using Volume driver

```
$ docker volume create --driver  
tiborvass/sample-volume-plugin --name  
vol-plug-busybox
```



5 List out volumes

```
$ docker volume ls
```

6 Mount this volume to container

```
$ docker run -itd --name alpha-busybox \  
--mount type=volume,volume-  
driver=tiborvass/sample-volume-  
plugin,source=vol-plug-  
busybox,destination=/tmp \  
busybox
```

7 List containers

```
$ docker ps -a
```

8 Execute shell in container

```
$ docker exec -it alpha-busybox sh  
  
echo "This is busybox" > /tmp/foo.txt  
  
ls /tmp  
  
exit
```

9

Check out volume contents on host

```
$ sudo su -  
  
cd /var/lib/docker  
  
ls  
  
cd plugins  
  
ls  
  
cd <volume_ID>  
  
ls  
  
cd propagated-mount  
  
ls  
  
cd vol-plugin-busybox  
  
ls  
  
cat foo.txt
```

