

**ZebOS-XP BFD SMI Reference**  
IP Infusion Inc.

Generated by Doxygen 1.6.1

Wed Dec 16 12:33:43 2015



# Contents

<b>1</b>	<b>File Index</b>	<b>1</b>
1.1	File List . . . . .	1
<b>2</b>	<b>File Documentation</b>	<b>3</b>
2.1	smi_oam_bfd.h File Reference . . . . .	3
2.1.1	Detailed Description . . . . .	12
2.1.2	Function Documentation . . . . .	12
2.1.2.1	smi_bfd_add_user_session . . . . .	12
2.1.2.2	smi_bfd_api_get_sess_diag_sdkapi . . . . .	13
2.1.2.3	smi_bfd_api_sess_auth_key_id_sdkapi . . . . .	14
2.1.2.4	smi_bfd_api_sess_auth_type_sdkapi . . . . .	14
2.1.2.5	smi_bfd_del_user_session . . . . .	15
2.1.2.6	smi_bfd_echo_interval_set . . . . .	15
2.1.2.7	smi_bfd_echo_interval_unset . . . . .	16
2.1.2.8	smi_bfd_echo_mode_set . . . . .	16
2.1.2.9	smi_bfd_echo_mode_unset . . . . .	16
2.1.2.10	smi_bfd_get_discmap_index_sdkapi . . . . .	17
2.1.2.11	smi_bfd_get_perf_disc_time_sdkapi . . . . .	17
2.1.2.12	smi_bfd_get_perf_lastcomm_lost_diag_sdkapi . . . . .	18
2.1.2.13	smi_bfd_get_perf_lastses_down_time_sdkapi . . . . .	18
2.1.2.14	smi_bfd_get_perf_pkt_in_hc_sdkapi . . . . .	19
2.1.2.15	smi_bfd_get_perf_pkt_in_sdkapi . . . . .	19
2.1.2.16	smi_bfd_get_perf_pkt_out_hc_sdkapi . . . . .	20
2.1.2.17	smi_bfd_get_perf_pkt_out_sdkapi . . . . .	20
2.1.2.18	smi_bfd_get_perf_sess_up_count_sdkapi . . . . .	21
2.1.2.19	smi_bfd_get_sess_addr_type_sdkapi . . . . .	21

2.1.2.20	<a href="#">smi_bfd_get_sess_admin_status_sdkapi</a>	22
2.1.2.21	<a href="#">smi_bfd_get_sess_auth_pres_flag_sdkapi</a>	23
2.1.2.22	<a href="#">smi_bfd_get_sess_cntrlplane_indep_flag_sdkapi</a>	23
2.1.2.23	<a href="#">smi_bfd_get_sess_dest_udp_port_sdkapi</a>	24
2.1.2.24	<a href="#">smi_bfd_get_sess_detectmult_sdkapi</a>	24
2.1.2.25	<a href="#">smi_bfd_get_sess_disc_sdkapi</a>	25
2.1.2.26	<a href="#">smi_bfd_get_sess_dmnd_mode_dsrd_flag_sdkapi</a>	25
2.1.2.27	<a href="#">smi_bfd_get_sess_dsrd_min_tx_intvl_sdkapi</a>	26
2.1.2.28	<a href="#">smi_bfd_get_sess_echo_src_udp_port_sdkapi</a>	26
2.1.2.29	<a href="#">smi_bfd_get_sess_gtsm_sdkapi</a>	27
2.1.2.30	<a href="#">smi_bfd_get_sess_interface_sdkapi</a>	27
2.1.2.31	<a href="#">smi_bfd_get_sess_mh_unlnk_mode_sdkapi</a>	28
2.1.2.32	<a href="#">smi_bfd_get_sess_neg_detect_mult_sdkapi</a>	28
2.1.2.33	<a href="#">smi_bfd_get_sess_neg_echo_intvl_sdkapi</a>	29
2.1.2.34	<a href="#">smi_bfd_get_sess_neg_intvl_sdkapi</a>	29
2.1.2.35	<a href="#">smi_bfd_get_sess_oper_mode_sdkapi</a>	30
2.1.2.36	<a href="#">smi_bfd_get_sess_req_min_echo_rx_intvl_sdkapi</a>	30
2.1.2.37	<a href="#">smi_bfd_get_sess_req_min_rx_intvl_sdkapi</a>	31
2.1.2.38	<a href="#">smi_bfd_get_sess_rmte_disc_sdkapi</a>	31
2.1.2.39	<a href="#">smi_bfd_get_sess_rmte_heard_flag_sdkapi</a>	32
2.1.2.40	<a href="#">smi_bfd_get_sess_row_status_sdkapi</a>	32
2.1.2.41	<a href="#">smi_bfd_get_sess_src_udp_port_sdkapi</a>	33
2.1.2.42	<a href="#">smi_bfd_get_sess_state_sdkapi</a>	33
2.1.2.43	<a href="#">smi_bfd_get_sess_stor_type_sdkapi</a>	34
2.1.2.44	<a href="#">smi_bfd_get_sess_type_sdkapi</a>	34
2.1.2.45	<a href="#">smi_bfd_get_sess_up_time_sdkapi</a>	35
2.1.2.46	<a href="#">smi_bfd_get_sess_version_sdkapi</a>	35
2.1.2.47	<a href="#">smi_bfd_interface_echo_mode_set_sdkapi</a>	36
2.1.2.48	<a href="#">smi_bfd_interface_echo_mode_unset_sdkapi</a>	36
2.1.2.49	<a href="#">smi_bfd_interface_slow_timer_set_sdkapi</a>	37
2.1.2.50	<a href="#">smi_bfd_interface_slow_timer_unset_sdkapi</a>	37
2.1.2.51	<a href="#">smi_bfd_multihop_proto_interval_set_sdkapi</a>	38
2.1.2.52	<a href="#">smi_bfd_multihop_proto_interval_unset_sdkapi</a>	38
2.1.2.53	<a href="#">smi_bfd_notification_set</a>	39

2.1.2.54	<a href="#">smi_bfd_process_set</a> . . . . .	39
2.1.2.55	<a href="#">smi_bfd_proto_auth_set</a> . . . . .	40
2.1.2.56	<a href="#">smi_bfd_proto_auth_unset</a> . . . . .	41
2.1.2.57	<a href="#">smi_bfd_proto_interval_set_sdkapi</a> . . . . .	41
2.1.2.58	<a href="#">smi_bfd_proto_interval_unset_sdkapi</a> . . . . .	42
2.1.2.59	<a href="#">smi_bfd_proto_multihop_auth_ipv4_set_sdkapi</a> . .	42
2.1.2.60	<a href="#">smi_bfd_proto_multihop_auth_unset_ipv4_sdkapi</a> .	43
2.1.2.61	<a href="#">smi_bfd_proto_slow_timer_set</a> . . . . .	44
2.1.2.62	<a href="#">smi_bfd_proto_slow_timer_unset</a> . . . . .	44
2.1.2.63	<a href="#">smi_bfd_sess_gtsm_ttl_sdkapi</a> . . . . .	45
2.1.2.64	<a href="#">smi_bfd_set_sess_addr_type_sdkapi</a> . . . . .	45
2.1.2.65	<a href="#">smi_bfd_set_sess_admin_status_sdkapi</a> . . . . .	46
2.1.2.66	<a href="#">smi_bfd_set_sess_detect_mult_sdkapi</a> . . . . .	46
2.1.2.67	<a href="#">smi_bfd_set_sess_dmnd_mode_dsrd_flag_sdkapi</a> .	47
2.1.2.68	<a href="#">smi_bfd_set_sess_dsrd_min_tx_intvl_sdkapi</a> . . . .	47
2.1.2.69	<a href="#">smi_bfd_set_sess_echo_src_udp_port_sdkapi</a> . . .	48
2.1.2.70	<a href="#">smi_bfd_set_sess_gtsm_sdkapi_sdkapi</a> . . . . .	48
2.1.2.71	<a href="#">smi_bfd_set_sess_gtsm_ttl_sdkapi</a> . . . . .	49
2.1.2.72	<a href="#">smi_bfd_set_sess_interface_sdkapi</a> . . . . .	49
2.1.2.73	<a href="#">smi_bfd_set_sess_req_min_echo_rx_intvl_sdkapi</a> .	50
2.1.2.74	<a href="#">smi_bfd_set_sess_req_min_rx_intvl_sdkapi</a> . . . .	50
2.1.2.75	<a href="#">smi_bfd_set_sess_row_status_sdkapi</a> . . . . .	51
2.1.2.76	<a href="#">smi_bfd_set_sess_src_udp_port_sdkapi</a> . . . . .	51
2.1.2.77	<a href="#">smi_bfd_set_sess_stor_type_sdkapi</a> . . . . .	52
2.1.2.78	<a href="#">smi_bfd_set_sess_version_no_sdkapi</a> . . . . .	52



# Chapter 1

## File Index

### 1.1 File List

Here is a list of all documented files with brief descriptions:

<a href="#">smi_oam_bfd.h</a> (Provides APIs for managing Bidirectional Forwarding De- tection(BFD) in ZebOS ) . . . . .	3
---	---





## Chapter 2

# File Documentation

### 2.1 smi\_oam\_bfd.h File Reference

Provides APIs for managing Bidirectional Forwarding Detection(BFD) in ZebOS.

```
#include "smi_client.h"
#include "smi_oam_bfd_msg.h"
```

#### Functions

- s\_int32\_t [smi\\_bfd\\_notification\\_set](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, u\_int32\_t notif\_flag)

*Sets to enable or disable the notification emission of BFD session on this device. If this object is set to true(1), then it enables the emission of bfdSessUp and bfdSessDown notifications; otherwise these notifications are not emitted.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_version\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*version, bool\_t snmp)

*This function gets the version number of the BFD protocol.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_type\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*session\_type, bool\_t snmp)

*This function is used to get the session type for an SNMP Get request.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_mh\\_unlnk\\_mode\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*mh\_unlnk\_mode, bool\_t snmp)

*This function is used to get the session multihop UNI(Unidirectional) link mode for SNMP Get request.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_disc\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_disc, bool\_t snmp)

*This function is used to get the session discriminator for an SNMP Get request.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_rmte\\_disc\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_rmte\_disc, bool\_t snmp)

*This function is used to get the session discriminator chosen by the remote system for the BFD session.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_dest\\_udp\\_port\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_dest\_udp\_port, bool\_t snmp)

*This function is used to get the destination UDP port number used for the BFD session's control packets.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_src\\_udp\\_port\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_src\_udp\_port, bool\_t snmp)

*This function is used to get the source UDP port number used for the BFD session's control packets.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_echo\\_src\\_udp\\_port\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_echo\_src\_udp\_port, bool\_t snmp)

*This function is used to get the source UDP port number used for BFD session's echo packets.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_admin\\_status\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_admin\_status, bool\_t snmp)

*This function is used to get the session administration status. A transition from 'stop' to 'start' will start the BFD state machine for the session. The state machine will have an initial state of down.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_state\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_state, bool\_t snmp)

*This function is used to get the session state.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_rmte\\_heard\\_flag\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_rmte\_heard\_flag, bool\_t snmp)

*This function is used to get the status of BFD packet reception from the remote system. Specifically, it is set to true if the local system is actively receiving BFD packets from the remote system, and is set to false(2) if the local system has not received BFD packets recently.*

- s\_int32\_t [smi\\_bfd\\_api\\_get\\_sess\\_diag\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_diag, bool\_t snmp)

*This function is used to get the session diagram, a diagnostic code specifying the local system's reason for the last transition of the session from up to some other state.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_oper\\_mode\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_oper\_mode, bool\_t snmp)

*This function is used to get the current operating mode that BFD session is operating in.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_dmnd\\_mode\\_dsrd\\_flag\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_dmnd\_mode\_dsrd\_flag, bool\_t snmp)

*This function is used to get the session demand mode desired flag which indicates that the local system's desire to use Demand mode.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_cntrlplane\\_indep\\_flag\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_cntrlplane\_indep\_flag, bool\_t snmp)

*This function is used to get the session control plane independent flag indicates that the local system's ability to continue to function through a disruption of the control plane.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_interface\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_interface, bool\_t snmp)

*This function is used to get the session interface used to indicate the interface which the BFD session is running on.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_addr\\_type\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_addr\_type, bool\_t snmp)

*This function is used to get the session address type of the BFD session.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_gtsm\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_gtsm, bool\_t snmp)

*This function is used to get the session GTSM(Generalized TTL Security Mechanism) whether is enabled or not.*

- s\_int32\_t [smi\\_bfd\\_sess\\_gtsm\\_ttl\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_gtsm\_ttl, bool\_t snmp)

*This function is used to get the session GTSM(Generalized TTL Security Mechanism) TTL(Time to live) which specifies the minimum allowed TTL for received BFD control packets. GTSM TTL valid only when GTSM is enabled.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_dsrd\\_min\\_tx\\_intvl\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_dsrd\_min\_tx\_intvl, bool\_t snmp)

*This function is used to get the session desired minimum transmission interval, which is the minimum interval, in microseconds, that the local system would like to use when transmitting BFD Control packets.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_req\\_min\\_rx\\_intvl\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_req\_min\_rx\_intvl, bool\_t snmp)

*This function is used to get the session required minimum receive interval, which specifies the minimum interval, in microseconds, between received BFD Control packets the system is capable of supporting.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_req\\_min\\_echo\\_rx\\_intvl\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_req\_min\_echo\_rx\_intvl, bool\_t snmp)

*This function is used to get the session required minimum echo receive interval, which specifies the minimum interval, in microseconds, between received BFD Echo packets system is capable of supporting.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_detectmult\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_detectmult, bool\_t snmp)

*This function is used to get the session detect time multiplier.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_neg\\_intvl\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_neg\_intvl, bool\_t snmp)

*This function is used to get the session negotiated interval in microseconds, that the local system is transmitting BFD Control packets.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_neg\\_echo\\_intvl\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_neg\_echo\_intvl, bool\_t snmp)

*This function is used to get the session negotiated echo interval in microseconds, that the local system is transmitting BFD echo packets.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_neg\\_detect\\_mult\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_neg\_detect\_mult, bool\_t snmp)

*This function is used to get the session negotiated detect multiplier.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_auth\\_pres\\_flag\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_auth\_pres\_flag, bool\_t snmp)

*This function is used to get the session authentication preserve flag which indicates that the local system's desire to use Authentication.*

- s\_int32\_t [smi\\_bfd\\_api\\_sess\\_auth\\_type\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_auth\_type, bool\_t snmp)

*This function is used to get the session authentication type.*

- s\_int32\_t [smi\\_bfd\\_api\\_sess\\_auth\\_key\\_id\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_auth\_key\_id, bool\_t snmp)

*This function is used to get the session authentication key ID. It permits multiple keys to be active simultaneously.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_stor\\_type\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_stor\_type, bool\_t snmp)

*This function is used to get the session storage type.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_row\\_status\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_row\_status, bool\_t snmp)

*This function is used to get the session row status.*

- s\_int32\_t [smi\\_bfd\\_get\\_perf\\_pkt\\_in\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*perf\_pkt\_in, bool\_t snmp)

*This function is used to get total number of BFD control messages received for the BFD session.*

- s\_int32\_t [smi\\_bfd\\_get\\_perf\\_pkt\\_out\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*perf\_pkt\_out, bool\_t snmp)

*This function is used to get total number of BFD control messages sent for the BFD session.*

- s\_int32\_t [smi\\_bfd\\_get\\_sess\\_up\\_time\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_up\_time, bool\_t snmp)

*This function is used to get value of sysUpTime on the most recent occasion at which the session came up.*

- s\_int32\_t [smi\\_bfd\\_get\\_perf\\_lastses\\_down\\_time\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*perf\_lastses\_down\_time, bool\_t snmp)

*This function is used to get value of sysUpTime on the most recent occasion at which the last time communication was lost with the neighbor.*

- s\_int32\_t [smi\\_bfd\\_get\\_perf\\_lastcomm\\_lost\\_diag\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*perf\_lastcomm\_lost\_diag, bool\_t snmp)

*This function is used to get the BFD diag code for the last time communication was lost with the neighbor.*

- s\_int32\_t [smi\\_bfd\\_get\\_perf\\_sess\\_up\\_count\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*perf\_sess\_up\_count, bool\_t snmp)

*This function is used to get number of times the session has gone into the Up state since the system last rebooted.*

- s\_int32\_t [smi\\_bfd\\_get\\_perf\\_disc\\_time\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*perf\_disc\_time, bool\_t snmp)

*This function is used to get value of sysUpTime on the most recent occasion which any one or more of the session counters suffered a discontinuity.*

- s\_int32\_t [smi\\_bfd\\_get\\_perf\\_pkt\\_in\\_hc\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, ut\_int64\_t \*perf\_pkt\_in\_hc, bool\_t snmp)

*This function is used to get value represents the total number of BFD control messages received with respect to high capacity for the BFD session.*

- s\_int32\_t [smi\\_bfd\\_get\\_perf\\_pkt\\_out\\_hc\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, ut\_int64\_t \*perf\_pkt\_out\_hc, bool\_t snmp)

*This function is used to get value represents the total number of BFD control messages sent with respect to high capacity for the BFD session.*

- s\_int32\_t [smi\\_bfd\\_get\\_discmap\\_index\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*discmap\_index, bool\_t snmp)

*This function is used to get the BfdSessIndexTC value referred to by the indices of the Discriminator Mapping entry.*

- s\_int32\_t [smi\\_bfd\\_set\\_sess\\_version\\_no\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_version\_no, bool\_t snmp)

*This function is used to set the version number of the BFD protocol.*

- s\_int32\_t [smi\\_bfd\\_set\\_sess\\_src\\_udp\\_port\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_src\_udp\_port, bool\_t snmp)

*This function is used to set the source UDP port number used for the BFD session's control packets.*

- s\_int32\_t [smi\\_bfd\\_set\\_sess\\_echo\\_src\\_udp\\_port\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_echo\_src\_udp\_port, bool\_t snmp)

*This function is used to set the source UDP port number used for BFD session's echo packets.*

- `s_int32_t smi_bfd_set_sess_admin_status_sdkapi` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t set\_sess\_admin\_status, bool\_t snmp)

*This function is used to set the session administration status.*

- `s_int32_t smi_bfd_set_sess_dmnd_mode_dsrd_flag_sdkapi` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_dmnd\_mode\_dsrd\_flag, bool\_t snmp)

*This function is used to set the session demand mode desired flag which indicates that the local system's desire to use Demand mode.*

- `s_int32_t smi_bfd_set_sess_interface_sdkapi` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_interface, bool\_t snmp)

*This function is used to get the session interface used to indicate the interface which the BFD session is running on.*

- `s_int32_t smi_bfd_set_sess_addr_type_sdkapi` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_addr\_type, bool\_t snmp)

*This function is used to get the session address type of the BFD session.*

- `s_int32_t smi_bfd_set_sess_gtsm_sdkapi_sdkapi` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_gtsm, bool\_t snmp)

*This function is used to set the session GTSM(Generalized TTL Security Mechanism) enable/disable mode.*

- `s_int32_t smi_bfd_set_sess_gtsm_ttl_sdkapi` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_gtsm\_ttl, bool\_t snmp)

*This function is used to set the session GTSM(Generalized TTL Security Mechanism) TTL(Time to live) which specifies the minimum allowed TTL for received BFD control packets.*

- `s_int32_t smi_bfd_set_sess_dsrd_min_tx_intvl_sdkapi` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_dsrd\_min\_tx\_intvl, bool\_t snmp)

*This function is used to set the session desired minimum transmission interval.*

- `s_int32_t smi_bfd_set_sess_req_min_rx_intvl_sdkapi` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_req\_min\_rx\_intvl, bool\_t snmp)

*This function is used to set the session required minimum receive interval, which specifies the minimum interval in microseconds. between received BFD Echo packets system is capable of supporting.*

- s\_int32\_t [smi\\_bfd\\_set\\_sess\\_req\\_min\\_echo\\_rx\\_intvl\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_req\_min\_echo\_rx\_intvl, bool\_t snmp)

*This function is used to set the session required minimum echo receive interval, which specifies the minimum interval, in microseconds, between received BFD Echo packets system is capable of supporting.*

- s\_int32\_t [smi\\_bfd\\_set\\_sess\\_detect\\_mult\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t set\_sess\_detect\_mult, bool\_t snmp)

*This function is used to set the session detect time multiplier.*

- s\_int32\_t [smi\\_bfd\\_set\\_sess\\_stor\\_type\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_stor\_type, bool\_t snmp)

*This function is used to set the session storage type.*

- s\_int32\_t [smi\\_bfd\\_set\\_sess\\_row\\_status\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t sess\_row\_status, bool\_t snmp)

*This function is used to get the session row status.*

- s\_int32\_t [smi\\_bfd\\_process\\_set](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, int proc\_id)

*Creates a new Bidirectional Forward Detection (BFD) process instance, if not before created, else returns the existing one.*

- s\_int32\_t [smi\\_bfd\\_proto\\_interval\\_set\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*ifname, u\_int32\_t min\_tx, u\_int32\_t min\_rx, u\_int32\_t multiplier)

*Sets different time intervals of singlehop BFD in microseconds.*

- s\_int32\_t [smi\\_bfd\\_proto\\_interval\\_unset\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*ifname)

*Unsets different time intervals of BFD.*

- s\_int32\_t [smi\\_bfd\\_multihop\\_proto\\_interval\\_set\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*ifname, struct pal\_in4\_addr ip\_addr, u\_int32\_t min\_tx, u\_int32\_t min\_rx, u\_int32\_t multiplier)

*Sets different time intervals of multihop BFD in microseconds.*

- s\_int32\_t [smi\\_bfd\\_multihop\\_proto\\_interval\\_unset\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*ifname, struct pal\_in4\_addr ipv4)

*Unsets different time intervals of multihop BFD in microseconds.*

- s\_int32\_t [smi\\_bfd\\_echo\\_mode\\_set](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id)



*Sets this BFD session to run in Echo mode at switch level.*

- s\_int32\_t [smi\\_bfd\\_echo\\_mode\\_unset](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id)

*Unsets this BFD session to run in Echo mode at switch level.*

- s\_int32\_t [smi\\_bfd\\_proto\\_slow\\_timer\\_set](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t slow\_interval)

*Sets this BFD session's slow time interval in microseconds at switch level.*

- s\_int32\_t [smi\\_bfd\\_proto\\_slow\\_timer\\_unset](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id)

*Unsets this BFD session's slow time interval in microseconds at switch level.*

- s\_int32\_t [smi\\_bfd\\_interface\\_echo\\_mode\\_set\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*ifname)

*Sets this BFD session to run in Echo mode at interface level.*

- s\_int32\_t [smi\\_bfd\\_interface\\_echo\\_mode\\_unset\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*ifname)

*Unsets this BFD session to run in Echo mode at interface level.*

- s\_int32\_t [smi\\_bfd\\_interface\\_slow\\_timer\\_set\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*ifname, u\_int32\_t slow\_interval)

*Sets this BFD session's slow time interval in microseconds at interface level.*

- s\_int32\_t [smi\\_bfd\\_interface\\_slow\\_timer\\_unset\\_sdkapi](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*ifname)

*Unsets this BFD session's slow time interval in microseconds at interface level.*

- s\_int32\_t [smi\\_bfd\\_add\\_user\\_session](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, struct pal\_in4\_addr \*src\_addr, struct pal\_in4\_addr \*dst\_addr, s\_int32\_t ifindex, u\_int32\_t flags)

*This function adds an IPv4 BFD user session.*

- s\_int32\_t [smi\\_bfd\\_del\\_user\\_session](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, struct pal\_in4\_addr \*src\_addr, struct pal\_in4\_addr \*dst\_addr, s\_int32\_t ifindex, u\_int32\_t flags)

*This function deletes an IPv4 BFD user session.*

- s\_int32\_t [smi\\_bfd\\_echo\\_interval\\_set](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*name, u\_int32\_t echo\_tx)

*This function sets the BFD echo mode transmission interval for all single-hop sessions on an interface.*

- s\_int32\_t [smi\\_bfd\\_echo\\_interval\\_unset](#) (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*name)

*This function resets the BFD echo mode transmission interval to its default value for all sessions on an interface.*

- `s_int32_t smi_bfd_proto_auth_set` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, char \*ifname, char \*auth\_type\_str, u\_int32\_t key\_id, char \*key\_str, char \*key\_chain)

*This function adds an IPv6 BFD user session.*

- `s_int32_t smi_bfd_proto_auth_unset` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t ifindex)

*This function unsets the authentication information on an interface having sessions.*

- `s_int32_t smi_bfd_proto_multihop_auth_ipv4_set_sdkapi` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t ifindex, struct pal\_in4\_addr \*ipv4\_addr, char \*auth\_type\_str, u\_int32\_t key\_id, char \*key\_str, char \*key\_chain)

*This function sets the authentication information for a multihop session.*

- `s_int32_t smi_bfd_proto_multihop_auth_unset_ipv4_sdkapi` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, s\_int32\_t ifindex, struct pal\_in4\_addr \*ipv4\_addr)

*This function unsets the authentication information from a multihop session.*

## 2.1.1 Detailed Description

Provides APIs for managing Bidirectional Forwarding Detection(BFD) in ZebOS. The ZebOS Bidirectional Forwarding Detection (BFD) module is designed to work with most router architectures wherever hardware supports some level of Bidirectional Forwarding Detection capabilities, and in situations where there is no hardware support at all. The BFD module is designed to work in conjunction with application protocol modules (for example, OSPF, BGP, RIP) to enable them to configure BFD sessions and for the sessions to get the bidirectional forwarding failure notifications from BFD. The way each application reacts to a session-down event is application-specific.

## 2.1.2 Function Documentation

- ### 2.1.2.1 `s_int32_t smi_bfd_add_user_session` (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, struct pal\_in4\_addr \*src\_addr, struct pal\_in4\_addr \*dst\_addr, s\_int32\_t ifindex, u\_int32\_t flags)

This function adds an IPv4 BFD user session. `smi_bfd_add_user_session`

#### Parameters:

- ← `azg` Pointer to the SMI client global structure
- ← `vr_id` Virtual router ID. Default is 0, Pass 0 for a non-VR implementation

- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *src\_addr* Source address for the session
- ← *dst\_addr* Destination address for the session
- ← *ifindex* Interface index
- ← *flags* Define the properties of a session
  - BFD\_MSG\_SESSION\_FLAG\_MH(Multi-Hop)
  - BFD\_MSG\_SESSION\_FLAG\_DC(Demand Circuit)
  - BFD\_MSG\_SESSION\_FLAG\_PS(Persistent Session)
  - BFD\_MSG\_SESSION\_FLAG\_AD(User Admin Down)

**Returns:**

BFD\_SUCCESS on success, otherwise one of the following errors BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_INVALID\_ADDR  
 BFD\_FAILURE

### 2.1.2.2 s\_int32\_t smi\_bfd\_api\_get\_sess\_diag\_sdkapi (struct smiclient\_globals \* azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \* sess\_diag, bool\_t snmp)

This function is used to get the session diagram, a diagnostic code specifying the local system's reason for the last transition of the session from up to some other state. smi\_bfd\_api\_get\_sess\_diag\_sdkapi

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_diag* The session diagram (diagnostic code) numeric <0-10>
  - 0 - bfd\_diag\_no\_diag, 1 - bfd\_diag\_ctrl\_detect\_exp,
  - 2 - bfd\_diag\_echo\_failed, 3 - bfd\_diag\_nbr\_session\_down,
  - 4 - bfd\_diag\_fwd\_reset, 5 - bfd\_diag\_path\_down,
  - 6 - bfd\_diag\_concat\_path\_down, 7 - bfd\_diag\_admin\_down,
  - 8 - bfd\_diag\_rev\_concat\_path\_down, 9 - bfd\_diag\_config\_error,
  - 10 - bfd\_diag\_not\_forwarding
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.3 `s_int32_t smi_bfd_api_sess_auth_key_id_sdkapi` (struct `smiclient_globals * azg`, `u_int32_t vr_id`, `s_int32_t proc_id`, `u_int32_t index`, `u_int32_t * sess_auth_key_id`, `bool_t snmp`)

This function is used to get the session authentication key ID. It permits multiple keys to be active simultaneously. `smi_bfd_api_sess_auth_key_id_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_auth\_key\_id* Session authentication type
  - 1 - BFD\_AUTH\_KEY\_ID
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.4 `s_int32_t smi_bfd_api_sess_auth_type_sdkapi` (struct `smiclient_globals * azg`, `u_int32_t vr_id`, `s_int32_t proc_id`, `u_int32_t index`, `u_int32_t * sess_auth_type`, `bool_t snmp`)

This function is used to get the session authentication type. `smi_bfd_api_sess_auth_type_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_auth\_type* Session authentication type
  - 0 - BFD\_AUTH\_TYPE\_RESERVED
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.5 s\_int32\_t smi\_bfd\_del\_user\_session (struct smiclient\_globals \* *azg*, u\_int32\_t *vr\_id*, s\_int32\_t *proc\_id*, struct pal\_in4\_addr \* *src\_addr*, struct pal\_in4\_addr \* *dst\_addr*, s\_int32\_t *ifindex*, u\_int32\_t *flags*)

This function deletes an IPv4 BFD user session. smi\_bfd\_del\_user\_session

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *src\_addr* Source address for the session
- ← *dst\_addr* Destination address for the session
- ← *ifindex* Interface index
- ← *flags* Define the properties of a session
  - BFD\_MSG\_SESSION\_FLAG\_MH(Multi-Hop)
  - BFD\_MSG\_SESSION\_FLAG\_DC(Demand Circuit)
  - BFD\_MSG\_SESSION\_FLAG\_PS(Persistent Session)
  - BFD\_MSG\_SESSION\_FLAG\_AD(User Admin Down)

#### Returns:

BFD\_SUCCESS on success, otherwise one of the following errors BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_INVALID\_ADDR  
 BFD\_FAILURE

### 2.1.2.6 s\_int32\_t smi\_bfd\_echo\_interval\_set (struct smiclient\_globals \* *azg*, u\_int32\_t *vr\_id*, s\_int32\_t *proc\_id*, char \* *name*, u\_int32\_t *echo\_tx*)

This function sets the BFD echo mode transmission interval for all single-hop sessions on an interface. smi\_bfd\_echo\_interval\_set

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *name* Interface name
- ← *echo\_tx* Echo transmission interval

#### Returns:

BFD\_SUCCESS on success, otherwise one of the following errors BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_INVALID\_ADDR  
 BFD\_FAILURE

### 2.1.2.7 `s_int32_t smi_bfd_echo_interval_unset (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, char * name)`

This function resets the BFD echo mode transmission interval to its default value for all sessions on an interface. `smi_bfd_echo_interval_unset`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *name* Interface name

#### Returns:

BFD\_SUCCESS on success, otherwise one of the following errors BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
BFD\_API\_INSTANCE\_NOT\_FOUND  
BFD\_API\_INVALID\_ADDR  
BFD\_FAILURE

### 2.1.2.8 `s_int32_t smi_bfd_echo_mode_set (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id)`

Sets this BFD session to run in Echo mode at switch level. `smi_bfd_echo_mode_set`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>

#### Returns:

0 on success, otherwise one of the following error codes  
BFD\_API\_INSTANCE\_NOT\_FOUND  
BFD\_API\_SET\_ERROR

### 2.1.2.9 `s_int32_t smi_bfd_echo_mode_unset (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id)`

Unsets this BFD session to run in Echo mode at switch level. `smi_bfd_echo_mode_unset`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation

← *proc\_id* Process ID for the BFD instance numeric <0-65535>

#### Returns:

0 on success, otherwise one of the following error codes  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_SET\_ERROR

#### 2.1.2.10 s\_int32\_t smi\_bfd\_get\_discmap\_index\_sdkapi (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*discmap\_index, bool\_t snmp)

This function is used to get the BfdSessIndexTC value referred to by the indices of the Discriminator Mapping entry. smi\_bfd\_get\_discmap\_index\_sdkapi

#### Parameters:

← *azg* Pointer to the SMI client global structure  
 ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation  
 ← *proc\_id* Process ID for the BFD instance numeric <0-65535>  
 ← *index* BFD session index value  
 → *discmap\_index* BfdSessIndexTC value  
 ← *snmp* SNMP Enable/Disable numeric (0 | 1)  
     0 - PAL\_FALSE (SNMP disabled)  
     1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

#### 2.1.2.11 s\_int32\_t smi\_bfd\_get\_perf\_disc\_time\_sdkapi (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*perf\_disc\_time, bool\_t snmp)

This function is used to get value of sysUpTime on the most recent occasion which any one or more of the session counters suffered a discontinuity. smi\_bfd\_get\_perf\_disc\_time\_sdkapi

#### Parameters:

← *azg* Pointer to the SMI client global structure  
 ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation  
 ← *proc\_id* Process ID for the BFD instance numeric <0-65535>  
 ← *index* BFD session index value  
 → *perf\_disc\_time* Value of sysUpTime when one or more of the session counters suffered a discontinuity

- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
- 0 - PAL\_FALSE (SNMP disabled)
- 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

#### 2.1.2.12 `s_int32_t smi_bfd_get_perf_lastcomm_lost_diag_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * perf_lastcomm_lost_diag, bool_t snmp)`

This function is used to get the BFD diag code for the last time communication was lost with the neighbor. `smi_bfd_get_perf_lastcomm_lost_diag_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *perf\_lastcomm\_lost\_diag* The session diagram (diagnostic code) numeric <0-10>
  - 0 - bfd\_diag\_no\_diag, 1 - bfd\_diag\_ctrl\_detect\_exp,
  - 2 - bfd\_diag\_echo\_failed, 3 - bfd\_diag\_nbr\_session\_down,
  - 4 - bfd\_diag\_fwd\_reset, 5 - bfd\_diag\_path\_down,
  - 6 - bfd\_diag\_concat\_path\_down, 7 - bfd\_diag\_admin\_down,
  - 8 - bfd\_diag\_rev\_concat\_path\_down, 9 - bfd\_diag\_config\_error,
  - 10 - bfd\_diag\_not\_forwarding
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
- 0 - PAL\_FALSE (SNMP disabled)
- 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

#### 2.1.2.13 `s_int32_t smi_bfd_get_perf_lastses_down_time_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * perf_lastses_down_time, bool_t snmp)`

This function is used to get value of sysUpTime on the most recent occasion at which the last time communication was lost with the neighbor. `smi_bfd_get_perf_lastses_down_time_sdkapi`



**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *perf\_lastses\_down\_time* Value of sysUpTime at which the last time communication was lost with neighbor
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

#### 2.1.2.14 s\_int32\_t smi\_bfd\_get\_perf\_pkt\_in\_hc\_sdkapi (struct smiclient\_globals \* azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, ut\_int64\_t \* perf\_pkt\_in\_hc, bool\_t snmp)

This function is used to get value represents the total number of BFD control messages received with respect to high capacity for the BFD session. smi\_bfd\_get\_perf\_pkt\_in\_hc\_sdkapi

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *perf\_pkt\_in\_hc* Total number of BFD control messages received
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

#### 2.1.2.15 s\_int32\_t smi\_bfd\_get\_perf\_pkt\_in\_sdkapi (struct smiclient\_globals \* azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \* perf\_pkt\_in, bool\_t snmp)

This function is used to get total number of BFD control messages received for the BFD session. smi\_bfd\_get\_perf\_pkt\_in\_sdkapi

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *perf\_pkt\_in* Number of packets received
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

#### 2.1.2.16 s\_int32\_t smi\_bfd\_get\_perf\_pkt\_out\_hc\_sdkapi (struct smiclient\_globals \* azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, ut\_int64\_t \* perf\_pkt\_out\_hc, bool\_t snmp)

This function is used to get value represents the total number of BFD control messages sent with respect to high capacity for the BFD session. smi\_bfd\_get\_perf\_pkt\_out\_hc\_sdkapi

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *perf\_pkt\_out\_hc* Total number of BFD control messages sent
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

#### 2.1.2.17 s\_int32\_t smi\_bfd\_get\_perf\_pkt\_out\_sdkapi (struct smiclient\_globals \* azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \* perf\_pkt\_out, bool\_t snmp)

This function is used to get total number of BFD control messages sent for the BFD session. smi\_bfd\_get\_perf\_pkt\_out\_sdkapi

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *perf\_pkt\_out* Number of packets sent
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

#### 2.1.2.18 s\_int32\_t smi\_bfd\_get\_perf\_sess\_up\_count\_sdkapi (struct smiclient\_globals \* azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \* perf\_sess\_up\_count, bool\_t snmp)

This function is used to get number of times the session has gone into the Up state since the system last rebooted. smi\_bfd\_get\_perf\_sess\_up\_count\_sdkapi

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)
- *perf\_sess\_up\_count* Number of times the session has gone into the Up state

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

#### 2.1.2.19 s\_int32\_t smi\_bfd\_get\_sess\_addr\_type\_sdkapi (struct smiclient\_globals \* azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \* sess\_addr\_type, bool\_t snmp)

This function is used to get the session address type of the BFD session. smi\_bfd\_get\_sess\_addr\_type\_sdkapi

**Parameters:**

- ← *azg* Pointer to the SMI client global structure

- ← ***vr\_id*** Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← ***proc\_id*** Process ID for the BFD instance numeric <0-65535>
- ← ***index*** BFD session index value
- ***sess\_addr\_type*** Session address type numeric <0-4>
  - 0 - ADDR\_TYPE\_unknown
  - 1 - ADDR\_TYPE\_ipv4
  - 2 - ADDR\_TYPE\_ipv6
  - 3 - ADDR\_TYPE\_ipv4z
  - 4 - ADDR\_TYPE\_ipv6z
- ← ***snmp*** SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

#### 2.1.2.20 s\_int32\_t smi\_bfd\_get\_sess\_admin\_status\_sdkapi (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \*sess\_admin\_status, bool\_t snmp)

This function is used to get the session administration status.A transition from 'stop' to 'start' will start the BFD state machine for the session. The state machine will have an initial state of down. smi\_bfd\_get\_sess\_admin\_status\_sdkapi

**Parameters:**

- ← ***azg*** Pointer to the SMI client global structure
- ← ***vr\_id*** Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← ***proc\_id*** Process ID for the BFD instance numeric <0-65535>
- ← ***index*** BFD session index value
- ***sess\_admin\_status*** Session administration status
- ← ***snmp*** SNMP Enable/Disable numeric <0 | 1>
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.21 s\_int32\_t smi\_bfd\_get\_sess\_auth\_pres\_flag\_sdkapi (struct smiclient\_globals \* azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \* sess\_auth\_pres\_flag, bool\_t snmp)

This function is used to get the session authentication preserve flag which indicates that the local system's desire to use Authentication. smi\_bfd\_get\_sess\_auth\_pres\_flag\_sdkapi

#### Parameters:

- ← **azg** Pointer to the SMI client global structure
- ← **vr\_id** Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← **proc\_id** Process ID for the BFD instance numeric <0-65535>
- ← **index** BFD session index value
- **sess\_auth\_pres\_flag** Session authentication preserve flag value numeric (1 | 2)
  - 1 - BFD\_API\_TRUE (If BFD session must be authenticated)
  - 2 - BFD\_API\_FALSE (If BFD session doesnot need to be authenticated)
- ← **snmp** SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.22 s\_int32\_t smi\_bfd\_get\_sess\_cntrlplane\_indep\_flag\_sdkapi (struct smiclient\_globals \* azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, u\_int32\_t index, u\_int32\_t \* sess\_cntrlplane\_indep\_flag, bool\_t snmp)

This function is used to get the session control plane independent flag indicates that the local system's ability to continue to function through a disruption of the control plane. smi\_bfd\_get\_sess\_cntrlplane\_indep\_flag\_sdkapi

#### Parameters:

- ← **azg** Pointer to the SMI client global structure
- ← **vr\_id** Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← **proc\_id** Process ID for the BFD instance numeric <0-65535>
- ← **index** BFD session index value
- **sess\_cntrlplane\_indep\_flag** Control plane independent flag of the session numeric (0 | 1)
  - 0 - PAL\_FALSE
  - 1 - PAL\_TRUE
- ← **snmp** SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.23** `s_int32_t smi_bfd_get_sess_dest_udp_port_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_dest_udp_port, bool_t snmp)`

This function is used to get the destination UDP port number used for the BFD session's control packets. `smi_bfd_get_sess_dest_udp_port_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_dest\_udp\_port* Destination UDP port number of the session
- ← *snmp* SNMP Enable/Disable numeric <0 | 1>
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.24** `s_int32_t smi_bfd_get_sess_detectmult_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_detectmult, bool_t snmp)`

This function is used to get the session detect time multiplier. `smi_bfd_get_sess_detectmult_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_detectmult* The detect multiple value of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.25** `s_int32_t smi_bfd_get_sess_disc_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_disc, bool_t snmp)`

This function is used to get the session discriminator for an SNMP Get request. `smi_bfd_get_sess_disc_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_disc* Local session Discriminator
- ← *snmp* SNMP Enable/Disable numeric <0 | 1>  
0 - PAL\_FALSE (SNMP disabled) 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.26** `s_int32_t smi_bfd_get_sess_dmnd_mode_dsrd_flag_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_dmnd_mode_dsrd_flag, bool_t snmp)`

This function is used to get the session demand mode desired flag which indicates that the local system's desire to use Demand mode. `smi_bfd_get_sess_dmnd_mode_dsrd_flag_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_dmnd\_mode\_dsrd\_flag* Demand mode desired flag of the session (1 | 2)  
1 - BFD\_API\_TRUE  
2 - BFD\_API\_FALSE
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)  
0 - PAL\_FALSE (SNMP disabled)  
1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.27 `s_int32_t smi_bfd_get_sess_dsrd_min_tx_intvl_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_dsrd_min_tx_intvl, bool_t snmp)`

This function is used to get the session desired minimum transmission interval, which is the minimum interval, in microseconds, that the local system would like to use when transmitting BFD Control packets. `smi_bfd_get_sess_dsrd_min_tx_intvl_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_dsrd\_min\_tx\_intvl* Minimum transmission interval value of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.28 `s_int32_t smi_bfd_get_sess_echo_src_udp_port_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_echo_src_udp_port, bool_t snmp)`

This function is used to get the source UDP port number used for BFD session's echo packets. `smi_bfd_get_sess_echo_src_udp_port_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_echo\_src\_udp\_port* Echo source UDP port number of the session
- ← *snmp* SNMP Enable/Disable numeric <0 | 1>
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails



**2.1.2.29** `s_int32_t smi_bfd_get_sess_gtsm_sdkapi (struct smiclient_globals *  
azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t *  
sess_gtsm, bool_t snmp)`

This function is used to get the session GTSM(Generalized TTL Security Mechanism) whether is enabled or not. smi\_bfd\_get\_sess\_gtsm\_sdkapi

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_gtsm* GTSM status numeric (0 | 1)  
0 - PAL\_FALSE (GTSM disabled) 1 - PAL\_TRUE (GTSM enabled)
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)  
0 - PAL\_FALSE (SNMP disabled)  
1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.30** `s_int32_t smi_bfd_get_sess_interface_sdkapi (struct smiclient_globals  
*azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t *  
sess_interface, bool_t snmp)`

This function is used to get the session interface used to indicate the interface which the BFD session is running on. smi\_bfd\_get\_sess\_interface\_sdkapi

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_interface* Session interface
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)  
0 - PAL\_FALSE (SNMP disabled)  
1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.31 `s_int32_t smi_bfd_get_sess_mh_unlnk_mode_sdkapi` (struct `smiclient_globals * azg`, `u_int32_t vr_id`, `s_int32_t proc_id`, `u_int32_t index`, `u_int32_t * mh_unlnk_mode`, `bool_t snmp`)

This function is used to get the session multihop UNI(Unidirectional) link mode for SNMP Get request. `smi_bfd_get_sess_mh_unlnk_mode_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *mh\_unlnk\_mode* Multihop UNI link mode of the session numeric <1-3>
  - 1 - BFD\_MH\_UNLINK\_MODE\_NONE
  - 2 - BFD\_MH\_UNLINK\_MODE\_ACTIVE
  - 3 - BFD\_MH\_UNLINK\_MODE\_PASSIVE
- ← *snmp* SNMP Enable/Disable numeric <0 | 1>
  - 0 - PAL\_FALSE (SNMP disabled) 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.32 `s_int32_t smi_bfd_get_sess_neg_detect_mult_sdkapi` (struct `smiclient_globals * azg`, `u_int32_t vr_id`, `s_int32_t proc_id`, `u_int32_t index`, `u_int32_t * sess_neg_detect_mult`, `bool_t snmp`)

This function is used to get the session negotiated detect multiplier. `smi_bfd_get_sess_neg_detect_mult_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_neg\_detect\_mult* Negotiated detect multiple value
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.33 s\_int32\_t smi\_bfd\_get\_sess\_neg\_echo\_intvl\_sdkapi (struct smiclient\_globals \* *azg*, u\_int32\_t *vr\_id*, s\_int32\_t *proc\_id*, u\_int32\_t *index*, u\_int32\_t \* *sess\_neg\_echo\_intvl*, bool\_t *snmp*)

This function is used to get the session negotiated echo interval in microseconds, that the local system is transmitting BFD echo packets. smi\_bfd\_get\_sess\_neg\_echo\_intvl\_sdkapi

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_neg\_echo\_intvl* Negotiated echo interval of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.34 s\_int32\_t smi\_bfd\_get\_sess\_neg\_intvl\_sdkapi (struct smiclient\_globals \* *azg*, u\_int32\_t *vr\_id*, s\_int32\_t *proc\_id*, u\_int32\_t *index*, u\_int32\_t \* *sess\_neg\_intvl*, bool\_t *snmp*)

This function is used to get the session negotiated interval in microseconds, that the local system is transmitting BFD Control packets. smi\_bfd\_get\_sess\_neg\_intvl\_sdkapi

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_neg\_intvl* Negotiated interval of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.35 `s_int32_t smi_bfd_get_sess_oper_mode_sdkapi` (struct `smiclient_globals * azg`, `u_int32_t vr_id`, `s_int32_t proc_id`, `u_int32_t index`, `u_int32_t * sess_oper_mode`, `bool_t snmp`)

This function is used to get the current operating mode that BFD session is operating in. `smi_bfd_get_sess_oper_mode_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_oper\_mode* Operational mode of the session numeric <1-4>
  - 1 - BFD\_ASYN\_ECHO\_MODE
  - 2 - BFD\_ASYN\_WO\_ECHO\_MODE
  - 3 - BFD\_DMND\_ECHO\_MODE
  - 4 - BFD\_DMND\_WO\_ECHO\_MODE
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.36 `s_int32_t smi_bfd_get_sess_req_min_echo_rx_intvl_sdkapi` (struct `smiclient_globals * azg`, `u_int32_t vr_id`, `s_int32_t proc_id`, `u_int32_t index`, `u_int32_t * sess_req_min_echo_rx_intvl`, `bool_t snmp`)

This function is used to get the session required minimum echo receive interval, which specifies the minimum interval, in microseconds, between received BFD Echo packets system is capable of supporting. `smi_bfd_get_sess_req_min_echo_rx_intvl_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_req\_min\_echo\_rx\_intvl* Required minimum echo receive interval of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.37** `s_int32_t smi_bfd_get_sess_req_min_rx_intvl_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_req_min_rx_intvl, bool_t snmp)`

This function is used to get the session required minimum receive interval, which specifies the minimum interval, in microseconds, between received BFD Control packets the system is capable of supporting. `smi_bfd_get_sess_req_min_rx_intvl_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_req\_min\_rx\_intvl* Required minimum receive interval of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.38** `s_int32_t smi_bfd_get_sess_rmte_disc_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_rmte_disc, bool_t snmp)`

This function is used to get the session discriminator chosen by the remote system for the BFD session. `smi_bfd_get_sess_rmte_disc_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_rmte\_disc* Session remote discriminator
- ← *snmp* SNMP Enable/Disable numeric <0 | 1>
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.39 `s_int32_t smi_bfd_get_sess_rmte_heard_flag_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_rmte_heard_flag, bool_t snmp)`

This function is used to get the status of BFD packet reception from the remote system. Specifically, it is set to true if the local system is actively receiving BFD packets from the remote system, and is set to false(2) if the local system has not received BFD packets recently. `smi_bfd_get_sess_rmte_heard_flag_sdkapi`

#### Parameters:

- ← **azg** Pointer to the SMI client global structure
- ← **vr\_id** Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← **proc\_id** Process ID for the BFD instance numeric <0-65535>
- ← **index** BFD session index value
- **sess\_rmte\_heard\_flag** Remote heard flag of the session numeric (1 | 2)  
1 - BFD\_API\_TRUE 2 - BFD\_API\_FALSE
- ← **snmp** SNMP Enable/Disable numeric (0 | 1)  
0 - PAL\_FALSE (SNMP disabled)  
1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.40 `s_int32_t smi_bfd_get_sess_row_status_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_row_status, bool_t snmp)`

This function is used to get the session row status. `smi_bfd_get_sess_row_status_sdkapi`

#### Parameters:

- ← **azg** Pointer to the SMI client global structure
- ← **vr\_id** Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← **proc\_id** Process ID for the BFD instance numeric <0-65535>
- ← **index** BFD session index value
- **sess\_row\_status** Session row status
- ← **snmp** SNMP Enable/Disable numeric (0 | 1)  
0 - PAL\_FALSE (SNMP disabled)  
1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.41** `s_int32_t smi_bfd_get_sess_src_udp_port_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_src_udp_port, bool_t snmp)`

This function is used to get the source UDP port number used for the BFD session's control packets. `smi_bfd_get_sess_src_udp_port_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_src\_udp\_port* Source UDP port number of the session
- ← *snmp* SNMP Enable/Disable numeric <0 | 1>
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.42** `s_int32_t smi_bfd_get_sess_state_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_state, bool_t snmp)`

This function is used to get the session state. `smi_bfd_get_sess_state_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_state* Session status numeric <1-4>
  - 1 - BFD\_API\_SESS\_ST\_AD\_DWN 2 - BFD\_API\_SESS\_ST\_DWN 3 - BFD\_API\_SESS\_ST\_INIT 4 - BFD\_API\_SESS\_ST\_UP
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.43 `s_int32_t smi_bfd_get_sess_stor_type_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_stor_type, bool_t snmp)`

This function is used to get the session storage type. `smi_bfd_get_sess_stor_type_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_stor\_type* Session storage type
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.44 `s_int32_t smi_bfd_get_sess_type_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * session_type, bool_t snmp)`

This function is used to get the session type for an SNMP Get request. `smi_bfd_get_sess_type_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *session\_type* Type of BFD session type
- ← *snmp* SNMP Enable/Disable numeric <0 | 1>
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails



**2.1.2.45** `s_int32_t smi_bfd_get_sess_up_time_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_up_time, bool_t snmp)`

This function is used to get value of sysUpTime on the most recent occasion at which the session came up. `smi_bfd_get_sess_up_time_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_up\_time* Value of sysUpTime at which session came up
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.46** `s_int32_t smi_bfd_get_sess_version_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * version, bool_t snmp)`

This function gets the version number of the BFD protocol. `smi_bfd_get_sess_version_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *version* Version number
- ← *snmp* SNMP Enable/Disable numeric <0 | 1>
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.47 `s_int32_t smi_bfd_interface_echo_mode_set_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, char * ifname)`

Sets this BFD session to run in Echo mode at interface level. `smi_bfd_interface_echo_mode_set_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ifname* Interface name

#### Returns:

0 on success, otherwise one of the following error codes  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_IF\_NOT\_FOUND  
 BFD\_API\_SET\_ERROR

### 2.1.2.48 `s_int32_t smi_bfd_interface_echo_mode_unset_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, char * ifname)`

Unsets this BFD session to run in Echo mode at interface level. `smi_bfd_interface_echo_mode_unset_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ifname* Interface name

#### Returns:

0 on success, otherwise one of the following error codes  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_IF\_NOT\_FOUND  
 BFD\_API\_SET\_ERROR

**2.1.2.49** `s_int32_t smi_bfd_interface_slow_timer_set_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, char * ifname, u_int32_t slow_interval)`

Sets this BFD session's slow time interval in microseconds at interface level. `smi_bfd_interface_slow_timer_set_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ifname* Interface name
- ← *slow\_interval* Slow timer interval <1000-4294967000>

**Returns:**

0 on success, otherwise one of the following error codes  
BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
BFD\_API\_INSTANCE\_NOT\_FOUND  
BFD\_API\_IF\_NOT\_FOUND  
BFD\_API\_SET\_ERROR

**2.1.2.50** `s_int32_t smi_bfd_interface_slow_timer_unset_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, char * ifname)`

Unsets this BFD session's slow time interval in microseconds at interface level. `smi_bfd_interface_slow_timer_unset_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ifname* Interface name

**Returns:**

0 on success, otherwise one of the following error codes  
BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
BFD\_API\_INSTANCE\_NOT\_FOUND  
BFD\_API\_IF\_NOT\_FOUND  
BFD\_API\_SET\_ERROR

### 2.1.2.51 `s_int32_t smi_bfd_multihop_proto_interval_set_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, char * ifname, struct pal_in4_addr ip_addr, u_int32_t min_tx, u_int32_t min_rx, u_int32_t multiplier)`

Sets different time intervals of multihop BFD in microseconds. `smi_bfd_multihop_proto_interval_set_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ifname* Interface name
- ← *ip\_addr* IPv4 Peer address
- ← *min\_tx* Minimum BFD Control packets transmitting interval in microseconds <1000-4294967000>
- ← *min\_rx* Minimum BFD Control packets receiving interval in microseconds <1000-4294967000>
- ← *multiplier* BFD failure detection multiplier <1-255>

#### Returns:

0 on success, otherwise one of the following error codes  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_IF\_NOT\_FOUND  
 BFD\_API\_MH\_NOT\_FOUND  
 BFD\_API\_SET\_ERROR

### 2.1.2.52 `s_int32_t smi_bfd_multihop_proto_interval_unset_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, char * ifname, struct pal_in4_addr ipv4)`

Unsets different time intervals of multihop BFD in microseconds. `smi_bfd_multihop_proto_interval_unset_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ifname* Interface name
- ← *ip\_addr* IPv4 Peer address

**Returns:**

0 on success, otherwise one of the following error codes  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_IF\_NOT\_FOUND  
 BFD\_API\_MH\_NOT\_FOUND  
 BFD\_API\_SET\_ERROR

**2.1.2.53 s\_int32\_t smi\_bfd\_notification\_set (struct smiclient\_globals \* azg,  
 u\_int32\_t vr\_id, u\_int32\_t notif\_flag)**

Sets to enable or disable the notification emission of BFD session on this device. If this object is set to true(1), then it enables the emission of bfdSessUp and bfdSessDown notifications; otherwise these notifications are not emitted. smi\_bfd\_notification\_set

**Parameters:**

← *azg* Pointer to the SMI client global structure  
 ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation  
 ← *notif\_flag* Enable/Disable flag

**Returns:**

0 on success, otherwise one of the following error codes

**2.1.2.54 s\_int32\_t smi\_bfd\_process\_set (struct smiclient\_globals \* azg,  
 u\_int32\_t vr\_id, int proc\_id)**

Creates a new Bidirectional Forward Detection (BFD) process instance, if not before created, else returns the existing one. smi\_bfd\_process\_set

**Parameters:**

← *azg* Pointer to the SMI client global structure  
 ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation  
 ← *proc\_id* Process ID for the BFD instance numeric <0-65535>

**Returns:**

0 on success, otherwise one of the following error codes  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_SET\_ERR\_PROCESS\_ID\_INVALID

**2.1.2.55** `s_int32_t smi_bfd_proto_auth_set (struct smiclient_globals *  
azg, u_int32_t vr_id, s_int32_t proc_id, char * ifname, char *  
auth_type_str, u_int32_t key_id, char * key_str, char * key_chain)`

This function adds an IPv6 BFD user session. `smi_bfd_add_ipv6_user_session`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ipv6\_src\_addr* Source address for the session
- ← *ipv6\_dst\_addr* Destination address for the session
- ← *ifindex* Interface index
- ← *flags* Define the properties of a session
  - BFD\_MSG\_SESSION\_FLAG\_MH(Multi-Hop)
  - BFD\_MSG\_SESSION\_FLAG\_DC(Demand Circuit)
  - BFD\_MSG\_SESSION\_FLAG\_PS(Persistent Session)
  - BFD\_MSG\_SESSION\_FLAG\_AD(User Admin Down)

**Returns:**

BFD\_SUCCESS on success, otherwise one of the following errors BFD\_API\_-  
 SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_INVALID\_ADDR  
 BFD\_FAILURE

`smi_bfd_proto_auth_set`

This function sets the authentication information on an interface having sessions.

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ifname* Interface name string
- ← *auth\_type\_str* Authentication string type
- ← *key\_id* Key identifier
- ← *key\_str* Key string
- ← *key\_chain* Key chain

**Returns:**

BFD\_SUCCESS on success, otherwise one of the following errors BFD\_API\_-  
 INVALID\_AUTH\_TYPE

BFD\_API\_INVALID\_KEY\_ID  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_IF\_NOT\_FOUND

### 2.1.2.56 s\_int32\_t smi\_bfd\_proto\_auth\_unset (struct smiclient\_globals \* *azg*, u\_int32\_t *vr\_id*, s\_int32\_t *proc\_id*, u\_int32\_t *ifindex*)

This function unsets the authentication information on an interface having sessions.  
 smi\_bfd\_proto\_auth\_unset

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ifindex* Interface index

#### Returns:

BFD\_SUCCESS on success, otherwise one of the following errors BFD\_API\_INVALID\_AUTH\_TYPE  
 BFD\_API\_INVALID\_KEY\_ID  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_IF\_NOT\_FOUND

### 2.1.2.57 s\_int32\_t smi\_bfd\_proto\_interval\_set\_sdkapi (struct smiclient\_globals \* *azg*, u\_int32\_t *vr\_id*, s\_int32\_t *proc\_id*, char \* *ifname*, u\_int32\_t *min\_tx*, u\_int32\_t *min\_rx*, u\_int32\_t *multiplier*)

Sets different time intervals of singlehop BFD in microseconds. smi\_bfd\_proto\_interval\_set\_sdkapi

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ifname* Interface name
- ← *min\_tx* Minimum BFD Control packets transmitting interval in microseconds <1000-4294967000>
- ← *min\_rx* Minimum BFD Control packets receiving interval in microseconds <1000-4294967000>
- ← *multiplier* BFD failure detection multiplier <1-255>

**Returns:**

0 on success, otherwise one of the following error codes  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_IF\_NOT\_FOUND  
 BFD\_API\_SET\_ERROR

**2.1.2.58** `s_int32_t smi_bfd_proto_interval_unset_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, char * ifname)`

Unsets different time intervals of BFD. smi\_bfd\_proto\_interval\_unset\_sdkapi

**Parameters:**

← *azg* Pointer to the SMI client global structure  
 ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation  
 ← *proc\_id* Process ID for the BFD instance numeric <0-65535>  
 ← *ifname* Interface name

**Returns:**

0 on success, otherwise one of the following error codes  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_IF\_NOT\_FOUND  
 BFD\_API\_SET\_ERROR

**2.1.2.59** `s_int32_t smi_bfd_proto_multihop_auth_ipv4_set_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t ifindex, struct pal_in4_addr * ipv4_addr, char * auth_type_str, u_int32_t key_id, char * key_str, char * key_chain)`

This function sets the authentication information for a multihop session. smi\_bfd\_proto\_multihop\_auth\_ipv6\_set\_sdkapi

**Parameters:**

← *azg* Pointer to the SMI client global structure  
 ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation  
 ← *proc\_id* Process ID for the BFD instance numeric <0-65535>  
 ← *ifindex* Interface index  
 ← *ipv6\_addr* ipv6 Address  
 ← *auth\_type\_str* Authentication string type  
 ← *key\_id* Key identifier  
 ← *key\_str* Key string



← *key\_chain* Key chain

#### Returns:

BFD\_SUCCESS on success, otherwise one of the following errors BFD\_API\_INVALID\_AUTH\_TYPE  
 BFD\_API\_MH\_NOT\_FOUND  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_IF\_NOT\_FOUND

smi\_bfd\_proto\_multihop\_auth\_ipv4\_set\_sdkapi

This function sets the authentication information for a multihop session.

#### Parameters:

← *azg* Pointer to the SMI client global structure  
 ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation  
 ← *proc\_id* Process ID for the BFD instance numeric <0-65535>  
 ← *ifindex* Interface index  
 ← *ipv4\_addr* ipv4 Address  
 ← *auth\_type\_str* Authentication string type  
 ← *key\_id* Key identifier  
 ← *key\_str* Key string  
 ← *key\_chain* Key chain

#### Returns:

BFD\_SUCCESS on success, otherwise one of the following errors BFD\_API\_INVALID\_AUTH\_TYPE  
 BFD\_API\_MH\_NOT\_FOUND  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_IF\_NOT\_FOUND

#### 2.1.2.60 s\_int32\_t smi\_bfd\_proto\_multihop\_auth\_unset\_ipv4\_sdkapi (struct smiclient\_globals \*azg, u\_int32\_t vr\_id, s\_int32\_t proc\_id, s\_int32\_t ifindex, struct pal\_in4\_addr \*ipv4\_addr)

This function unsets the authentication information from a multihop session. smi\_bfd\_proto\_multihop\_auth\_unset\_ipv4\_sdkapi

#### Parameters:

← *azg* Pointer to the SMI client global structure  
 ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation

- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *ifindex* Interface index
- ← *ipv4\_addr* ipv4 Address

**Returns:**

BFD\_SUCCESS on success, otherwise one of the following errors BFD\_API\_INVALID\_AUTH\_TYPE  
 BFD\_API\_MH\_NOT\_FOUND  
 BFD\_API\_SET\_ERR\_VR\_NOT\_EXIST  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_IF\_NOT\_FOUND

### 2.1.2.61 `s_int32_t smi_bfd_proto_slow_timer_set (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t slow_interval)`

Sets this BFD session's slow time interval in microseconds at switch level. smi\_bfd\_proto\_slow\_timer\_set

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *slow\_interval* Slow timer inerval <1000-4294967000>

**Returns:**

0 on success, otherwise one of the following error codes  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_SET\_ERROR

### 2.1.2.62 `s_int32_t smi_bfd_proto_slow_timer_unset (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id)`

Unsets this BFD session's slow time interval in microseconds at switch level. smi\_bfd\_proto\_slow\_timer\_unset

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>

**Returns:**

0 on success, otherwise one of the following error codes  
 BFD\_API\_INSTANCE\_NOT\_FOUND  
 BFD\_API\_SET\_ERROR

### 2.1.2.63 `s_int32_t smi_bfd_sess_gtsm_ttl_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t * sess_gtsm_ttl, bool_t snmp)`

This function is used to get the session GTSM (Generalized TTL Security Mechanism) TTL (Time to live) which specifies the minimum allowed TTL for received BFD control packets. GTSM TTL valid only when GTSM is enabled. `smi_bfd_sess_gtsm_ttl_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- *sess\_gtsm\_ttl* GTSM TTL value numeric <0-255>
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.64 `s_int32_t smi_bfd_set_sess_addr_type_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_addr_type, bool_t snmp)`

This function is used to get the session address type of the BFD session. `smi_bfd_set_sess_addr_type_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_addr\_type* Session address type numeric <0-4>
  - 0 - ADDR\_TYPE\_unknown
  - 1 - ADDR\_TYPE\_ipv4
  - 2 - ADDR\_TYPE\_ipv6
  - 3 - ADDR\_TYPE\_ipv4z
  - 4 - ADDR\_TYPE\_ipv6ze
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.65 `s_int32_t smi_bfd_set_sess_admin_status_sdkapi` (struct `smiclient_globals *azg`, `u_int32_t vr_id`, `s_int32_t proc_id`, `u_int32_t index`, `u_int32_t set_sess_admin_status`, `bool_t snmp`)

This function is used to set the session administration status. `smi_bfd_set_sess_admin_status_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *set\_sess\_admin\_status* Session administration status
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.66 `s_int32_t smi_bfd_set_sess_detect_mult_sdkapi` (struct `smiclient_globals *azg`, `u_int32_t vr_id`, `s_int32_t proc_id`, `u_int32_t index`, `u_int32_t set_sess_detect_mult`, `bool_t snmp`)

This function is used to set the session detect time multiplier. `smi_bfd_set_sess_detect_mult_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *set\_sess\_detect\_mult* The detect multiple value of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.67** `s_int32_t smi_bfd_set_sess_dmnd_mode_dsrd_flag_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_dmnd_mode_dsrd_flag, bool_t snmp)`

This function is used to set the session demand mode desired flag which indicates that the local system's desire to use Demand mode. `smi_bfd_set_sess_dmnd_mode_dsrd_flag_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_dmnd\_mode\_dsrd\_flag* Demand mode desired flag of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.68** `s_int32_t smi_bfd_set_sess_dsrd_min_tx_intvl_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_dsrd_min_tx_intvl, bool_t snmp)`

This function is used to set the session desired minimum transmission interval. `smi_bfd_set_sess_dsrd_min_tx_intvl_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_dsrd\_min\_tx\_intvl* Minimum transmission interval value of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.69 `s_int32_t smi_bfd_set_sess_echo_src_udp_port_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_echo_src_udp_port, bool_t snmp)`

This function is used to set the source UDP port number used for BFD session's echo packets. `smi_bfd_set_sess_echo_src_udp_port_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_echo\_src\_udp\_port* Source UDP port number for echo packets
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.70 `s_int32_t smi_bfd_set_sess_gtsm_sdkapi_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_gtsm, bool_t snmp)`

This function is used to set the session GTSM (Generalized TTL Security Mechanism) enable/disable mode. `smi_bfd_set_sess_gtsm_sdkapi_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_gtsm* Session address type numeric (1 | 2)
  - 1 - BFD\_GTSM\_ENABLED
  - 2 - BFD\_GTSM\_DISABLED
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.71 `s_int32_t smi_bfd_set_sess_gtsm_ttl_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_gtsm_ttl, bool_t snmp)`

This function is used to set the session GTSM (Generalized TTL Security Mechanism) TTL (Time to live) which specifies the minimum allowed TTL for received BFD control packets. `smi_bfd_set_sess_gtsm_ttl_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_gtsm\_ttl* GTSM TTL value numeric <0-255>
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.72 `s_int32_t smi_bfd_set_sess_interface_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_interface, bool_t snmp)`

This function is used to get the session interface used to indicate the interface which the BFD session is running on. `smi_bfd_set_sess_interface_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_interface* BFD session interface
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.73 `s_int32_t smi_bfd_set_sess_req_min_echo_rx_intvl_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_req_min_echo_rx_intvl, bool_t snmp)`

This function is used to set the session required minimum echo receive interval, which specifies the minimum interval, in microseconds, between received BFD Echo packets system is capable of supporting. `smi_bfd_set_sess_req_min_echo_rx_intvl_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_req\_min\_echo\_rx\_intvl* Required minimum echo receive interval of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)  
0 - PAL\_FALSE (SNMP disabled)  
1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.74 `s_int32_t smi_bfd_set_sess_req_min_rx_intvl_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_req_min_rx_intvl, bool_t snmp)`

This function is used to set the session required minimum receive interval, which specifies the minimum interval in microseconds. between received BFD Echo packets system is capable of supporting. `smi_bfd_set_sess_req_min_rx_intvl_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_req\_min\_rx\_intvl* Required minimum receive interval of the session
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)  
0 - PAL\_FALSE (SNMP disabled)  
1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails



**2.1.2.75** `s_int32_t smi_bfd_set_sess_row_status_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_row_status, bool_t snmp)`

This function is used to get the session row status. `smi_bfd_set_sess_row_status_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_row\_status* Session row status
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

**2.1.2.76** `s_int32_t smi_bfd_set_sess_src_udp_port_sdkapi (struct smiclient_globals * azg, u_int32_t vr_id, s_int32_t proc_id, u_int32_t index, u_int32_t sess_src_udp_port, bool_t snmp)`

This function is used to set the source UDP port number used for the BFD session's control packets. `smi_bfd_set_sess_src_udp_port_sdkapi`

**Parameters:**

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID. Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_src\_udp\_port* Source UDP port number
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)
  - 0 - PAL\_FALSE (SNMP disabled)
  - 1 - PAL\_TRUE (SNMP enabled)

**Returns:**

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.77 `s_int32_t smi_bfd_set_sess_stor_type_sdkapi` (struct `smiclient_globals` \* *azg*, `u_int32_t` *vr\_id*, `s_int32_t` *proc\_id*, `u_int32_t` *index*, `u_int32_t` *sess\_stor\_type*, `bool_t` *snmp*)

This function is used to set the session storage type. `smi_bfd_set_sess_stor_type_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_stor\_type* Session storage type
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)  
0 - PAL\_FALSE (SNMP disabled)  
1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

### 2.1.2.78 `s_int32_t smi_bfd_set_sess_version_no_sdkapi` (struct `smiclient_globals` \* *azg*, `u_int32_t` *vr\_id*, `s_int32_t` *proc\_id*, `u_int32_t` *index*, `u_int32_t` *sess\_version\_no*, `bool_t` *snmp*)

This function is used to set the version number of the BFD protocol. `smi_bfd_set_sess_version_no_sdkapi`

#### Parameters:

- ← *azg* Pointer to the SMI client global structure
- ← *vr\_id* Virtual router ID.Default is 0, Pass 0 for a non-VR implementation
- ← *proc\_id* Process ID for the BFD instance numeric <0-65535>
- ← *index* BFD session index value
- ← *sess\_version\_no* Version number
- ← *snmp* SNMP Enable/Disable numeric (0 | 1)  
0 - PAL\_FALSE (SNMP disabled)  
1 - PAL\_TRUE (SNMP enabled)

#### Returns:

BFD\_SUCCESS on success, otherwise BFD\_FAILURE when the function fails

# Index

smi\_bfd\_add\_user\_session  
    smi\_oam\_bfd.h, [12](#)  
smi\_bfd\_api\_get\_sess\_diag\_sdkapi  
    smi\_oam\_bfd.h, [13](#)  
smi\_bfd\_api\_sess\_auth\_key\_id\_sdkapi  
    smi\_oam\_bfd.h, [13](#)  
smi\_bfd\_api\_sess\_auth\_type\_sdkapi  
    smi\_oam\_bfd.h, [14](#)  
smi\_bfd\_del\_user\_session  
    smi\_oam\_bfd.h, [14](#)  
smi\_bfd\_echo\_interval\_set  
    smi\_oam\_bfd.h, [15](#)  
smi\_bfd\_echo\_interval\_unset  
    smi\_oam\_bfd.h, [15](#)  
smi\_bfd\_echo\_mode\_set  
    smi\_oam\_bfd.h, [16](#)  
smi\_bfd\_echo\_mode\_unset  
    smi\_oam\_bfd.h, [16](#)  
smi\_bfd\_get\_discmap\_index\_sdkapi  
    smi\_oam\_bfd.h, [17](#)  
smi\_bfd\_get\_perf\_disc\_time\_sdkapi  
    smi\_oam\_bfd.h, [17](#)  
smi\_bfd\_get\_perf\_lastcomm\_lost\_diag\_  
    sdkapi  
    smi\_oam\_bfd.h, [18](#)  
smi\_bfd\_get\_perf\_lastses\_down\_time\_  
    sdkapi  
    smi\_oam\_bfd.h, [18](#)  
smi\_bfd\_get\_perf\_pkt\_in\_hc\_sdkapi  
    smi\_oam\_bfd.h, [19](#)  
smi\_bfd\_get\_perf\_pkt\_in\_sdkapi  
    smi\_oam\_bfd.h, [19](#)  
smi\_bfd\_get\_perf\_pkt\_out\_hc\_sdkapi  
    smi\_oam\_bfd.h, [20](#)  
smi\_bfd\_get\_perf\_pkt\_out\_sdkapi  
    smi\_oam\_bfd.h, [20](#)  
smi\_bfd\_get\_perf\_sess\_up\_count\_sdkapi  
    smi\_oam\_bfd.h, [21](#)  
smi\_bfd\_get\_sess\_addr\_type\_sdkapi  
    smi\_oam\_bfd.h, [21](#)  
smi\_bfd\_get\_sess\_admin\_status\_sdkapi  
    smi\_oam\_bfd.h, [22](#)  
smi\_bfd\_get\_sess\_auth\_pres\_flag\_sdkapi  
    smi\_oam\_bfd.h, [22](#)  
smi\_bfd\_get\_sess\_cntrlplane\_indep\_  
    flag\_sdkapi  
    smi\_oam\_bfd.h, [23](#)  
smi\_bfd\_get\_sess\_dest\_udp\_port\_sdkapi  
    smi\_oam\_bfd.h, [24](#)  
smi\_bfd\_get\_sess\_detectmult\_sdkapi  
    smi\_oam\_bfd.h, [24](#)  
smi\_bfd\_get\_sess\_disc\_sdkapi  
    smi\_oam\_bfd.h, [24](#)  
smi\_bfd\_get\_sess\_dmnd\_mode\_dsrd\_  
    flag\_sdkapi  
    smi\_oam\_bfd.h, [25](#)  
smi\_bfd\_get\_sess\_dsrd\_min\_tx\_intvl\_  
    sdkapi  
    smi\_oam\_bfd.h, [25](#)  
smi\_bfd\_get\_sess\_echo\_src\_udp\_port\_  
    sdkapi  
    smi\_oam\_bfd.h, [26](#)  
smi\_bfd\_get\_sess\_gtsm\_sdkapi  
    smi\_oam\_bfd.h, [26](#)  
smi\_bfd\_get\_sess\_interface\_sdkapi  
    smi\_oam\_bfd.h, [27](#)  
smi\_bfd\_get\_sess\_mh\_unlnk\_mode\_  
    sdkapi  
    smi\_oam\_bfd.h, [27](#)  
smi\_bfd\_get\_sess\_neg\_detect\_mult\_  
    sdkapi  
    smi\_oam\_bfd.h, [28](#)  
smi\_bfd\_get\_sess\_neg\_echo\_intvl\_  
    sdkapi  
    smi\_oam\_bfd.h, [28](#)  
smi\_bfd\_get\_sess\_neg\_intvl\_sdkapi  
    smi\_oam\_bfd.h, [29](#)  
smi\_bfd\_get\_sess\_oper\_mode\_sdkapi  
    smi\_oam\_bfd.h, [29](#)  
smi\_bfd\_get\_sess\_req\_min\_echo\_rx\_  
    intvl\_sdkapi  
    smi\_oam\_bfd.h, [30](#)

- smi\_bfd\_get\_sess\_req\_min\_rx\_intvl\_-  
    sdkapi  
    smi\_oam\_bfd.h, [30](#)
- smi\_bfd\_get\_sess\_rmte\_disc\_sdkapi  
    smi\_oam\_bfd.h, [31](#)
- smi\_bfd\_get\_sess\_rmte\_heard\_flag\_-  
    sdkapi  
    smi\_oam\_bfd.h, [31](#)
- smi\_bfd\_get\_sess\_row\_status\_sdkapi  
    smi\_oam\_bfd.h, [32](#)
- smi\_bfd\_get\_sess\_src\_udp\_port\_sdkapi  
    smi\_oam\_bfd.h, [32](#)
- smi\_bfd\_get\_sess\_state\_sdkapi  
    smi\_oam\_bfd.h, [33](#)
- smi\_bfd\_get\_sess\_stor\_type\_sdkapi  
    smi\_oam\_bfd.h, [33](#)
- smi\_bfd\_get\_sess\_type\_sdkapi  
    smi\_oam\_bfd.h, [34](#)
- smi\_bfd\_get\_sess\_up\_time\_sdkapi  
    smi\_oam\_bfd.h, [34](#)
- smi\_bfd\_get\_sess\_version\_sdkapi  
    smi\_oam\_bfd.h, [35](#)
- smi\_bfd\_interface\_echo\_mode\_set\_-  
    sdkapi  
    smi\_oam\_bfd.h, [35](#)
- smi\_bfd\_interface\_echo\_mode\_unset\_-  
    sdkapi  
    smi\_oam\_bfd.h, [36](#)
- smi\_bfd\_interface\_slow\_timer\_set\_-  
    sdkapi  
    smi\_oam\_bfd.h, [36](#)
- smi\_bfd\_interface\_slow\_timer\_unset\_-  
    sdkapi  
    smi\_oam\_bfd.h, [37](#)
- smi\_bfd\_multihop\_proto\_interval\_set\_-  
    sdkapi  
    smi\_oam\_bfd.h, [37](#)
- smi\_bfd\_multihop\_proto\_interval\_-  
    unset\_sdkapi  
    smi\_oam\_bfd.h, [38](#)
- smi\_bfd\_notification\_set  
    smi\_oam\_bfd.h, [39](#)
- smi\_bfd\_process\_set  
    smi\_oam\_bfd.h, [39](#)
- smi\_bfd\_proto\_auth\_set  
    smi\_oam\_bfd.h, [39](#)
- smi\_bfd\_proto\_auth\_unset  
    smi\_oam\_bfd.h, [41](#)
- smi\_bfd\_proto\_interval\_set\_sdkapi  
    smi\_oam\_bfd.h, [41](#)
- smi\_bfd\_proto\_interval\_unset\_sdkapi  
    smi\_oam\_bfd.h, [42](#)
- smi\_bfd\_proto\_multihop\_auth\_ipv4\_-  
    set\_sdkapi  
    smi\_oam\_bfd.h, [42](#)
- smi\_bfd\_proto\_multihop\_auth\_unset\_-  
    ipv4\_sdkapi  
    smi\_oam\_bfd.h, [43](#)
- smi\_bfd\_proto\_slow\_timer\_set  
    smi\_oam\_bfd.h, [44](#)
- smi\_bfd\_proto\_slow\_timer\_unset  
    smi\_oam\_bfd.h, [44](#)
- smi\_bfd\_sess\_gtsm\_ttl\_sdkapi  
    smi\_oam\_bfd.h, [44](#)
- smi\_bfd\_set\_sess\_addr\_type\_sdkapi  
    smi\_oam\_bfd.h, [45](#)
- smi\_bfd\_set\_sess\_admin\_status\_sdkapi  
    smi\_oam\_bfd.h, [45](#)
- smi\_bfd\_set\_sess\_detect\_mult\_sdkapi  
    smi\_oam\_bfd.h, [46](#)
- smi\_bfd\_set\_sess\_dmnd\_mode\_dsrd\_-  
    flag\_sdkapi  
    smi\_oam\_bfd.h, [46](#)
- smi\_bfd\_set\_sess\_dsrd\_min\_tx\_intvl\_-  
    sdkapi  
    smi\_oam\_bfd.h, [47](#)
- smi\_bfd\_set\_sess\_echo\_src\_udp\_port\_-  
    sdkapi  
    smi\_oam\_bfd.h, [47](#)
- smi\_bfd\_set\_sess\_gtsm\_sdkapi\_sdkapi  
    smi\_oam\_bfd.h, [48](#)
- smi\_bfd\_set\_sess\_gtsm\_ttl\_sdkapi  
    smi\_oam\_bfd.h, [48](#)
- smi\_bfd\_set\_sess\_interface\_sdkapi  
    smi\_oam\_bfd.h, [49](#)
- smi\_bfd\_set\_sess\_req\_min\_echo\_rx\_-  
    intvl\_sdkapi  
    smi\_oam\_bfd.h, [49](#)
- smi\_bfd\_set\_sess\_req\_min\_rx\_intvl\_-  
    sdkapi  
    smi\_oam\_bfd.h, [50](#)
- smi\_bfd\_set\_sess\_row\_status\_sdkapi  
    smi\_oam\_bfd.h, [50](#)
- smi\_bfd\_set\_sess\_src\_udp\_port\_sdkapi  
    smi\_oam\_bfd.h, [51](#)
- smi\_bfd\_set\_sess\_stor\_type\_sdkapi  
    smi\_oam\_bfd.h, [51](#)
- smi\_bfd\_set\_sess\_version\_no\_sdkapi  
    smi\_oam\_bfd.h, [52](#)
- smi\_oam\_bfd.h, [3](#)

- smi\_bfd\_add\_user\_session, [12](#)
- smi\_bfd\_api\_get\_sess\_diag\_sdkapi, [13](#)
- smi\_bfd\_api\_sess\_auth\_key\_id\_sdkapi, [13](#)
- smi\_bfd\_api\_sess\_auth\_type\_sdkapi, [14](#)
- smi\_bfd\_del\_user\_session, [14](#)
- smi\_bfd\_echo\_interval\_set, [15](#)
- smi\_bfd\_echo\_interval\_unset, [15](#)
- smi\_bfd\_echo\_mode\_set, [16](#)
- smi\_bfd\_echo\_mode\_unset, [16](#)
- smi\_bfd\_get\_discmap\_index\_sdkapi, [17](#)
- smi\_bfd\_get\_perf\_disc\_time\_sdkapi, [17](#)
- smi\_bfd\_get\_perf\_lastcomm\_lost\_diag\_sdkapi, [18](#)
- smi\_bfd\_get\_perf\_lastses\_down\_time\_sdkapi, [18](#)
- smi\_bfd\_get\_perf\_pkt\_in\_hc\_sdkapi, [19](#)
- smi\_bfd\_get\_perf\_pkt\_in\_sdkapi, [19](#)
- smi\_bfd\_get\_perf\_pkt\_out\_hc\_sdkapi, [20](#)
- smi\_bfd\_get\_perf\_pkt\_out\_sdkapi, [20](#)
- smi\_bfd\_get\_perf\_sess\_up\_count\_sdkapi, [21](#)
- smi\_bfd\_get\_sess\_addr\_type\_sdkapi, [21](#)
- smi\_bfd\_get\_sess\_admin\_status\_sdkapi, [22](#)
- smi\_bfd\_get\_sess\_auth\_pres\_flag\_sdkapi, [22](#)
- smi\_bfd\_get\_sess\_cntrlplane\_indep\_flag\_sdkapi, [23](#)
- smi\_bfd\_get\_sess\_dest\_udp\_port\_sdkapi, [24](#)
- smi\_bfd\_get\_sess\_detectmult\_sdkapi, [24](#)
- smi\_bfd\_get\_sess\_disc\_sdkapi, [24](#)
- smi\_bfd\_get\_sess\_dmnd\_mode\_dsrd\_flag\_sdkapi, [25](#)
- smi\_bfd\_get\_sess\_dsrd\_min\_tx\_intvl\_sdkapi, [25](#)
- smi\_bfd\_get\_sess\_echo\_src\_udp\_port\_sdkapi, [26](#)
- smi\_bfd\_get\_sess\_gtsm\_sdkapi, [26](#)
- smi\_bfd\_get\_sess\_interface\_sdkapi, [27](#)
- smi\_bfd\_get\_sess\_mh\_unlnk\_mode\_sdkapi, [27](#)
- smi\_bfd\_get\_sess\_neg\_detect\_mult\_sdkapi, [28](#)
- smi\_bfd\_get\_sess\_neg\_echo\_intvl\_sdkapi, [28](#)
- smi\_bfd\_get\_sess\_neg\_intvl\_sdkapi, [29](#)
- smi\_bfd\_get\_sess\_oper\_mode\_sdkapi, [29](#)
- smi\_bfd\_get\_sess\_req\_min\_echo\_rx\_intvl\_sdkapi, [30](#)
- smi\_bfd\_get\_sess\_req\_min\_rx\_intvl\_sdkapi, [30](#)
- smi\_bfd\_get\_sess\_rmte\_disc\_sdkapi, [31](#)
- smi\_bfd\_get\_sess\_rmte\_heard\_flag\_sdkapi, [31](#)
- smi\_bfd\_get\_sess\_row\_status\_sdkapi, [32](#)
- smi\_bfd\_get\_sess\_src\_udp\_port\_sdkapi, [32](#)
- smi\_bfd\_get\_sess\_state\_sdkapi, [33](#)
- smi\_bfd\_get\_sess\_stor\_type\_sdkapi, [33](#)
- smi\_bfd\_get\_sess\_type\_sdkapi, [34](#)
- smi\_bfd\_get\_sess\_up\_time\_sdkapi, [34](#)
- smi\_bfd\_get\_sess\_version\_sdkapi, [35](#)
- smi\_bfd\_interface\_echo\_mode\_set\_sdkapi, [35](#)
- smi\_bfd\_interface\_echo\_mode\_unset\_sdkapi, [36](#)
- smi\_bfd\_interface\_slow\_timer\_set\_sdkapi, [36](#)
- smi\_bfd\_interface\_slow\_timer\_unset\_sdkapi, [37](#)
- smi\_bfd\_multihop\_proto\_interval\_set\_sdkapi, [37](#)
- smi\_bfd\_multihop\_proto\_interval\_unset\_sdkapi, [38](#)
- smi\_bfd\_notification\_set, [39](#)
- smi\_bfd\_process\_set, [39](#)
- smi\_bfd\_proto\_auth\_set, [39](#)
- smi\_bfd\_proto\_auth\_unset, [41](#)
- smi\_bfd\_proto\_interval\_set\_sdkapi, [41](#)

smi\_bfd\_proto\_interval\_unset\_-  
    sdkapi, [42](#)  
smi\_bfd\_proto\_multihop\_auth\_-  
    ipv4\_set\_sdkapi, [42](#)  
smi\_bfd\_proto\_multihop\_auth\_-  
    unset\_ipv4\_sdkapi, [43](#)  
smi\_bfd\_proto\_slow\_timer\_set, [44](#)  
smi\_bfd\_proto\_slow\_timer\_unset,  
    [44](#)  
smi\_bfd\_sess\_gtsm\_ttl\_sdkapi, [44](#)  
smi\_bfd\_set\_sess\_addr\_type\_-  
    sdkapi, [45](#)  
smi\_bfd\_set\_sess\_admin\_status\_-  
    sdkapi, [45](#)  
smi\_bfd\_set\_sess\_detect\_mult\_-  
    sdkapi, [46](#)  
smi\_bfd\_set\_sess\_dmnd\_mode\_-  
    dsrd\_flag\_sdkapi, [46](#)  
smi\_bfd\_set\_sess\_dsrd\_min\_tx\_-  
    intvl\_sdkapi, [47](#)  
smi\_bfd\_set\_sess\_echo\_src\_udp\_-  
    port\_sdkapi, [47](#)  
smi\_bfd\_set\_sess\_gtsm\_sdkapi\_-  
    sdkapi, [48](#)  
smi\_bfd\_set\_sess\_gtsm\_ttl\_sdkapi,  
    [48](#)  
smi\_bfd\_set\_sess\_interface\_sdkapi,  
    [49](#)  
smi\_bfd\_set\_sess\_req\_min\_echo\_-  
    rx\_intvl\_sdkapi, [49](#)  
smi\_bfd\_set\_sess\_req\_min\_rx\_-  
    intvl\_sdkapi, [50](#)  
smi\_bfd\_set\_sess\_row\_status\_-  
    sdkapi, [50](#)  
smi\_bfd\_set\_sess\_src\_udp\_port\_-  
    sdkapi, [51](#)  
smi\_bfd\_set\_sess\_stor\_type\_sdkapi,  
    [51](#)  
smi\_bfd\_set\_sess\_version\_no\_-  
    sdkapi, [52](#)