



IceWall SSO

Version 10.0

Troubleshooting Guide

August 2010

Printed in Japan

HP Part No. B1544-97003

Rev.111020B

Notice

The information contained in this document is subject to change without notice.

Meticulous care has been taken in the preparation of this document, however, if a questionable or erroneous item, or an omission of content is found, please contact us.

Hewlett-Packard Japan, Ltd. shall not be liable for errors contained herein or for incidental or consequential damage in connection with the furnishing, performance or use of this document.

The copyright of this document is assigned to Hewlett-Packard Development Company, L.P. No part of this document may be photocopied or reproduced without prior written consent by Hewlett-Packard Japan, Ltd.

This manual and media, such as the CD-ROM supplied as a part of the product's package, are only to be used with this product.

IceWall is a trademark of Hewlett-Packard Japan, Ltd.

Adobe is a trademark of Adobe Systems Incorporated in the United States and/or other countries.

Intel, the Intel logo, Intel. Leap ahead., Intel. Leap ahead. logo, Itanium and Itanium Inside are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Microsoft and Windows are trademarks or registered trademarks of Microsoft Corporation in the United States and other countries.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

– Table of Contents –

1	Introduction.....	1
1.1	Version designations in the text.....	1
2	Available Resources	2
2.1	Product manuals	2
2.2	Resources on the Internet.....	3
3	IceWall SSO Technical Training.....	4
4	Frequently Asked Questions (FAQ).....	5
4.1	Forwarder (dfw) FAQ.....	6
4.2	Authentication Module (certd) FAQ.....	17
4.3	Common questions and other FAQs	25
5	Making Inquiries about Problems	46
5.1	Before making an inquiry	46
5.2	Contact information	46
6	Minimum and Maximum Parameter Values	47
6.1	Forwarder (dfw).....	47
6.1.1	Forwarder configuration file (dfw.conf)	47
6.1.2	Host configuration file (arbitrary file name)	50
6.1.3	Form authentication configuration file (arbitrary file name).....	52
6.1.4	HTML configuration file (html.conf)	53
6.2	Authentication Module (certd)	56
6.2.1	Authentication Module configuration file (cert.conf)	56
6.2.2	Group configuration file (cert.grp).....	59
6.2.3	Access control file (cert.acl).....	59
6.2.4	Authentication DB column information file (dbattr.conf).....	60
6.2.5	Log column information file (logdbattr.conf)	60
6.2.6	Forbidden password configuration file (pwdforbid.conf).....	60
6.2.7	Request control configuration file (request.acl).....	60
6.3	Dynamic Menu Portal (dmp)	62
6.3.1	Servlet configuration file (web.xml)	62
6.3.2	Log configuration file (log4j.properties)	62
6.3.3	Dynamic Menu Portal configuration file (dmp.xml).....	63
7	Log Message List	66
7.1	Access log message list	66
7.1.1	Authentication Module access log	66
7.2	Error log message list	80
7.2.1	Forwarder error log	80
7.2.2	Authentication Module error log (same for all authentication databases)	207
7.2.3	Authentication Module error log (for ORACLE edition only)	285
7.2.4	Authentication Module error log (LDAP, OpenLDAP, MSAD, and NED editions only)	290
7.2.5	Authentication Module error log (for CSV edition only)	296
7.2.6	Authentication Module error log (for MySQL edition only).....	298

7.3	Audit log message list	301
7.4	Security log message list	303
7.5	Information log message list	304

1 Introduction



This guide will help you troubleshoot common problems you may encounter with IceWall SSO and provide the information on known issues in this version.

The guide also provides contact information you can access if problems cannot be resolved after using this guide together with the information you need to collect before you make an inquiry.

If a problem occurs, be sure to read this guide before making an inquiry.

1.1 Version designations in the text

The table below gives the meanings of the version designations added to the description.

Designation	Meaning
	An item added with the version enclosed in the square. In this case, the designation indicates the item was added with 10.0.
	An item where the functional specification was changed or a function added with the version enclosed in the oval. In this case, the designation indicates a specification change or added function with 10.0.

2 Available Resources

2.1 Product manuals

To examine a problem by using the product manuals, refer to the documentation sets which fit each audience group below:

- **To everyone using IceWall SSO for the first time**
IceWall SSO Version 10.0 Enterprise Edition Read Me First
or
IceWall SSO Version 10.0 Standard Edition Read Me First
- **To everyone installing IceWall SSO for the first time**
IceWall SSO Version 10.0 Installation Guide
IceWall SSO Version 10.0 User's Manual
IceWall SSO Version 10.0 Sample Setup Guide
- **To everyone upgrading from a previous version**
IceWall SSO Version 10.0 Installation Guide
- **To everyone configuring advanced settings**
IceWall SSO Version 10.0 User's Manual
IceWall SSO Version 10.0 Configuration Manual for Automatic Form Authentication
IceWall SSO Version 10.0 Installation Guide for Client Certificates Option
- **To everyone using ancilliary tools**
IceWall SSO Version 10.0 Installation Guide for Dynamic Menu Portal
IceWall SSO Version 10.0 Installation Guide for Configuration Manager
IceWall SSO Version 10.0 Installation Guide of Domain Gateway Option for UNIX
IceWall SSO Version 10.0 Registration Tool Manual
- **To everyone who can and/or wants to customize parameter**
IceWall SSO Version 10.0 Reference Manual

- **To everyone who wants to customize the authentication process and/or HTML pages**

IceWall SSO Version 10.0 UserExit Routine Developer's Manual

IceWall SSO Version 10.0 Password Encryption Library Developer's Manual

IceWall SSO Version 10.0 Standard HTML Customization Guide

IceWall SSO Version 10.0 Standard HTML Customization Guide of Domain Gateway Option for UNIX

IceWall SSO Version 10.0 IceWall Cert Protocol 2.0 Developer's Manual

IceWall SSO Version 10.0 Authentication Database Encryption Routine Developer's Manual

- **To Administrators managing applications connected to IceWall SSO**

IceWall SSO Version 10.0 Web Application Developer's Manual

IceWall SSO Version 10.0 IceWall Cert Protocol 2.0 Developer's Manual

2.2 Resources on the Internet

- **HP Japan IceWall SSO system requirements and configuration**

<http://h50146.www5.hp.com/products/software/security/icewall/ssospec/index.html>

- **HP Japan IceWall SSO FAQ**

<http://h50146.www5.hp.com/products/software/security/icewall/ssofaq/index.html>

Customers who have purchased support coverage for IceWall products should also use the URL below.

3 IceWall SSO Technical Training

A training course is available to acquire the knowledge needed to install and operate HP IceWall SSO. In this training course, you will learn the overall architecture and functions of HP IceWall SSO through hands-on training.

For details, see the site below.

IceWall SSO training information

<http://h50146.www5.hp.com/products/software/security/icewall/sso/training.html>

4 Frequently Asked Questions (FAQ)

This chapter describes frequently asked questions and the answers to those questions.

The questions and answers in this manual are extracted from the FAQ in the HP IceWall support page. If you cannot find an appropriate answer here, please visit the HP IceWall support page.

4.1 Forwarder (dfw) FAQ

Frequently asked questions regarding Forwarder are listed below:

Q. Why does Forwarder not start?

Q. How can I change the configuration?

Q. The system does not convert the URLs into ones accessible through IceWall SSO.
How can I correct this?

Q. It takes a long time to display the contents. Can this be fixed?

Q. Forwarder cannot communicate with the Backend Web Server.

Q. The page or image is not displayed. Is there a fix for this?

Q. The page is only partially displayed. How do I fix this?

Q. The system error page is displayed.

Q. Requests are not logged to the dfw.log/dfwerr.log files even though they are received;
at the same time, errors are recorded in the web server that runs the IceWall server.

Q. Can communication errors between the client and Forwarder be detected?

Q. Why does Forwarder not start?

A. Check the items below:

- **Are the links to the library set correctly?**
→ See “Installing the Forwarder” in the Installation Guide.
- **Is the library version correct?**
→ See “Verifying version information” in the Installation Guide.
- **Is the web server configured correctly?**
→ See “Installing the Forwarder” in the Installation Guide.
- **Has an error occurred in the web server?**
→ Forwarder will not start if an error has occurred on the web server. Check the error logs on the web server.
- **Are the owner and permissions correct?**
→ The user who runs the web server must have read/write permission for the IceWall SSO configuration files. See “Installation” in the Installation Guide.

Q. How can I change the configuration?

A. Be aware of the following:

- **Modifications in the configuration files are reflected in Forwarder as soon as they are made.**
→ See “Forwarder configuration file” in the User's Manual.
- **Use UNIX linefeeds (0x0a) as the line terminator in the configuration files.**
→ If you save the files on Windows, the UNIX linefeed (LF) codes might be modified to LF + CR. Keep this in mind when saving the files in the target server.

Q. The system does not convert the URLs into ones accessible through IceWall SSO. How can I correct this?

A. Check the items below:

- **Does URL conversion apply to the Content-type?**
→ Check CTYPE in the host configuration file.
- **Are the elements and attributes to be converted set in URLKEY in the host configuration file?**
→ Check URLKEY in the host configuration file.
- **Is the URL written in JavaScript?**
→ URLs that cannot be converted with URLKEY can be converted with REPKEY. See “REPKEY” in the Reference Manual and “URL Conversion,” “Keyword Conversion,” “JavaScript,” and other chapters in the Web Application Developer's Manual.
- **Is the content compressed by HTTP compression? 10.0**
→ URL conversion and keyword conversion will not function for compressed HTTP contents that IceWall receives.
Configure the Backend Web Server to send content that is not compressed by HTTP compression, if IceWall has to perform URL conversion or keyword conversion.

Q. It takes a long time to display the contents. Can this be fixed?

A. Check the items below:

- **Are there any DNS or other network delays?**
→ Ask the network administrator.
- **Does the IceWall server have enough system resources?**
→ Use the top command to check the CPU utilization, web server memory utilization, swap activity, and other parameters.
- **Is the Keep-Alive configuration of the Backend Web Server set to ON?**
→ See “Keep-Alive configuration” in the Web Application Developer's Manual and “Keep-Alive between Forwarder and the Backend Web Server” in the User's Manual.
- **Has any problem occurred on the Backend Web Server?**
→ Check the error logs on the Backend Web Server.
- **Has the performance of the Authentication Server declined?**
→ See “Authentication Module performance” in the User's Manual.
- **Have you identified the processes which cause the delay?**
→ The communication duration with the Backend Web Server and processing duration at Forwarder can be confirmed in the Forwarder access log. See “Forwarder access log format” in the User's Manual.

Q. Forwarder cannot communicate with the Backend Web Server.

A. Check the items below:

- **Are there any network problems such as incorrect firewall settings?**
→ Ask the network administrator.
- **Is the connection with the Backend Web Server successful?**
→ Use a browser, a telnet command, or other means to check communication between the IceWall server and Backend Web Server.
- **Is the Backend Web Server returning a response?**
→ Check the Backend Web Server access log.
- **Is the host name that is set in HOST (SHOST) correct?**
→ Check HOST (SHOST) in the Forwarder configuration file (dfw.conf).
- **Is SSL 3.0 used with the SSL Option enabled?**
→ See “Version of SSL connection and usable encryption methods” in the Web Application Developer's Manual.
- **Is the “TripleDES” cipher specified for Apache with the SSL Option enabled?**
→ See “SSL 3.0 cipher with Apache” in the Web Application Developer's Manual.

Q. The page or image is not displayed. Is there a fix for this?

A. Check the items below:

- **Is the connection between the client and the IceWall server successful?**
 - Use the browser output, ping command, or other means to check communication. If there is no communication, check if there are any Forwarder processes on the web server where Forwarder runs and if any log messages have been output to the access log.
- **Are there any DNS or other network problems?**
 - Ask the network administrator.
- **Have you specified the wrong URL?**
 - When IceWall SSO is installed, the URL for accessing the Backend Web Server changes. Check the URL.
- **Is the connection with the Backend Web Server successful?**
 - Use telnet commands or other means to check communication between the IceWall server and Backend Web Server.
- **Is the Backend Web Server returning a response?**
 - Check the Backend Web Server access log.
- **Is the correct MIME type set for the Backend Web Server?**
 - Check the Backend Web Server configuration files.
- **Has an error occurred on the web server?**
 - Check the error logs on the Backend Web Server.
- **Has a timeout occurred in Forwarder or the web server?**
 - Check the Forwarder error log. For details about the Forwarder timeout settings, see “TIMEOUT” and “CLOSETIME” in the Reference Manual. Check the error logs on the web server to make sure that web server CGI timeouts, request timeouts, or other timeouts have not occurred.
- **Is the content cached in a proxy server?**
 - Delete the browser file cache, and then try accessing again.

Q. The page is only partially displayed. How do I fix this?

A. Check the items below:

- **Is the source content complete?**
→ Check if the source content is correct.
- **Does the content pass through a proxy server?**
→ The content that is cached in the proxy server may not be complete. Check the proxy server settings.
- **Is the Backend Web Server responding correctly?**
→ Check the log of the Backend Web Server and other data.
- **Is the correct MIME type set for the Backend Web Server?**
→ If the correct MIME type is not set, the content may not be displayed correctly because the default value is applied. Check the Backend Web Server configuration files.
- **Is the CLOSETIME setting correct?**
→ See “CLOSETIME” in the Reference Manual.

Q. The system error page is displayed.

A. Check the items below:

- **Are the configuration values for MAXURL and MAXQUERY correct?**
→ See “MAXURL” and “MAXQUERY” in the Reference Manual.

Q. Requests are not logged to the dfw.log/dfwerr.log files even though they are received; at the same time, errors are recorded in the web server that runs the IceWall server.

A. If a request from the client is identified as an error by the web server that runs the IceWall server, the request is not delivered to Forwarder, so it can not be logged to dfw.log or dfwerr.log. Check the error logs on the web server.

Q. Can communication errors between the client and Forwarder be detected?

- A. Forwarder is a CGI process that runs on a web server.
Communication with the client is performed with the web server.
As a result, network problems between the client and web server are not detected as communication errors by Forwarder.
Check the error logs on the web server where Forwarder runs.

4.2 Authentication Module (certd) FAQ

Common questions and issues regarding the Authentication Module are listed below:

- Q. The Authentication Module does not start. How can this be fixed?
- Q. The Authentication Module does not stop. How can this be fixed?
- Q. How can I change the configuration?
- Q. The error "Pool Queue is Full" has occurred. How can I locate the source of the problem?
- Q. The following error message is logged to the Authentication Module error log (certerr.log).
"Fatal: Cookie:IW_INFO=xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx is Locked by Another Thread. [EC11302-20013]"
- Q. The following error message is logged to the Authentication Module error log (certerr.log).
"Warning: Unknown RequestID Error. [XXNNNNN-NNNNN]"
- Q. The following error message is output to the Authentication Module error log (certerr.log).
"Fatal: accept() Error: too many open files. [XXNNNNN-NNNNN]"

Q. The Authentication Module does not start. How can this be fixed?

A. Check the items below:

- **Are you logged in to the Authentication Server as a user who can start the Authentication Module?**
→ Log in again as a user who can start the Authentication Module.
- **Are the links to the library set correctly?**
→ See “Verifying installed files” in the Installation Guide.
- **Is the library version correct?**
→ See “Verifying version information” in the Installation Guide.
- **Are the start and stop commands (start-cert and end-cert) set correctly?**
→ See “Installing the Authentication Module” in the Installation Guide.
- **Are the owner and permission of the Authentication Module and start command correct?**
→ See “Verifying installed files” in the Installation Guide.
- **Are the owner and permission of the configuration files (cert.conf, cert.acl, cert.grp, etc.) correct?**
→ See “Verifying installed files” in the Installation Guide.
- **Is the content of the configuration file (PWDFORBID in cert.conf) correct?**
→ Check the PWDFORBID parameter in the Authentication Module configuration file and the forbidden password configuration file.

Q. The Authentication Module does not stop. How can this be fixed?

A. Check the items below:

- **Are you logged in to the Authentication Server as a user who can stop the Authentication Module?**
→ Log in again as a user who can start the Authentication Module.
- **Are the links to the library set correctly?**
→ See “Verifying installed files” in the Installation Guide.
- **Is the library version correct?**
→ See “Verifying version information” in the Installation Guide.
- **Is the stop command (end-cert) setting correct?**
→ See “Installing the Authentication Module” in the Installation Guide.
- **Are the owner and permission correct?**
→ See “Verifying installed files” in the Installation Guide.
- **Has an [EC01202-25078] request queue overflow error message been output to the error log?**
→ A stop request of the Authentication Module is also a type of request. A stop request may not be accepted if the queue has overflowed.
- **Did you execute the stop command (end-cert) on the running server? 10.0**
→ In version 10.0, IceWall rejects stop requests if you do not execute the stop command (end-cert) on the running server.

Q. How can I change the configuration?

A. Check the items below:

- **To have the changes reflected in the Authentication Module, shut down the module and restart it. However, the configuration can be reloaded without shutting down and restarting for the files and parameters below.**

- A portion of the parameters in the Authentication Module configuration file
- Group configuration file
- Access control file
- Forbidden password configuration file
- Request control configuration file

Some changes may not be reflected if the number of requests is high, so make changes when the number is low. Use info-cert or other means to check the utilization.

→ See “Authentication Module configuration file” in the User's Manual.

* The information of the logged-in user is not deleted for a reload (reload-cert).

- **Use UNIX linefeeds (0x0a) as the line terminator in the configuration files.**

→ If you save the files on Windows, the UNIX linefeed (LF) codes might be modified to CR + LF. Keep this in mind when transferring the files to the target server.

- **On the Authentication Servers configured as a redundant system, you can change the configuration without stopping all the servers.**

→ See “Changing a configuration that uses the Authentication Module's non-stop maintenance function” in the User's Manual.

Q. The error “Pool Queue is Full” has occurred. How can I locate the source of the problem?

A. Check the message IDs of the error messages in the error log to see which queue has overflowed.

● **Has the error [EC01202-25078] been output?**

→ This error indicates that a request queue has overflowed.

The configuration values for REQQESIZE, MAXREQTHREAD, and MAXDBCONNECT must be revised.

● **Has the error [EC134xx-25078] been output?**

→ This error indicates that a replication queue has overflowed.

The configuration values for REPQESIZE and MAXREPTHREAD must be revised.

* To find the method for calculating the configuration values, see “Parameter calculation method” in the User's Manual.

For details on each configuration parameter, see the Reference Manual.

● **Is there a problem with the Authentication DB?**

→ If the Authentication DB does not return a response, the requests can accumulate in the Authentication Module, which prevents requests waiting in the queue from being processed. Check the log and other data of the Authentication DB.

Q. The following error message is logged to the Authentication Module error log (certerr.log).

“Fatal: Cookie:IW_INFO=xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx is Locked by Another Thread. [EC11302-20013]”

A. This error message is output when the automatic logout operation of the Authentication Module occurs at the same time as user-generated requests for access control.

This is a design specification of the product.

**Q. The following error message is logged to the Authentication Module error log (certerr.log).
“Warning: Unknown RequestID Error. [XXNNNNN-NNNNN]”**

A. Check the items below:

- **Has the following message been output to the Forwarder error log?**

Warning: Bad Response Data. [XXNNNNN-NNNNN]

Warning: Send Request Failed. [XXNNNNN-NNNNN]

or

Fatal: Recv Data Failed. [XXNNNNN-NNNNN]

Fatal: Data Receive Failed. [XXNNNNN-NNNNN]

→ A timeout may have occurred in the Authentication Module.

See “RECVWAITTIME” in the Reference Manual, and change the request receive timeout value.

Also, network or related problems may make it impossible to receive a request. Ask the network administrator.

**Q. The following error message is output to the Authentication Module error log (certerr.log).
“Fatal: accept() Error: too many open files. [XXNNNNN-NNNNN]”**

A. Check the items below:

- **Is the maximum number of file descriptors (MAXDBCONNECT +MAXREQTHREAD+REQQESIZE+MAXREPTHREAD+20) used by the Authentication Module set higher than the maximum number of the OS configuration?**

→ The above message is output when the maximum number of file descriptors that can be handled by the Authentication Module exceeds the maximum number of the OS (Operating System) configuration.

The maximum number of file descriptors that can be handled by the Authentication Module varies by OS as follows:

HP-UX: 60,000, Linux: 8192

Correct the configuration values of these parameters so that the sum of the file descriptors does not exceed the maximum number which the OS can accommodate.

4.3 Common questions and other FAQs

Common questions regarding both Forwarder and the Authentication Module and other common questions are listed below.

- Q. Users can access the content even though they are not logged in. How is this problem fixed?
- Q. The login page is displayed repeatedly.
- Q. "Message Nothing[XXNNNNN-NNNNN]" is output to the error log.
- Q. Can you explain the meaning of the log messages?
- Q. When accessing a file with a Japanese file name, the Japanese file name in the access log appears as garbled characters.
- Q. How do I tune the performance?
- Q. Could you explain the parameter calculation methods for tuning IceWall performance?
- Q. Can I use basic authentication in reverse proxy mode?
- Q. Does IceWall possibly query the DNS server?
- Q. Status-Code 408 "Request Timeout" is output to the browser. What does this mean?
- Q. Can I set the Keep-Alive configuration of the Backend Web Servers to ON?
- Q. Could you explain the IceWall operating environment (such as OS, web server, and database)?
- Q. Does installing patches for the OS have any effect on IceWall?
- Q. How long will the product be supported?
- Q. Does the number of user licenses mean the number of simultaneous connections, or the number of registered users?
- Q. Could you explain the version upgrade procedure?
- Q. When upgrading, can I still use the configuration files of the previous version?
- Q. Does IceWall run correctly even on leap days?
- Q. What precautions should I take when backing up IceWall?
- Q. Does IceWall convert character code?

**Q. Users can access the content even though they are not logged in.
How is this problem fixed?**

A. Check the items below:

- **Are you using a cookie with an expiration date?**
→ Delete the cookies stored in the browser.
- **Is the system in reverse proxy mode?**
→ The login operation does not work in reverse proxy mode.
- **Is this really a URL by which the IceWall forwards the content?**
→ Check the URL.
- **Does the browser have an old cache?**
→ Delete the browser file cache, and then try accessing again. Also, enabling LASTMOD_HEADER of Forwarder can fix this problem in some cases.
See “LASTMOD_HEADER” in the Reference Manual.
- **Are you using the Forwarder functions where authentication or authorization is not needed?**
→ See “REV_PATH” and “NOCHK_EXT_ALIAS” in the Reference Manual.

Q. The login page is displayed repeatedly.

A. Check the items below:

- **Is the browser set to “Disable cookies”?**
→ Check the browser settings.
- **Is the content cached in a proxy server?**
→ The proxy server cache is displayed. Either change the path so that it does not pass through the proxy server, or change the proxy server settings.
- **Has a session timeout occurred?**
→ See “COOKIE TIME” and “LOMETHOD” in the Reference Manual.
- **Are duplicate logins set as forbidden?**
→ See “Session management” in the Web Application Developer's Manual and “COOKIE TIME,” “COOKIE EXP,” “LOMETHOD,” “DUP LOGIN,” and “DUP KIND” in the Reference Manual.

Q. “Message Nothing[XXNNNNN-NNNNN]” is output to the error log.

A. Check the items below:

The above error message may be output if the message catalog was not loaded properly due to an incomplete update of the message catalog or insufficient server resources.

Search the message ID of [XXNNNNN-NNNNN] in “8. Log Message List” in this manual and find the message text that should normally be output.

Q. Can you explain the meaning of the log messages?

A. Check the items below:

- **Access logs**

- See “Access logs” in the User's Manual and “8.1 Access log message list” in this manual.

- **Error logs**

- See “8.2 Error log message list” in this manual.

Q. When accessing a file with a Japanese file name, the Japanese file name in the access log appears as garbled characters.

A. Check the item below:

Japanese text in the access log cannot be displayed.

Currently, IceWall SSO is not fully compatible with URLs that contain Japanese, so no support is provided for Japanese URLs.

Q. How do I tune the performance?

A. Check the items below:

- **I want to do performance tuning of the IceWall SSO.**
→ See “Performance Tuning” in the User's Manual.
- **I want to do performance tuning of the web server.**
→ Refer to the web server manual and others.
- **I want to do performance tuning of the Authentication DB.**
→ Refer to the appropriate database manual.
- **I want to get system information to help me tune performance.**
→ For the Authentication Module, execute the info-cert command, and refer to the statistical information output to the access log.
- **I want to do performance tuning of the server itself.**
→ Please inquire with the OS provider and related resources directly.

Q. Could you explain the parameter calculation methods for tuning IceWall performance?

- A. See “Parameter calculation method” in the User's Manual.
For details on each configuration parameter, see the Reference Manual.

Q. Can I use basic authentication in reverse proxy mode?

A. No.

For details, see “Basic authentication configuration for reverse proxy mode” in the Web Application Developer's Manual.

Q. Does IceWall possibly query the DNS server?

- A. IceWall SSO does not directly query the DNS server.
Host name resolution and similar operations depend on the server network settings.

Q. Status-Code 408 “Request Timeout” is output to the browser. What does this mean?

- A. Status-Code request timeout may have occurred in the web server which runs Forwarder. Refer to the error logs on the web server, manuals, and others.

Q. Can I set the Keep-Alive configuration of the Backend Web Servers to ON?

- A. Depending on the content and configuration of the Backend Web Servers, the Keep-Alive configuration may cause a response delay, so HP recommends disabling it. For details, see “Keep-Alive configuration” in the Web Application Developer's Manual.

Q. Could you explain the IceWall operating environment (such as OS, web server, and database)?

- A. See “System Requirements” in the Installation Guide.
For the latest operating environment, see the Hewlett-Packard Japan homepage.
<http://h50146.www5.hp.com/products/software/security/icewall/ss0/spec/index.html>

Q. Does installing patches for the OS have any effect on IceWall?

- A. See “Known Issues” in the Release Note and “System Requirements” in the Installation Guide.

For the latest operating environment, see the Hewlett-Packard Japan homepage.

<http://h50146.www5.hp.com/products/software/security/icewall/ss0/spec/index.html>

Q. How long will the product be supported?

A. Product support will be provided as follows:

- Until two years after the end of availability of the product.

For details about service agreements, contact a Hewlett-Packard sales representative.

Q. Does the number of user licenses mean the number of simultaneous connections, or the number of registered users?

A. It means the number of registered users. For details, see “Understanding the Authentication Server licenses” in Read Me First.

Q. Could you explain the version upgrade procedure?

- A. See “Upgrading from Previous Versions” in the Installation Guide, or see the Release Note.

Q. When upgrading, can I still use the configuration files of the previous version?

- A. You can use it without changes since IceWall SSO supports backwards compatibility.
For notes about operation after upgrading, see “Upgrading from Previous Versions” in the Installation Guide, or see the Release Note.

Q. Does IceWall run correctly even on leap days?

A. IceWall does not perform calendar management, so leap years have no effect.

Q. What precautions should I take when backing up IceWall?

A. The following precautions should be taken when using tar and other commands to make a backup.

● **Authentication Module**

→ Perform a backup with an Authentication Module in a stopped state.

● **Forwarder**

→ Stop the web server running Forwarder before performing a backup.

● **Dynamic Menu**

→ Stop the web application server running Dynamic Menu before performing a backup.

● **Dynamic Menu Portal**

→ Stop the web application server running Dynamic Menu Portal before performing a backup.

● **Domain Gateway Option module**

→ Stop the web server running Forwarder and the Domain Gateway Option module before performing a backup.

● **Configuration Manager**

→ Stop the web application server running Configuration Manager before performing a backup.

● **CFGAgent**

→ CFGAgent is started and run only when a request is made. Therefore, as long as configuration changes are not being made with Configuration Manager, it does not need to be stopped.

Q. Does IceWall convert character code?

A. IceWall SSO modules basically do not convert character code.

The Authentication Module retrieves the user information from the authentication database without changing the character code stored in the authentication database. The Authentication Module sends the user information to Forwarder without converting the character code, and it also sends the information to the Backend Web Server in the same character code.

However, the Authentication Module converts character code exceptionally, only when all of the following conditions apply.

- **The LDAPLANG parameter is set to 1 in the Authentication Module configuration file (cert.conf).**
- **The authentication database is keeping user information registered in Unicode.**
- **A character code is specified by the environment variable IW_LANG.**

With all of these conditions satisfied, user information held in the Authentication Module is converted from Unicode to the character code specified with the IW_LANG environmental variable.

User information sent to Forwarder also remains in the same converted character code, and it is also sent to the Backend Web Server in that character code.

* If using Oracle, the character code depends on the locale set by NSL_LANG.
For details, see the Oracle manual.

5 Making Inquiries about Problems

This chapter describes the information necessary for making inquiries.

If your problem was not found in “4 Frequently Asked Questions (FAQ),” check the information here before making an inquiry.

5.1 Before making an inquiry

If your problem could not be resolved by examining the information in the manuals or through Internet references, collect the information below before making an inquiry.

- Type and version of the OS in use
- Type and version of the browser in use
- Type and version of the web server and Authentication DB
- Whether UserExit routines developed by the customer are installed.
Basically, support cannot be provided if UserExit routines that were developed by the customer are installed. However, if the UserExit routines cannot be uninstalled due to operational convenience or other reasons, check specific information such as what types of processes are performed and what types of libraries are used.
- Version information of Forwarder and the Authentication Module
For details on how to retrieve the version information, see “Verifying version information” in the Installation Guide.
- Log file information about the problem
For details on how to retrieve the log files, see “Log Files” in the User's Manual.

5.2 Contact information

After collecting the information above, please direct your inquiry to the contacts below.

A Service Agreement and System Handle are required for making inquiries.

Contact information for problems

HP Response Center

Refer to the set of documents titled “Support Service Information.”

Inquiries about HP IceWall SSO prices and non-technical matters

Inquiries about the HP IceWall family

http://www.hp.com/jp/iw_contact

6 Minimum and Maximum Parameter Values

This chapter describes the minimum and maximum parameter values that can be defined in the configuration files.

Parameters where the configuration parameters and values have been extended starting with a certain version are shown with their version numbers.

6.1 Forwarder (dfw)

6.1.1 Forwarder configuration file (dfw.conf)

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Basic configuration	ALEVEL	Number	0	2
	ELEVEL	Number	0	3
	ACCESS	String	1 character	255 characters
	ERROR	String	1 character	255 characters
	ERRORINFO	String	UID, URL, IP, or AGENT	UID, URL, IP, AGENT
	TRACE	String	1 character	255 characters
	CATALOG	String	1 character	255 characters
	SECURITY	String	1 character	255 characters
	SECINFO <small>(10.0)</small>	String	LOGIN, LOGOUT, PWDCHG, or AGENT	LOGIN, LOGOUT, PWDCHG, AGENT
	SECLEVEL	Number	0	2
	SECEXCPAGE	String	1 character	1024 characters
	SPKEY_TOPPAGE_URL <small>(10.0)</small>	String	1 character	255 characters
	TRANSID <small>(10.0)</small>	Number	0	1
	TRANSID_STR <small>(10.0)</small>	String	1 character	16 characters
	TRACETIME <small>(10.0)</small>	String	1 character	255 characters
	DFW_PROTOCOL	Number	0	1
	REQUEST_URI	Number	0	1
	VIRTUALPATH_ENV	String	1 character	255 characters
User authentication	VIRTUALURL_ALIAS	String	Alias name: 1 character URL: 1 character	Alias name: 64 characters URL: 128 characters
	CERT	String	Host name: 1 character Port number: 0	Host name: 64 characters Port number: 65535
	CERTLB <small>(10.0)</small>	String	Authentication module identification key: 1 character Host name: 1 character Port number: 0	Authentication module identification key: 1 character Host name: 64 characters Port number: 65535
	CERTLB_TYPE <small>(10.0)</small>	Number	0	1
	CERTFAILBACK <small>(10.0)</small>	String	Host name: 1 character Port number: 0	Host name: 64 characters Port number: 65535

IceWall SSO Version 10.0 / Troubleshooting Guide

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
User authentication	CERTLBFAILBACK <small>(10.0)</small>	String	Authentication module identification key: 1 character Host name: 1 character Port number: 0	Authentication module identification key: 1 character Host name: 64 characters Port number: 65535
	COOKIE_NAME	String	1 character	64 characters
	COOKIE_ATTR	String	1 character	256 characters
	COOKIE_ALWAYS	Number	0	2
	POSTLIMIT_PAGE	String	LOGIN, FORCELOGIN, or PWDCHG	LOGIN, FORCELOGIN, PWDCHG
	POSTLIMIT_TIME	Number	1	3600
	POSTLIMIT_ENC	String	1 character	256 characters
	FORCELOGIN_ENC	String	1 character	256 characters
	SESSION	Number	0	1
	POSTKEY_LOGIN	String	1 character	64 characters
	POSTKEY_LOGOUT	String	1 character	64 characters
	POSTKEY_PWDCHG	String	1 character	64 characters
	REDIRECT	String	1 character	255 characters
	LOALIAS	String	1 character	64 characters
	ICP_VERSION	String	1.1, or 2.0	1.1, or 2.0
	ICP_AGENTSTR	String	1 character	35 characters
	ICP_ENCSTR <small>(10.0)</small>	String	1 character	32 characters
Template HTML	DOCS	String	1 character	255 characters
	LOCATIONURL	String	1 character	255 characters
	LOCATIONRETRY	Number	1	9
	HTML_CHARSET	String	1 character	64 characters
Backend web server	HOST	String	Alias name: 1 character Host name: 1 character Proxy server name: 1 character	Alias name: 64 characters Host name: 64 characters Proxy server name: 64 characters
	SHOST	String	Alias name: 1 character Host name: 1 character	Alias name: 64 characters Host name: 64 characters
	SVRFILE	String	Alias name: 1 character File name: 1 character	Alias name: 64 characters File name: 255 characters
Password change	PWDALIAS	String	1 character	64 characters
	MINLEN	Number	1	128
	MAXLEN	Number	1	128
	EXPIRE	Number	0	2048
	SAMEPASS	Number	0	1
	ALPHANUM	Number	0	13
Performance tuning	RETRYCNTC	Number	1	256
	RETRYTMC	Number	0	60
	CERT_TOUT	Number	1	600
	ALLOC	Number	1	1048576
	SET_CONTENT_LENGTH	Number	0	1
	POSTWAITTIME	Number	0	65536
Security	MAXURL	Number	1	4096
	MAXQUERY	Number	1	4096

IceWall SSO Version 10.0 / Troubleshooting Guide

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Security	REV_PATH	Number	1 character	255 characters
	SESSION_ENC_KEY	String	1 character	256 characters
	DFWFILTER	String	0	2
	NOCHK_EXT_ALIAS	Number	Alias name: 1 character Case sensitivity flag: 0 Extension: 0 characters Overall settings: 4 characters	Alias name: 64 characters Case sensitivity flag: 1 Extension: 16 characters Overall settings: 256 characters
	REQUESTFILTER <small>10.0</small>	String	LOGIN,LOG-OUT,PWD-CHG,AGTLOGIN,or AGTPWDCHG	LOGIN,LOG-OUT,PWD-CHG,AGTLOGIN,A GTPWDCHG
Client certificates	CC_UID	String	CN, EMAIL, or OU	CN, EMAIL, or OU
	CC_UIDKEYS	String	1 character	64 characters
	CC_UIDKEYE	String	1 character	64 characters
	CC_ENVNAME	String	1 character	64 characters
	CC_DECODE_FLG	Number	0	1
	CC_ENVUID	String	1 character	64 characters
	CC_ENVSERIAL	String	1 character	64 characters
	CC_ENVEXPIRE	String	1 character	64 characters
POST data inheritance	CC_ENVISSUER	String	1 character	64 characters
	POST_INHERIT	Number	0	1
	MAXPOST	Number	1	1024
	POSTNAME	String	1 character	64 characters
	POST_HTML	String	1 character	255 characters
Agent	POST_ENC	String	1 character	256 characters
	AGENT_KEY	String	Keyword: 1 character Alias name: 1 character	Keyword: 32 characters Alias name: 32 characters
	AGENT_PERMIT	String	Alias name: 1 character Determination method: IP, HOST, DOMAIN, or IPV6 Value: 1 character	Alias name: 64 characters Determination method: IP, HOST, DOMAIN or IPV6 Value: 256 characters
	QUERY_ENC	String	1 character	256 characters
	QUERY_ENC_NAME	String	1 character	16 characters
	QUERRY_ENC_KIND <small>10.0</small>	String	1 character	16 characters
	RELOGIN_KEY	String	1 character	64 characters

6.1.2 Host configuration file (arbitrary file name)

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Content conversion	CTYPE	String	1 character	255 characters
	URLKEY	String	Tag name: 1 character Attribute name: 1 character	Tag name: 30 characters Attribute name: 32 characters
	REPKEY	String	Search string: 1 character Replacement string: 1 character	Search string: 1024 characters Replacement string: 1024 characters
	REPKEY_EXT <small>10.0</small>	String	Search string: 1 character Replacement string: 1 character	Search string: 1024 characters Replacement string: 1024 characters
	URLCONV_FLG	Number	0	1
	URLCONV_ATTR_FLG <small>10.0</small>	Number	0	1
	ATTRQUOT_FLG	Number	0	1
Error page	SYSERR	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	SYSTOUT	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	ERRKEY	String	Search string: 1 character File name: 1 character	Search string: 1024 characters File name: 255 characters
Basic authentication	BASICAUTH	Number	0	1
	BA_UID	String	1 character	64 characters
	BA_PWD	String	1 character	64 characters
Information inheritance	HTTPDATA	String	Authentication DB column name: 1 character Send header name: 1 character	Authentication DB column name: 255 characters Send header name: 255 characters
	HEADER	String	Target header name: 1 character Process: ADD, ENVADD, NOTSEND, MODNAME, or MODVALUE Value: 1 character	Target header name: 255 characters Process: ADD, ENVADD, NOTSEND, MODNAME, or MODVALUE Value: 255 characters
	HEADER_FILTER	String	UID, SESSION, COOKIE, or TID	UID, SESSION, COOKIE, or TID
	COOKIE_FILTER	String	1 character	64 characters
	HEADER_NAME_TID <small>10.0</small>	String	1 character	64 characters
	HEADER_NAME_UID <small>10.0</small>	String	1 character	64 characters
	HEADER_NAME_SID <small>10.0</small>	String	1 character	64 characters

IceWall SSO Version 10.0 / Troubleshooting Guide

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Information inheritance	RES_HEADER	String	Header name: 1 character Process: ADD, NOTSEND, MODNAME, or MODVALUE Value: 1 character	Header name: 255 characters Process: ADD, NOTSEND, MODNAME, or MODVALUE Value: 255 characters
	UNCONV_HEADER	String	LOCATION, or SET-COOKIE	LOCATION, SET-COOKIE
	CTRL_SPKEY	String	0 characters	\$DFW,\$REQUEST_URL,\$HI-DEURL,\$ALIAS,\$USER_ID,\$PASSWORD,\$IW_INFO,\$KEY_LOGIN,\$KEY_LOG-OUT,\$KEY_PWDCHG,\$PWDCHG_URL,\$LOGOUT_URL,\$TOPPAGE_URL,\$PW-DHIDEURL,\$IWTID
Handling of cross-site scripting	GETFILTER	String	1 character	32 characters
	GETEXCEPTION	String	1 character	32 characters
	GETFILTERERR	Number	0	2
	GETFILTER_LOG_FLG	Number	0	1
	POSTFILTER	String	1 character	32 characters
	POSTEXCEPTION	String	1 character	32 characters
	POSTFILTERERR	Number	0	2
	POSTFILTER_LOG_FLG	Number	0	1
	HTMLFILTER	String	1 character	32 characters
	HTMLFILTERERR	Number	0	2
	SVRFILTER	Number	0	2
	SVREXCEPTION	String	1 character	256 characters
	SVRFILTERERR	Number	0	2
	SVRFILTERSTR	String	1 character	64 characters
System tuning configuration	RETRYCNTW	Number	1	256
	RETRYTMW	Number	0	60
	TIMEOUT	Number	1	600
	CLOSETIME	Number	1	600
	BUFFER	Number	0	1
	LASTMOD_HEADER	Number	0	1
	CENCODE	Number	0	1
	URL_SCOLON	Number	0	1
	FO_SEND	Number	0	1
	FO_RECV	Number	0	1
	FO_NODATA	Number	0	1
	RECV_ZERO_FLG	Number	0	1
Form authentication	FORM_FILE	String	1 character	255 characters
Security	SSL_CIPHER_SUITE	String	1 character	512 characters

6.1.3 Form authentication configuration file (arbitrary file name)

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Form authentication	FORM_METHOD	String	GET or POST	GET or POST
	FORM_SEND	String	Group name: 1 character Recipient path: 1 character	Group name: 64 characters Recipient path: 4096 characters
	FORM_URL	String	Group name: 1 character Target path: 1 character	Group name: 64 characters Target path: 255 characters
	FORM_KEY	String	Group name: 1 character Keyword: 1 character	Group name: 64 characters Keyword: 1024 characters
	FORM_HTML	String	Group name: 1 character File name: 1 character	Group name: 64 characters File name: 255 characters
	FORM_DATA_STR	String	Group name: 1 character Data type: POSTDATA, QUERY, ENCVAL, or NOENCVAL Attribute name: 1 character Attribute value: 1 character	Group name: 64 characters Data type: POSTDATA, QUERY, ENCVAL, or NOENCVAL Attribute name: 64 characters Attribute value: 1024 characters
	FORM_DATA_USR	String	Group name: 1 character Data type: POSTDATA, QUERY, ENCVAL, or NOENCVAL Attribute name: 1 character Authentication DB column name: 1 character	Group name: 64 characters Data type: POSTDATA, QUERY, ENCVAL, or NOENCVAL Attribute name: 64 characters Authentication DB column name: 64 characters
	FORM_DATA_PAGE	String	Group name: 1 character Data type: POSTDATA, QUERY, ENCVAL, or NOENCVAL Attribute name: 1 character Search attribute name: 1 character	Group name: 64 characters Data type: POSTDATA, QUERY, ENCVAL, or NOENCVAL Attribute name: 64 characters Search attribute name: 64 characters
	FORM_KEY_EXCEPTION <small>(10.0)</small>	String	Group name: 1 character Keyword: 1 character	Group name: 64 characters Keyword: 1024 characters
	FORM_DATA_PAGE_REF <small>(10.0)</small>	Number	0	1

6.1.4 HTML configuration file (html.conf)

Page parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Login	LOGIN_UID	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_CERT	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_FORCE	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_ERR_UID	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_ERR_PWD	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_ERR_LOCK	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_ERR_1STCERT	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_ERR_SERIAL	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_ERR_NOGRP	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_ERR_STOP	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_ERR_LIMIT	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGIN_ERR_POSTLIMIT	String	1 character	255 characters

IceWall SSO Version 10.0 / Troubleshooting Guide

Page parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Access control	ACCESS_DENY	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	DATA_SEND_ERR	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	REQUEST_ACL_ERR <small>10.0</small>	String	Filename: 1 character Status: 000 Status message: 1 character	Storage location, filename: 255 characters Status: 999 Status message: 255 characters
	FILTER_REQUEST <small>10.0</small>	String	Filename: 1 character Status: 000 Status message: 1 character	Filename: 255 characters Status: 999 Status message: 255 characters
POST data inheritance error	MAXPOST_ERR	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
Logout	LOGOUT	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGOUT_SUCCESS	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGOUT_EXPIRE	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	LOGOUT_FAILURE	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
Password change	PWDCHG	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	PWDCHG_SUCCESS	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	PWDCHG_ERR_OLD	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	PWDCHG_ERR_REENT	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	PWDCHG_ERR_POLICY	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters

IceWall SSO Version 10.0 / Troubleshooting Guide

Page parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Password change	PWDCHG_ERR_LOG NG	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	PWDCHG_ERR_VIO	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	PWDCHG_FAILURE	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	PWDCHG_WARNING	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	PWDCHG_ERR_POST LIMIT	String	1 character	255 characters
Cross-site scripting errors	FILTER_GET	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	FILTER_POST	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	FILTER_HTML	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	FILTER_SVR	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
System errors	SYSTEM_ERR	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	SYSTEM_ERR_NOALIAS	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	SYSTEM_ERR_BADALIAS	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	SYSTEM_DOWN_CERTD	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	SYSTEM_DOWN_DB	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	SYSTEM_DOWN_HTTP	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters

Page parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
System errors	SYSTEM_TOUT_CER TD	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	SYSTEM_TOUT_HTTP	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	SYSTEM_BUSY_DB (10.0)	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
User-defined errors	USREXT_ERR1	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	USREXT_ERR2	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	USREXT_ERR3	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	USREXT_ERR4	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	USREXT_ERR5	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters
	USREXT_ERR6	String	URL: 1 character Status: 000 Status message: 1 character	URL: 255 characters Status: 999 Status message: 255 characters

6.2 Authentication Module (certd)

6.2.1 Authentication Module configuration file (cert.conf)

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Basic configuration	ALEVEL	Number	0	3
	ELEVEL	Number	0	3
	ACCESS	String	1 character	255 characters
	ERROR	String	1 character	255 characters
	TRACE	String	1 character	255 characters
	CATALOG	String	1 character	255 characters
	LOGINFO	Number	0	2
	LOGPERF	Number	0	1
	PERFORMANCE	String	1 character	255 characters
	INFORMATION	String	1 character	255 characters
	TRANSID	Number	0	1
	PORT	Number	0	65535
	IPV6LISTEN (10.0)	Number	0	2

IceWall SSO Version 10.0 / Troubleshooting Guide

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Basic configuration	HTTPPORT <small>(10.0)</small>	Number	1	65535
	HTTPECHOHEADER <small>(10.0)</small>	Number	0	1
Access control	GROUP	String	1 character	255 characters
	ACL	String	1 character	255 characters
	ACLREQUEST	String	1 character	255 characters
	ADGROUP	Number	0	1
	ADGROUPDN	String	1 character	255 characters
	ADGROUPINTERVAL	Number	0	86400
	ADGROUPPRINAME	String	1 character	255 characters
	ADGROUPPREFIX	String	1 character	255 characters
	ADGROUPMAXMEMBER	Number	0	50
Session policy	COOKIE TIME	Number	1	32768
	COOKIEEXP	Number	0	1
	COOKIERETRY	Number	0	100
	LOMETHOD	Number	0	1
	DUPLOGIN	Number	0	1
	DUPKIND	Number	0	1
	PARALOGIN	Number	0	1
	ACCCTRLFLG	Number	0	2
	CERTUNIQUEKEY <small>(10.0)</small>	String	1 character	1 character
	SESSIONIDLEN <small>(10.0)</small>	Number	32 or 64	32 or 64
Password policy	LOCKCOUNT	Number	0	256
	PWDEXPCHK	Number	0	1
	PWDHISCHK	Number	0	1
	PWDHISCNT	Number	1	9
	PWDFORBID	String	1 character	255 characters
	PWDEXPWARN	Number	0	365
	PWDLOGINHASH <small>(10.0)</small>	String	MD5, SHA, SHA256, PLAIN, AUTO-PLAIN, or AUTO-MD5	MD5, SHA, SHA256, PLAIN, AUTO-PLAIN, or AUTO-MD5
	PWDCHGHASH <small>(10.0)</small>	String	MD5, SHA, SHA256, PLAIN, AUTO-PLAIN, or AUTO-MD5	MD5, SHA, SHA256, PLAIN, AUTO-PLAIN, or AUTO-MD5
	PWDMINLEN <small>(10.0)</small>	Number	1	128
	PWDMAXLEN <small>(10.0)</small>	Number	1	128
	PWDEXPIRE <small>(10.0)</small>	Number	0	2048
	PWDSAMEPASS <small>(10.0)</small>	Number	0	1
	PWDALPHANUM <small>(10.0)</small>	Number	0	13
Authentication DB	DBHOST (ORACLE edition)	String	SID: 1 character	SID: 32 characters
	DBHOST (LDAP edition)	String	Host name: 1 character Port number: 0	Host name: 64 characters Port number: 65535
	DBHOST (MSAD edition)	String	Host name: 1 character Port number: 0	Host name: 64 characters Port number: 65535

IceWall SSO Version 10.0 / Troubleshooting Guide

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Authentication DB	DBHOST (NED edition)	String	Host name: 1 character Port number: 0	Host name: 64 characters Port number: 65535
	DBHOST (MySQL edition)	String	Database name: 1 character Host name: 1 character Port number: 0 ODBC driver name: 1 character	Database name: 64 characters Host name: 64 characters Port number: 65535 ODBC driver name: 64 characters
	DBUID	String	1 character	256 characters
	DBPWD	String	1 character	256 characters
	DBTBL	String	1 character	255 characters
	DBATTR	String	1 character	255 characters
	DBEXATTR	String	1 character	4087 characters
	LDAPBIND	Number	0	1
	LDAPPCHG	Number	0	1
	LDAPLANG	Number	0	1
	LDAPSSL	Number	0	1
	LDAPCACERT	String	1 character	255 characters
	LDAPVERIFYS-VRCERT	Number	0	1
	LDAPCIPHERSUITE	String	1 character	255 characters
	LDAPSSLBIND	Number	0	1
	ADPCHG	Number	0	1
	LDAPMULTIVAL	Number	0	1
	LDAPREFERRAL	Number	0	1
	ADDGFWBIND	Number	0	1
	DBCRYPTOATTR	String	1 character	4087 characters
	DBCRYPTOTYPE	Number	0	3
	DBIWCRYPTOSEED	String	1 character	255 characters
Expansion table (ORACLE edition only)	LOGDBTBL	String	1 character	64 characters
	LOGDBATTR	String	1 character	255 characters
	LOGDBSEQNAME	String	1 character	64 characters
Reference table (ORACLE and MySQL editions only)	REFTBL	String	1 character	64 characters
	REFATTR	String	1 character	Number of columns: 1000 4087 characters
	REFUID	String	1 character	64 characters

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
System tuning configuration	MAXREQTHREAD	Number	1	4096
	REQQUEZISE	Number	1	65535
	MAXDBCONNECT	Number	1	4096
	LOGBUFSIZE	Number	1	65535
	CACHE	Number	1	int maximum value
	RECVWAITTIME	Number	1	60
	THREADSTACKSIZE	Number	HP-UX: 4 Linux: 16	2048
	ACCTHREAD (10.0)	Number	0	MAXREQTHREAD parameter value: -1
	DBQUESIZE (10.0)	Number	0	CACHE parameter value
	LOGDBQUESIZE (10.0)	Number	0	CACHE parameter value
	DOWNLOADCONF-FLG (10.0)	Number	0	1
	MAXLOGINUSER (10.0)	Number	0	CACHE parameter value
	DBQUERYCNT (10.0)	Number	0	1
Replication	CERT	String	Host name: 1 character Port number: 0	Host name: 64 characters Port number: 65535
	CERTREPTYPE	Number	0	1
	RETRYCNTC	Number	0	256
	RETRYTMC	Number	0	60
	LIVETIMER	Number	1	600
Replication	HEALTHTIMER	Number	1	60
	HEALTHCNT	Number	1	256
	FAILBACK	Number	0	1
	MAXREPTHREAD	Number	1	4096
	REPQUESIZE	Number	1	65535

6.2.2 Group configuration file (cert.grp)

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
	Group definition	String	Group name: 1 character Conditions: 1 character	Group name: 32 characters Conditions: 2048 characters

6.2.3 Access control file (cert.acl)

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
	Access control definition	String	URL: 1 character Conditions: 1 character	URL: 1024 characters Conditions: 2048 characters

6.2.4 Authentication DB column information file (dbattr.conf)

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Basic user information	UID	String	1 character	64 characters
	PASSWORD	String	1 character	64 characters
	PWDEXPDATE	String	1 character	64 characters
	PWDHISTORY	String	1 character	64 characters
	PCHGOK	String	1 character	64 characters
	PCHGDATE	String	1 character	64 characters
	LLOGINDATE	String	1 character	64 characters
	PLOGINDATE	String	1 character	64 characters
	FLOGINDATE	String	1 character	64 characters
	PWDRETRY	String	1 character	64 characters
	PWDLOCK	String	1 character	64 characters
	LOGINOK	String	1 character	64 characters
	LOCKDATE	String	1 character	64 characters
	LOGINSTAT	String	1 character	64 characters
Client certificate information	RASERIALNO	String	1 character	64 characters
	IWSERIALNO	String	1 character	64 characters
	CERTEXPDATE	String	1 character	64 characters
	GETCERT	String	1 character	64 characters
	ONLINE	String	1 character	64 characters

6.2.5 Log column information file (logdbattr.conf)

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
Basic information	NO	String	1 character	64 characters
	TIME	String	1 character	64 characters
	UID	String	1 character	64 characters
	KIND	String	1 character	64 characters
	RESULT	String	1 character	64 characters
	MSG	String	1 character	64 characters
	CLIP	String	1 character	64 characters
Client certificate information	SERIAL	String	1 character	64 characters

6.2.6 Forbidden password configuration file (pwdforbid.conf)

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
	forbidden_character_string	String	1 character 1 line	128 characters 256 lines

6.2.7 Request control configuration file (request.acl)

IceWall SSO Version 10.0 / Troubleshooting Guide

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
	TARGET	String	Condition expression: 1 character	Condition expression: 2048 characters
	VERSION	String	Either 1.0 or 2.0	Either 1.0 or 2.0
	REJECT	String	LOGINUID, FLOGINUID, LOGINCERT, FLOGINCERT, ACCESSUID, ACCESSCERT, PWDCHG, LOGOUT, or ALL	LOGINUID, FLOGINUID, LOGINCERT, FLOGINCERT, ACCESSUID, ACCESSCERT, PWDCHG, LOGOUT, ALL
	SEND	String	1 character	4091 characters
	NOTSEND	String	User information name: 1 character	4088 characters
	ACCCTRL	String	uid, cert, or certnoid	uid, cert, certnoid

6.3 Dynamic Menu Portal (dmp)**6.3.1 Servlet configuration file (web.xml)**

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
context-param	ContentEncoding	String	1 character	Maximum size of string
	Log4jPropertiesFilePath	String	1 character	Maximum size of string
	ConfigurationFilePath	String	1 character	Maximum size of string
	SystemErrorFilePath	String	1 character	Maximum size of string
	SystemErrorFileEncoding	String	1 character	Maximum size of string
	NoLoginErrorFilePath	String	1 character	Maximum size of string
	NoLoginErrorFileEncoding	String	1 character	Maximum size of string
	RequestACLErrorFilePath (10.0)	String	1 character	Maximum size of string
	RequestACLErrorFileEncoding (10.0)	String	1 character	Maximum size of string
servlet-mapping	DynamicMenuPortalServlet (10.0)	String	1 character	Maximum size of string

6.3.2 Log configuration file (log4j.properties)

Not restricted in Dynamic Menu Portal.

See the log4j manual.

6.3.3 Dynamic Menu Portal configuration file (dmp.xml)

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
dmp:CertInformation	dmp:Active	String	Host name: 1 character Port number: 1	Maximum size of string
	dmp:Standby	String	Host name: 1 character Port number: 1	Maximum size of string
	dmp:Master (10.0)	String	Host name: 1 character Port number: 1	Maximum size of string
	dmp:Replica (10.0)	String	Host name: 1 character Port number: 1	Maximum size of string
	dmp:Timeout	Number	1	600
	dmp:RetryInterval	Number	1	60
	dmp:RetryCount	Number	1	256
	dmp:SessionHeaderName	String	1 character	Maximum size of string
	dmp:TransactionHeaderName (10.0)	String	1 character	Maximum size of string
	dmp:ICPVersion (10.0)	String	1 character	Maximum size of string
	dmp:ICPAgentStr (10.0)	String	1 character	Maximum size of string
	dmp:ICPRemoteAddressHeaderName (10.0)	String	1 character	Maximum size of string
	dmp:ICPMethodHeaderName (10.0)	String	1 character	Maximum size of string
	dmp:ICPUserAgentHeaderName (10.0)	String	1 character	Maximum size of string

IceWall SSO Version 10.0 / Troubleshooting Guide

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
dmp:CertInformation, dmp:CertLB 10.0	dmp:Active	String	Host name: 1 character Port number: 1	Maximum size of string
	dmp:Standby	String	Host name: 1 character Port number: 1	Maximum size of string
	dmp:Master	String	Host name: 1 character Port number: 1	Maximum size of string
	dmp:Replica	String	Host name: 1 character Port number: 1	Maximum size of string
	dmp:CertUniqueKey	String	1 character	1 character
dmp:Template	dmp:Path	String	1 character	Maximum size of string
	dmp:Encoding	String	1 character	Maximum size of string
dmp:Source (FILE format)	dmp:Alias	String	1 character	Maximum size of string
	dmp:Type	String	Fixed to file	Fixed to file
dmp:Source, dmp:Params	dmp:Path	String	1 character	Maximum size of string
	dmp:Encoding	String	1 character	Maximum size of string
dmp:Source (TEXT format)	dmp:Alias	String	1 character	Maximum size of string
	dmp:Type	String	Fixed to text	Fixed to text
dmp:Source, dmp:Params	dmp:Text	String	1 character	Maximum size of string
dmp:Source (HTTP format)	dmp:Alias	String	1 character	Maximum size of string
	dmp:Type	String	Fixed to http	Fixed to http
dmp:Source, dmp:Params	dmp:URL	String	1 character	Maximum size of string
	dmp:Text	String	1 character	Maximum size of string
	dmp:HeaderName	String	1 character	Maximum size of string
dmp:Condition (Header format)	dmp:Alias	String	1 character	Maximum size of string
	dmp:Type	String	Fixed to header	Fixed to header
dmp:Condition, dmp:Params	dmp:HeaderName	String	1 character	Maximum size of string
	dmp:HeaderValue	String	1 character	Maximum size of string
dmp:Condition (ACL format)	dmp:Alias	String	1 character	Maximum size of string
	dmp:Type	String	Fixed to ACL	Fixed to ACL
dmp:Condition, dmp:Params	dmp:URL	String	1 character	Maximum size of string
dmp:Condition (Time format)	dmp:Alias	String	1 character	Maximum size of string
	dmp:Type	String	Fixed to time	Fixed to time
dmp:Condition, dmp:Params	dmp:Time	String	1 character	Maximum size of string

IceWall SSO Version 10.0 / Troubleshooting Guide

Parameter category	Parameter name	Configuration attribute type	Minimum value	Maximum value
dmp:Condition (Unconditional format)	dmp:Alias	String	1 character	Maximum size of string
	dmp:Type	String	Fixed to unconditional	Fixed to unconditional
dmp:Replace	dmp:Alias	String	1 character	Maximum size of string
	dmp:SourceAlias	String	1 character	Maximum size of string
	dmp:ConditionAlias	String	1 character	Maximum size of string

7 Log Message List

This chapter provides lists of log messages produced by IceWall SSO.
Refer to this chapter for the logs that you cannot understand the meaning of.

The log messages are listed in the order following order:
First, Level is sorted in the order of FATAL, WARNING, and INFO.
Second, Code IDs are sorted in ascending order within each level.

7.1 Access log message list

7.1.1 Authentication Module access log

Code ID	Level	Message	Description
AC01904-25035	FATAL	Password Expired. UserID=%s	Password has expired. Output value: [UserID= <u>user ID</u>]
AC01905-25001	FATAL	Access Control Request Auth Type Not Match. UserID=%s	The cache authentication method and received authentication method are different. Output value: [UserID= <u>user ID</u>]
AC01906-25005	FATAL	Access Request Auth User Not Match. OldUser=%s, NewUser=%s	The logged in user and user ID requesting access are different. Output value: [OldUser= <u>first logged in user ID</u>] [NewUser= <u>current user ID</u>]
AC01907-25001	FATAL	Access Control Request Auth Type Not Match. UserID=%s	The cache authentication method and received authentication method are different. Output value: [UserID= <u>user ID</u>]
AC01908-25052	FATAL	Request URL Denied. UserID=%s URL=%s	The access permission check did not allow the user with the User ID to access the URL. Output value: [UserID= <u>user ID</u>] [URL= <u>URL</u>]
AC01909-25051	FATAL	Request Group Denied. UserID=%s URL=%s	The group access permission check did not allow the user with the group membership to access the URL. Output value: [UserID= <u>user ID</u>] [URL= <u>URL</u>]
AC01911-25112	FATAL	Deny Request From SOURCE_ADDR=%s Accctrl=%s	URL access privilege verification using user ID was denied. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Accctrl= <u>UID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC01912-25112	FATAL	Deny Request From SOURCE_ADDR=%s Accctrl=%s	URL access privilege verification using client certificate was denied. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Accctrl= <u>CERT</u>]
AC01913-25005	FATAL	Access Request Auth User Not Match. OldUser=%s, NewUser=%s	The logged in user and user ID requesting access are different. Output value: [OldUser= <u>first logged in user ID</u>] [NewUser= <u>current user ID</u>]
AC05901-25016	FATAL	IW Serial Exist. But RA Serial Not Exist. UserID=%s Cert=%d	RA serial does not exist, but IW serial exists. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC05902-25047	FATAL	RA Serial is Not Registered. UserID=%s Cert=%d	Neither RA serial nor IW serial exists. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC06001-25047	FATAL	RA Serial is Not Registered. UserID=%s Cert=%d	RA serial is not registered in Authentication DB. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC06003-25041	FATAL	RA Serial And Receive Serial Not Match. UserID=%s Cert=%d	RA serial and received serial do not match. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC06005-25049	FATAL	Receive Unknown Serial. UserID=%s Cert=%d	Received serial is abnormal. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC10101-25072	FATAL	UserID Not Exist.	User ID does not exist.
AC10104-25058	FATAL	Unknown UserID. UserID=%s	User ID is not registered in the Authentication DB. Output value: [UserID= <u>user ID</u>]
AC10105-25061	FATAL	User Login Error (Database Access). UserID=%s	Could not retrieve user information from the Authentication DB. Output value: [UserID= <u>user ID</u>]
AC10106-25061	FATAL	User Login Error (Database Access). UserID=%s	Could not retrieve user information from the Authentication DB. Output value: [UserID= <u>user ID</u>]
AC10107-25050	FATAL	Reference Unknown UserID. UserID=%s	Cannot retrieve reference database information. Output value: [UserID= <u>user ID</u>]
AC10108-25050	FATAL	Reference Unknown UserID. UserID=%s	Cannot retrieve reference database information. Output value: [UserID= <u>user ID</u>]
AC10109-25017	FATAL	Login Lock. UserID=%s	Login is locked. Output value: [UserID= <u>user ID</u>]
AC10110-25040	FATAL	Password Lock Error. UserID=%s	Password is locked. Output value: [UserID= <u>user ID</u>]
AC10111-25037	FATAL	Password is NULL. UserID=%s	Password is NULL. Output value: [UserID= <u>user ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC10112-25038	FATAL	Password Lock. UserID=%s	Password is locked. Output value: [UserID= <u>user ID</u>]
AC10113-25079	FATAL	Login Password Hash Error. UserID=%s	Password hash error occurred. Output value: [UserID= <u>user ID</u>]
AC10115-25034	FATAL	Password Error. UserID=%s	Password error occurred. Output value: [UserID= <u>user ID</u>]
AC10116-25038	FATAL	Password Lock. UserID=%s	Password is locked. Output value: [UserID= <u>user ID</u>]
AC10117-25007	FATAL	Can Not Access For Uid/Password. UserID=%s	Cannot log in with Uid/Password. Output value: [UserID= <u>user ID</u>]
AC10118-25008	FATAL	Client Certificate Error. UserID=%s	Failed to check the Client Certificate used for certificate login. Output value: [UserID= <u>user ID</u>]
AC10123-25023	FATAL	Max User Login. Login Failed. UserID=%s	Could not log in because the number of user logins reached the maximum count. Output value: [UserID= <u>user ID</u>]
AC10127-25061	FATAL	User Login Error (Database Access). UserID=%s	Cannot retrieve SAML user information. Output value: [UserID= <u>user ID</u>]
AC10903-25066	FATAL	User Logout Error. UserID=%s	Could not delete the user information from the user cache. Output value: [UserID= <u>user ID</u>]
AC11404-25077	FATAL	Password Change Database Error. UserID=%s	Could not retrieve the password information from the cache or authentication database column. Output value: [UserID= <u>user ID</u>]
AC11407-25080	FATAL	New Password Hash Error. UserID=%s	Failed to hash new password. Output value: [UserID= <u>user ID</u>]
AC11413-25077	FATAL	Password Change Database Error. UserID=%s	Failed to change authentication database password data. Output value: [UserID= <u>user ID</u>]
AC11415-25027	FATAL	Password Change Error. UserID=%s	Failed to change password. Output value: [UserID= <u>user ID</u>]
AC11417-25027	FATAL	Password Change Error. UserID=%s	Failed to change password. Output value: [UserID= <u>user ID</u>]
AC17802-25088	FATAL	Reference User Login Status Request. UserID=%s	Login status request occurred. Output value: [UserID= <u>user ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC17804-25089	FATAL	Reference Forced to Logout Request. UserID=%s	Forced logout request occurred. Output value: [UserID= <u>user ID</u>]
AC17805-25090	FATAL	Reference Forced to Logout Request. UserID(First)=%s	Forced logout request occurred. Output value: [UserID= <u>user ID</u>]
AC17806-25091	FATAL	Reference Forced to Logout Request. UserID(ALL)=%s	Forced logout request occurred. Output value: [UserID= <u>user ID</u>]
AC17807-25091	FATAL	Reference Forced to Logout Request. UserID(ALL)=%s	Forced logout request occurred. Output value: [UserID= <u>user ID</u>]
AC18001-25092	FATAL	Reference Unknown UserID Status Error. UserID=%s	Target user ID of login status request does not exist. Output value: [UserID= <u>user ID</u>]
AC18002-25097	FATAL	Reference Unknown UserID Logout Error. UserID=%s.	Cannot log out because target user ID does not exist. Output value: [UserID= <u>user ID</u>]
AC18003-25098	FATAL	Reference Format Error. Req-ID=%c.	Status request format error occurred. Output value: [Req-ID= <u>request ID</u>]
AC18004-25098	FATAL	Reference Format Error. Req-ID=%c.	Status request format error occurred. Output value: [Req-ID= <u>request ID</u>]
AC18005-25094	FATAL	Reference Forced to Logout Success. UserID=%s.	Forced logout succeeded. Output value: [UserID= <u>user ID</u>]
AC18006-25095	FATAL	Reference Forced to Logout Success. UserID(First)=%s.	Forced logout succeeded. Output value: [UserID= <u>user ID</u>]
AC18007-25096	FATAL	Reference Forced to Logout Success. UserID(ALL)=%s.	Forced logout succeeded. Output value: [UserID= <u>user ID</u>]
AC18008-25096	FATAL	Reference Forced to Logout Success. UserID(ALL)=%s.	Forced logout succeeded. Output value: [UserID= <u>user ID</u>]
AC18101-25093	FATAL	Reference User Login. UserID=%s. Count=%d.	Login request occurred. Output value: [UserID= <u>user ID</u>] [Count= <u>number of users</u>]
AC18201-25093	FATAL	Reference User Login. UserID=%s. Count=%d.	Login request occurred. Output value: [UserID= <u>user ID</u>] [Count= <u>number of users</u>]
AC18202-25092	FATAL	Reference Unknown UserID Status Error. UserID=%s	Target user ID of login status request does not exist. Output value: [UserID= <u>user ID</u>]
AC18401-25097	FATAL	Reference Unknown UserID Logout Error. UserID=%s.	Cannot log out because target user ID does not exist. Output value: [UserID= <u>user ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC18503-25100	FATAL	Reference User Logout Error. UserID=%s	Failed to log out. Output value: [UserID= <u>user ID</u>]
AC31004-25111	FATAL	Ununique Cookie. UserID=%s %s	Existing session ID was generated. Output value: [UserID= <u>user ID</u>] [<u>session ID</u>]
AC70286-25061	FATAL	User Login Error (Database Access). UserID=%s	Could not decrypt user information when retrieving from the authenticatin DB. Output value: [UserID= <u>user ID</u>]
AC70369-25017	FATAL	Login Lock. UserID=%s	Login is locked. Output value: [UserID= <u>user ID</u>]
AC70379-25007	FATAL	Can Not Access For Uid/Password. UserID=%s	Cannot log in with Uid/Password. Output value: [UserID= <u>user ID</u>]
AC70382-25008	FATAL	Client Certificate Error. UserID=%s	Failed to check the Client Certificate used for certificate login. Output value: [UserID= <u>user ID</u>]
AC70515-25100	FATAL	Reference User Logout Error. UserID=%s	Failed to log out. Output value: [UserID= <u>user ID</u>]
AC71120-25016	FATAL	IW Serial Exist. But RA Serial Not Exist. UserID=%s Cert=%d	RA serial does not exist, but IW serial exists. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC71122-25047	FATAL	RA Serial is Not Registered. UserID=%s Cert=%d	RA serial is not registered in Authentication DB. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC71124-25041	FATAL	RA Serial And Receive Serial Not Match. UserID=%s Cert=%d	RA serial and received serial do not match. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC71126-25049	FATAL	Receive Unknown Serial. UserID=%s Cert=%d	Received serial is abnormal. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC71136-25072	FATAL	UserID Not Exist.	User ID does not exist.
AC71137-25058	FATAL	Unknown UserID. UserID=%s	User ID is not registered in the Authentication DB. Output value: [UserID= <u>user ID</u>]
AC71138-25017	FATAL	Login Lock. UserID=%s	Login is locked. Output value: [UserID= <u>user ID</u>]
AC71139-25037	FATAL	Password is NULL. UserID=%s	Password is NULL. Output value: [UserID= <u>user ID</u>]
AC71140-25038	FATAL	Password Lock. UserID=%s	Login is locked. Output value: [UserID= <u>user ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC71141-25034	FATAL	Password Error. UserID=%s	Password error occurred. Output value: [UserID= <u>user ID</u>]
AC71142-25038	FATAL	Password Lock. UserID=%s	Login is locked. Output value: [UserID= <u>user ID</u>]
AC71143-25007	FATAL	Can Not Access For Uid/Password. UserID=%s	Cannot log in with Uid/Password. Output value: [UserID= <u>user ID</u>]
AC71144-25008	FATAL	Client Certificate Error. UserID=%s	Failed to check the Client Certificate used for certificate login. Output value: [UserID= <u>user ID</u>]
AC71147-25023	FATAL	Max User Login. Login Failed. UserID=%s	Could not log in because the number of user logins reached the maximum count. Output value: [UserID= <u>user ID</u>]
AC71150-25066	FATAL	User Logout Error. UserID=%s	Could not delete the user information from the user cache. Output value: [UserID= <u>user ID</u>]
AC01901-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC01910-25006	WARNING	Access. UserID=%s, URL=%s	Finished access privilege verification. Output value: [UserID= <u>user ID</u>] [URL= <u>URL</u>]
AC07102-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC10102-25063	WARNING	User Login Request. UserID=%s IPAddress=%s	User authentication using user ID. Output value: [UserID= <u>user ID</u>] [IPaddress= <u>IP address</u>]
AC10103-25064	WARNING	User Login Request. UserID=%s SerialNo=%s Expire=%s IPAddress=%s	User authentication using client certificate. Output value: [UserID= <u>user ID</u>] [Serial No.= <u>certificate serial</u>] [Expire= <u>certificate expiration date</u>] [IPaddress= <u>IP address</u>]
AC10119-25026	WARNING	No Group User. UserID=%s	There is no group assigned. Output value: [UserID= <u>user ID</u>]
AC10121-25013	WARNING	Forced to Logout. UserID=%s %s	Forced logout occurred. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]
AC10124-25065	WARNING	User Login. UserID=%s	User logged in. Output value: [UserID= <u>user ID</u>]
AC10125-25108	WARNING	SAML User Login Request. UserID=%s IPAddress=%s	SAML user ID authentication started (forced authentication). Output value: [UserID= <u>user ID</u>] [IPaddress= <u>IP address</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC10126-25109	WARNING	Federation User Login Request. UserID=%s IPAddress=%s	Federation user ID authentication started (forced authentication). Output value: [UserID= <u>user ID</u>] [IPAddress= <u>IP address</u>]
AC10901-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC10904-25068	WARNING	User Logout. UserID=%s %s	Logged out. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]
AC11304-25020	WARNING	Login Timeout. UserID=%s %s	User logged out due to a timeout. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]
AC11402-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC11405-25031	WARNING	Password Change Permission Error. UserID=%s	No password change privileges. Output value: [UserID= <u>user ID</u>]
AC11409-25028	WARNING	Password Change History Error. UserID=%s	Current password matches new password, or current password is NULL. Output value: [UserID= <u>user ID</u>]
AC11410-25028	WARNING	Password Change History Error. UserID=%s	New password matches one in password history. Output value: [UserID= <u>user ID</u>]
AC11411-25030	WARNING	Password Change Pattern Error. UserID=%s	New password matches forbidden character string. Output value: [UserID= <u>user ID</u>]
AC11412-25027	WARNING	Password Change Error. UserID=%s	Failed to change password. Output value: [UserID= <u>user ID</u>]
AC11416-25033	WARNING	Password Changed. UserID=%s	Password change succeeded. Output value: [UserID= <u>user ID</u>]
AC11418-25113	WARNING	Password Change Invalid Character Error. UserID=%s	New password contains invalid characters. Output value: [UserID= <u>user ID</u>]
AC13002-25014	WARNING	Forced to Logout. (Replication) UserID=%s	Duplicate logins are not permitted, so the previously logged in user was forced to logout. Output value: [UserID= <u>user ID</u>]
AC16003-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC17808-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	Forced logout request was denied. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request= <u>FORCELOGOUT</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC18501-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC18504-25101	WARNING	Reference User Logout. UserID=%s %s	Logged out. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]
AC22101-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	No request execution permission. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request= <u>authentication method</u> (LOGINSAML)]
AC22102-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	No request execution permission. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request= <u>authentication method</u> (FLOGINSAML)]
AC22103-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	No request execution permission. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request= <u>authentication method</u> (LOGINFEDE)]
AC22104-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	No request execution permission. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request= <u>authentication method</u> (FLOGINFEDE)]
AC24201-25106	WARNING	Deny Request From SOURCE_ADDR=%s Version=%s	No request execution permission. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Version= <u>ICP version</u>]
AC24202-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	No request execution permission. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request= <u>authentication method</u>]
AC70156-25027	WARNING	Password Change Error. UserID=%s	Failed to change password. Output value: [UserID= <u>user ID</u>]
AC70157-25119	WARNING	Min Length Error. UserID=%s	Password is less than the minimum number of characters. Output value: [UserID= <u>user ID</u>]
AC70158-25118	WARNING	Max Length Error. UserID=%s	Password is more than the maximum number of characters. Output value: [UserID= <u>user ID</u>]
AC70159-25120	WARNING	Password Change Agreed With UserID Error. UserID=%s	User ID is used in the password. Output value: [UserID= <u>user ID</u>]
AC70160-25027	WARNING	Password Change Error. UserID=%s	Failed to change password. Output value: [UserID= <u>user ID</u>]
AC70161-25027	WARNING	Password Change Error. UserID=%s	Failed to change password. Output value: [UserID= <u>user ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC70162-25121	WARNING	Forbidden Character Include Error. UserID=%s	Password contains forbidden character(s). Output value: [UserID= <u>user ID</u>]
AC70163-25117	WARNING	Alpha Numeric Include Error. UserID=%s	Password contains characters other than alphanumeric characters. Output value: [UserID= <u>user ID</u>]
AC70164-25122	WARNING	Numeric Include Error. UserID=%s	Password contains characters other than numbers. Output value: [UserID= <u>user ID</u>]
AC70165-25123	WARNING	Alpha Include Error. UserID=%s	Password contains characters other than alphabetical characters. Output value: [UserID= <u>user ID</u>]
AC70166-25124	WARNING	Sign Include Error. UserID=%s	Password contains characters other than symbols. Output value: [UserID= <u>user ID</u>]
AC70167-25125	WARNING	Numeric Sign Include Error. UserID=%s	Password must consist of numeric characters and symbol characters. Output value: [UserID= <u>user ID</u>]
AC70168-25126	WARNING	Alpha Sign Include Error. UserID=%s	Password must consist of alphabetic characters and symbol characters. Output value: [UserID= <u>user ID</u>]
AC70169-25127	WARNING	Alpha Numeric Sign Include Error. UserID=%s	Password must consist of alphabetic characters, symbol characters and numeric characters. Output value: [UserID= <u>user ID</u>]
AC70170-25128	WARNING	Alpha Numeric No Include Error. UserID=%s	Password must contain both numeric character and alphabetic character. Output value: [UserID= <u>user ID</u>]
AC70171-25129	WARNING	Numeric No Include Error. UserID=%s	Password does not contain numbers. Output value: [UserID= <u>user ID</u>]
AC70172-25130	WARNING	Alpha No Include Error. UserID=%s	Password does not contain alphabetical characters. Output value: [UserID= <u>user ID</u>]
AC70173-25131	WARNING	Sign No Include Error. UserID=%s	Password does not contain symbols. Output value: [UserID= <u>user ID</u>]
AC70174-25132	WARNING	Numeric Sign No Include Error. UserID=%s	Password must contain both numeric character and symbol character. Output value: [UserID= <u>user ID</u>]
AC70175-25133	WARNING	Alpha Sign No Include Error. UserID=%s	Password must contain alphabetic character and symbol character. Output value: [UserID= <u>user ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC70176-25117	WARNING	Alpha Numeric Include Error. UserID=%s	Password must consist of alphanumeric characters. Output value: [UserID= <u>user ID</u>]
AC70336-25138	WARNING	User Logout. (All User Logout) UserID=%s %s	User logged out. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]
AC70831-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	Memory dump request was denied. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request=DUMP]
AC70832-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	Configuration file data output request (cdump-cert) was denied. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request=DUMPCONFIG]
AC70833-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	Operating information output request (info-cert) was denied. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request=INFO]
AC70834-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	Request for logging out all users (logout-cert) was denied. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request=FORCELOGOUTALL]
AC70835-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	Reload request (reload-cert) was denied. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request=RELOAD]
AC70836-25107	WARNING	Deny Request From SOURCE_ADDR=%s Request=%s	Authentication Module stop request (stop-cert) was denied. Output value: [SOURCE_ADDR= <u>sender IP address</u>] [Request=STOP]
AC70967-25134	WARNING	DB busy Error. Request=%s	The connection to the authentication database is busy. Output value: [Request= <u>request name</u>]
AC70969-25134	WARNING	DB busy Error. Request=%s	The connection to the authentication database is busy. Output value: [Request= <u>request name</u>]
AC71132-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC71133-25101	WARNING	Reference User Logout. UserID=%s %s	Logged out. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]
AC71134-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC71135-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC71145-25013	WARNING	Forced to Logout. UserID=%s %s	Forced logout occurred. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]
AC71148-25065	WARNING	User Login. UserID=%s	User logged in. Output value: [UserID= <u>user ID</u>]
AC71149-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC71151-25068	WARNING	User Logout. UserID=%s %s	Logged out. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]
AC71152-25138	WARNING	User Logout. (All User Logout) UserID=%s %s	User logged out. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]
AC71153-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC71154-25053	WARNING	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
AC71155-25020	WARNING	Login Timeout. UserID=%s %s	User was logged out due to a timeout. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]
AC71169-20013	WARNING	Cookie : %s is Locked by Another Thread.	Cannot delete session ID because it is locked. Output value: [<u>session ID</u>]
AC71170-20013	WARNING	Cookie : %s is Locked by Another Thread.	Cannot delete session ID because it is locked. Output value: [<u>session ID</u>]
AC71171-20013	WARNING	Cookie : %s is Locked by Another Thread.	Cannot delete session ID because it is locked. Output value: [<u>session ID</u>]
AC71172-20013	WARNING	Cookie : %s is Locked by Another Thread.	Cannot delete session ID because it is locked. Output value: [<u>session ID</u>]
AC71173-20013	WARNING	Cookie : %s is Locked by Another Thread.	Cannot delete session ID because it is locked. Output value: [<u>session ID</u>]
AC71174-20013	WARNING	Cookie : %s is Locked by Another Thread.	Cannot delete session ID because it is locked. Output value: [<u>session ID</u>]
AC01902-25003	INFO	Access Control Request. (Client Certificate) UserID=%s, URL=%s	Access privilege verification using client certificate. Output value: [UserID= <u>user ID</u>] [URL= <u>URL</u>]
AC01903-25004	INFO	Access Control Request. (Uid/Password) UserID=%s, URL=%s	Access privilege verification using user ID. Output value: [UserID= <u>user ID</u>] [URL= <u>URL</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC05903-25045	INFO	RA Serial Exist. IW Serial Not Exist. UserID=%s Cert=%d	RA serial exists, but IW serial does not exist. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC05904-25042	INFO	RA Serial Exist & IW Serial Exist. UserID=%s Cert=%d	RA serial and IW serial exist. Since a client certificate has already been issued, this is an initial authentication error. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC06002-25045	INFO	RA Serial Exist. IW Serial Not Exist. UserID=%s Cert=%d	RA serial exists, but IW serial does not exist. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC06004-25042	INFO	RA Serial Exist & IW Serial Exist. UserID=%s Cert=%d	RA serial, IW serial, and received serial match. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC06006-25042	INFO	RA Serial Exist & IW Serial Exist. UserID=%s Cert=%d	RA serial, IW serial, and received serial match. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC07101-25011	INFO	Dynamic Menu Request.	Starts Dynamic Menu request.
AC07103-25012	INFO	Dynamic Menu. UserID=%s	Finished Dynamic Menu request. Output value: [UserID= <u>user ID</u>]
AC07104-25012	INFO	Dynamic Menu. UserID=%s	Finished Dynamic Menu request. Output value: [UserID= <u>user ID</u>]
AC09208-25071	INFO	UserExit Result. UserID=%s code=%d	Finished external interface procedure. Output value: [UserID= <u>user ID</u>] [code= <u>external interface procedure return value</u>]
AC10120-25035	INFO	Password Expired. UserID=%s	Password has expired. Output value: [UserID= <u>user ID</u>]
AC10122-25009	INFO	Duplicate Login. UserID=%s	Duplicate login. Output value: [UserID= <u>user ID</u>]
AC10128-25110	INFO	Password Will Be Expired. UserID=%s	Password expiration date is near. Output value: [UserID= <u>user ID</u>]
AC10301-25025	INFO	No Check Password Expiration.	Password expiration date verification is OFF.
AC10902-25067	INFO	User Logout Request. UserID=%s	Logout request started. Output value: [UserID= <u>user ID</u>]
AC11303-25060	INFO	User Auto Logout Request. UserID=%s	Automatic logout request started. Output value: [UserID= <u>user ID</u>]
AC11401-25032	INFO	Password Change Request.	Password change request started.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC13001-25018	INFO	Login Request (Replication). UserID=%s	Login request replication started. Output value: [UserID= <u>user ID</u>]
AC13003-25014	INFO	Forced to Logout. (Replication) UserID=%s	Duplicate logins are not permitted, so the previously logged in user was logged out. Output value: [UserID= <u>user ID</u>]
AC13004-25019	INFO	Login Success. (Replication) UserID=%s	Login request replication succeeded. Output value: [UserID= <u>user ID</u>]
AC13101-25073	INFO	User-Info Replication Error (Cookie Search).UserID=%s	Failed to replicate the user information update because the user is not found. Output value: [UserID= <u>user ID</u>]
AC13102-25076	INFO	User-Info Replication Error (Modify).UserID=%s	Failed to replicate the user information update because the user is not found. Output value: [UserID= <u>user ID</u>]
AC13103-25024	INFO	Modify Success (Replication). UserID=%s	Successfully replicated user information update. Output value: [UserID= <u>user ID</u>]
AC13201-25021	INFO	Logout Request (Replication). UserID=%s	Logout request replication started. Output value: [UserID= <u>user ID</u>]
AC13202-25073	INFO	User-Info Replication Error (Cookie Search).UserID=%s	Failed in logout request replication because no user was found. Output value: [UserID= <u>user ID</u>]
AC13203-25075	INFO	User-Info Replication Error (Logout).UserID=%s	Failed in logout request replication because no user was found. Output value: [UserID= <u>user ID</u>]
AC13204-25022	INFO	Logout Success. (Replication) UserID=%s	Logout request replication succeeded. Output value: [UserID= <u>user ID</u>]
AC16001-25069	INFO	User Query Request.	User information query request executed.
AC16004-25070	INFO	User Query. UserID=%s	User information referral request executed. Output value: [UserID= <u>user ID</u>]
AC17101-25086	INFO	External Select %s.	User external reference function executed. Output value: [Request]
AC17106-25087	INFO	External Select %s. UserID=%s	User external reference function terminated. Output value: [Success] [UserID= <u>user ID</u>]
AC18502-25099	INFO	Reference Forced to Logout. UserID=%s. Cookie=%s.	Forced logout request occurred. Output value: [UserID= <u>user ID</u>] [Cookie= <u>session ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
AC18801-25102	INFO	Reference Logout Request (Replication). UserID=%s	Logout request occurred. Output value: [UserID= <u>user ID</u>]
AC18802-25103	INFO	Reference User-Info Replication Error (Cookie Search).UserID=%s	User information replication error occurred (cookie search). Output value: [UserID= <u>user ID</u>]
AC18803-25104	INFO	Reference User-Info Replication Error (Logout).UserID=%s	User information replication error occurred (logout). Output value: [UserID= <u>user ID</u>]
AC18804-25105	INFO	Reference Logout Success. (Replication) UserID=%s	Logout succeeded. Output value: [UserID= <u>user ID</u>]
AC70333-25137	INFO	User Logout Request. (All User Logout) UserID=%s	Starting to process one user during the logout sequence for all users. Output value: [UserID= <u>user ID</u>]
AC71121-25045	INFO	RA Serial Exist. IW Serial Not Exist. UserID=%s Cert=%d	RA serial exists, but IW serial does not exist. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC71123-25045	INFO	RA Serial Exist. IW Serial Not Exist. UserID=%s Cert=%d	RA serial exists, but IW serial does not exist. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC71125-25042	INFO	RA Serial Exist & IW Serial Exist. UserID=%s Cert=%d	RA serial, IW serial, and received serial match. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC71127-25042	INFO	RA Serial Exist & IW Serial Exist. UserID=%s Cert=%d	RA serial, IW serial, and received serial match. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
AC71146-25009	INFO	Duplicate Login. UserID=%s	Duplicate login. Output value: [UserID= <u>user ID</u>]
AC71163-25021	INFO	Logout Request (Replication). UserID=%s	Logout request replication started. Output value: [UserID= <u>user ID</u>]
AC71167-25075	INFO	User-Info Replication Error (Logout).UserID=%s	Failed in logout request replication because no user was found. Output value: [UserID= <u>user ID</u>]
AC71168-25022	INFO	Logout Success. (Replication) UserID=%s	Logout request replication succeeded. Output value: [UserID= <u>user ID</u>]
AC71175-20013	INFO	Cookie : %s is Locked by Another Thread.	Cannot delete session ID because it is locked. Output value: [<u>session ID</u>]

7.2 Error log message list

7.2.1 Forwarder error log

Code ID	Level	Message	Description
ED00101-00015	FATAL	IW_CreateSocketData() Error.	Could not allocate buffer area.
ED00120-00026	FATAL	malloc() Error. Errno=%d	Could not retrieve processing area for storing error log file path. Output value: [Errno= <u>error number output from OS</u>]
ED00125-00026	FATAL	malloc() Error. Errno=%d	Could not retrieve the storage operation area for security log file path. Output value: [Errno= <u>error number output from OS</u>]
ED00201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED00202-10087	FATAL	Create SocketData Error.	Could not allocate socket structure area.
ED00203-00026	FATAL	malloc() Error. Errno=%d	Could not allocate response message structure area. Output value: [Errno= <u>error number output from OS</u>]
ED00209-10098	FATAL	DFW_CreateFWResponseHeader() Error.	Operation to change header that is returned to browser was not performed correctly.
ED00215-10213	FATAL	Wrong Response Data.	Response data is out of scope.
ED00216-10246	FATAL	DFW_GETFilter() Error.	An error occurred in executing GET filter operation.
ED00217-10247	FATAL	DFW_POSTFilter() Error.	An error occurred in executing POST filter operation.
ED00226-00015	FATAL	IW_CreateSocketData() Error.	An error occurred during creation of communication buffer.
ED00227-10244	FATAL	PATH_INFO is over the maximum length.	PATH_INFO has exceeded the maximum length.
ED00228-10245	FATAL	QUERY_STRING is over the maximum length.	QUERY_STRING is longer than the maximum length.
ED00230-10366	FATAL	Request denied by Certification Server.(ACLREQUEST)	Connection to Authentication Module was denied.
ED00236-10043	FATAL	Can't Find Failover Entry.	Cannot find failover entry.
ED00239-00026	FATAL	malloc() Error. Errno=%d	Failed to create area for storing host. Output value: [Errno= <u>error number output from OS</u>]
ED00301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED00308-10089	FATAL	Data Send Failed.	Failed to send data.
ED00309-10088	FATAL	Data Receive Failed.	Failed to receive data.
ED00310-10107	FATAL	DFW_HTTPForward() Error.	An error occurred during HTTP forwarding.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED00314-10236	FATAL	Can't Modified RequestHeaderPath.	Cannot change request header path.
ED00316-10237	FATAL	A proxy setup cannot be performed to a SSL server.(%s:%d)	Proxy configuration performed with SSL. Output value: [host name:port number]
ED00401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED00407-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing user ID. Output value: [Errno=error number output from OS]
ED00408-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing password. Output value: [Errno=error number output from OS]
ED00409-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing user information. Output value: [Errno=error number output from OS]
ED00414-10422	FATAL	Can't Find.[%s]	Failed to retrieve User-Agent header. Output value: [unretrievable data]
ED00418-10057	FATAL	Can't Get REMOTE_ADDR.	Failed to retrieve remote address.
ED00501-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate output buffer size area. Output value: [Errno=error number output from OS]
ED00502-10250	FATAL	DFW_GetContentLength() Error.	An error occurred during content length retrieval process.
ED00503-10250	FATAL	DFW_GetContentLength() Error.	An error occurred during content length retrieval process.
ED00601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED00602-10143	FATAL	IW_CreateConfig() Error.	An error occurred during IW_CONF-type structure creation process.
ED00604-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate name area. Output value: [Errno=error number output from OS]
ED00606-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate value area. Output value: [Errno=error number output from OS]
ED00607-00012	FATAL	IW_CreateConfigEntry() Error.	An error occurred during operation to add information to append information structure.
ED00608-00023	FATAL	IW_SetBuf() Error.	Cannot store user ID in buffer.
ED00609-00023	FATAL	IW_SetBuf() Error.	Cannot store user ID in buffer.
ED00610-00023	FATAL	IW_SetBuf() Error.	Cannot store [\r\n] in buffer.
ED00611-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate description processing area. Output value: [Errno=error number output from OS]
ED00612-00023	FATAL	IW_SetBuf() Error.	Cannot store [description] information in buffer.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED00613-00023	FATAL	IW_SetBuf() Error.	Cannot store [description] information in buffer.
ED00614-00023	FATAL	IW_SetBuf() Error.	Cannot store [\r\n] in buffer.
ED00615-00023	FATAL	IW_SetBuf() Error.	Cannot split [description] information to store it in buffer.
ED00616-00023	FATAL	IW_SetBuf() Error.	Cannot split [description] information to store it in buffer.
ED00617-00023	FATAL	IW_SetBuf() Error.	Cannot store [\r\n] in buffer.
ED00618-00023	FATAL	IW_SetBuf() Error.	Cannot store [description] information in buffer.
ED00619-00023	FATAL	IW_SetBuf() Error.	Cannot store [description] information in buffer.
ED00620-00023	FATAL	IW_SetBuf() Error.	Cannot store [\r\n] in buffer.
ED00621-00023	FATAL	IW_SetBuf() Error.	Cannot store [description] information in buffer.
ED00622-00023	FATAL	IW_SetBuf() Error.	Cannot store [\r\n] in buffer.
ED00623-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate output area. Output value: [Errno=error number output from OS]
ED00624-00023	FATAL	IW_SetBuf() Error.	Cannot expand HTTPDATA.
ED00625-00023	FATAL	IW_SetBuf() Error.	Cannot store [\r\n] in buffer.
ED00628-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for storing [Authorization] in buffer. Output value: [Errno=error number output from OS]
ED00629-00023	FATAL	IW_SetBuf() Error.	Could not store header name in buffer.
ED00631-00023	FATAL	IW_SetBuf() Error.	Could not store encoded string in buffer.
ED00632-00023	FATAL	IW_SetBuf() Error.	Cannot store [\r\n] in buffer.
ED00633-00023	FATAL	IW_SetBuf() Error.	Cannot store [\r\n] for header end in buffer.
ED00634-10148	FATAL	IW_ReleaseConfig(): Error.	Cannot discard IW_CONF structure
ED00635-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate the HTTPDATA expanded area. Output value: [Errno=error number output from OS]
ED00636-10436	FATAL	CMN_Base64Encode() Error.	Failed to convert to Base64 string.
ED00637-00003	FATAL	Configuration Invalid Entry. Entry=%s	Failed to retrieve user ID information transmission header name. Output value: [Entry=parameter name not retrieved]
ED00901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED00902-00043	FATAL	IW_CreateBuf() Error.	Failed to create tag information structure.
ED00903-10203	FATAL	Tag Set Failed.	Failed to retrieve tag.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED00905-10201	FATAL	StrInsert() Error.	Failed to Insert tag.
ED00907-10253	FATAL	DFW_CreateHostList() Error.	An error occurred during operation to create list of permitted hosts.
ED01001-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate URL information structure area within tag. Output value: [Errno= <u>error number output from OS</u>]
ED01002-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate URL information structure area within tag. Output value: [Errno= <u>error number output from OS</u>]
ED01004-10203	FATAL	Tag Set Failed.	Failed to set new URL.
ED01005-10203	FATAL	Tag Set Failed.	Failed to set new URL.
ED01009-10203	FATAL	Tag Set Failed.	Failed to set new URL.
ED01010-10203	FATAL	Tag Set Failed.	Failed to set new URL.
ED01101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED01106-10202	FATAL	Tag Insert Failed.	Failed to insert tag.
ED01201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED01202-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for URL conversion. Output value: [Errno= <u>error number output from OS</u>]
ED01205-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing URL after conversion. Output value: [Errno= <u>error number output from OS</u>]
ED01206-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing URL after conversion. Output value: [Errno= <u>error number output from OS</u>]
ED01301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED01302-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED01305-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving BASE tag alias. Output value: [Errno= <u>error number output from OS</u>]
ED01306-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing URL after conversion. Output value: [Errno= <u>error number output from OS</u>]
ED01307-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for URL conversion. Output value: [Errno= <u>error number output from OS</u>]
ED01401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED01501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED01507-10139	FATAL	HostData Create Error.	Failed to create host entry.
ED01508-10138	FATAL	HostData Add Error.	Failed to add host entry.
ED01601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED01604-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving name. Output value: [Errno=error number output from OS]
ED01605-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for retrieving value. Output value: [Errno=error number output from OS]
ED01606-10155	FATAL	KeyData Create Error.	Failed to create KeyData.
ED01607-10156	FATAL	KeyData Add Error.	Failed to add KeyData.
ED01608-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving name. Output value: [Errno=error number output from OS]
ED01701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED01704-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno=error number output from OS]
ED01705-10155	FATAL	KeyData Create Error.	Failed to create KeyData.
ED01706-10156	FATAL	KeyData Add Error.	Failed to add KeyData.
ED01801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED01803-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving name. Output value: [Errno=error number output from OS]
ED01804-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving value. Output value: [Errno=error number output from OS]
ED01806-10155	FATAL	KeyData Create Error.	Failed to create KeyData.
ED01807-10132	FATAL	Entry Add Error.	Failed to add entry.
ED01901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED02005-10133	FATAL	Entry Create Error.	Failed to create entry. (DOCS path)
ED02006-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (DOCS path)
ED02007-10133	FATAL	Entry Create Error.	Failed to create entry. (Log level)
ED02008-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Log level)
ED02009-10133	FATAL	Entry Create Error.	Failed to create entry. (Access log file)
ED02010-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Access log file)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED02011-10133	FATAL	Entry Create Error.	Failed to create entry. (Error log file)
ED02012-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Error log file)
ED02013-10133	FATAL	Entry Create Error.	Failed to create entry. (Receive timeout)
ED02014-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Receive timeout)
ED02015-10133	FATAL	Entry Create Error.	Failed to create entry. (Buffer extension size)
ED02016-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Buffer extension size)
ED02019-10133	FATAL	Entry Create Error.	Failed to create entry. (Configuration automatic loading switch)
ED02020-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Configuration automatic loading switch)
ED02021-10133	FATAL	Entry Create Error.	Failed to create entry. (Backend server failover switch)
ED02022-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Backend server failover switch)
ED02033-10133	FATAL	Entry Create Error.	Failed to create entry. (Common log file usage verification flag)
ED02034-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Common log file usage verification flag)
ED02035-10133	FATAL	Entry Create Error.	Failed to create entry. (BASIC authentication send verification flag)
ED02036-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (BASIC authentication send verification flag)
ED02037-10133	FATAL	Entry Create Error.	Failed to create entry. (COOKIE authentication flag)
ED02038-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (COOKIE authentication flag)
ED02039-10133	FATAL	Entry Create Error.	Failed to create entry. (WebServer retry count)
ED02040-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (WebServer retry count)
ED02041-10133	FATAL	Entry Create Error.	Failed to create entry. (certd retry count)
ED02042-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (certd retry count)
ED02043-10133	FATAL	Entry Create Error.	Failed to create entry. (WebServer retry time)
ED02044-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (WebServer retry time)
ED02045-10133	FATAL	Entry Create Error.	Failed to create entry. (certd retry time)
ED02046-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (certd retry time)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED02047-10133	FATAL	Entry Create Error.	Failed to create entry. (COOKIE session ID name)
ED02048-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (COOKIE session ID name)
ED02049-10133	FATAL	Entry Create Error.	Failed to create entry. (BUFFER flag)
ED02050-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (BUFFER flag)
ED02051-10133	FATAL	Entry Create Error.	Failed to create entry. (Trace log level)
ED02052-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Trace log level)
ED02053-10133	FATAL	Entry Create Error.	Failed to create entry. (Login keyword)
ED02054-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Login keyword)
ED02055-10133	FATAL	Entry Create Error.	Failed to create entry. (Logout keyword)
ED02056-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Logout keyword)
ED02057-10133	FATAL	Entry Create Error.	Failed to create entry. (Password change keyword)
ED02058-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Password change keyword)
ED02059-10133	FATAL	Entry Create Error.	Failed to create entry. (LASTMOD_HEADER flag)
ED02060-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (LASTMOD_HEADER flag)
ED02061-10133	FATAL	Entry Create Error.	Failed to create entry. (LOCATIONRETRY flag)
ED02062-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (LOCATIONRETRY flag)
ED02063-10133	FATAL	Entry Create Error.	Failed to create entry. (CENCODE flag)
ED02064-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (CENCODE flag)
ED02065-10133	FATAL	Entry Create Error.	Failed to create entry. (GETFILTERERR)
ED02066-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (GETFILTERERR)
ED02067-10133	FATAL	Entry Create Error.	Failed to create entry. (POSTFILTERERR)
ED02068-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (POSTFILTERERR)
ED02069-10133	FATAL	Entry Create Error.	Failed to create entry. (HTMLFILTERERR)
ED02070-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (HTMLFILTERERR)
ED02071-10133	FATAL	Entry Create Error.	Failed to create entry. (SVRFILTERERR)
ED02072-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (SVRFILTERERR)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED02073-10133	FATAL	Entry Create Error.	Failed to create entry. (SVRFILTER)
ED02074-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (SVRFILTER)
ED02075-10133	FATAL	Entry Create Error.	Failed to create entry. (SVRFILTERSTR)
ED02076-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (SVRFILTERSTR)
ED02077-10133	FATAL	Entry Create Error.	Failed to create entry. (SET_CONTENT_LENGTH flag)
ED02078-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (SET_CONTENT_LENGTH flag)
ED02079-10133	FATAL	Entry Create Error.	Failed to create entry. (URL_SCOLON)
ED02080-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (URL_SCOLON)
ED02081-10133	FATAL	Entry Create Error.	Failed to create entry. (COOKIEALWAYS)
ED02082-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (COOKIEALWAYS)
ED02083-10133	FATAL	Entry Create Error.	Failed to create entry. (RECV_ZERO_FLG flag)
ED02084-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (RECV_ZERO_FLG flag)
ED02085-10133	FATAL	Entry Create Error.	Failed to create entry. (FO_SEND flag)
ED02086-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (FO_SEND flag)
ED02087-10133	FATAL	Entry Create Error.	Failed to create entry. (FO_RECV flag)
ED02088-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (FO_RECV flag)
ED02089-10133	FATAL	Entry Create Error.	Failed to create entry. (FO_NODATA flag)
ED02090-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (FO_NODATA flag)
ED02091-10133	FATAL	Entry Create Error.	Failed to create entry. (Security log level)
ED02092-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (Security log level)
ED02093-10133	FATAL	Entry Create Error.	Failed to create entry. (DFW_PROTOCOL flag)
ED02094-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (DFW_PROTOCOL flag)
ED02095-10133	FATAL	Entry Create Error.	Failed to create entry. (ENCODE_FLG flag)
ED02096-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (ENCODE_FLG flag)
ED02097-10133	FATAL	Entry Create Error.	Failed to create entry. (DFWFILTER)
ED02098-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (DFWFILTER)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED02099-10133	FATAL	Entry Create Error.	Failed to create entry. (REQHTTPVER)
ED020A0-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (REQHTTPVER)
ED020A1-10133	FATAL	Entry Create Error.	Failed to create entry. (CC_DECODE_FLG flag)
ED020A2-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (CC_DECODE_FLG flag)
ED020A3-10133	FATAL	Entry Create Error.	Failed to create entry. (REQUEST_URI flag)
ED020A4-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (REQUEST_URI flag)
ED020A5-10133	FATAL	Entry Create Error.	Failed to create entry. (QUERY_ENC_NAME flag)
ED020A6-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (QUERY_ENC_NAME flag)
ED020A7-10133	FATAL	Entry Create Error.	Failed to create entry. (POST_INHERIT flag)
ED020A8-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (POST_INHERIT flag)
ED020A9-10133	FATAL	Entry Create Error.	Failed to create entry. (POSTNAME flag)
ED020B0-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (POSTNAME flag)
ED020B1-10133	FATAL	Entry Create Error.	Failed to create entry. (POSTWAITTIME flag)
ED020B2-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (POSTWAITTIME flag)
ED020B3-10133	FATAL	Entry Create Error.	Failed to create entry. (ICP_VERSION flag)
ED020B4-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (ICP_VERSION flag)
ED020B5-10133	FATAL	Entry Create Error.	Failed to create entry. (CERT_TOUT flag)
ED020B6-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (CERT_TOUT flag)
ED020B7-10133	FATAL	Entry Create Error.	Failed to create entry. (URLCONV_FLG)
ED020B8-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (URLCONV_FLG)
ED020B9-10133	FATAL	Entry Create Error.	Failed to create entry. (QUERY_ENC_KIND)
ED020C1-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (QUERY_ENC_KIND)
ED020C2-10133	FATAL	Entry Create Error.	Failed to create entry. (POSTLIMIT_TIME)
ED020C3-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (POSTLIMIT_TIME)
ED020C4-10133	FATAL	Entry Create Error.	Failed to create entry. (ATTRQUOT_FLG)
ED020C5-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (ATTRQUOT_FLG)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED020C6-10133	FATAL	Entry Create Error.	Failed to create entry. (GETFILTER_LOG_FLG)
ED020C7-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (GETFILTER_LOG_FLG)
ED020C8-10133	FATAL	Entry Create Error.	Failed to create entry. (POSTFILTER_LOG_FLG)
ED020C9-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (POSTFILTER_LOG_FLG)
ED020D0-10133	FATAL	Entry Create Error.	Failed to create entry. (HEADER_NAME_UID)
ED020D1-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (HEADER_NAME_UID)
ED020D3-10133	FATAL	Entry Create Error.	Failed to create entry. (HEADER_NAME_SID)
ED020D4-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (HEADER_NAME_SID)
ED020D5-10133	FATAL	Entry Create Error.	Failed to create entry. (URLCONV_ATTR_FLG)
ED020D6-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (URLCONV_ATTR_FLG)
ED020D7-10133	FATAL	Entry Create Error.	Failed to create entry. (CONNECTCNTC)
ED020D8-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (CONNECTCNTC)
ED020D9-10133	FATAL	Entry Create Error.	Failed to create entry. (CONNECTTMC)
ED020E0-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (CONNECTTMC)
ED020E1-10133	FATAL	Entry Create Error.	Failed to create entry. (CONNECTCNTW)
ED020E2-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (CONNECTCNTW)
ED020E3-10133	FATAL	Entry Create Error.	Failed to create entry. (CONNECTTMW)
ED020E4-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (CONNECTTMW)
ED020E5-10133	FATAL	Entry Create Error.	Failed to create entry structure.
ED020E6-10132	FATAL	Entry Add Error.	Failed to add entry structure.
ED020E7-10133	FATAL	Entry Create Error.	Failed to create entry. (TRANSID flag)
ED020E8-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (TRANSID flag)
ED020E9-10133	FATAL	Entry Create Error.	Failed to create entry. (TRANSID_STR)
ED020F0-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (TRANSID_STR)
ED020F1-10133	FATAL	Entry Create Error.	Failed to create entry. (HEADER_NAME_TID)
ED020F2-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (HEADER_NAME_TID)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED020F3-10133	FATAL	Entry Create Error.	Failed to create entry. (ICP_ENCSTR)
ED020F4-10132	FATAL	Entry Add Error.	Failed to add to basic information structure. (ICP_ENCSTR)
ED02201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED02401-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for operation to create host data. Output value: [Errno= <u>error number output from OS</u>]
ED02502-10046	FATAL	Can't Find Host Entry.	Failed to retrieve host entry.
ED02503-00043	FATAL	IW_CreateBuf() Error.	Failed to create configuration buffer.
ED02504-10176	FATAL	Open Error.[%s]	Failed to open configuration file. Output value: [<u>file name</u>]
ED02505-10135	FATAL	fdopen() Error.	Failed to convert fd.
ED02506-00023	FATAL	IW_SetBuf() Error.	Failed to verify comment line.
ED02507-00023	FATAL	IW_SetBuf() Error.	Failed in rewriting operation.
ED02508-00023	FATAL	IW_SetBuf() Error.	Failed in rewriting operation.
ED02509-10194	FATAL	seek() Error.	Failed in seek operation.
ED02510-10310	FATAL	ftruncate() Error.	Failed in ftruncate operation.
ED02512-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing configuration values. Output value: [Errno= <u>error number output from OS</u>]
ED02601-10038	FATAL	Can't Find Backend Web Server's Configuration File Path.	Cannot retrieve configuration file path from alias.
ED02629-00026	FATAL	malloc() Error. Errno=%d	Failed to create work buffer. Output value: [Errno= <u>error number output from OS</u>]
ED02630-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for setting transaction ID. Output value: [Errno= <u>error number output from OS</u>]
ED02701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED02702-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory for entry structure. Output value: [Errno= <u>error number output from OS</u>]
ED02703-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory for list structure. Output value: [Errno= <u>error number output from OS</u>]
ED02704-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory area for member allhost of entry structure. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED02705-00002	FATAL	Configuration Format Error.[failover]	The separator is followed by '\0.'
ED02801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED02802-00026	FATAL	malloc() Error. Errno=%d	Could not allocate request header area. Output value: [Errno= <u>error number output from OS</u>]
ED02803-00023	FATAL	IW_SetBuf() Error.	Could not store request header in buffer.
ED02804-00023	FATAL	IW_SetBuf() Error.	Could not add name to header.
ED02805-00023	FATAL	IW_SetBuf() Error.	Could not add name to header.
ED02806-00023	FATAL	IW_SetBuf() Error.	Could not add value to header.
ED02807-00023	FATAL	IW_SetBuf() Error.	Could not add value to header.
ED02808-00023	FATAL	IW_SetBuf() Error.	Could not add cookie to header.
ED02809-00023	FATAL	IW_SetBuf() Error.	Could not add cookie to header.
ED02810-00023	FATAL	IW_SetBuf() Error.	Could not add cookie to header.
ED02811-00023	FATAL	IW_SetBuf() Error.	Could not add session to header.
ED02812-00023	FATAL	IW_SetBuf() Error.	Could not add session to header.
ED02813-00023	FATAL	IW_SetBuf() Error.	Could not add session to header.
ED02814-00023	FATAL	IW_SetBuf() Error.	Could not add Content-type to header.
ED02815-00023	FATAL	IW_SetBuf() Error.	Could not add Content-type to header.
ED02816-00023	FATAL	IW_SetBuf() Error.	Could not add Content-type to header.
ED02817-00023	FATAL	IW_SetBuf() Error.	Could not add Content-length to header.
ED02818-00023	FATAL	IW_SetBuf() Error.	Could not add Content-length to header.
ED02819-00023	FATAL	IW_SetBuf() Error.	Could not add Content-length to header.
ED02821-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for verifying if cookie filter exists in notification cookie. Output value: [Errno= <u>error number output from OS</u>]
ED02822-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for parsing cookies by semicolons. Output value: [Errno= <u>error number output from OS</u>]
ED02824-00003	FATAL	Configuration Invalid Entry. Entry=%s	Invalid configuration entry.
ED02825-00003	FATAL	Configuration Invalid Entry. Entry=%s	Failed to retrieve session ID information transmission header name. Output value: [Entry= <u>parameter name not retrieved</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED02826-10474	FATAL	CMN_SetBuf() Error.	Could not add transaction ID header to header.
ED02827-10474	FATAL	CMN_SetBuf() Error.	Could not add head separator to header.
ED02828-10474	FATAL	CMN_SetBuf() Error.	Could not add transaction ID header to header.
ED02829-10474	FATAL	CMN_SetBuf() Error.	Could not add [\r\n] to header.
ED02830-00003	FATAL	Configuration Invalid Entry. Entry=%s	HEADER_NAME_TID is not set in the configuration file. Output value: [Entry=HEADER_NAME_TID]
ED02901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED02906-10080	FATAL	Connection Library Error. [%s:%d]	A library error occurred. Output value: [host name:port number]
ED02907-10211	FATAL	Backend Web Server Down. [%s:%d]	Backend web server is down. Output value: [host name:port number]
ED02908-10082	FATAL	Connection Timeout. [%s:%d]	Connection timed out. Output value: [host name:port number]
ED02910-10197	FATAL	Send System Failed. [%s:%d]	Failed to send data. Output value: [host name:port number]
ED02911-10195	FATAL	Send Library Failed. [%s:%d]	Failed to send library data. Output value: [host name:port number]
ED02912-10198	FATAL	Send Timeout. [%s:%d]	Send operation timed out. Output value: [host name:port number]
ED02913-10188	FATAL	recv() System Error. [%s:%d]	Failed to receive data. Output value: [host name:port number]
ED02914-10187	FATAL	recv() Library Error. [%s:%d]	Failed to receive library data. Output value: [host name:port number]
ED02915-10189	FATAL	recv() Timeout. [%s:%d]	Receive operation timed out. Output value: [host name:port number]
ED02918-10035	FATAL	Can't Find '\n'	Cannot find line feed code.
ED02919-10039	FATAL	Can't Find Content Length Separator.	Cannot find content length separator.
ED02920-10320	FATAL	The size of the received data is 0.	Receive data size is 0.
ED02923-10400	FATAL	failed to negotiate SSL algorithm. host=[%s:%d]	Failed in SSL negotiations due to invalid encryption method. Output value: [host=[host name:port number]]
ED03001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED03007-00023	FATAL	IW_SetBuf() Error.	Cannot output line feed at end of header.
ED03009-00023	FATAL	IW_SetBuf() Error.	Failed to set POST data.
ED03101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED03301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED03302-00026	FATAL	malloc() Error. Errno=%d	Failed to create area required for retrieving pointer with HTTP removed. Output value: [Errno=error number output from OS]
ED03303-10113	FATAL	DFW_ModifyHeaderstring() Error.	Could not convert to format for comparison.
ED03305-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for converting VALUE to be output. Output value: [Errno=error number output from OS]
ED03306-10113	FATAL	DFW_ModifyHeaderstring() Error.	Cannot convert to format for storage.
ED03307-10014	FATAL	Can't Create Entry.[%s]	Failed to create entry. Output value: [entry name]
ED03308-10008	FATAL	Can't Add Entry.[%s]	Failed to add entry. Output value: [entry name]
ED03309-10030	FATAL	Can't Delete Entry.[%s]	Failed to delete entry. Output value: [entry name]
ED03312-10014	FATAL	Can't Create Entry.[%s]	Failed to create entry. Output value: [entry name]
ED03313-10008	FATAL	Can't Add Entry.[%s]	Failed to add entry. Output value: [entry name]
ED03314-10030	FATAL	Can't Delete Entry.[%s]	Failed to delete entry. Output value: [entry name]
ED03315-10134	FATAL	Env Select Error.	A process flag error occurred.
ED03316-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate temporary area used for operation to delete new lines from certificate. Output value: [Errno=error number output from OS]
ED03323-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate header value area after change. Output value: [Errno=error number output from OS]
ED03324-10014	FATAL	Can't Create Entry.[%s]	Failed to create entry for header to be added. Output value: [header name]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED03325-10008	FATAL	Can't Add Entry.[%s]	Failed to add header. Output value: [header name]
ED03401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED03501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED03502-10087	FATAL	Create SocketData Error.	Could not allocate socket structure area.
ED03503-00026	FATAL	malloc() Error. Errno=%d	Could not allocate response message structure area. Output value: [Errno=error number output from OS]
ED03505-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving authentication information position. Output value: [Errno=error number output from OS]
ED03511-10010	FATAL	Can't Connect Directory Server or Database.	Cannot connect to directory server or database.
ED03525-10213	FATAL	Wrong Response Data.	Reply data is abnormal data.
ED03526-10213	FATAL	Wrong Response Data.	Response data is out of scope.
ED03528-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required in rewriting ALIAS. Output value: [Errno=error number output from OS]
ED03529-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required in rewriting URL. Output value: [Errno=error number output from OS]
ED03530-00026	FATAL	malloc() Error. Errno=%d	Could not allocate area for setting IW_INFO in structure. Output value: [Errno=error number output from OS]
ED03534-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for QUERY information in POSTDATA. Output value: [Errno=error number output from OS]
ED03535-10312	FATAL	DFW_SplitQueryString() Error.	Failed to split QUERY_STRING.
ED03537-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area after session ID encryption. Output value: [Errno=error number output from OS]
ED03538-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area after session ID encryption. Output value: [Errno=error number output from OS]
ED03539-10355	FATAL	SessionID Encrypt Failed.	An error occurred in the session ID encryption library.
ED03540-10358	FATAL	DFW_ModifyStrings() Error.	Failed in session ID replacement operation.
ED03541-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area after session ID encryption. Output value: [Errno=error number output from OS]
ED03542-10366	FATAL	Request denied by Certification Server.(ACLREQUEST)	Connection to Authentication Module was denied.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED03544-10378	FATAL	failed to generate sessionid.	Failed to generate session ID in Authentication Module.
ED03601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED03605-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate area for retrieving a UID when a certificate is used. Output value: [Errno= <u>error number output from OS</u>]
ED03609-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate area for storing hideurl in structure. Output value: [Errno= <u>error number output from OS</u>]
ED03614-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate Uid storage area. Output value: [Errno= <u>error number output from OS</u>]
ED03615-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate password storage area. Output value: Errno=(<u>error number output from OS</u>)
ED03618-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate cookie storage area. Output value: [Errno= <u>error number output from OS</u>]
ED03620-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving UID from POSTDATA. Output value: [Errno= <u>error number output from OS</u>]
ED03622-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving PASSWORD from POSTDATA. Output value: [Errno= <u>error number output from OS</u>]
ED03624-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving HIDEURL from POSTDATA. Output value: [Errno= <u>error number output from OS</u>]
ED03626-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving PROC from POSTDATA. Output value: [Errno= <u>error number output from OS</u>]
ED03633-10422	FATAL	Can't Find.[%s]	Failed to retrieve User-Agent header. Output value: [<u>unretrievable data</u>]
ED03637-10057	FATAL	Can't Get REMOTE_ADDR.	Failed to retrieve remote address.
ED03638-10432	FATAL	Keyword Decrypto Error.[%s]	Failed to decrypt the user ID sent from the forced login page. Output value: [<u>string before decryption</u>]
ED03639-10432	FATAL	Keyword Decrypto Error.[%s]	Failed to decrypt the password sent from the forced login page. Output value: [<u>string before decryption</u>]
ED03643-10450	FATAL	sessionid length error. (certd) sid=[%s]	Length of session ID received from Authentication Module is invalid. Output value: [sid= <u>session ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED03644-00044	FATAL	Format Error.[%s]	Session ID received from Authentication Module is invalid. Output value: [session ID]
ED03701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED03702-10043	FATAL	Can't Find Failover Entry.	Cannot find certd failover entry.
ED03703-10076	FATAL	Certification Server Down.[%s:%d]	Authentication Server is down. Output value: [host name:port number]
ED03704-10089	FATAL	Data Send Failed.	Failed to send data.
ED03705-10088	FATAL	Data Receive Failed.	Failed to receive data.
ED03706-10083	FATAL	Connection Timeout.	Connection timed out.
ED03707-00017	FATAL	IW_MessageExchange() Error.	An error occurred during message replacement operation.
ED03708-30003	FATAL	All Certification Server Down.	All Authentication Servers are down.
ED03710-10043	FATAL	Can't Find Failover Entry.	Failed to allocate Authentication Server information.
ED03711-00031	FATAL	Parameter is NULL.	Argument parameter is NULL (during ICP 1.0 communication).
ED03712-10404	FATAL	Can't find ICP Connection Data.	Failed to retrieve ICP 2.0 communication information.
ED03801-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate receive buffer structure creation area. Output value: [Errno=error number output from OS]
ED03802-00008	FATAL	IW_ClearBuf() Error.	An error occurred in creating receive buffer structure.
ED03803-00008	FATAL	IW_ClearBuf() Error.	An error occurred in creating send buffer structure.
ED04001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED04101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED04102-10125	FATAL	DFW_SetForwarderPage() Error.	An error occurred during HTML construction for the logout error page.
ED04103-10087	FATAL	Create SocketData Error.	An error occurred during operation to acquire area for socket structure.
ED04104-00026	FATAL	malloc() Error. Errno=%d	Could not allocate structure area for a response message. Output value: [Errno=error number output from OS]
ED04106-10125	FATAL	DFW_SetForwarderPage() Error.	An error occurred during HTML construction for the logout success page.
ED04107-10125	FATAL	DFW_SetForwarderPage() Error.	An error occurred during HTML construction for logout error page.
ED04108-10213	FATAL	Wrong Response Data.	Response data is out of scope.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED04109-10366	FATAL	Request denied by Certification Server.(ACLREQUEST)	Connection to Authentication Module was denied.
ED04201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED04205-00026	FATAL	malloc() Error. Errno=%d	Could not allocate area used for creating cookie with arbitrary session ID name. Output value: [Errno= <u>error number output from OS</u>]
ED04206-00026	FATAL	malloc() Error. Errno=%d	Could not allocate area used for creating cookie. Output value: [Errno= <u>error number output from OS</u>]
ED04209-10422	FATAL	Can't Find.[%s]	Failed to retrieve User-Agent header. Output value: [<u>unretrievable data</u>]
ED04212-10057	FATAL	Can't Get REMOTE_ADDR.	Failed to retrieve remote address.
ED04213-10450	FATAL	sessionid length error. (certd) sid=[%s]	Length of session ID received from Authentication Module is invalid. Output value: [sid= <u>session ID</u>]
ED04301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED04302-10087	FATAL	Create SocketData Error.	An error occurred during operation to acquire area for socket structure.
ED04303-00026	FATAL	malloc() Error. Errno=%d	Could not allocate structure area for a response message. Output value: [Errno= <u>error number output from OS</u>]
ED04304-10153	FATAL	IW_SetUserQueryRequest() Error.	An error occurred during operation to create user query message.
ED04306-00026	FATAL	malloc() Error. Errno=%d	Could not allocate UID request structure storage area. Output value: [Errno= <u>error number output from OS</u>]
ED04307-00026	FATAL	malloc() Error. Errno=%d	Could not allocate password request structure storage area. Output value: [Errno= <u>error number output from OS</u>]
ED04312-10213	FATAL	Wrong Response Data.	Response data is out of scope.
ED04314-10366	FATAL	Request denied by Certification Server.(ACLREQUEST)	Connection to Authentication Module was denied.
ED04317-10422	FATAL	Can't Find.[%s]	Failed to retrieve User-Agent header. Output value: [<u>unretrievable data</u>]
ED04320-10057	FATAL	Can't Get REMOTE_ADDR.	Failed to retrieve remote address.
ED04401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED04501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED04514-10251	FATAL	FilterString is over the maximum size.	HOST Filter keyword has exceeded the maximum size.
ED04601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED04602-10154	FATAL	IW_StrInsertBuf() Error.	An error occurred during header information conversion for HTTP/1.0.
ED04603-10154	FATAL	IW_StrInsertBuf() Error.	An error occurred during header information conversion for HTTP/1.1.
ED04701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED04702-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area required for HTTP_HOST search. Output value: [Errno= <u>error number output from OS</u>]
ED04703-00018	FATAL	IW_ModifyConfigValue() Error.	An error occurred during conversion in HTTP_HOST search operation.
ED04801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED04802-00018	FATAL	IW_ModifyConfigValue() Error.	An error occurred during HTTP_CONNECTION entry conversion.
ED04901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED04903-10166	FATAL	Not Found.[Alias]	Cannot find alias start position.
ED04904-10166	FATAL	Not Found.[Alias]	Cannot find alias start position.
ED04905-00026	FATAL	malloc() Error. Errno=%d	Cannot re-allocate HTTP_REFERER area after conversion. Output value: [Errno= <u>error number output from OS</u>]
ED04906-00018	FATAL	IW_ModifyConfigValue() Error.	An error occurred during conversion.
ED04907-10220	FATAL	DFW_SetTemplateHost() Error.	An error occurred while splitting URL information.
ED04908-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for REFERER conversion. Output value: [Errno= <u>error number output from OS</u>]
ED04909-10422	FATAL	Can't Find.[%s]	Failed to extract alias from URL. Output value: [<u>unretrievable data</u>]
ED05001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED05002-10051	FATAL	Can't Find Status Separator.	An error occurred during status line retrieval.
ED05003-10050	FATAL	Can't Find Status Point.	An error occurred during status position retrieval.
ED05004-10048	FATAL	Can't Find Space.	Cannot find spaces.
ED05005-10041	FATAL	Can't Find End of URL.	Cannot retrieve end position of the URL.
ED05006-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate area for copying the URL. Output value: [Errno= <u>error number output from OS</u>]
ED05008-10207	FATAL	URL Insert Failed.	Could not replace the URL with a URL that passes through IceWall.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED05101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED05102-10154	FATAL	IW_StrInsertBuf() Error.	An error occurred during process to create a modified path.
ED05201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED05206-10250	FATAL	DFW_GetContentLength() Error.	An error occurred during Content-length retrieving process from content.
ED05301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED05302-10145	FATAL	IW_FindConfigValue(): Not Found.[DOCS]	Cannot retrieve DOCS.
ED05303-10130	FATAL	DOCSPath Not Found.[%s]	Cannot find DOCS path. Output value: <u>[DOCS directory name]</u>
ED05304-10143	FATAL	IW_CreateConfig() Error.	Failed to create the IW_CONF-type HTML path structure.
ED05306-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Login page)
ED05307-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Certificate login page)
ED05308-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Forced login page)
ED05309-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Unregistered user ID page)
ED05310-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Password error page)
ED05311-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (User ID lock page)
ED05312-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Certificate error page)
ED05313-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Login serial number error page)
ED05314-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Login group error page)
ED05315-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Login stop page)
ED05316-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Error page for number of login users exceeded)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED05317-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Logout success page)
ED05318-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Logout error page)
ED05319-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Logout error page)
ED05320-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Access error page)
ED05321-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (POST send error page)
ED05322-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (External interface error page 1)
ED05323-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (External interface error page 2)
ED05324-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (External interface error page 3)
ED05325-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Logout page)
ED05326-10141	FATAL	IceWallPage Select Error.	An error occurred in page selection operation.
ED05328-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (GET filter page)
ED05329-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (POST filter page)
ED05330-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (HTML filter page)
ED05331-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (SVR filter page)
ED05332-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (External interface error page 4)
ED05333-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (External interface error page 5)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED05334-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (External interface error page 6)
ED05335-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (POST data maximum size error page)
ED05336-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Login transmission time limit error page)
ED05337-10475	FATAL	CMN_FindConfValue(): Not Found.	An error occurred during DOCS parameter backward compatibility operation. (Request filter error page)
ED05401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED05402-10145	FATAL	IW_FindConfigValue(): Not Found.[DOCS]	An error occurred in DOCS retrieval operation.
ED05403-10130	FATAL	DOCSPath Not Found.[%s]	An error occurred during DOCS directory verification. Output value: [DOCS directory name]
ED05404-10143	FATAL	IW_CreateConfig() Error.	An error occurred in creating IW_CONF-type HTML path structure.
ED05406-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Password change page)
ED05407-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Password change success page)
ED05408-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Old password error page)
ED05409-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (New password input error page)
ED05410-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Password policy error page)
ED05411-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (No password change permission page)
ED05412-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (No login error page)
ED05413-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Password change failure page)
ED05414-10141	FATAL	IceWallPage Select Error.	An error occurred in page selection operation.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED05416-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Error page 1 for the external routine for password changes)
ED05417-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Error page 2 for the external routine for password changes)
ED05418-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Error page 3 for the external routine for password changes)
ED05419-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Password change warning page)
ED05420-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Password change transmission time limit error page)
ED05501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED05502-10145	FATAL	IW_FindConfigValue(): Not Found.[DOCS]	An error occurred in DOCS retrieval operation.
ED05503-10130	FATAL	DOCSPath Not Found.[%s]	An error occurred during DOCS directory verification. Output value: [DOCS directory name]
ED05504-10143	FATAL	IW_CreateConfig() Error.	An error occurred in creating IW_CONF-type HTML path structure.
ED05506-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (System error page)
ED05507-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (No alias error page)
ED05508-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Unregistered alias page)
ED05509-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Authentication Server down page)
ED05510-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Database server down page)
ED05511-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Backend web server down page)
ED05512-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Authentication Server connection timeout page)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED05513-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during DOCS parameter backward compatibility operation. (Backend web server connection timeout page)
ED05514-10141	FATAL	IceWallPage Select Error.	An error occurred in page selection operation.
ED05515-10475	FATAL	CMN_FindConfValue(): Not Found.	An error occurred during DOCS parameter backward compatibility operation. (Database busy error page)
ED05516-10475	FATAL	CMN_FindConfValue(): Not Found.	An error occurred during DOCS parameter backward compatibility operation. (Request ACL error page)
ED05601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED05602-00008	FATAL	IW_ClearBuf() Error.	An error occurred during buffer clearing.
ED05603-10147	FATAL	IW_INFO format Error.	Failed in cookie name change operation.
ED05604-10040	FATAL	Can't Find COOKIENAME.	Could not retrieve SessionID name from configuration.
ED05605-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for Expires attribute deletion. Output value: [Errno= <u>error number output from OS</u>]
ED05606-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for using COOKIEATTR as an additional attribute. Output value: [Errno= <u>error number output from OS</u>]
ED05607-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for function to add cookie attribute. Output value: [Errno= <u>error number output from OS</u>]
ED05608-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for creating COOKIE. Output value: [Errno= <u>error number output from OS</u>]
ED05609-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for setting Forwarder path attribute. Output value: [Errno= <u>error number output from OS</u>]
ED05618-10358	FATAL	DFW_ModifyStrings() Error.	Failed in session ID replacement operation.
ED05619-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for session ID replacement. Output value: [Errno= <u>error number output from OS</u>]
ED05620-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for HTML file format verification. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED05624-10382	FATAL	format error:[%s]	Parameter format is invalid. Output value: [HTML file path]
ED05625-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area required for session ID replacement. Output value: [Erno=error number output from OS]
ED05701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED05705-10089	FATAL	Data Send Failed.	Failed to send data.
ED05706-10088	FATAL	Data Receive Failed.	Failed to receive data.
ED05707-10107	FATAL	DFW_HTTPForward() Error.	An error occurred during Erno insertion process.
ED05708-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate memory area required for retrieving status value. Output value: [Erno=error number output from OS]
ED05709-10225	FATAL	LocationHeader Retry Error.(RemoteHTML)	The number of retries exceeded.
ED05711-10086	FATAL	Backend Web Server Result. Host=[%s] Code=[%d]	The status value is not a number in the 200s or 300s. Output value: [Host=[host name]] [Code=[status value]]
ED05712-10049	FATAL	Can't Find Status in Remote HTML.	Cannot find status value.
ED05713-10098	FATAL	DFW_CreateFWResponseHeader() Error.	An error occurred during operation to change header returned to browser.
ED05714-10045	FATAL	Can't Find End of Header.	Cannot find header end section.
ED05715-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate area for creating Set-cookie header to be inserted. Output value: [Erno=error number output from OS]
ED05716-10062	FATAL	Can't Insert Header.[Set-Cookie]	An error occurred during Set-cookie header insertion operation.
ED05717-10147	FATAL	IW_INFO format Error.	Failed in cookie name change operation.
ED05718-10040	FATAL	Can't Find COOKIENAME.	Cannot retrieve SessionID name from configuration.
ED05719-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area required for Expires attribute deletion. Output value: [Erno=error number output from OS]
ED05720-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area required for using COOKIEATTR as an additional attribute. Output value: [Erno=error number output from OS]
ED05721-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area required for function to add cookie attribute. Output value: [Erno=error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED05722-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for creating COOKIE. Output value: [Errno= <u>error number output from OS</u>]
ED05723-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for setting Forwarder path attribute. Output value: [Errno= <u>error number output from OS</u>]
ED05724-00018	FATAL	IW_ModifyConfigValue() Error.	Failed in operation to change LASTMOD_HEADER.
ED05725-10358	FATAL	DFW_ModifyStrings() Error.	Failed in session ID replacement operation.
ED05726-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area after session ID encryption. Output value: [Errno= <u>error number output from OS</u>]
ED05801-10071	FATAL	Can't Set Keyword.	Failed to create keyword entry.
ED05901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED05902-10143	FATAL	IW_CreateConfig() Error.	An error occurred during configuration creation.
ED05905-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for storing keyword \$REQUEST_URL entry. Output value: [Errno= <u>error number output from OS</u>]
ED05906-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for storing keyword \$REQUEST_URL entry. Output value: [Errno= <u>error number output from OS</u>]
ED05908-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for storing w_imode_pat. Output value: [Errno= <u>error number output from OS</u>]
ED05915-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for creating buffer. Output value: [Errno= <u>error number output from OS</u>]
ED05923-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for creating buffer. Output value: [Errno= <u>error number output from OS</u>]
ED05926-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for creating buffer. Output value: [Errno= <u>error number output from OS</u>]
ED05929-00008	FATAL	IW_ClearBuf() Error.	Failed to allocate work buffer area for Agent transfer login.
ED05930-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work buffer area for Agent transfer login. Output value: [Errno= <u>error number output from OS</u>]
ED05935-10399	FATAL	DFW_PostFwGetParmFromQuery() Error.	Could not extract path information from inheritance data.
ED05936-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area to create REQUEST_URI. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED05938-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area to create REQUEST_URI. Output value: [Errno= <u>error number output from OS</u>]
ED05939-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area to create REQUEST_URI. Output value: [Errno= <u>error number output from OS</u>]
ED05940-10399	FATAL	DFW_PostFwGetParmFromQuery() Error.	Could not extract path information from inheritance data.
ED05941-10431	FATAL	Keyword Encrypto Error.[%s]	Failed to encrypt the user ID to be set in the forced login page. Output value: [<u>string before encryption</u>]
ED05942-10431	FATAL	Keyword Encrypto Error.[%s]	Failed to encrypt the password to be set in the forced login page. Output value: [<u>string before encryption</u>]
ED05949-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for creating buffer. Output value: [Errno= <u>error number output from OS</u>]
ED05955-10439	FATAL	CMN_CreateBuf() Error.	Failed to create work area required to generate return URL for Agent.
ED06001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED06002-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Login page)
ED06003-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Login page)
ED06004-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Login page (CERT))
ED06005-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Login page (CERT))
ED06006-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Forced login page)
ED06007-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Forced login page)
ED06008-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Login user ID error page)
ED06009-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Login user ID error page)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06010-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Login password error page)
ED06011-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Login password error page)
ED06012-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Login user lock error page)
ED06013-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Login user lock error page)
ED06014-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Login initial authentication error page)
ED06015-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Login initial authentication error page)
ED06016-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Login serial number error page)
ED06017-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Login serial number error page)
ED06018-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Login group error page)
ED06019-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Login group error page)
ED06020-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Login stop error page)
ED06021-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Login stop error page)
ED06022-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Number of users exceeded error page)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06023-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Number of users exceeded error page)
ED06024-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Logout page)
ED06025-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Logout page)
ED06026-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Logout success page)
ED06027-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Logout success page)
ED06028-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Logout error page)
ED06029-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Logout error page)
ED06030-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Logout error page)
ED06031-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Logout error page)
ED06032-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Access control error page)
ED06033-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Access control error page)
ED06034-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (POST send error page)
ED06035-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (POST send error page)
ED06036-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Password change page)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06037-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Password change page)
ED06038-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Password change success page)
ED06039-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Password change success page)
ED06040-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Old password error page)
ED06041-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Old password error page)
ED06042-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (New password input error page)
ED06043-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (New password input error page)
ED06044-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Password policy error page)
ED06045-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Password policy error page)
ED06046-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Password change permission error page)
ED06047-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Password change permission error page)
ED06048-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Password change no login error page)
ED06049-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Password change no login error page)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06050-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Password change failure page)
ED06051-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Password change failure page)
ED06052-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (System error page)
ED06053-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (System error page)
ED06054-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Alias unspecified error page)
ED06055-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Alias unspecified error page)
ED06056-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Undefined alias error page)
ED06057-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Undefined alias error page)
ED06058-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Authentication Server down error page)
ED06059-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Authentication Server down error page)
ED06060-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Database down error page)
ED06061-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Database down error page)
ED06062-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Backend web server down error page)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06063-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Backend web server down error page)
ED06064-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Authentication Server timeout error page)
ED06065-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Authentication Server timeout error page)
ED06066-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Backend web server timeout error page)
ED06067-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Backend web server timeout error page)
ED06068-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (External interface page 1)
ED06069-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (External interface page 1)
ED06070-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (External interface page 2)
ED06071-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (External interface page 2)
ED06072-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (External interface page 3)
ED06073-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (External interface page 3)
ED06074-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (Logout page)
ED06075-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (Logout page)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06076-10146	FATAL	IW_FindConfigValue(): Not Found	An error occurred during operation to retrieve path of HTML configuration file.
ED06077-10065	FATAL	Can't Open HTML Configuration File.[%s]	Cannot open HTML configuration file. Output value: <u>[configuration file name]</u>
ED06080-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (GET filter page)
ED06081-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (GET filter page)
ED06082-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (POST filter page)
ED06083-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (POST filter page)
ED06084-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (HTML filter page)
ED06085-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (HTML filter page)
ED06086-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (SVR filter page)
ED06087-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (SVR filter page)
ED06088-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (External interface page 4)
ED06089-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (External interface page 4)
ED06090-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (External interface page 5)
ED06091-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (External interface page 5)
ED06092-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files. (External interface page 6)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06093-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (External interface page 6)
ED06094-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry by storing default values for HTML files.()
ED06095-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure by storing default values for HTML files. (error page for maximum size of POST data)
ED06096-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry in the procedure to store default values for HTML files. (Login transmission time limit error page)
ED06097-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure in the procedure to store default values for HTML files. (Password change transmission time limit error page)
ED06098-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry in the procedure to store default values for HTML files. (Login transmission time limit error page)
ED06099-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure in the procedure to store default values for HTML files. (Password change transmission time limit error page)
ED060A0-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry in the procedure to store default values for HTML files. (Database busy error page)
ED060A1-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure in the procedure to store default values for HTML files. (Database busy error page)
ED060A2-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry in the procedure to store default values for HTML files. (Request ACL error page)
ED060A3-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure in the procedure to store default values for HTML files. (Request ACL error page)
ED060A4-10133	FATAL	Entry Create Error.	An error occurred in the operation to create an entry in the procedure to store default values for HTML files. (Request filter error page)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED060A5-10132	FATAL	Entry Add Error.	An error occurred in the operation to add a basic information structure in the procedure to store default values for HTML files. (Request filter error page)
ED06201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED06301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED06401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED06404-10017	FATAL	Can't Create Password ChangeNoLogin Page.	Cannot change password on no login page.
ED06408-10214	FATAL	Wrong Result.	Response result is abnormal.
ED06409-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing password change user ID. Output value: [Errno= <u>error number output from OS</u>]
ED06410-10366	FATAL	Request denied by Certification Server.(ACLREQUEST)	Connection to Authentication Module was denied.
ED06413-10422	FATAL	Can't Find.[%s]	Failed to retrieve User-Agent header. Output value: [<u>unretrievable data</u>]
ED06415-10087	FATAL	Create SocketData Error.	Could not allocate socket structure area.
ED06416-10057	FATAL	Can't Get REMOTE_ADDR.	Failed to retrieve remote address.
ED06501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED06513-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for retrieving POST data. Output value: [Errno= <u>error number output from OS</u>]
ED06523-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work area for entered old password. Output value: [Errno= <u>error number output from OS</u>]
ED06524-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work area for entered password. Output value: [Errno= <u>error number output from OS</u>]
ED06525-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work area for reentered new password. Output value: [Errno= <u>error number output from OS</u>]
ED06601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED06602-10021	FATAL	Can't Create Password Change Reenter Password Error Page.	Cannot create the update error page.
ED06701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED06704-10059	FATAL	Can't Get Response.	Cannot retrieve response data.
ED06705-10018	FATAL	Can't Create Password Change OK Page.	Cannot build the password change success page.
ED06706-10028	FATAL	Can't Create Update NG Page.	Cannot create the update error page.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06707-10011	FATAL	Can't Connect Directory Server or Database.	Cannot connect to directory server or database.
ED06709-10129	FATAL	DFW_SetPasswordPage() Error.	Cannot build the access error page.
ED06711-10013	FATAL	Can't Create Password Change Policy Error Page.	Cannot build the policy error page.
ED06712-10213	FATAL	Wrong Response Data.	Response data is invalid.
ED06713-10129	FATAL	DFW_SetPasswordPage() Error.	Failed in operation to create error page 1 for the external routine for password changes.
ED06714-10129	FATAL	DFW_SetPasswordPage() Error.	Failed in operation to create error page 2 for the external routine for password changes.
ED06715-10129	FATAL	DFW_SetPasswordPage() Error.	Failed in operation to create error page 3 for the external routine for password changes.
ED06716-10366	FATAL	Request denied by Certification Server.(ACLREQUEST)	Connection to Authentication Module was denied.
ED06719-10422	FATAL	Can't Find.[%s]	Failed to retrieve User-Agent header. Output value: [unretrievable data]
ED06722-10057	FATAL	Can't Get REMOTE_ADDR.	Failed to retrieve remote address.
ED06723-10087	FATAL	Create SocketData Error.	Could not allocate socket structure area.
ED06724-10013	FATAL	Can't Create Password Change Policy Error Page.	An error occurred when creating the password policy error page.
ED06725-10013	FATAL	Can't Create Password Change Policy Error Page.	An error occurred when creating the password policy error page.
ED06726-10013	FATAL	Can't Create Password Change Policy Error Page.	An error occurred when creating the password policy error page.
ED06727-10013	FATAL	Can't Create Password Change Policy Error Page.	An error occurred when creating the password policy error page.
ED06801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED06802-10087	FATAL	Create SocketData Error.	Cannot allocate socket structure area.
ED06803-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate structure area for response message. Output value: [Errno=error number output from OS]
ED06804-10153	FATAL	IW_SetUserQueryRequest() Error.	An error occurred in operation to create user query message.
ED06806-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate area for storing UID in request structure. Output value: [Errno=error number output from OS]
ED06807-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate area for storing in password request structure. Output value: [Errno=error number output from OS]
ED06812-10213	FATAL	Wrong Response Data.	Response data is invalid.
ED06813-10366	FATAL	Request denied by Certification Server.(ACLREQUEST)	Connection to Authentication Module was denied.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06816-10422	FATAL	Can't Find.[%s]	Failed to retrieve User-Agent header. Output value: <u>[unretrievable data]</u>
ED06819-10057	FATAL	Can't Get REMOTE_ADDR.	Failed to retrieve remote address.
ED06901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED06902-00008	FATAL	IW_ClearBuf() Error.	An error occurred during buffer clearing.
ED06903-00023	FATAL	IW_SetBuf() Error.	An error occurred during output to status entry.
ED06904-00023	FATAL	IW_SetBuf() Error.	An error occurred in outputting MIME entry.
ED06905-00023	FATAL	IW_SetBuf() Error.	An error occurred in outputting MIME entry.
ED06906-10147	FATAL	IW_INFO format Error.	IW_INFO format is invalid.
ED06907-10040	FATAL	Can't Find COOKIENAME.	Cannot find cookie name.
ED06908-00026	FATAL	malloc() Error. Errno=%d	Could not allocate area for creating cookie by using arbitrary session ID name. Output value: [Errno= <u>error number output from OS</u>]
ED06909-00023	FATAL	IW_SetBuf() Error.	An error occurred in outputting created cookie.
ED06910-10190	FATAL	RedirectURL is NULL.	Redirect URL is NULL.
ED06911-00023	FATAL	IW_SetBuf() Error.	An error occurred in outputting redirect location to location entry.
ED07001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED07003-10362	FATAL	DFW_ReplaceFilterChar() Error.	An error occurred during redirect URL filtering.
ED07101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED07103-10362	FATAL	DFW_ReplaceFilterChar() Error.	An error occurred during redirect URL filtering.
ED07301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED07303-00008	FATAL	IW_ClearBuf() Error.	An error occurred during buffer clearing.
ED07304-00023	FATAL	IW_SetBuf() Error.	An error occurred during output to status entry.
ED07305-00023	FATAL	IW_SetBuf() Error.	An error occurred in outputting MIME entry.
ED07306-00023	FATAL	IW_SetBuf() Error.	An error occurred in outputting MIME entry.
ED07307-00026	FATAL	malloc() Error. Errno=%d	Cannot create area for storing HOST name. Output value: [Errno= <u>error number output from OS</u>]
ED07308-00026	FATAL	malloc() Error. Errno=%d	Cannot create area for storing HOST name. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED07309-00026	FATAL	malloc() Error. Errno=%d	Cannot create area for storing SESSION. Output value: [Errno= <u>error number output from OS</u>]
ED07310-00026	FATAL	malloc() Error. Errno=%d	Cannot create area for storing SESSION. Output value: [Errno= <u>error number output from OS</u>]
ED07311-00023	FATAL	IW_SetBuf() Error.	An error occurred in setting redirect URL to buffer.
ED07401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED07407-10012	FATAL	Can't Create Configuration.[env]	Could not create IW_CONF-type env structure.
ED07408-10105	FATAL	DFW_GetOtherEnv() Error.	An error occurred during header information retrieval.
ED07411-10244	FATAL	PATH_INFO is over the maximum length.	PATH_INFO length exceeds the maximum length.
ED07420-10380	FATAL	DFW_GetPathinfoFromRequestUri() Error.	Failed to retrieve Backend Web Server connection path from environment variable REQUEST_URI.
ED07421-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate PATH_INFO information area. Output value: [Errno= <u>error number output from OS</u>]
ED07426-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate SessionID area. Output value: [Errno= <u>error number output from OS</u>]
ED07427-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate SessionID area. Output value: [Errno= <u>error number output from OS</u>]
ED07429-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area for storing request path. Output value: [Errno= <u>error number output from OS</u>]
ED07430-10472	FATAL	DFW_CertLBSidJudge() Error.	Failed in the procedure to assign Authentication Module.
ED07501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED07601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED07701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED07801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED07901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED08101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED08102-10040	FATAL	Can't Find COOKIENAME.	Failed to retrieve SessionID name from configuration.
ED08103-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate SessionID area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED08104-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate cookie.value area. Output value: [Errno= <u>error number output from OS</u>]
ED08105-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate cookie.others area. Output value: [Errno= <u>error number output from OS</u>]
ED08106-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate cookie.name area. Output value: [Errno= <u>error number output from OS</u>]
ED08107-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate cookie.send_info area. Output value: [Errno= <u>error number output from OS</u>]
ED08108-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate cookie.others area. Output value: [Errno= <u>error number output from OS</u>]
ED08109-00026	FATAL	malloc() Error. Errno=%d	Failed to create area for storing cookie key. Output value: [Errno= <u>error number output from OS</u>]
ED08110-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate session ID encryption work area. Output value: [Errno= <u>error number output from OS</u>]
ED08111-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate session ID encryption work area. Output value: [Errno= <u>error number output from OS</u>]
ED08112-10356	FATAL	SessionID Decrypt Failed.	An error occurred in the session ID encryption library.
ED08113-10358	FATAL	DFW_ModifyStrings() Error.	Failed in session ID replacement operation.
ED08114-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area after session ID encryption. Output value: [Errno= <u>error number output from OS</u>]
ED08115-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED08201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED08202-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing PATH_INFO in structure. Output value: [Errno= <u>error number output from OS</u>]
ED08203-10131	FATAL	Encode PATH_INFO Failed.	Failed to encode PATH_INFO.
ED08204-00026	FATAL	malloc() Error. Errno=%d	Failed to create area for storing cookie.iw_info. Output value: [Errno= <u>error number output from OS</u>]
ED08205-00026	FATAL	malloc() Error. Errno=%d	Failed to create area for storing cookie.value. Output value: [Errno= <u>error number output from OS</u>]
ED08206-00026	FATAL	malloc() Error. Errno=%d	Failed to create area for storing cookie.send_info. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED08207-00026	FATAL	malloc() Error. Erno=%d	Failed to create area for storing cookie.others. Output value: [Erno=error number output from OS]
ED08208-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area for storing alias name in structure. Output value: [Erno=error number output from OS]
ED08209-00026	FATAL	malloc() Error. Erno=%d	Failed to create area for storing host. Output value: [Erno=error number output from OS]
ED08211-00026	FATAL	malloc() Error. Erno=%d	Failed to create area for storing URL. Output value: [Erno=error number output from OS]
ED08212-00026	FATAL	malloc() Error. Erno=%d	Failed to create area for storing PATH_INFO. Output value: [Erno=error number output from OS]
ED08214-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area required for buffer extension. Output value: [Erno=error number output from OS]
ED08215-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area for storing SessionID name. Output value: [Erno=error number output from OS]
ED08219-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate session ID encryption work area. Output value: [Erno=error number output from OS]
ED08220-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate session ID encryption work area. Output value: [Erno=error number output from OS]
ED08221-10356	FATAL	SessionID Decrypt Failed.	An error occurred in the session ID encryption library.
ED08222-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate session ID encryption work area. Output value: [Erno=error number output from OS]
ED08223-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate session ID encryption work area. Output value: [Erno=error number output from OS]
ED08224-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area. Output value: [Erno=error number output from OS]
ED08301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED08302-00026	FATAL	malloc() Error. Erno=%d	Failed to create area for storing forwarder.script. Output value: [Erno=error number output from OS]
ED08303-00026	FATAL	malloc() Error. Erno=%d	Failed to create area for storing forwarder.hostname. Output value: [Erno=error number output from OS]
ED08304-00026	FATAL	malloc() Error. Erno=%d	Failed to create area for storing forwarder.http_host. Output value: [Erno=error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED08305-10061	FATAL	Can't Get.[%s]	Could not retrieve environment variable. Output value: [entry name]
ED08306-10061	FATAL	Can't Get.[%s]	Could not retrieve environment variable. Output value: [entry name]
ED08307-00026	FATAL	malloc() Error. Erno=%d	Failed to create area for storing forwarder.http_host. Output value: [Erno=error number output from OS]
ED08401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED08403-00026	FATAL	malloc() Error. Erno=%d	Could not allocate area for storing client.method. Output value: [Erno=error number output from OS]
ED08404-00026	FATAL	malloc() Error. Erno=%d	Could not allocate area for storing request method. Output value: [Erno=error number output from OS]
ED08406-00026	FATAL	malloc() Error. Erno=%d	Could not allocate area for storing client.address. Output value: [Erno=error number output from OS]
ED08407-00026	FATAL	malloc() Error. Erno=%d	Could not allocate area for storing REMOTE_ADDR. Output value: [Erno=error number output from OS]
ED08408-10245	FATAL	QUERY_STRING is over the maximum length.	QUERY_STRING is longer than the maximum length.
ED08409-00026	FATAL	malloc() Error. Erno=%d	Could not allocate area for storing content type. Output value: [Erno=error number output from OS]
ED08410-00026	FATAL	malloc() Error. Erno=%d	Could not allocate area for storing POST data. Output value: [Erno=error number output from OS]
ED08412-00026	FATAL	malloc() Error. Erno=%d	Could not allocate area for storing QUERY_STRING. Output value: [Erno=error number output from OS]
ED08413-10029	FATAL	Can't Decode Client Certificate.	Could not decode client certificate.
ED08418-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory for storing encrypted QUERY_STRING. Output value: [Erno=error number output from OS]
ED08419-00003	FATAL	Configuration Invalid Entry. Entry=%s	Failed to retrieve encryption parameter name. Output value: [Entry=unretrievable parameter name]
ED08420-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate work area for encryption parameter format change. Output value: [Erno=error number output from OS]
ED08422-10387	FATAL	stdin select() Error.(errno=%d)	Failed in select() operation. Output value: [errno=error number output from OS]
ED08423-10386	FATAL	read timeout. [postdata]	POST data receive timeout occurred.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED08424-10390	FATAL	stdin read() Error.(errno=%d)	Failed to receive POST data. Output value: [errno= <u>error number output from OS</u>]
ED08425-10391	FATAL	Read POSTDATA is fewer than contentlength.	Received POST data size does not match the Content-length value.
ED08601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED08602-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving name. Output value: [Errno= <u>error number output from OS</u>]
ED08603-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving value. Output value: [Errno= <u>error number output from OS</u>]
ED08604-10155	FATAL	KeyData Create Error.	Cannot create key data.
ED08605-10132	FATAL	Entry Add Error.	Entry addition error occurred.
ED08701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED08801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED08802-10092	FATAL	Decode System Error(ClientCert).	Certificate information decoding system error.
ED08803-10091	FATAL	Decode Library Error(ClientCert).	Certificate information decoding library error.
ED08804-00026	FATAL	malloc() Error. Errno=%d	Failed to create serial number storage area. Output value: [Errno= <u>error number output from OS</u>]
ED08805-10053	FATAL	Can't Get CertSerial.	Cannot retrieve certificate serial number.
ED08806-00026	FATAL	malloc() Error. Errno=%d	Could not allocate area required for storing Expire. Output value: [Errno= <u>error number output from OS</u>]
ED08807-10052	FATAL	Can't Get CertExpire.	Could not retrieve certificate expiration date.
ED08808-10054	FATAL	Can't Get Configuration Data.[CC_UID]	Cannot retrieve configuration data.
ED08809-10175	FATAL	Not Found.[OU]	Cannot find [OU].
ED08810-10174	FATAL	Not Found UserID.[OU]	No hits found for search string.
ED08811-10005	FATAL	Bad Configuration Data.[CC_UID]	User ID splitting location is not CN.
ED08812-10034	FATAL	Can't Divide UserID.[CC_UIDKEYS]	Failed to split user ID.
ED08813-10033	FATAL	Can't Divide UserID.[CC_UIDKEYE]	Failed to split user ID.
ED08814-00026	FATAL	malloc() Error. Errno=%d	Could not create User ID storage area. Output value: [Errno= <u>error number output from OS</u>]
ED08815-10060	FATAL	Can't Get UserID.	Cannot retrieve UID.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED08816-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate area required for creating string separated by ':' that concatenates the serial number and issuer. Output value: [Errno= <u>error number output from OS</u>]
ED09201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED09301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED09302-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate structure area. Output value: [Errno= <u>error number output from OS</u>]
ED09304-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate host name retrieval area. Output value: [Errno= <u>error number output from OS</u>]
ED09306-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate PATH_INFO retrieval area. Output value: [Errno= <u>error number output from OS</u>]
ED09308-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for splitting URL. Output value: [Errno= <u>error number output from OS</u>]
ED09501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED09502-00008	FATAL	IW_ClearBuf() Error.	An error occurred during clearing of send/receive buffer.
ED09503-00008	FATAL	IW_ClearBuf() Error.	An error occurred during clearing of send/receive buffer.
ED09504-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate creation area for method line. Output value: [Errno= <u>error number output from OS</u>]
ED09505-00023	FATAL	IW_SetBuf() Error.	An error occurred during operation to set method line.
ED09509-00023	FATAL	IW_SetBuf() Error.	Could not add name to header.
ED09510-00023	FATAL	IW_SetBuf() Error.	Could not add name to header.
ED09511-00023	FATAL	IW_SetBuf() Error.	Could not add value to header.
ED09512-00023	FATAL	IW_SetBuf() Error.	Could not add value to header.
ED09513-00023	FATAL	IW_SetBuf() Error.	Could not add cookie to header.
ED09514-00023	FATAL	IW_SetBuf() Error.	Could not add cookie to header.
ED09515-00023	FATAL	IW_SetBuf() Error.	Could not add cookie to header.
ED09516-00023	FATAL	IW_SetBuf() Error.	Could not set end of header.
ED09601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED09602-10222	FATAL	LocationHeader Format Error.(RemoteHTML)	Cannot retrieve URL start position.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED09603-10222	FATAL	LocationHeader Format Error.(RemoteHTML)	Cannot retrieve the end of header line. (Cannot find end of header section.)
ED09604-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate area used for location header search. Output value: [Erno= <u>error number output from OS</u>]
ED09605-10045	FATAL	Can't Find End of Header.	Cannot set the next search position.
ED09607-10222	FATAL	LocationHeader Format Error.(RemoteHTML)	Location header format is invalid.
ED09608-10224	FATAL	LocationURL Permission Error.(RemoteHTML)	LocationURL permission is invalid.
ED09609-10461	FATAL	CMN_CreateURLHost() Error.	Failed in URL information split and storage operation.
ED09701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED09704-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
ED09801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED09802-10035	FATAL	Can't Find '\n'	Cannot find "\n".
ED09803-10039	FATAL	Can't Find Content Length Separator.	Cannot find end position for the header of the content received.
ED09901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED10001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED10005-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area required for retrieving values. Output value: [Erno= <u>error number output from OS</u>]
ED10006-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area required for creating proxy connection path. (when QUERY_STRING is included) Output value: [Erno= <u>error number output from OS</u>]
ED10007-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area required for creating proxy connection path. (when QUERY_STRING is not included) Output value: [Erno= <u>error number output from OS</u>]
ED10008-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area required for creating normal connection path. (when QUERY_STRING is included) Output value: [Erno= <u>error number output from OS</u>]
ED10009-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area required for creating normal connection path. (when QUERY_STRING is not included) Output value: [Erno= <u>error number output from OS</u>]
ED10010-10154	FATAL	IW_StrInsertBuf() Error.	An error occurred in changing the newly created path.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED10101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED10102-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate the area required for filter data creation function. Output value: [Erno= <u>error number output from OS</u>]
ED10103-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate filter buffer area. Output value: [Erno= <u>error number output from OS</u>]
ED10104-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate area for search/replacement source key. Output value: [Erno= <u>error number output from OS</u>]
ED10105-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate string area for replacing replacement source key. Output value: [Erno= <u>error number output from OS</u>]
ED10301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED10302-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate buffer area after replacement. Output value: [Erno= <u>error number output from OS</u>]
ED10401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED10402-10251	FATAL	FilterString is over the maximum size.	String exceeded the maximum size after replacement.
ED10403-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate buffer area after replacement. Output value: [Erno= <u>error number output from OS</u>]
ED10404-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate filter structure area. Output value: [Erno= <u>error number output from OS</u>]
ED10405-00026	FATAL	malloc() Error. Erno=%d	Cannot create area for storing host name. Output value: [Erno= <u>error number output from OS</u>]
ED10406-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area required for filter structure. Output value: [Erno= <u>error number output from OS</u>]
ED10407-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area for creating extension buffer. Output value: [Erno= <u>error number output from OS</u>]
ED10501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED10601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED10602-10249	FATAL	DFW_CreateFilterData() Error.	An error occurred during operation to set tag in filter structure.
ED10604-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area for storing filter string. Output value: [Erno= <u>error number output from OS</u>]
ED10607-10248	FATAL	DFW_RequestFilter() Error.	Failed in filter operation.
ED10701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED10702-10249	FATAL	DFW_CreateFilterData() Error.	An error occurred during operation to set tag in filter structure.
ED10704-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing filter string. Output value: [Errno= <u>error number output from OS</u>]
ED10707-10248	FATAL	DFW_RequestFilter() Error.	Failed in filter operation.
ED10801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED10802-10253	FATAL	DFW_CreateHostList() Error.	An error occurred during operation to create list of permitted hosts.
ED10803-10249	FATAL	DFW_CreateFilterData() Error.	An error occurred during operation to set tag in filter structure.
ED10807-10254	FATAL	DFW_ReplaceHostData() Error.	Failed in filter operation.
ED10901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED10902-10035	FATAL	Can't Find '\n'	Cannot find "\n".
ED10903-10039	FATAL	Can't Find Content Length Separator.	Cannot find end of received header.
ED11001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED11002-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area for applying filter. Output value: [Errno= <u>error number output from OS</u>]
ED11003-10249	FATAL	DFW_CreateFilterData() Error.	An error occurred during operation to set tag in filter structure.
ED11005-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate filter processing area. Output value: [Errno= <u>error number output from OS</u>]
ED11006-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate filter processing area. Output value: [Errno= <u>error number output from OS</u>]
ED11101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED11105-10254	FATAL	DFW_ReplaceHostData() Error.	Failed in filter operation.
ED11201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED11202-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for setting host entry. Output value: [Errno= <u>error number output from OS</u>]
ED11203-10155	FATAL	KeyData Create Error.	Failed to create KeyData.
ED11204-10156	FATAL	KeyData Add Error.	Failed to add KeyData.
ED11205-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED11206-10155	FATAL	KeyData Create Error.	Failed to create KeyData.
ED11207-10156	FATAL	KeyData Add Error.	Failed to add KeyData.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED11208-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED11209-10155	FATAL	KeyData Create Error.	Failed to create KeyData.
ED11210-10156	FATAL	KeyData Add Error.	Failed to add KeyData.
ED11211-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED11212-10155	FATAL	KeyData Create Error.	Failed to create KeyData.
ED11213-10156	FATAL	KeyData Add Error.	Failed to add KeyData.
ED11301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED11401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED11501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED11502-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED11503-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED11601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED11701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED11702-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED11801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED11901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED11902-00023	FATAL	IW_SetBuf() Error.	Cannot store to buffer.
ED11903-00023	FATAL	IW_SetBuf() Error.	Cannot store to buffer.
ED12001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED12002-10258	FATAL	The external library returned the unjust value.	Invalid value returned from external routine.
ED12101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED12105-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for creating comparison PATH_INFO during logout. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED12106-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for creating comparison PATH_INFO during password change. Output value: [Errno= <u>error number output from OS</u>]
ED12201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED12301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED12901-00026	FATAL	malloc() Error. Errno=%d	Cannot create memory area for form authentication information structure. Output value: [Errno= <u>error number output from OS</u>]
ED13001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED13201-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory area for entry structure. Output value: [Errno= <u>error number output from OS</u>]
ED13202-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory area for setting alias. Output value: [Errno= <u>error number output from OS</u>]
ED13203-00010	FATAL	IW_CreateChain() Error.	Failed to create form authentication keyword structure.
ED13204-10278	FATAL	DFW_CreateFormSendData() Error.	An error occurred when creating the data structure for sending text.
ED13205-10278	FATAL	DFW_CreateFormSendData() Error.	An error occurred when creating the data structure for sending user information.
ED13206-10278	FATAL	DFW_CreateFormSendData() Error.	An error occurred when creating the data structure for sending page information.
ED13601-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for information structure for sending form. Output value: [Errno= <u>error number output from OS</u>]
ED13801-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for entry structure. Output value: [Errno= <u>error number output from OS</u>]
ED13802-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for sending attribute name information. Output value: [Errno= <u>error number output from OS</u>]
ED13803-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for sending attribute value information. Output value: [Errno= <u>error number output from OS</u>]
ED14001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED14009-10279	FATAL	DFW_CreateFormDataEntry() Error.	Cannot set entry.
ED14010-10280	FATAL	DFW_AddFormDataEntry() Error.	Cannot add entry.
ED14011-10155	FATAL	KeyData Create Error.	Failed to create chain structure entry.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED14012-10156	FATAL	KeyData Add Error.	Failed to add KeyData.
ED14013-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for FORM_URL and FORM_HTML operations. Output value: [Errno= <u>error number output from OS</u>]
ED14014-10279	FATAL	DFW_CreateFormDataEntry() Error.	Cannot set entry.
ED14015-10280	FATAL	DFW_AddFormDataEntry() Error.	Cannot add entry.
ED14016-10281	FATAL	DFW_CreateFormSendDataEntry() Error.	Failed to create send information entry for addition.
ED14017-10282	FATAL	DFW_AddFormSendDataEntry() Error.	Failed to add send information entry for addition.
ED14201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED14205-10098	FATAL	DFW_CreateFWResponseHeader() Error.	Failed to convert header in direct transmission method.
ED14207-10143	FATAL	IW_CreateConfig() Error.	Failed to allocate storage area for form authentication Set-cookie header.
ED14212-10043	FATAL	Can't Find Failover Entry.	Cannot find failover entry.
ED14301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED14303-10287	FATAL	The ACTION attribute of a FORM tag was unacquirable from the page.[%s]	Could not retrieve ACTION attribute value from FORM tag list. Output value: [<u>alias name</u>]
ED14306-00010	FATAL	IW_CreateChain() Error.	Failed to allocate area required for acquiring INPUT tag from HTML.
ED14601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED14602-10143	FATAL	IW_CreateConfig() Error.	Failed to create structure for QUERY_STRING acquisition.
ED14603-10143	FATAL	IW_CreateConfig() Error.	Failed to create structure for POSTDATA acquisition.
ED14608-00010	FATAL	IW_CreateChain() Error.	Could not acquire INPUT tag from HTML.
ED14613-00043	FATAL	IW_CreateBuf() Error.	Failed to create QUERY_STRING buffer during direct transmission method.
ED14615-00043	FATAL	IW_CreateBuf() Error.	Failed to create POSTDATA buffer during direct transmission method.
ED14701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED14703-10268	FATAL	DFW_EncodeBuf() Error.	Failed to encode Name value.
ED14704-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for setting "\$" at start. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED14705-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory area for encoding value of Value. Output value: [Errno= <u>error number output from OS</u>]
ED14706-10268	FATAL	DFW_EncodeBuf() Error.	Failed to encode value of Value.
ED14707-00026	FATAL	malloc() Error. Errno=%d	Could not retrieve memory area for setting value of Value. Output value: [Errno= <u>error number output from OS</u>]
ED14708-00012	FATAL	IW_CreateConfigEntry() Error.	Could not set entry in structure.
ED14709-10132	FATAL	Entry Add Error.	Failed to add entry.
ED14710-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for encoding and setting QUERY_STRING. Output value: [Errno= <u>error number output from OS</u>]
ED14711-10268	FATAL	DFW_EncodeBuf() Error.	Failed to encode QUERY_STRING.
ED14801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED14802-00023	FATAL	IW_SetBuf() Error.	Could not set data in form send data buffer.
ED14803-00023	FATAL	IW_SetBuf() Error.	Could not set data in form send data buffer.
ED14804-00023	FATAL	IW_SetBuf() Error.	Could not set data in form send data buffer.
ED14805-00023	FATAL	IW_SetBuf() Error.	Could not set data in form send data buffer.
ED14901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED14902-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for Value. Output value: [Errno= <u>error number output from OS</u>]
ED14903-10291	FATAL	DFW_FormSetSendData() Error.	Could not set data structure of acquired send data.
ED14904-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for form authentication input user ID. Output value: [Errno= <u>error number output from OS</u>]
ED14905-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for form authentication input user password. Output value: [Errno= <u>error number output from OS</u>]
ED15001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED15002-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for retrieving Value. Output value: [Errno= <u>error number output from OS</u>]
ED15101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED15102-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for method and path conversion. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED15105-10154	FATAL	IW_StrInsertBuf() Error.	Failed to replace buffer.
ED15106-10297	FATAL	DFW_DeleteHeaderValue() Error.	Failed to delete Content-type.
ED15107-10297	FATAL	DFW_DeleteHeaderValue() Error.	Failed to delete Content-length.
ED15108-10296	FATAL	DFW_ModifyHeaderValueAdd() Error.	Failed to change or add Content-type.
ED15109-10296	FATAL	DFW_ModifyHeaderValueAdd() Error.	Failed to change or add Content-length.
ED15110-10035	FATAL	Can't Find '\n'	Cannot find "\n".
ED15111-10045	FATAL	Can't Find End of Header.	Cannot find end of header.
ED15112-10154	FATAL	IW_StrInsertBuf() Error.	Failed to replace buffer.
ED15115-00026	FATAL	malloc() Error. Errno=%d	Could not retrieve area for setting path in data structure. Output value: [Errno=error number output from OS]
ED15116-00026	FATAL	malloc() Error. Errno=%d	Could not retrieve area for setting host name in data structure. Output value: [Errno=error number output from OS]
ED15117-10305	FATAL	DFW_ChangeRelativePath() Error.	Could not retrieve send path from current path.
ED15118-00026	FATAL	malloc() Error. Errno=%d	Could not retrieve area for setting host name in data structure. Output value: [Errno=error number output from OS]
ED15120-10319	FATAL	The connection place of form certification is a non-set up host.[%s:%d]	Data receiver host for form authentication is undefined. Output value: [host name:port number]
ED15121-10237	FATAL	A proxy setup cannot be performed to a SSL server.[%s:%d]	Proxy configuration performed with SSL. Output value: [host name:port number]
ED15123-10237	FATAL	A proxy setup cannot be performed to a SSL server.[%s:%d]	Proxy configuration performed with SSL. Output value: [host name:port number]
ED15124-00026	FATAL	malloc() Error. Errno=%d	Could not retrieve area required for operation. Output value: [Errno=error number output from OS]
ED15125-00026	FATAL	malloc() Error. Errno=%d	Could not retrieve area required for operation. Output value: [Errno=error number output from OS]
ED15129-10297	FATAL	DFW_DeleteHeaderValue() Error.	An error occurred during HTTP header delete for form authentication.
ED15201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED15301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED15305-10154	FATAL	IW_StrInsertBuf() Error.	Failed to replace target request header value.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED15306-10035	FATAL	Can't Find '\n'	Cannot find "\n".
ED15307-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating insertion buffer. Output value: [Errno= <u>error number output from OS</u>]
ED15308-10154	FATAL	IW_StrInsertBuf() Error.	Failed to add header.
ED15401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED15402-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area required for retrieving tag. Output value: [Errno= <u>error number output from OS</u>]
ED15403-10155	FATAL	KeyData Create Error.	Failed to create KeyData.
ED15404-10156	FATAL	KeyData Add Error.	Failed to add KeyData.
ED15501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED15502-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for retrieving Value value. Output value: [Errno= <u>error number output from OS</u>]
ED15601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED15602-10301	FATAL	FormTemplateHTML is not defined.	No HTML information found in entry structure.
ED15606-10143	FATAL	IW_CreateConfig() Error.	Cannot set Method and Action information to structure.
ED15607-00012	FATAL	IW_CreateConfigEntry() Error.	Could not set Method information.
ED15608-10132	FATAL	Entry Add Error.	Failed to add entry.
ED15609-00012	FATAL	IW_CreateConfigEntry() Error.	Failed to set Action information.
ED15610-10132	FATAL	Entry Add Error.	Failed to add entry.
ED15901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED15902-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for retrieving attribute value. Output value: [Errno= <u>error number output from OS</u>]
ED16001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED16002-10304	FATAL	The class of the relative path of URL is inaccurate.	Class error occurred.
ED16003-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for creating path. Output value: [Errno= <u>error number output from OS</u>]
ED16101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED16102-10306	FATAL	No data is in an output buffer.	Cannot retrieve buffer.
ED16104-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory area for creating new buffer. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED16105-00008	FATAL	IW_ClearBuf() Error.	Failed to clear buffer.
ED16106-00023	FATAL	IW_SetBuf() Error.	Failed to set new buffer.
ED16301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED16302-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area for creating a path with a port. Output value: [Errno=error number output from OS]
ED16304-10462	FATAL	CMN_UriCmpIPv6() Error.	Failed in URL comparison operation.
ED16401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED16402-10143	FATAL	IW_CreateConfig() Error.	Failed to create IW_CONF type structure.
ED16403-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for retrieving NAME value. Output value: [Errno=error number output from OS]
ED16404-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for retrieving value of VALUE. Output value: [Errno=error number output from OS]
ED16405-10133	FATAL	Entry Create Error.	Failed to create entry.
ED16406-10132	FATAL	Entry Add Error.	Failed to add entry.
ED16407-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for retrieving value of VALUE. Output value: [Errno=error number output from OS]
ED16408-10133	FATAL	Entry Create Error.	Failed to create entry.
ED16409-10132	FATAL	Entry Add Error.	Failed to add entry.
ED16501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED16502-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for encoding keyword. Output value: [Errno=error number output from OS]
ED16601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED16606-10313	FATAL	QUERY_STRING Format Error.[AGENT_KEY]	QUERY_STRING format is invalid.
ED16701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED16702-10087	FATAL	Create SocketData Error.	Failed to allocate socket structure area.
ED16703-10153	FATAL	IW_SetUserQueryRequest() Error.	Failed to create user query message.
ED16704-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for response message structure. Output value: [Errno=error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED16706-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area required for storing user ID in structure. Output value: [Errno= <u>error number output from OS</u>]
ED16707-00026	FATAL	malloc() Error. Errno=%d	Cannot allocate memory area required for storing password in structure. Output value: [Errno= <u>error number output from OS</u>]
ED16708-10213	FATAL	Wrong Response Data.	Response data is invalid.
ED16709-10366	FATAL	Request denied by Certification Server.(ACLREQUEST)	Connection to Authentication Module was denied.
ED16712-10422	FATAL	Can't Find.[%s]	Failed to retrieve User-Agent header. Output value: [<u>unretrievable data</u>]
ED16715-10317	FATAL	Can't get IW_INFO.	Failed to retrieve session ID.
ED16716-10057	FATAL	Can't Get REMOTE_ADDR.	Failed to retrieve remote address.
ED16801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED16804-10313	FATAL	QUERY_STRING Format Error.[AGENT_KEY]	QUERY_STRING format is invalid.
ED16805-10313	FATAL	QUERY_STRING Format Error.[AGENT_KEY]	QUERY_STRING format is invalid.
ED16806-10317	FATAL	Can't get IW_INFO.	Cannot retrieve IW_INFO.
ED16807-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory area for storing session ID. Output value: [Errno= <u>error number output from OS</u>]
ED16808-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory area for storing QUERY_STRING. Output value: [Errno= <u>error number output from OS</u>]
ED16810-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for storing redirect URL. Output value: [Errno= <u>error number output from OS</u>]
ED16813-10317	FATAL	Can't get IW_INFO.	Cannot retrieve IW_INFO.
ED16814-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory area for storing session ID. Output value: [Errno= <u>error number output from OS</u>]
ED16815-10362	FATAL	DFW_ReplaceFilterChar() Error.	An error occurred during redirect URL filtering.
ED16816-10369	FATAL	QUERY_STRING Encrypt Failed.(No Encryption Key.)	Failed to encrypt QUERY_STRING because the encryption key is not set.
ED16817-10371	FATAL	QUERY_STRING Encrypt Failed.	Failed to encrypt QUERY_STRING.
ED16818-00003	FATAL	Configuration Invalid Entry. Entry=%s	Failed to retrieve encryption parameter name. Output value: [Entry= <u>unretrievable parameter name</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED16819-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area for encryption parameter format change. Output value: [Erno= <u>error number output from OS</u>]
ED17101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED17102-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate semicolon decoding area. Output value: [Erno= <u>error number output from OS</u>]
ED17201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED17301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED17303-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area for session ID encryption. Output value: [Erno= <u>error number output from OS</u>]
ED17401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED17404-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate add header area in header insertion operation. Output value: [Erno= <u>error number output from OS</u>]
ED17405-10154	FATAL	IW_StrInsertBuf() Error.	An error occurred in header insertion operation.
ED17501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED17601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED17602-10312	FATAL	DFW_SplitQueryString() Error.	Failed to split QUERY_STRING.
ED17603-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate area to store QUERY_STRING temporarily. Output value: [Erno= <u>error number output from OS</u>]
ED17604-10312	FATAL	DFW_SplitQueryString() Error.	An error occurred during operation to split QUERY_STRING.
ED17607-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate entire area for Agent transfer information. Output value: [Erno= <u>error number output from OS</u>]
ED17608-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate AGENT_KEY area for request. Output value: [Erno= <u>error number output from OS</u>]
ED17609-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate return URL area for Agent. Output value: [Erno= <u>error number output from OS</u>]
ED17610-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate path information area for Agent. Output value: [Erno= <u>error number output from OS</u>]
ED17611-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate QUERY_STRING information area for Agent. Output value: [Erno= <u>error number output from OS</u>]
ED17615-00003	FATAL	Configuration Invalid Entry. Entry=%s	Failed to retrieve encryption parameter name. Output value: [Entry= <u>unretrievable parameter name</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED17616-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for encryption parameter format change. Output value: [Errno= <u>error number output from OS</u>]
ED17617-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory required for retrieving transaction ID sent from Agent. Output value: [Errno= <u>error number output from OS</u>]
ED17618-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory required for retrieving request type sent from Agent. Output value: [Errno= <u>error number output from OS</u>]
ED17701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED17702-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED17704-10342	FATAL	DFW_FindAgentDataEntry() Error.	An error occurred during the data search operation for Agent.
ED17712-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate Agent alias information area. Output value: [Errno= <u>error number output from OS</u>]
ED17801-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for Agent control structure. Output value: [Errno= <u>error number output from OS</u>]
ED18001-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for Agent data creation. Output value: [Errno= <u>error number output from OS</u>]
ED18002-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate alias information area for Agent structure. Output value: [Errno= <u>error number output from OS</u>]
ED18003-00010	FATAL	IW_CreateChain() Error.	Failed to allocate IP control information area for Agent structure. Output value: [Errno= <u>error number output from OS</u>]
ED18004-00010	FATAL	IW_CreateChain() Error.	Failed to allocate host control information area for Agent structure. Output value: [Errno= <u>error number output from OS</u>]
ED18005-00010	FATAL	IW_CreateChain() Error.	Failed to allocate domain control information area for Agent structure. Output value: [Errno= <u>error number output from OS</u>]
ED18006-10470	FATAL	CMN_CreateChain() Error.	Failed to create chain structure.
ED18201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED18401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED18501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED18601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED18604-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work buffer area for Agent IP control. Output value: [Errno=error number output from OS]
ED18701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED18801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED18901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED18905-10133	FATAL	Entry Create Error.	An error occurred in creating structure entry.
ED18906-10132	FATAL	Entry Add Error.	An error occurred in adding structure entry.
ED18907-10330	FATAL	DFW_CreateAgentDataEntry() Error.	An error occurred in creating a data entry for Agent structure.
ED18908-10332	FATAL	DFW_AddAgentDataEntry() Error.	An error occurred in adding a data entry for Agent structure.
ED18909-10155	FATAL	KeyData Create Error.	An error occurred in creating a keydata structure for Agent structure.
ED18910-10156	FATAL	KeyData Add Error.	An error occurred when adding a keydata structure for Agent structure.
ED18912-10330	FATAL	DFW_CreateAgentDataEntry() Error.	An error occurred in creating a data entry for Agent structure.
ED18913-10332	FATAL	DFW_AddAgentDataEntry() Error.	An error occurred in adding a data entry for Agent structure.
ED19001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED19002-10064	FATAL	Can't Open File.[%s]	Cannot open configuration file. Output value: [file path]
ED19003-00033	FATAL	File Lock Error. File=(%s) errno=(%d) errmsg=(%s).	Cannot lock configuration file. Output value: [File=[file path]] [errno=[error number output from OS]] [errmsg=[error message retrieved from OS]]
ED19004-10135	FATAL	fdopen() Error.	Failed in fopen() of configuration file.
ED19005-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for loading configuration file. Output value: [Errno=error number output from OS]
ED19006-00034	FATAL	Configuration format error.[%s]	Failed to retrieve file information. Output value: [fstat() error]
ED19101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED19102-10346	FATAL	DFW_SetDFWConf() Error.	An error occurred while splitting configuration file.
ED19103-10347	FATAL	DFW_SetHostConf() Error.	An error occurred while splitting host configuration file.
ED19104-10348	FATAL	DFW_SetFormConf() Error.	An error occurred while splitting form configuration file.
ED19201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED19301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED19401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED19501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED19502-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work buffer area during conversion of request header URL. Output value: [Errno= <u>error number output from OS</u>]
ED19503-10166	FATAL	Not Found.[Alias]	Alias not included in URL by operation to convert request header URL.
ED19504-10166	FATAL	Not Found.[Alias]	Alias not included in URL by operation to convert request header URL.
ED19505-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work buffer area after operation to convert request header URL. Output value: [Errno= <u>error number output from OS</u>]
ED19506-00018	FATAL	IW_ModifyConfigValue() Error.	Failed to convert header by operation to convert request header URL.
ED19507-10220	FATAL	DFW_SetTemplateHost() Error.	An error occurred while splitting URL information.
ED19508-10422	FATAL	Can't Find.[%s]	Failed to extract alias from URL. Output value: [<u>unretrievable data</u>]
ED19601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED19604-00043	FATAL	IW_CreateBuf() Error.	Failed to create buffer to be added to header.
ED19605-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate add header area in add header operation. Output value: [Errno= <u>error number output from OS</u>]
ED19606-10154	FATAL	IW_StrInsertBuf() Error.	An error occurred in header insertion operation.
ED19701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED19703-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate header area in header retrieval operation. Output value: [Errno= <u>error number output from OS</u>]
ED19705-00012	FATAL	IW_CreateConfigEntry() Error.	Failed to create header management structure entry in header retrieval operation.
ED19706-00007	FATAL	IW_AddConfigEntry() Error.	Failed to add header management structure entry in header retrieval operation.
ED19801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED19802-00043	FATAL	IW_CreateBuf() Error.	Failed to allocate work area required for Set-Cookie header conversion.
ED19803-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate conversion area in Set-cookie header conversion. Output value: [Errno= <u>error number output from OS</u>]
ED19804-10143	FATAL	IW_CreateConfig() Error.	Failed to create header management structure entry in Set-cookie header conversion operation.
ED19805-00012	FATAL	IW_CreateConfigEntry() Error.	Failed to add header management structure entry in Set-cookie header conversion operation.
ED19901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED19902-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work area for session ID retrieval. Output value: [Errno= <u>error number output from OS</u>]
ED19903-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work area for session ID retrieval. Output value: [Errno= <u>error number output from OS</u>]
ED20001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED20002-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work buffer area in string replacement operation. Output value: [Errno= <u>error number output from OS</u>]
ED20003-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area after replacement in string replacement operation. Output value: [Errno= <u>error number output from OS</u>]
ED20004-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work buffer area in string replacement operation. Output value: [Errno= <u>error number output from OS</u>]
ED20101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED20301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED20302-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work buffer area in add charset operation. Output value: [Errno= <u>error number output from OS</u>]
ED20303-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work buffer area in add charset operation. Output value: [Errno= <u>error number output from OS</u>]
ED20304-10296	FATAL	DFW_ModifyHeaderValueAdd() Error.	Failed to allocate replacement process in add charset operation.
ED20401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED20402-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work buffer area in header retrieval operation. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED20403-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work buffer area in header retrieval operation. Output value: [Errno= <u>error number output from OS</u>]
ED20501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED20601-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work area for POSTDATA retrieval operation. Output value: [Errno= <u>error number output from OS</u>]
ED20602-10260	FATAL	Encode POST KEYWORD Failed.	Failed in keyword encoding process for POSTDATA retrieval.
ED20603-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work area for POSTDATA retrieval operation. Output value: [Errno= <u>error number output from OS</u>]
ED20701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED20702-10365	FATAL	Unconfigured parameter=[%s]	Required configuration missing. Output value: [parameter= <u>configuration value</u>]
ED20703-10365	FATAL	Unconfigured parameter=[%s]	Required configuration missing. Output value: [parameter= <u>configuration value</u>]
ED20704-10365	FATAL	Unconfigured parameter=[%s]	Required configuration missing. Output value: [parameter= <u>configuration value</u>]
ED20705-10365	FATAL	Unconfigured parameter=[%s]	Required configuration missing. Output value: [parameter= <u>configuration value</u>]
ED20706-00026	FATAL	malloc() Error. Errno=%d	Could not create SerialNo storage area. Output value: [Errno= <u>error number output from OS</u>]
ED20707-00026	FATAL	malloc() Error. Errno=%d	Could not create SerialNo storage area. Output value: [Errno= <u>error number output from OS</u>]
ED20708-00026	FATAL	malloc() Error. Errno=%d	Could not create Expires storage area. Output value: [Errno= <u>error number output from OS</u>]
ED20709-10034	FATAL	Can't Divide UserID.[CC_UIDKEYS]	Failed to split user ID.
ED20710-10033	FATAL	Can't Divide UserID.[CC_UIDKEYE]	Failed to split user ID.
ED20711-10060	FATAL	Can't Get UserID.	Failed to split user ID.
ED20712-00026	FATAL	malloc() Error. Errno=%d	Could not create User ID storage area. Output value: [Errno= <u>error number output from OS</u>]
ED20801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED20802-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area after filtering operation for DFW. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED20901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED20902-10030	FATAL	Can't Delete Entry.[%s]	Failed to delete specified keyword entry. Output value: <u>[specific keyword name]</u>
ED21001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED21002-10362	FATAL	DFW_ReplaceFilterChar() Error.	Failed in DFW filter replacement operation.
ED21101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED21107-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for storing Uid during re-login operation from Agent when using certificate. Output value: <u>[Errno=error number output from OS]</u>
ED21201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED21202-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for comma-separated extension area. Output value: <u>[Errno=error number output from OS]</u>
ED21203-00010	FATAL	IW_CreateChain() Error.	Failed to allocate memory for storing extension list.
ED21205-10375	FATAL	File Extension Check Failed.	Failed in extension comparison operation.
ED21301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED21303-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for ALIAS section of extension information not requiring authentication and authorization. Output value: <u>[Errno=error number output from OS]</u>
ED21304-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for extension section of extension information not requiring authentication and authorization. Output value: <u>[Errno=error number output from OS]</u>
ED21306-00036	FATAL	IW_CreateFlagConfigEntry() Error.	An error occurred during operation to add IW_FLGCONF-type structure.
ED21307-00037	FATAL	IW_AddFlagConfigEntry() Error.	An error occurred during operation for adding an information structure with flag.
ED21401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED21402-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for work area. Output value: <u>[Errno=error number output from OS]</u>
ED21403-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for storing value when parsing extension. Output value: <u>[Errno=error number output from OS]</u>
ED21404-10155	FATAL	KeyData Create Error.	Failed to create KeyData.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED21405-10156	FATAL	KeyData Add Error.	Failed to add KeyData.
ED21501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED21502-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for return value area. Output value: [Errno=error number output from OS]
ED21601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED21602-10381	FATAL	failed to read environment variables.[%s]	Failed to retrieve environment variable. Output value: [environment variable]
ED21603-10382	FATAL	format error.[%s]	Retrieved SCRIPT_NAME information format is invalid. Output value: [environment variable]
ED21604-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for PATH_INFO information. Output value: [Errno=error number output from OS]
ED21605-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for REQUEST_URI information. Output value: [Errno=error number output from OS]
ED21607-10381	FATAL	failed to read environment variables.[%s]	Failed to retrieve environment variable. Output value: [environment variable]
ED21608-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for PATH_INFO information. Output value: [Errno=error number output from OS]
ED21610-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for editing REQUEST_URI information. Output value: [Errno=error number output from OS]
ED21611-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating PATH_INFO information. Output value: [Errno=error number output from OS]
ED21801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED21802-10382	FATAL	format error.[%s]	Header format is invalid. Output value: [invalid header]
ED21803-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating status header after replacement. Output value: [Errno=error number output from OS]
ED21804-10154	FATAL	IW_StrInsertBuf() Error.	Failed to replace status header.
ED21805-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating status header after replacement. Output value: [Errno=error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED22001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED22101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED22201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED22301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED22401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED22402-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating PATH information. Output value: [Errno= <u>error number output from OS</u>]
ED22403-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work memory area for URL encoding. Output value: [Errno= <u>error number output from OS</u>]
ED22404-10268	FATAL	DFW_EncodeBuf() Error.	Failed to encode URL.
ED22405-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work memory area for URL encoding. Output value: [Errno= <u>error number output from OS</u>]
ED22406-10268	FATAL	DFW_EncodeBuf() Error.	Failed to encode URL.
ED22407-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating POST data. Output value: [Errno= <u>error number output from OS</u>]
ED22408-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating parameter name for POST data inheritance. Output value: [Errno= <u>error number output from OS</u>]
ED22409-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for encryption determination of inheritance data. Output value: [Errno= <u>error number output from OS</u>]
ED22410-10393	FATAL	HIDEURL Encrypt Failed.	Failed to encrypt HIDEURL.
ED22501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED22502-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED22503-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED22504-10370	FATAL	QUERY_STRING Decrypt Failed.	Failed to decrypt QueryString.
ED22505-10090	FATAL	Decode Error.	Failed to decode URL for inheritance target parameter.
ED22601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED22602-10090	FATAL	Decode Error.	Failed to decode URL for inheritance data.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED22611-10075	FATAL	DFW_SetForwarderPage() Error.	Failed in operation to create POST filter page.
ED22612-10248	FATAL	DFW_RequestFilter() Error.	Failed in POST filter operation.
ED22613-00038	FATAL	Undefined parameter.[%s]	No parameter found. Output value: [parameter name]
ED22701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED22702-00034	FATAL	Configuration format error.[%s]	Parameter value format is invalid. Output value: [parameter name]
ED22704-10403	FATAL	DFW_PostFwCreateFormTag() Error.	Could not convert inheritance POST data to tag.
ED22705-00026	FATAL	malloc() Error. Errno=%d	Failed to retrieve memory area for creating cookie authentication path. Output value: [Errno=error number output from OS]
ED22706-10143	FATAL	IW_CreateConfig() Error.	Failed during creation of keyword conversion structure.
ED22707-00012	FATAL	IW_CreateConfigEntry() Error.	Failed during creation of ACTION attribute information structure.
ED22708-10132	FATAL	Entry Add Error.	Failed to add keyword conversion entry.
ED22709-00012	FATAL	IW_CreateConfigEntry() Error.	Failed during creation of POSTDATA attribute information structure.
ED22710-10132	FATAL	Entry Add Error.	Failed to add keyword conversion entry.
ED22712-00026	FATAL	malloc() Error. Errno=%d	Failed to retrieve memory area for creating cookie authentication path. Output value: [Errno=error number output from OS]
ED22713-00026	FATAL	malloc() Error. Errno=%d	Failed to retrieve memory area for creating cookie authentication path. Output value: [Errno=error number output from OS]
ED22801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED22802-10143	FATAL	IW_CreateConfig() Error.	Failed during creation of filtering process structure.
ED22803-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for POST data verification. Output value: [Errno=error number output from OS]
ED22804-10090	FATAL	Decode Error.	Failed in POST data decoding.
ED22805-10090	FATAL	Decode Error.	Failed in POST data decoding.
ED22806-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for filtering process. Output value: [Errno=error number output from OS]
ED22807-00012	FATAL	IW_CreateConfigEntry() Error.	Failed to create filtering target data entry.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED22808-10132	FATAL	Entry Add Error.	Failed to add filtering target data entry.
ED22812-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for setting inheritance data. Output value: [Errno= <u>error number</u> output from OS]
ED22813-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for setting inheritance data. Output value: [Errno= <u>error number</u> output from OS]
ED22814-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for setting inheritance data. Output value: [Errno= <u>error number</u> output from OS]
ED22901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23002-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23102-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23103-10404	FATAL	Can't find ICP Connection Data.	ICP 2.0 communication information structure missing.
ED23106-10452	FATAL	Can't get CertdLBAlias.	Could not retrieve Authentication Module information from the Authentication Module identification key.
ED23201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23204-10406	FATAL	IW_ExEncrypto IW_EXCRYPTO is NULL.	Failed to encrypt ICP 2.0 request.
ED23205-10407	FATAL	IW_ExEncrypto ErrNo[%d] ErrMsg[%s]	ICP 2.0 encryption library error. Output value: [return value][<u>error message</u>]
ED23301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23304-10410	FATAL	IW_ExDecrypto IW_EXCRYPTO is NULL.	Failed to decrypt ICP 2.0 request.
ED23305-10411	FATAL	IW_ExDecrypto ErrNo[%d] ErrMsg[%s]	ICP 2.0 encryption library decryption error. Output value: [return value][<u>error message</u>]
ED23401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23402-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for hexadecimal conversion. Output value: [Errno= <u>error number</u> output from OS]
ED23501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23503-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for Description information optimization. Output value: [Errno= <u>error number</u> output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED23508-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for Description information optimization. Output value: [Errno= <u>error number output from OS</u>]
ED23512-10423	FATAL	Invalid Response type.	Invalid response data.
ED23601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23613-00038	FATAL	Undefined parameter.[%s]	No parameter found. Output value: [<u>parameter name</u>]
ED23701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23702-10399	FATAL	DFW_PostFwGetParmFromQuery() Error.	Could not extract path information from inheritance data.
ED23703-10422	FATAL	Can't Find.[%s]	No session ID in inheritance data. Output value: [<u>retrieve failure data</u>]
ED23704-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating inheritance path. Output value: [Errno= <u>error number output from OS</u>]
ED23705-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for URL encoding. Output value: [Errno= <u>error number output from OS</u>]
ED23706-10268	FATAL	DFW_EncodeBuf() Error.	Failed in URL encoding.
ED23707-10399	FATAL	DFW_PostFwGetParmFromQuery() Error.	Failed to retrieve inheritance POST data value.
ED23708-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for URL encoding. Output value: [Errno= <u>error number output from OS</u>]
ED23709-10268	FATAL	DFW_EncodeBuf() Error.	Failed in URL encoding.
ED23710-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating encrypted section for new inheritance data. Output value: [Errno= <u>error number output from OS</u>]
ED23711-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating unencrypted section for new inheritance data. Output value: [Errno= <u>error number output from OS</u>]
ED23712-10393	FATAL	HIDEURL Encrypt Failed.	Failed in encryption.
ED23801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23802-40023	FATAL	ioctl() Error: %s	Could not change descriptor to non-blocking mode. Output value: [Errno= <u>error number output from OS</u>]
ED23802-40049	FATAL	fcntl() Error: %s	Could not change descriptor to non-blocking mode. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED23901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED23902-40023	FATAL	ioctl() Error: %s	Could not change descriptor to blocking mode. Output value: [Erno= <u>error number output from OS</u>]
ED23902-40049	FATAL	fcntl() Error: %s	Could not change descriptor to blocking mode. Output value: [Erno= <u>error number output from OS</u>]
ED24001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED24003-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area required for URL encoding. Output value: [Erno= <u>error number output from OS</u>]
ED24004-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for storing encrypted QUERY_STRING. Output value: [Erno= <u>error number output from OS</u>]
ED24005-10431	FATAL	Keyword Encrypto Error.[%s]	Failed to encrypt QUERY_STRING. (High strength encryption method) Output value: [<u>string before encryption</u>]
ED24006-10431	FATAL	Keyword Encrypto Error.[%s]	Failed to encrypt QUERY_STRING. (Traditional encryption method) Output value: [<u>string before encryption</u>]
ED24101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED24102-00003	FATAL	Configuration Invalid Entry. Entry=%s	Failed to retrieve encryption type judgment parameter name. Output value: [<u>unretrievable parameter name</u>]
ED24103-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area required for URL encoding. Output value: [Erno= <u>error number output from OS</u>]
ED24104-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory for work area to decrypt QUERY_STRING. Output value: [Erno= <u>error number output from OS</u>]
ED24201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED24301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED24302-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area required for URL conversion. Output value: [Erno= <u>error number output from OS</u>]
ED24303-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area required for URL conversion. Output value: [Erno= <u>error number output from OS</u>]
ED24401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED24402-10365	FATAL	Unconfigured parameter=[%s]	Required configuration missing. Output value: [parameter= <u>parameter name</u>]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED24403-00044	FATAL	Format Error.[%s]	Process flag is invalid. Output value: <u>[invalid flag]</u>
ED24501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED24502-10365	FATAL	Unconfigured parameter=[%s]	Required configuration missing. Output value: <u>[parameter=[parameter name]]</u>
ED24503-10431	FATAL	Keyword Encrypto Error.[%s]	Failed to encrypt POST transmission time limit data. Output value: <u>[string before encryption]</u>
ED24601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED24602-10365	FATAL	Unconfigured parameter=[%s]	Required configuration missing. Output value: <u>[parameter=[parameter name]]</u>
ED24603-10365	FATAL	Unconfigured parameter=[%s]	Required configuration missing. Output value: <u>[parameter=[parameter name]]</u>
ED24604-10432	FATAL	Keyword Decrypto Error.[%s]	Failed to decrypt POST transmission time limit data. Output value: <u>[string before decryption]</u>
ED24605-00044	FATAL	Format Error.[%s]	POST transmission time limit data format is invalid. Output value: <u>[Invalid parameter]</u>
ED24701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED24801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED24802-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate structure area for filter information. Output value: <u>[Errno=error number output from OS]</u>
ED24803-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate structure area for backend information. Output value: <u>[Errno=error number output from OS]</u>
ED24804-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate structure area for module information. Output value: <u>[Errno=error number output from OS]</u>
ED24805-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate structure area for cookie information. Output value: <u>[Errno=error number output from OS]</u>
ED24901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED25001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED25002-10439	FATAL	CMN_CreateBuf() Error.	Failed to allocate work area in ERRORINFO creation operation.
ED25003-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: <u>[Errno=error number output from OS]</u>

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED25101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED25201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED25301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED25319-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED25320-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED25321-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED25322-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area. Output value: [Errno= <u>error number output from OS</u>]
ED25323-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate trace time log output buffer area. Output value: [Errno= <u>error number output from OS</u>]
ED25401-00031	FATAL	Parameter is NULL.	Parameter is NULL.
ED25402-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area. Output value: [Errno= <u>error number output from OS</u>]
ED25404-10452	FATAL	Can't get CertdLBAlias.	Could not retrieve Authentication Module information from the Authentication Module identification key.
ED25405-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area. Output value: [Errno= <u>error number output from OS</u>]
ED25501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED25502-10043	FATAL	Can't Find Failover Entry.	Cannot find certd failover entry.
ED25601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ED25602-10470	FATAL	CMN_CreateChain() Error.	Failed to create request filter information.
ED25701-00031	FATAL	Parameter is NULL.	Parameter is NULL.
ED25702-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area. Output value: [Errno= <u>error number output from OS</u>]
ED25703-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area. Output value: [Errno= <u>error number output from OS</u>]
ED25801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED25835-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for storing transaction ID. Output value: [Errno= <u>error number output from OS</u>]
ED25836-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for storing transaction ID. Output value: [Errno= <u>error number output from OS</u>]
EI25002-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area. Output value: [Errno= <u>error number output from OS</u>]
EI25405-11072	FATAL	Illegal Parameter.	Argument parameter is invalid.
EI25406-11072	FATAL	Illegal Parameter.	Argument parameter is invalid.
EI25501-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI26101-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI26301-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI26401-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI26501-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI26601-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI26701-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI27001-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI27101-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI27201-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI27301-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI27606-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing configuration values. Output value: [Errno= <u>error number output from OS</u>]
EI27801-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI28401-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area after URL encoding. Output value: [Errno= <u>error number output from OS</u>]
EI28501-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI28701-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI28702-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area after Base64 encoding. Output value: [Errno= <u>error number output from OS</u>]
EI28801-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI28802-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate buffer area after Base64 decoding. Output value: [Erno=error number output from OS]
EI29001-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI29201-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI29301-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI29401-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI29501-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI29801-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate structure area for configuration parameter. Output value: [Erno=error number output from OS]
EI30001-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI30002-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate configuration parameter structure entry area. Output value: [Erno=error number output from OS]
EI30003-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate entry structure member area. Output value: [Erno=error number output from OS]
EI30004-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate entry structure member area. Output value: [Erno=error number output from OS]
EI30005-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate entry structure member area. Output value: [Erno=error number output from OS]
EI30201-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI30301-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI30401-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI30701-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI30702-11014	FATAL	CMN_FindConfValue() Error.	Failed to search for specified configuration value.
EI30809-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate buffer area. Output value: [Erno=error number output from OS]
EI30810-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate buffer area. Output value: [Erno=error number output from OS]
EI30811-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate buffer area. Output value: [Erno=error number output from OS]
EI31001-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI31201-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI31501-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI31701-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI31801-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI31901-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI32001-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI32101-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI32201-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI32301-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI32401-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI32402-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate area. Output value: [Erno= <u>error number output from OS</u>]
EI32501-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI32601-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI32602-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate area. Output value: [Erno= <u>error number output from OS</u>]
EI32603-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate area. Output value: [Erno= <u>error number output from OS</u>]
EI32701-00002	FATAL	Parameter is NULL.	Parameter is NULL.
EI32801-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI32802-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate buffer area for storing escape character. Output value: [Erno= <u>error number output from OS</u>]
EI32901-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI32902-11075	FATAL	CMN_GetTimeNow() Error.	Failed in current time retrieval operation.
EI32903-11073	FATAL	localtime_r() Error.	Failed to retrieve time component.
EI32904-11068	FATAL	Module type Format Error [%s].	Format of the module type included in the transaction ID is invalid. Output value: [<u>configuration value</u>]
EI32905-11069	FATAL	Transid_str Format Error [%s].	Format of the identification string included in the transaction ID is invalid. Output value: [<u>configuration value</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI32906-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for generating transaction ID. Output value: [Errno= <u>error number output from OS</u>]
EI33001-00002	FATAL	Parameter is NULL.	Parameter is NULL.
EI33101-00002	FATAL	Parameter is NULL.	Parameter is NULL.
EI33102-00002	FATAL	Parameter is NULL.	Parameter is NULL.
EI33103-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area. Output value: [Errno= <u>error number output from OS</u>]
EI33104-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area. Output value: [Errno= <u>error number output from OS</u>]
EI33201-00002	FATAL	Parameter is NULL.	Parameter is NULL.
EI33301-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI33401-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI40007-12020	FATAL	File Access Mode Error.	File access mode is invalid.
EI40101-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI40701-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI40703-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving name. Output value: [Errno= <u>error number output from OS</u>]
EI40704-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving value. Output value: [Errno= <u>error number output from OS</u>]
EI40705-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving name. Output value: [Errno= <u>error number output from OS</u>]
EI40706-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving value1. Output value: [Errno= <u>error number output from OS</u>]
EI40707-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for retrieving value2. Output value: [Errno= <u>error number output from OS</u>]
EI40708-11011	FATAL	CMN_CreateConfEntry() Error.	Failed to create entry.
EI40709-11012	FATAL	CMN_AddConfEntry() Error.	Failed to add entry.
EI40816-11005	FATAL	CMN_SetBuf() Error.	Failed to create HTML buffer.
EI40902-00001	FATAL	malloc() Error. Errno=%d	Failed to create work buffer. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI41101-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI41102-12016	FATAL	Not Include '='.	Cannot find “=”.
EI41103-11011	FATAL	CMN_CreateConfEntry() Error.	Failed to create entry.
EI41104-11012	FATAL	CMN_AddConfEntry() Error.	Failed to add entry.
EI45301-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI45304-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate replacement header separator area. Output value: [Errno= <u>error number output from OS</u>]
EI45305-11007	FATAL	CMN_StrInsertBuf() Error.	An error occurred in header insertion operation.
EI45401-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI45404-11007	FATAL	CMN_StrInsertBuf() Error.	An error occurred in header insertion operation.
EI45506-13006	FATAL	Can't Find '\n'	Cannot find “\n”.
EI45507-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for creating insertion buffer. Output value: [Errno= <u>error number output from OS</u>]
EI45508-11007	FATAL	CMN_StrInsertBuf() Error.	Failed to add header.
EI45903-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate Content-Length header area after change. Output value: [Errno= <u>error number output from OS</u>]
EI45904-13014	FATAL	HTTP_ModHeaderValue() Error.	Failed to change header.
EI46201-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI46202-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate area required for URL conversion. Output value: [Errno= <u>error number output from OS</u>]
EI46205-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing URL after conversion. Output value: [Errno= <u>error number output from OS</u>]
EI46206-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing URL after conversion. Output value: [Errno= <u>error number output from OS</u>]
EI46603-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for header to be added. Output value: [Errno= <u>error number output from OS</u>]
EI46604-13009	FATAL	HTTP_AddHeader() Error.	Failed to add header.
EI46607-13011	FATAL	HTTP_DelHeader() Error.	Failed to delete header.
EI46608-13013	FATAL	HTTP_ModHeaderName() Error.	Failed to change header name.
EI46609-13014	FATAL	HTTP_ModHeaderValue() Error.	Failed to change header value.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI46612-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate header conversion area. Output value: [Errno= <u>error number output from OS</u>]
EI46902-13006	FATAL	Can't Find '\n'	Cannot find “\n”.
EI47101-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI48801-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI48802-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate management area for session information. Output value: [Errno= <u>error number output from OS</u>]
EI55201-17002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI55208-17004	FATAL	FORM_CreateFormSend() Error.	Failed to create entry structure member.
EI55209-17003	FATAL	CMN_CreateChain() Error.	Failed to generate form authentication exclusion keyword structure.
EI55401-17002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI55501-17002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI56001-17002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI56112-17006	FATAL	FORM_CreateFormEntry() Error.	Failed to create form structure entry.
EI56113-17007	FATAL	FORM_AddFormEntry() Error.	Failed to add form structure entry.
EI56114-17001	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for the configuration information set operation. Output value: [Errno= <u>error number output from OS</u>]
EI56116-17010	FATAL	KeyData Create Error.	Failed to create KeyData.
EI56117-17011	FATAL	KeyData Add Error.	Failed to add KeyData.
EI56201-17002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI56423-17001	FATAL	malloc() Error. Errno=%d	Failed to allocate FORM authentication transmission data area. Output value: [Errno= <u>error number output from OS</u>]
EI57601-17002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI57602-17053	FATAL	CMN_CreateBuf() Error.	Failed to generate work area for entity reference character conversion.
EI57603-17033	FATAL	CMN_SetBuf() Error.	Could not store data in buffer.
EI65008-11017	FATAL	CMN_CreateChain() Error.	Failed to create chain structure.
EI65101-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI65113-00001	FATAL	malloc() Error. Errno=%d	Failed to allocate URL information structure member area within tag. Output value: [Errno= <u>error number output from OS</u>]
EI75101-00002	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI75408-16025	FATAL	FILTERERR value is unjust.	Filter error value is invalid.
EI75502-11017	FATAL	CMN_CreateChain() Error.	Failed to create chain structure.
EI75703-16025	FATAL	FILTERERR value is unjust.	Filter error value is invalid.
EI90001-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area for URL encoding. Output value: [Errno= <u>error number output from OS</u>]
EI90101-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area for URL decoding. Output value: [Errno= <u>error number output from OS</u>]
EI90201-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI90202-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI90203-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer disassembly work area. Output value: [Errno= <u>error number output from OS</u>]
EI90205-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate entry area. Output value: [Errno= <u>error number output from OS</u>]
EI90301-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI90303-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer for concatenation work area. Output value: [Errno= <u>error number output from OS</u>]
EI90401-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI90402-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI90403-19008	FATAL	IW_SetBuf() Error.	Failed to set fixed format for encryption data buffer.
EI90404-19008	FATAL	IW_SetBuf() Error.	Failed to set fixed format for encryption data buffer.
EI90405-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI90406-19008	FATAL	IW_SetBuf() Error.	Failed to set fixed format for encryption data buffer.
EI90407-19008	FATAL	IW_SetBuf() Error.	Failed to set fixed format for encryption data buffer.
EI90408-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI90409-19008	FATAL	IW_SetBuf() Error.	Failed to set fixed format for encryption data buffer.
EI90410-19008	FATAL	IW_SetBuf() Error.	Failed to set fixed format for encryption data buffer.
EI90411-19008	FATAL	IW_SetBuf() Error.	Failed to set fixed format for encryption data buffer.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI90413-19008	FATAL	IW_SetBuf() Error.	Failed to set the send data buffer header and arbitrary header separator.
EI90414-19008	FATAL	IW_SetBuf() Error.	Failed to set the send data buffer header and arbitrary header.
EI90415-19008	FATAL	IW_SetBuf() Error.	Failed to set the separator character in the send data buffer.
EI90416-19008	FATAL	IW_SetBuf() Error.	Failed to set the encrypted body in the send data buffer.
EI90417-11005	FATAL	CMN_SetBuf() Error.	Could not add transaction ID to header.
EI90418-11005	FATAL	CMN_SetBuf() Error.	Could not store [\r\n] in buffer.
EI90419-11005	FATAL	CMN_SetBuf() Error.	Could not store [\r\n] in buffer.
EI90420-11005	FATAL	CMN_SetBuf() Error.	Could not add ICP encryption method to header.
EI90501-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI90502-19015	FATAL	ICP Format Error.	ICP communication data format is invalid. (Failed to retrieve fixed header information.)
EI90503-19015	FATAL	ICP Format Error.	ICP communication data format is invalid. (Failed to retrieve fixed header information.)
EI90504-19015	FATAL	ICP Format Error.	ICP communication data format is invalid. (Failed to retrieve fixed header information.)
EI90505-19015	FATAL	ICP Format Error.	ICP communication data format is invalid. (Failed to retrieve separator for header suffix.)
EI90601-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI90602-19015	FATAL	ICP Format Error.	ICP communication data format is invalid. (Failed to retrieve body.)
EI90603-19015	FATAL	ICP Format Error.	ICP communication data format is invalid. (Body is 0 bytes.)
EI90604-19020	FATAL	Content-length Error. [%d] Body=[%d]	Content-length value and received body length do not match. Output value: [Content-length value] [Body=[Body length]]
EI92001-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate ICP communication structure area. Output value: [Errno=error number output from OS]
EI92002-19009	FATAL	IW_CreateSocketData() Error.	Failed to create send/receive data structure.
EI92101-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate structure area for split data. Output value: [Errno=error number output from OS]
EI92601-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI92602-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate method area in header structure. Output value: [Errno=error number output from OS]
EI92603-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate path area in header structure. Output value: [Errno=error number output from OS]
EI92604-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate ICP version area in header structure. Output value: [Errno=error number output from OS]
EI92605-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate ICP version area in header structure. Output value: [Errno=error number output from OS]
EI92606-19002	FATAL	malloc() Error. Errno=%d	Failed to allocate message area in header structure. Output value: [Errno=error number output from OS]
EI92701-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI92702-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI92703-19003	FATAL	Create Socket Failed.	Failed to create client socket.
EI92704-19006	FATAL	Send Data Failed.	Failed to send ICP 1.0 encryption data.
EI92705-19005	FATAL	Recv Data Failed.	Failed to receive ICP 1.0 decryption data.
EI92706-19006	FATAL	Send Data Failed.	Failed to send ICP 2.0 encryption data.
EI92707-19005	FATAL	Recv Data Failed.	Failed to receive ICP 2.0 encryption data.
EI92708-19004	FATAL	Close Socket Failed.	Failed to close socket.
EI94101-19007	FATAL	Bad Response Data.	Response data is invalid.
EI94201-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI94202-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI94203-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI94204-19002	FATAL	malloc() Error. Errno=%d	Failed to create area for AGENT_ID message. Output value: [Errno=error number output from OS]
EI94301-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI94302-19018	FATAL	Not Found. [%s]	Cannot retrieve session ID. Output value: [unretrievable data]
EI94306-19018	FATAL	Not Found. [%s]	Cannot retrieve access control URL. Output value: [unretrievable data]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI94309-19018	FATAL	Not Found. [%s]	Cannot retrieve client IP address. Output value: <u>[unretrievable data]</u>
EI94401-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI94402-19016	FATAL	No Match ICP Version. Send[%s] -> Recv[%s]	ICP version does not match. Output value: [Send[<u>sent ICP version</u>] -> Recv[<u>received ICP version</u>]]
EI94403-19007	FATAL	Bad Response Data.	Not a user ID access response.
EI94501-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI94502-19018	FATAL	Not Found. [%s]	Cannot retrieve session ID. Output value: <u>[unretrievable data]</u>
EI94506-19018	FATAL	Not Found. [%s]	Cannot retrieve access control URL. Output value: <u>[unretrievable data]</u>
EI94508-19018	FATAL	Not Found. [%s]	Cannot retrieve client certificate user ID. Output value: <u>[unretrievable data]</u>
EI94511-19018	FATAL	Not Found. [%s]	Cannot retrieve client IP address. Output value: <u>[unretrievable data]</u>
EI94601-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI94602-19016	FATAL	No Match ICP Version. Send[%s] -> Recv[%s]	ICP version does not match. Output value: [Send[<u>sent ICP version</u>] -> Recv[<u>received ICP version</u>]]
EI94603-19007	FATAL	Bad Response Data.	Not a certificate access response.
EI94701-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI94702-19018	FATAL	Not Found. [%s]	User ID not found. Output value: <u>[unretrievable data]</u>
EI94703-19018	FATAL	Not Found. [%s]	Password not found. Output value: <u>[unretrievable data]</u>
EI94704-19018	FATAL	Not Found. [%s]	Remote address not found. Output value: <u>[unretrievable data]</u>
EI94801-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI94802-19016	FATAL	No Match ICP Version. Send[%s] -> Recv[%s]	ICP version does not match. Output value: [Send[<u>sent ICP version</u>] -> Recv[<u>received ICP version</u>]]
EI94803-19007	FATAL	Bad Response Data.	Not a login response.
EI94901-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI94902-19018	FATAL	Not Found. [%s]	User ID not found. Output value: <u>[unretrievable data]</u>
EI94903-19018	FATAL	Not Found. [%s]	Password not found. Output value: <u>[unretrievable data]</u>
EI94904-19018	FATAL	Not Found. [%s]	Remote address not found. Output value: <u>[unretrievable data]</u>
EI95001-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI95002-19016	FATAL	No Match ICP Version. Send[%s] -> Recv[%s]	ICP version does not match. Output value: [Send[<u>sent ICP version</u>] -> Recv[<u>received ICP version</u>]]
EI95003-19007	FATAL	Bad Response Data.	Not certificate login response.
EI95101-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI95102-19018	FATAL	Not Found. [%s]	Session ID not found. Output value: <u>[unretrievable data]</u>
EI95103-19018	FATAL	Not Found. [%s]	Remote address not found. Output value: <u>[unretrievable data]</u>
EI95201-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI95202-19016	FATAL	No Match ICP Version. Send[%s] -> Recv[%s]	ICP version does not match. Output value: [Send[<u>sent ICP version</u>] -> Recv[<u>received ICP version</u>]]
EI95203-19007	FATAL	Bad Response Data.	Not logout response.
EI95301-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI95302-19018	FATAL	Not Found. [%s]	Session ID not found. Output value: <u>[unretrievable data]</u>
EI95303-19018	FATAL	Not Found. [%s]	Remote address not found. Output value: <u>[unretrievable data]</u>
EI95304-19018	FATAL	Not Found. [%s]	Changed password not found. Output value: <u>[unretrievable data]</u>
EI95401-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI95402-19016	FATAL	No Match ICP Version. Send[%s] -> Recv[%s]	ICP version does not match. Output value: [Send[<u>sent ICP version</u>] -> Recv[<u>received ICP version</u>]]
EI95403-19007	FATAL	Bad Response Data.	Not logout response.
EI95501-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI95502-19018	FATAL	Not Found. [%s]	Session ID not found. Output value: <u>[unretrievable data]</u>
EI95503-19018	FATAL	Not Found. [%s]	Remote address not found. Output value: <u>[unretrievable data]</u>
EI95601-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI95602-19016	FATAL	No Match ICP Version. Send[%s] -> Recv[%s]	ICP version does not match. Output value: [Send[<u>sent ICP version</u>] -> Recv[<u>received ICP version</u>]]
EI95603-19007	FATAL	Bad Response Data.	Not user query response.
EI95701-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI96005-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI96006-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI96101-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI96208-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI96209-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate buffer area. Output value: [Erno= <u>error number output from OS</u>]
EI96403-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI96705-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI96906-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EI97003-19001	FATAL	Parameter is NULL.	Argument parameter is NULL.
EIF3301-00002	FATAL	Parameter is NULL.	Parameter is NULL.
EIF3314-00001	FATAL	malloc() Error. Erno=%d	Failed to allocate buffer area. Output value: [Erno= <u>error number output from OS</u>]
EIF5603-11074	FATAL	realloc() Error. Erno=%d	Failed to allocate receive data storage area. Output value: [Erno= <u>error number output from OS</u>]
EL01101-40004	FATAL	alloc Size is 0.	The alloc size is 0.
EL01102-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate buffer area. Output value: [Erno= <u>error number output from OS</u>]
EL01201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL01301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL01302-40030	FATAL	IW_ExtendBuf() Error.	An error occurred during buffer extension.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL01501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL01601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL01603-40030	FATAL	IW_ExtendBuf() Error.	An error occurred during buffer extension.
EL01604-40030	FATAL	IW_ExtendBuf() Error.	An error occurred during buffer extension.
EL01901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL01903-00026	FATAL	malloc() Error. Erno=%d	Cannot allocate area for creating extended buffer. Output value: [Erno= <u>error number output from OS</u>]
EL02002-40030	FATAL	IW_ExtendBuf() Error.	An error occurred during buffer extension.
EL02101-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EL02302-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for entry structure. Output value: [Erno= <u>error number output from OS</u>]
EL02303-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for member value of entry structure. Output value: [Erno= <u>error number output from OS</u>]
EL02701-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for configuration structure. Output value: [Erno= <u>error number output from OS</u>]
EL02901-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for entry structure. Output value: [Erno= <u>error number output from OS</u>]
EL02902-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for member name of entry structure. Output value: [Erno= <u>error number output from OS</u>]
EL02903-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for member value of entry structure. Output value: [Erno= <u>error number output from OS</u>]
EL03402-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for search key escape. Output value: [Erno= <u>error number output from OS</u>]
EL03702-00026	FATAL	malloc() Error. Erno=%d	Failed to create area for storing search target entry. Output value: [Erno= <u>error number output from OS</u>]
EL04501-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for host information structure. Output value: [Erno= <u>error number output from OS</u>]
EL05101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL05102-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL05301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL05302-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL05501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL05502-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05503-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05504-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05505-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05506-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05507-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL05701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL05702-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05703-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05704-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05705-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05706-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05707-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05708-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05709-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05801-00031	FATAL	Parameter is NULL.	Parameter is NULL.
EL05901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL05902-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05903-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05904-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL05905-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL06101-00031	FATAL	Parameter is NULL.	Parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL06102-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06103-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06104-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06105-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL06301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL06302-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06303-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06304-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06305-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06306-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06307-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06308-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06309-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL06401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL07701-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory for failover structure. Output value: [Erno=error number output from OS]
EL08201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL08301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL08802-00008	FATAL	IW_ClearBuf() Error.	An error occurred during buffer clearing.
EL08803-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL08804-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL08805-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL08806-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL08807-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL08808-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL08809-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL08810-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL08811-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL08812-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL08813-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EL09001-40014	FATAL	Create Socket Failed.	Failed to create socket.
EL09002-40042	FATAL	Send Data Failed.	Failed to send data.
EL09004-40038	FATAL	Recv Data Failed.	Failed to receive data.
EL09005-40010	FATAL	Close Socket Failed.	Failed to close socket.
EL09201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL09203-40021	FATAL	Get HTML Failed.	Failed to retrieve HTML.
EL10301-40048	FATAL	socket() Error: %s	Socket error occurred. Output value: [Error: <u>message corresponding to error number output from OS</u>]
EL11501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL11503-00028	FATAL	No Match TagKey-Value.(argument)	Cannot find second keyword.
EL11504-00027	FATAL	No Match TagKey-Name.(argument)	Cannot find first keyword.
EL11801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL11802-00030	FATAL	NotFound '='.	Cannot find “=”.
EL11803-00028	FATAL	No Match TagKey-Value.(argument)	Cannot find second keyword.
EL11804-00027	FATAL	No Match TagKey-Name.(argument)	Cannot find first keyword.
EL12001-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for configuration structure with flag. Output value: [Erno= <u>error number output from OS</u>]
EL12201-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for entry structure. Output value: [Erno= <u>error number output from OS</u>]
EL12202-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for member name of entry structure. Output value: [Erno= <u>error number output from OS</u>]
EL12203-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area for member value of entry structure. Output value: [Erno= <u>error number output from OS</u>]
EL12602-00026	FATAL	malloc() Error. Erno=%d	Failed to create area for storing search target entry. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL12701-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work area for POST data decoding. Output value: [Errno= <u>error number output from OS</u>]
EL12702-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate work area for POST data decoding. Output value: [Errno= <u>error number output from OS</u>]
EL12801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EL12901-00031	FATAL	Parameter is NULL.	Parameter is NULL.
EL12902-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EL70602-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for work area. Output value: [Errno= <u>error number output from OS</u>]
EL70605-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for string after encryption. Output value: [Errno= <u>error number output from OS</u>]
EL70702-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for storing decryption target section. Output value: [Errno= <u>error number output from OS</u>]
EL70703-10090	FATAL	Decode Error.	Failed to decode URL.
EL70801-40015	FATAL	Data is NULL.	Parameter is NULL.
EL70802-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for work area. Output value: [Errno= <u>error number output from OS</u>]
EL70803-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for storing request extension. Output value: [Errno= <u>error number output from OS</u>]
ED00102-10172	WARNING	Not Found Path_Info in URL.	PATH_INFO not found.
ED00103-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred during creation of normal login page.
ED00104-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred during creation of client certificate login page.
ED00105-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred during creation of POST send error page.
ED00106-10108	WARNING	DFW_Login() Error.	A system error occurred during login.
ED00107-10094	WARNING	DFW_AccessControl() Error.	A system error occurred during access control operation.
ED00108-10110	WARNING	DFW_Logout() Error.	A system error occurred during logout.
ED00109-10119	WARNING	DFW_PasswordChangePage() Error.	A system error occurred during operation to output password change page.
ED00110-10118	WARNING	DFW_PassowrdChangeMain() Error.	A system error occurred during password change.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED00111-10471	WARNING	DFW_LogoutPage() Error.	Failed in operation to create logout page.
ED00112-10118	WARNING	DFW_PassowrdChangeMain() Error.	A system error occurred during redirect operation in omitting ReverseProxy “/.”
ED00113-10096	WARNING	DFW_ClientRequest() Error.	An error occurred in the request from the client.
ED00114-10159	WARNING	MIMECheck() Error.	An error occurred in the MIME verification of received content.
ED00115-10160	WARNING	MIMETextProc() Error.	An error occurred in the MIME verification (text) of received content.
ED00116-10257	WARNING	External Library Error.	An external routine error occurred.
ED00123-10314	WARNING	DFW_AgentJudge() Error.	An error occurred during Agent connection control operation.
ED00124-10324	WARNING	DFW_AddSidHeader() Error.	An error occurred during session ID insertion operation.
ED00126-10372	WARNING	DFW_ReLogin() Error.	Failed in relogin from Agent.
ED00127-10119	WARNING	DFW_PasswordChangePage() Error.	Cannot retrieve password change HTML.
ED00128-10395	WARNING	DFW_PostFwCreateLoginPage() Error.	Failed in process to create POST data inheritance login page.
ED00129-10395	WARNING	DFW_PostFwCreateLoginPage() Error.	Failed in process to create POST data inheritance login page.
ED00130-10414	WARNING	ICP_CreateComm() Error.	Failed to create ICP 2.0 communication information structure.
ED00131-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED00132-10448	WARNING	gettimeofday() Error. Erno=%d	Failed to retrieve the time. Output value: [Erno= <u>error number output from OS</u>]
ED00133-10448	WARNING	gettimeofday() Error. Erno=%d	Failed to retrieve the time. Output value: [Erno= <u>error number output from OS</u>]
ED00134-10463	WARNING	DFW_RequestFilterJudge() Error.	An error occurred in the request filter judgment operation.
ED00204-10093	WARNING	DFW_AccessConnection() Error.	Communication process (SSO) with Authentication Module is incorrect.
ED00205-10120	WARNING	DFW_ReadBackendConf() Error.	Backend configuration loading operation is incorrect.
ED00206-10097	WARNING	DFW_ControlForwardEnv() Error.	Browser information forwarding control operation is incorrect.
ED00207-10023	WARNING	Can't Create RequestHeader.	Could not create request header for Forwarder.
ED00208-10099	WARNING	DFW_ForwardToBackend() Error.	Forwarder operation to Backend Web Server was not performed correctly.
ED00210-10066	WARNING	Can't Set Access Error Page.	Cannot create the access permission error page.
ED00211-10075	WARNING	DFW_SetForwarderPage() Error.	Cannot create the relogin page when no certificate is used.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED00212-10075	WARNING	DFW_SetForwarderPage() Error.	Cannot create the relogin page when a certificate is used.
ED00213-10075	WARNING	DFW_SetForwarderPage() Error.	Cannot create the relogin page.
ED00214-10119	WARNING	DFW_PasswordChangePage() Error.	Cannot retrieve password change HTML.
ED00218-10066	WARNING	Can't Set Access Error Page.	Cannot create page for external interface error 1.
ED00219-10066	WARNING	Can't Set Access Error Page.	Cannot create page for external interface error 2.
ED00220-10066	WARNING	Can't Set Access Error Page.	Cannot create page for external interface error 3.
ED00221-10257	WARNING	External Library Error.	External routine error.
ED00222-10257	WARNING	External Library Error.	External routine error.
ED00223-10283	WARNING	DFW_FormCert() Error.	Failed in Automatic Form Authentication operation.
ED00224-10309	WARNING	DFW_AddContentLength() Error.	Failed in add Content-length operation.
ED00229-10321	WARNING	DFW_DecomposeSemicolon() Error.	An error occurred during semicolon conversion.
ED00231-10395	WARNING	DFW_PostFwCreateLoginPage() Error.	Failed in process to create POST data inheritance login page.
ED00232-10392	WARNING	Can't Get Status Code.	Status code was not included in the content retrieved from the Backend Web Server.
ED00233-10075	WARNING	DFW_SetForwarderPage() Error.	Failed to create the GET filter error page.
ED00234-10075	WARNING	DFW_SetForwarderPage() Error.	Failed to create POST filter error page.
ED00237-10441	WARNING	DFW_GetHttpComParamInfo() Error.	An error occurred during retrieval of HTTP communication configuration information.
ED00238-10442	WARNING	DFW_GetHttpConvInfo() Error.	An error occurred during retrieval of HTTP header conversion information.
ED00240-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED00241-10448	WARNING	gettimeofday() Error. Errno=%d	Failed to retrieve the time. Output value: [Errno= <u>error number output from OS</u>]
ED00242-10448	WARNING	gettimeofday() Error. Errno=%d	Failed to retrieve the time. Output value: [Errno= <u>error number output from OS</u>]
ED00311-10001	WARNING	All Backend Web Server Down.	All Backend Web Servers are down.
ED00312-10063	WARNING	Can't Modify Configuration File.	Could not change configuration file.
ED00315-10235	WARNING	DFW_ModifyHeaderValue() Error.	An error occurred in changing request header value.
ED00317-00040	WARNING	failover to %s:%d.	Failover occurred in %s:%d. Output value: [<u>host name:port number</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED00318-00041	WARNING	configuration file updated.	Configuration file was updated.
ED00403-10150	WARNING	IW_SetAccessRequest() Error.	An error occurred during process to create an access control request message. (Certificate not used)
ED00404-10149	WARNING	IW_SetAccessCertRequest() Error.	An error occurred during process to create an access control request message. (Certificate is used)
ED00405-10196	WARNING	Send Request Failed.	Failed to send request. (Certificate not used)
ED00406-10196	WARNING	Send Request Failed.	Failed to send request. (Certificate is used)
ED00410-10413	WARNING	DFW_ToUpperHexadecimal() Error.	Failed to convert hexadecimal string.
ED00411-10416	WARNING	ICP_SetAccessCertRequest() Error.	Failed to create access control request using ICP 2.0 certificate.
ED00412-10196	WARNING	Send Request Failed.	Failed to send request. (Certificate not used)
ED00413-10196	WARNING	Send Request Failed.	Failed to send request. (Certificate is used)
ED00415-10424	WARNING	DFW_OptimizeResponse() Error.	Failed to optimize ICP 2.0 response message.
ED00419-10415	WARNING	ICP_SetAccessRequest() Error.	Failed to create ICP 2.0 access control request.
ED00420-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED00603-10047	WARNING	Can't Find Separator.	Cannot find separator. (When retrieving end of name)
ED00605-10047	WARNING	Can't Find Separator.	Cannot find separator. (When verifying end of search)
ED00626-10037	WARNING	Can't Find BA_UID[%s] from certd's Response.	BASIC authentication user ID missing. Output value: [user ID]
ED00627-10036	WARNING	Can't Find BA_PWD[%s] from certd's Response.	BASIC authentication password missing. Output value: [password]
ED00904-10205	WARNING	URL Check Failed.	Failed in URL verification.
ED00906-10167	WARNING	Not Found '>'.	Cannot find ">" which indicates the end of the tag.
ED01003-10249	WARNING	DFW_CreateFilterData() Error.	An error occurred during operation to set tag in filter structure.
ED01006-10243	WARNING	DFW_HTMLFilter() Error.	A system error occurred during HTML filtering.
ED01007-10204	WARNING	Tag Replace Failed.	Failed in URL conversion.
ED01008-10249	WARNING	DFW_CreateFilterData() Error.	An error occurred during operation to set tag in filter structure.
ED01011-10256	WARNING	DFW_SVRTagFilter() Error.	A system error occurred during the Host filter operation.
ED01102-00006	WARNING	Get URL Failed.	Failed to retrieve URL.
ED01103-10206	WARNING	URL Replace Failed.	Failed to convert URL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED01104-10206	WARNING	URL Replace Failed.	Failed to convert URL.
ED01105-10206	WARNING	URL Replace Failed.	Failed to convert URL.
ED01107-00006	WARNING	Get URL Failed.	Failed to retrieve URL.
ED01203-10181	WARNING	Path Not Include '//'.	Cannot find "//".
ED01204-10181	WARNING	Path Not Include '//'.	Cannot find "//".
ED01303-10181	WARNING	Path Not Include '//'.	Cannot find "//".
ED01304-10181	WARNING	Path Not Include '//'.	Cannot find "//".
ED01402-10069	WARNING	Can't Set Default Data.	Failed to assign default data for basic information structure.
ED01423-10344	WARNING	DFW_ReadFile() Error.	An error occurred during file loading.
ED01424-10345	WARNING	DFW_SplitConf() Error.	An error occurred while splitting configuration file.
ED01503-00029	WARNING	Not Include '='.	Cannot find "=".
ED01504-10004	WARNING	Bad Configuration Format.[HOST]	Configuration format is invalid.
ED01505-00013	WARNING	IW_CreateFailoverEntry() Error.	Failed to create entry.
ED01506-10142	WARNING	IW_AddFailoverEntry() Error.	Failed to add entry.
ED01603-00029	WARNING	Not Include '='.	Cannot find "=".
ED01703-00029	WARNING	Not Include '='.	Cannot find "=".
ED01805-00018	WARNING	IW_ModifyConfigValue() Error.	An error occurred when changing configuration value.
ED01903-00029	WARNING	Not Include '='.	Cannot find "=".
ED01904-00013	WARNING	IW_CreateFailoverEntry() Error.	An error occurred when creating entry of failover structure.
ED01905-00019	WARNING	IW_ModifyFailoverEntry() Error.	An error occurred when changing entry of failover structure.
ED01906-10142	WARNING	IW_AddFailoverEntry() Error.	Failed to add entry.
ED02501-10042	WARNING	Can't Find Failover Alias.	Failed to create new configuration string.
ED02511-10440	WARNING	CONF_ModifyConfigFile() Error.	Could not change configuration file.
ED02626-10344	WARNING	DFW_ReadFile() Error.	An error occurred during file loading.
ED02627-10345	WARNING	DFW_SplitConf() Error.	An error occurred while splitting configuration file.
ED02628-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED02902-10209	WARNING	Backend Web Server Down(http). [%s:%d]	Backend web server is down. (http) Output value: [host name:port number]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED02903-10210	WARNING	Backend Web Server Down(SSL). [%s:%d]	Backend web server is down. (SSL) Output value: [host name:port number]
ED02904-10081	WARNING	Connection System Error. [%s:%d]	Connection system error occurred. Output value: [host name:port number]
ED02905-10211	WARNING	Backend Web Server Down. [%s:%d]	Backend web server is down. Output value: [host name:port number]
ED02916-10159	WARNING	MIMECheck() Error.	An error occurred during determination of received content-type.
ED02917-10098	WARNING	DFW_CreateFWResponseHeader() Error.	An error occurred during header conversion.
ED02921-10392	WARNING	Can't Get Status Code.	Status code was not included in the content retrieved from the Backend Web Server.
ED02922-10400	WARNING	failed to negotiate SSL algorithm. host=[%s:%d]	Failed in SSL negotiations due to invalid encryption method. Output value: [host=[host name:port number]]
ED02924-10427	WARNING	Library ErrorMessage=[%s]	Error occurred in SSL library. Output value: [ErrorMessage=[SSL library error message]]
ED02925-10427	WARNING	Library ErrorMessage=[%s]	Error occurred in SSL library. Output value: [Error Message=[SSL library error message]]
ED03002-10114	WARNING	DFW_ModifyHostHeader() Error.	An error occurred during HTTP_HOST conversion.
ED03003-10112	WARNING	DFW_ModifyConnectionHeader() Error.	An error occurred during HTTP_CONNECTION conversion.
ED03004-10116	WARNING	DFW_ModifyRefererHeader() Error.	An error occurred during HTTP_REFERER conversion.
ED03005-10073	WARNING	Can't Set Request Header.	An error occurred while creating request header for Forwarder.
ED03006-10074	WARNING	DFW_SetAuthHeader() Error.	An error occurred while adding request header for Forwarder.
ED03008-10350	WARNING	DFW_URLChangeReqHeader() Error.	An error occurred during URL conversion of HTTP_DESTINATION header.
ED03102-10163	WARNING	Status Header Modify Error.	An error occurred during status header change.
ED03103-10115	WARNING	DFW_ModifyLocationHeader() Error.	An error occurred during location header change.
ED03104-10117	WARNING	DFW_ModifySetcookieHeader() Error.	An error occurred when modifying path for Set-Cookie header.
ED03107-10219	WARNING	ResponseHeader Control Error.	An error occurred during response header control operation.
ED03108-10324	WARNING	DFW_AddSidHeader() Error.	An error occurred when adding session ID.
ED03310-10061	WARNING	Can't Get.[%s]	Could not retrieve environment variable. Output value: [entry name]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED03317-00034	WARNING	Configuration format error.[%s]	HEADER parameter format is invalid. Output value: [entry name]
ED03318-00034	WARNING	Configuration format error.[%s]	HEADER parameter format is invalid. Output value: [entry name]
ED03319-00034	WARNING	Configuration format error.[%s]	HEADER parameter format is invalid. Output value: [entry name]
ED03326-10447	WARNING	HTTP_ModifyHeaderstring() Error.	Failed in the header string conversion operation.
ED03327-10447	WARNING	HTTP_ModifyHeaderstring() Error.	Failed in the header string conversion operation.
ED03328-10447	WARNING	HTTP_ModifyHeaderstring() Error.	Failed in the header string conversion operation.
ED03461-10435	WARNING	DFW_CheckPostLimitTime() Error.	An error occurred during the POST transmission time limit verification operation.
ED03504-10109	WARNING	DFW_LoginConnection() Error.	Error occurred in communication process with certd.
ED03506-10020	WARNING	Can't Create Redirect URL.	Cannot retrieve redirect target URL. (URL authentication)
ED03507-10020	WARNING	Can't Create Redirect URL.	Cannot retrieve redirect target URL. (Cookie authentication)
ED03508-10070	WARNING	Can't Set Error Page.	Cannot find header.
ED03509-10070	WARNING	Can't Set Error Page.	Cannot retrieve login failure HTML.
ED03510-10119	WARNING	DFW_PasswordChangePage() Error.	Cannot retrieve password change HTML.
ED03512-10072	WARNING	Can't Set Page.	Cannot build the page for user ID not found.
ED03513-10072	WARNING	Can't Set Page.	Cannot build the page for user account lock.
ED03514-10072	WARNING	Can't Set Page.	Cannot build the certificate error page.
ED03515-10072	WARNING	Can't Set Page.	Cannot build the serial number error page.
ED03516-10072	WARNING	Can't Set Page.	Cannot build the forced login page.
ED03517-10072	WARNING	Can't Set Page.	Cannot build the login stop page.
ED03518-10072	WARNING	Can't Set Page.	Cannot build the login group error page.
ED03519-10072	WARNING	Can't Set Page.	Cannot build the user count exceeded error page.
ED03520-10072	WARNING	Can't Set Page.	Cannot build the page for external interface error 1.
ED03521-10072	WARNING	Can't Set Page.	Cannot build the page for external interface error 2.
ED03522-10072	WARNING	Can't Set Page.	Cannot build the page for external interface error 3.
ED03523-10072	WARNING	Can't Set Page.	Cannot build the error page for login user ID maximum length.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED03524-10072	WARNING	Can't Set Page.	Cannot build the password maximum length error page.
ED03527-10119	WARNING	DFW_PasswordChangePage() Error.	Cannot retrieve password change HTML.
ED03531-10314	WARNING	DFW_AgentJudge() Error.	An error occurred during login transfer verification operation.
ED03532-10215	WARNING	Wrong Value [w_hideurl].	An error occurred while retrieving HIDEURL from POSTDATA.
ED03533-10090	WARNING	Decode Error.	Failed to decode HIDEURL.
ED03536-10129	WARNING	DFW_SetPasswordPage() Error.	An error occurred in creation of the password expiration warning page.
ED03543-10061	WARNING	Can't Get.[%s]	Could not retrieve environment variable. Output value: [entry name]
ED03545-10401	WARNING	DFW_PostFwLoginCheck() Error.	Failed in POST data inheritance login verification.
ED03546-10401	WARNING	DFW_PostFwLoginCheck() Error.	Failed in POST data inheritance login verification.
ED03547-10401	WARNING	DFW_PostFwLoginCheck() Error.	Failed in POST data inheritance login verification.
ED03548-10072	WARNING	Can't Set Page.	Cannot build the login transmission time limit error page.
ED03549-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED03550-10456	WARNING	database busy.	A database connection busy error occurred.
ED03603-10217	WARNING	Wrong Value [w_uid].	UID is an incorrect value.
ED03606-10216	WARNING	Wrong Value [w_password].	Password is an incorrect value.
ED03607-10215	WARNING	Wrong Value [w_hideurl].	hideurl is an incorrect value.
ED03608-10006	WARNING	Bad HideURL.[%s]	An error occurred in changing backend structure value. Output value: [HIDEURL]
ED03610-10208	WARNING	UserID MaxSize Error.	User ID maximum size error.
ED03611-10180	WARNING	Password MAXLEN Error.	Password maximum size error.
ED03612-10152	WARNING	IW_SetLoginRequest() Error.	An error occurred in user authentication request message creation. (Certificate not used)
ED03613-10151	WARNING	IW_SetLoginCertRequest() Error.	An error occurred in user authentication request message creation. (Certificate is used)
ED03616-10031	WARNING	Can't Divide Login Response.	Cannot split response messages from Authentication Server. (During normal communication)
ED03617-10031	WARNING	Can't Divide Login Response.	Cannot split response messages from Authentication Server. (When certificate is used)

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED03619-10090	WARNING	Decode Error.	Decode error occurred.
ED03621-10090	WARNING	Decode Error.	Decode error occurred.
ED03623-10090	WARNING	Decode Error.	Decode error occurred.
ED03625-10090	WARNING	Decode Error.	Decode error occurred.
ED03627-10377	WARNING	DFW_DeleteString() Error.	An error occurred in deleting target character in entered user ID.
ED03628-10377	WARNING	DFW_DeleteString() Error.	An error occurred in deleting target character in entered password.
ED03629-10417	WARNING	ICP_SetLoginRequest() Error.	Failed in creation of ICP 2.0 login request message.
ED03630-10418	WARNING	ICP_SetLoginCertRequest() Error.	Failed in creation of login request message using ICP 2.0 certificate.
ED03631-10031	WARNING	Can't Divide Login Response.	Cannot split response messages from Authentication Server. (During normal communication)
ED03632-10031	WARNING	Can't Divide Login Response.	Cannot split response messages from Authentication Server. (When certificate is used)
ED03634-10424	WARNING	DFW_OptimizeResponse() Error.	Failed to optimize ICP 2.0 response.
ED03640-10090	WARNING	Decode Error.	Failed in POST data decoding.
ED03641-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED03642-10433	WARNING	DFW_CheckPostLimitSetting() Error.	An error occurred during operation verification of the POST transmission time limit function.
ED03645-10451	WARNING	DFW_GetCertAlias() Error.	Failed to retrieve Authentication Module identification key.
ED03709-10063	WARNING	Can't Modify Configuration File.	Could not update configuration file.
ED03713-00040	WARNING	failover to %s:%d.	Failover occurred in %s:%d. Output value: [host name:port number]
ED03714-00042	WARNING	communication failed. [%s:%d]	Communication failed. Output value: [host name:port number]
ED03715-00042	WARNING	communication failed. [%s:%d]	Communication failed. Output value: [host name:port number]
ED03716-00042	WARNING	communication failed. [%s:%d]	Communication failed. Output value: [host name:port number]
ED03717-00041	WARNING	configuration file updated.	Configuration file was updated.
ED04105-10111	WARNING	DFW_LogoutConnection() Error.	Error occurred during communication process with certd.
ED04110-10456	WARNING	database busy.	A database connection busy error occurred.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED04202-10150	WARNING	IW_SetAccessRequest() Error.	An error occurred during creation of logout request message.
ED04203-10136	WARNING	Get Response Failed.	An error occurred while splitting response message from Authentication Server.
ED04207-10420	WARNING	ICP_SetLogoutRequest() Error.	Failed during creation of ICP 2.0 logout request message.
ED04208-10136	WARNING	Get Response Failed.	An error occurred when splitting response message from Authentication Server.
ED04210-10424	WARNING	DFW_OptimizeResponse() Error.	Failed to optimize ICP 2.0 response message.
ED04305-10032	WARNING	Can't Divide Response Message.[UserQuery]	Cannot split response messages from Authentication Server.
ED04308-10016	WARNING	Can't Create Logout Page.	Could not create logout page.
ED04309-10172	WARNING	Not Found Path_Info in URL.	PATH_INFO not found.
ED04310-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred while displaying normal login page.
ED04311-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred while displaying login page of client certificate.
ED04315-10419	WARNING	ICP_SetUserInfoRequest() Error.	Failed when creating ICP 2.0 user query request message.
ED04316-10032	WARNING	Can't Divide Response Message.[UserQuery]	Cannot split response messages from Authentication Server.
ED04318-10424	WARNING	DFW_OptimizeResponse() Error.	Failed to optimize ICP 2.0 response message.
ED04321-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED04502-10078	WARNING	Change Keyword Failed	Failed to convert keyword.
ED04503-10077	WARNING	Change HTML Failed	Failed to convert HTML.
ED04504-10162	WARNING	Content Length Modify Error.	Failed in Content-length adjustment.
ED04505-10095	WARNING	DFW_ChangeIceWallKeyword() Error.	An error occurred during conversion of designated keyword.
ED04506-10233	WARNING	DFW_ContentsCheck() Error.	An error occurred during keyword search of ERRKEY received content.
ED04507-10255	WARNING	DFW_SVRFilter() Error.	An error occurred during host filter operation.
ED04508-10095	WARNING	DFW_ChangeIceWallKeyword() Error.	An error occurred during conversion of designated keyword.
ED04509-10095	WARNING	DFW_ChangeIceWallKeyword() Error.	An error occurred during conversion of designated keyword.
ED04510-10162	WARNING	Content Length Modify Error.	Failed in Content-length adjustment.
ED04511-10437	WARNING	DFW_GetConvInfo() Error.	An error occurred during contents conversion information retrieval.
ED04512-10075	WARNING	DFW_SetForwarderPage() Error.	Failed to create HTML filter error page.
ED04513-10075	WARNING	DFW_SetForwarderPage() Error.	Failed to create the SVR filter error page.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED04515-10075	WARNING	DFW_SetForwarderPage() Error.	Failed to create the SVR filter error page.
ED04516-10078	WARNING	Change Keyword Failed	Failed to convert extended keyword.
ED04517-10162	WARNING	Content Length Modify Error.	Failed in Content-length adjustment.
ED05007-10206	WARNING	URL Replace Failed.	Failed to convert URL.
ED05305-10121	WARNING	DFW_ReadHTMLConfig() Error.	An error occurred during loading of HTML file information when DOCS is a file.
ED05327-10104	WARNING	DFW_GetIceWallHTML() Error.	An error occurred during HTML retrieval.
ED05405-10121	WARNING	DFW_ReadHTMLConfig() Error.	An error occurred during HTML file information loading.
ED05415-10104	WARNING	DFW_GetIceWallHTML() Error.	An error occurred during HTML retrieval.
ED05505-10121	WARNING	DFW_ReadHTMLConfig() Error.	An error occurred during HTML file information loading.
ED05610-10144	WARNING	IW_CreateCookieHTML(): Error	An error occurred while pasting cookie.
ED05611-00014	WARNING	IW_CreateHTML() Error.	An error occurred when creating a page without cookies.
ED05612-10106	WARNING	DFW_GetRemoteHTML() Error.	An error occurred during HTML retrieval.
ED05613-10144	WARNING	IW_CreateCookieHTML(): Error	An error occurred when pasting a cookie.
ED05614-00014	WARNING	IW_CreateHTML() Error.	An error occurred when creating a page without cookies.
ED05615-10309	WARNING	DFW_AddContentLength() Error.	An error occurred during HTML retrieval.
ED05617-10359	WARNING	DFW_AddCharsetCtype() Error.	An error occurred when adding charset.
ED05622-10385	WARNING	Bad Response Status Code Error:[%s]	The status code specified in the configuration file is out of the valid range (100 to 999). Output value: [HTML file path]
ED05623-10384	WARNING	DFW_ModifyTopHeader() Error.	Failed to convert start header.
ED05702-10220	WARNING	DFW_SetTemplateHost() Error.	Cannot retrieve connection information.
ED05703-10221	WARNING	DFW_SetRequestHeaderTemplateHTML() Error.	Cannot create request.
ED05704-10085	WARNING	Backend Web Server Down. Host=[%s:%d]	Backend web server is down. Output value: [Host=[host name:port number]]
ED05710-10226	WARNING	DFW_CheckRedirectURL() Error.	Failed to verify LocationURL and retrieve URL.
ED05728-10441	WARNING	DFW_GetHttpComParamInfo() Error.	An error occurred during retrieval of HTTP communication configuration information.
ED05729-10442	WARNING	DFW_GetHttpConvInfo() Error.	An error occurred during retrieval of HTTP header conversion information.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED05903-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05904-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05907-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05909-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05910-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05911-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05912-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05913-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05914-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05916-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05917-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05918-10078	WARNING	Change Keyword Failed	Failed in conversion of designated keyword.
ED05919-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05920-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05921-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05922-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05924-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05925-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05927-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05928-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05931-10316	WARNING	DFW_CreateAgentRedirectHeader() Error.	An error occurred during creation of redirect URL for Agent transfer.
ED05932-10361	WARNING	DFW_DFWFilter() Error.	An error occurred during DFW filter operation.
ED05933-10363	WARNING	DFW_ControlSPKeyword() Error.	An error occurred during control of designated keyword.
ED05934-10128	WARNING	DFW_SetKeyword() Error.	Failed to set keyword for POST data inheritance.
ED05937-10428	WARNING	DFW_PostFwModifySidForFwData() Error.	Failed to replace session ID within inheritance data.
ED05943-10433	WARNING	DFW_CheckPostLimitSetting() Error.	An error occurred during operation verification of the POST transmission time limit function.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED05944-10434	WARNING	DFW_CreatePostLimitData() Error.	An error occurred during creation of the POST transmission time limit data.
ED05945-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05946-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05947-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05948-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05950-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05951-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05952-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05954-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05956-10316	WARNING	DFW_CreateAgentRedirectHeader() Error.	Failed to create a return URL for Agent.
ED05957-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05958-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05959-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05960-10437	WARNING	DFW_GetConvInfo() Error.	Failed to retrieve information required to convert return URL for Agent.
ED05961-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05962-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05963-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED05964-00034	WARNING	Configuration format error.[%s]	Parameter value format is invalid. Output value: [parameter name]
ED05965-10128	WARNING	DFW_SetKeyword() Error.	An error occurred while setting keyword.
ED06079-10122	WARNING	DFW_SetBasicInfo() Error.	An error occurred during storage of basic information structure.
ED06202-10009	WARNING	Can't Change Password.	Cannot change password.
ED06302-10157	WARNING	LoginCheck Failed.	Failed in login status verification.
ED06303-10193	WARNING	RequestCheck() Error.	An error occurred during request verification.
ED06304-10182	WARNING	Policy Check Failed.	Failed in policy verification.
ED06305-10212	WARNING	Wrong Password.	Password violates the policy.
ED06402-10055	WARNING	Can't Get HTTP_COOKIE.	Cannot retrieve HTTP_COOKIE.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06403-10017	WARNING	Can't Create Password ChangeNoLogin Page.	Cannot change password on no login page.
ED06405-10022	WARNING	Can't Create Request Message.	Cannot create request message.
ED06406-10059	WARNING	Can't Get Response.	Cannot retrieve response message
ED06407-10015	WARNING	Can't Create Error Page.	Cannot create the no login page.
ED06411-10419	WARNING	ICP_SetUserInfoRequest() Error.	Failed when creating ICP 2.0 user query request message.
ED06412-10059	WARNING	Can't Get Response.	Failed to retrieve response message.
ED06414-10424	WARNING	DFW_OptimizeResponse() Error.	Failed to optimize ICP 2.0 response message.
ED06417-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED06502-10192	WARNING	REQUEST_METHOD is Not [%s].	REQUEST_METHOD is not POST. Output value: [REQUEST_METHOD value]
ED06503-10084	WARNING	Content_Length is 0.	CONTENT_LENGTH is 0.
ED06505-10173	WARNING	Not Found proc.	Cannot find proc.
ED06506-10184	WARNING	Post Data is Not for Password Change.	Not POST data for password change.
ED06509-10028	WARNING	Can't Create Update NG Page.	Cannot create the update error page.
ED06510-10028	WARNING	Can't Create Update NG Page.	Cannot create the password change policy error page.
ED06511-10180	WARNING	Password MAXLEN Error.	Error for maximum number of password characters exceeded.
ED06512-10090	WARNING	Decode Error.	Decode error occurred.
ED06514-10090	WARNING	Decode Error.	Decode error occurred.
ED06516-10090	WARNING	Decode Error.	Decode error occurred.
ED06518-10090	WARNING	Decode Error.	Decode error occurred.
ED06520-10377	WARNING	DFW_DeleteString() Error.	An error occurred in deleting target character in entered user ID.
ED06521-10377	WARNING	DFW_DeleteString() Error.	An error occurred in deleting target character in entered password.
ED06522-10377	WARNING	DFW_DeleteString() Error.	An error occurred in deleting target character in reentered password.
ED06526-10028	WARNING	Can't Create Update NG Page.	Cannot create the password change transmission time limit error page.
ED06527-10090	WARNING	Decode Error.	Failed in POST data decoding.
ED06528-10028	WARNING	Can't Create Update NG Page.	Cannot create the password change transmission time limit error page.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06529-10435	WARNING	DFW_CheckPostLimitTime() Error.	An error occurred during the POST transmission time limit verification operation.
ED06530-10433	WARNING	DFW_CheckPostLimitSetting() Error.	An error occurred during operation verification of the POST transmission time limit function.
ED06531-10028	WARNING	Can't Create Update NG Page.	Cannot create the update error page.
ED06532-10455	WARNING	PWDHIDEURL or pwdchg cannot be acquired.	Cannot retrieve information required to change password.
ED06603-10164	WARNING	Password Not Entry.	Password is not entered.
ED06604-10028	WARNING	Can't Create Update NG Page.	Cannot create the update error page.
ED06607-10161	WARNING	Min Length Error. UserID=%s	Password is less than the minimum number of characters. Output value: [UserID= <u>user ID</u>]
ED06608-10158	WARNING	Max Length Error. UserID=%s	Password is more than the maximum number of characters. Output value: [UserID= <u>user ID</u>]
ED06609-10129	WARNING	DFW_SetPasswordPage() Error.	Cannot create the update error page.
ED06612-10177	WARNING	Password Change Agreed With UserID Error. UserID=%s	User ID is used in the password. Output value: [UserID= <u>user ID</u>]
ED06613-10019	WARNING	Can't Create Password Change Policy Error Page.	Cannot create the update error page.
ED06703-10199	WARNING	Set RequestData Failed.	Failed to set request data.
ED06708-10179	WARNING	Password Change Permission Error. UserID=%s	No permission to change password. Output value: [UserID= <u>user ID</u>]
ED06710-10178	WARNING	Password Change Policy Error for Database. UserID=%s	The changed password violates the Directory Server policy. Output value: [UserID= <u>user ID</u>]
ED06717-10421	WARNING	ICP_SetPasswdChgRequest() Error.	Failed in creation of ICP 2.0 password change request message.
ED06718-10059	WARNING	Can't Get Response.	Failed to retrieve response data.
ED06720-10424	WARNING	DFW_OptimizeResponse() Error.	Failed to optimize ICP 2.0 response message.
ED06728-10456	WARNING	database busy.	A database connection busy error occurred.
ED06805-10196	WARNING	Send Request Failed.	Failed to send request.
ED06808-10129	WARNING	DFW_SetPasswordPage() Error.	An error occurred in creation of the password change page when query was successful.
ED06809-10172	WARNING	Not Found Path_Info in URL.	Cannot find PATH_INFO in URL.
ED06810-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred during display of normal login page.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED06811-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred during login page display of client certificate.
ED06814-10419	WARNING	ICP_SetUserInfoRequest() Error.	Failed in creation of ICP 2.0 user query request message.
ED06815-10196	WARNING	Send Request Failed.	Failed to send request.
ED06817-10424	WARNING	DFW_OptimizeResponse() Error.	Failed to optimize ICP 2.0 response message.
ED06818-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED06820-10129	WARNING	DFW_SetPasswordPage() Error.	Cannot retrieve password change no login error HTML.
ED06822-10129	WARNING	DFW_SetPasswordPage() Error.	Cannot retrieve password change no login error HTML.
ED07002-10206	WARNING	URL Replace Failed.	Failed to replace URL.
ED07004-10437	WARNING	DFW_GetConvInfo() Error.	An error occurred during contents conversion information retrieval.
ED07102-10206	WARNING	URL Replace Failed.	Failed to replace URL.
ED07104-10437	WARNING	DFW_GetConvInfo() Error.	An error occurred during contents conversion information retrieval.
ED07302-10075	WARNING	DFW_SetForwarderPage() Error.	An error occurred during creation of the POST error page.
ED07402-10102	WARNING	DFW_GetCookie() Error.	An error occurred during cookie information retrieval.
ED07403-10101	WARNING	DFW_GetClientInfo() Error.	An error occurred during client information retrieval.
ED07404-10056	WARNING	Can't Get PATH_INFO.	Cannot retrieve PATH_INFO.
ED07405-10100	WARNING	DFW_GetBackendInfo() Error.	An error occurred during backend server information retrieval.
ED07406-10103	WARNING	DFW_GetForwarderInfo() Error.	An error occurred during Forwarder information retrieval.
ED07410-10056	WARNING	Can't Get PATH_INFO.	Cannot retrieve PATH_INFO.
ED07412-10257	WARNING	External Library Error.	An external routine error occurred.
ED07414-10311	WARNING	DFW_ReverseCertCheck() Error.	An error occurred during operation to verify path modification for authentication method.
ED07415-10326	WARNING	DFW_AgentControl() Error.	An error occurred during Agent connection control.
ED07417-10066	WARNING	Can't Set Access Error Page.	Cannot build the access error page.
ED07418-10066	WARNING	Can't Set Access Error Page.	An error occurred during creation of the access permission error page.
ED07419-10373	WARNING	DFW_NoAuthenticateExtCheck() Error.	Failed in extension verification not requiring authentication and authorization.
ED07422-10397	WARNING	DFW_PostFwGetCheck() Error.	Failed in POST data inheritance verification during GET method.
ED07423-10157	WARNING	LoginCheck Failed.	Failure in session ID validity verification.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED07424-10426	WARNING	DFW_PostFwLoggedInAutoSend() Error.	Failed in creation of the POST data inheritance automatic send page.
ED07425-10399	WARNING	DFW_PostFwGetParmFromQuery() Error.	Failed in data retrieval for POST data inheritance.
ED07428-10429	WARNING	DFW_ModifyReqHeaderVirtualPath() Error.	An error occurred while converting request header for original URL.
ED07431-10473	WARNING	DFW_TransactionIDJudge() Error.	Failed in operation to generate or retrieve transaction ID.
ED08210-10171	WARNING	Not Found.[hostname]	Cannot find host name.
ED08213-10183	WARNING	Post Data Decode Error.	Failed to decode POST data.
ED08225-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED08226-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED08402-10058	WARNING	Can't Get REQUEST_METHOD.	Cannot retrieve REQUEST_METHOD. Assigns GET to REQUEST_METHOD.
ED08405-10057	WARNING	Can't Get REMOTE_ADDR.	Cannot retrieve REQUEST_ADDR. Assigns "\0."
ED08414-10364	WARNING	DFW_GetSeparateCertInfo() Error.	An error occurred during retrieval of separate certificate information.
ED08415-10367	WARNING	QUERY_STRING Encryption Judgment Failed.	Failed to determine whether encryption is performed.
ED08416-10368	WARNING	QUERY_STRING Decrypt Failed.(No Encryption Key.)	Failed to decrypt QUERY_STRING because the encryption key is not set.
ED08417-10370	WARNING	QUERY_STRING Decrypt Failed.	Failed to decrypt QUERY_STRING.
ED08421-10388	WARNING	stdin cannot be changed to Nonblock.	Could not set standard input to non-blocking mode.
ED08426-10389	WARNING	stdin cannot be changed to Block.	Could not return standard input to blocking mode.
ED08427-10389	WARNING	stdin cannot be changed to Block.	Could not return standard input to blocking mode.
ED08428-10389	WARNING	stdin cannot be changed to Block.	Could not return standard input to blocking mode.
ED08429-10389	WARNING	stdin cannot be changed to Block.	Could not return standard input to blocking mode.
ED08430-10389	WARNING	stdin cannot be changed to Block.	Could not return standard input to blocking mode.
ED09219-00034	WARNING	Configuration format error.[%s]	RES_HEADER format is invalid. Output value: <u>[configuration name]</u>
ED09220-00034	WARNING	Configuration format error.[%s]	RES_HEADER format is invalid. Output value: <u>[configuration name]</u>
ED09506-10114	WARNING	DFW_ModifyHostHeader() Error.	An error occurred during HTTP_HOST conversion.
ED09507-10112	WARNING	DFW_ModifyConnectionHeader() Error.	An error occurred during HTTP_CONNECTION conversion.
ED09508-10116	WARNING	DFW_ModifyRefererHeader() Error.	An error occurred during HTTP_REFERER conversion.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED09702-10047	WARNING	Can't Find Separator.	An error occurred during retrieval of value start position.
ED09703-10045	WARNING	Can't Find End of Header.	Cannot find end of header.
ED09705-10045	WARNING	Can't Find End of Header.	Cannot find end of header.
ED09804-10234	WARNING	ERRKEY KeyWord is NULL.	ERRKEY search keyword is NULL.
ED09805-10234	WARNING	ERRKEY KeyWord is NULL.	ERRKEY search keyword is NULL.
ED09806-10104	WARNING	DFW_GetIceWallHTML() Error.	An error occurred in HTML retrieval operation specified in ERRKEY path.
ED09902-10047	WARNING	Can't Find Separator.	Cannot find separator.
ED09903-10045	WARNING	Can't Find End of Header.	Cannot find end of header.
ED09904-10045	WARNING	Can't Find End of Header.	Cannot find end of header.
ED09905-10154	WARNING	IW_StrInsertBuf() Error.	An error occurred during replacement of the Host line in the request header.
ED10002-10047	WARNING	Can't Find Separator.	Cannot retrieve path start position.
ED10003-10047	WARNING	Can't Find Separator.	Cannot retrieve path end position.
ED10004-10045	WARNING	Can't Find End of Header.	Cannot retrieve the end of header line.
ED10502-10238	WARNING	HTML Filter. Host:[%s:%d] Path:[%s] Tag:[<%s]	Filter search target exists. Output value: [Host:[<u>host name:port number</u>]] [Path:[<u>URL path</u>]] [Tag:[<u>filter buffer value</u>]]
ED10503-10242	WARNING	DFW_ReplaceFilterData() Error.	Filter data error.
ED10504-10238	WARNING	HTML Filter. Host:[%s:%d] Path:[%s] Tag:[<%s]	Filter operation was performed. Output value: [Host:[<u>host name:port number</u>]] [Path:[<u>URL path</u>]] [Tag:[<u>filter buffer value</u>]]
ED10603-10239	WARNING	GET Filter. Host:[%s:%d] Path:[%s] QUERY_STRING:[%s]	QUERY_STRING has been replaced because filter operation was performed. Output value: [Host:[<u>host name:port number</u>]] [Path:[<u>URL path</u>]] [QUERY_STRING:[<u>client QUERY_STRING value</u>]]
ED10605-10239	WARNING	GET Filter. Host:[%s:%d] Path:[%s] QUERY_STRING:[%s]	GET filter error page has been created because filter operation was performed. Output value: [Host:[<u>host name:port number</u>]] [Path:[<u>URL path</u>]] [QUERY_STRING:[<u>client QUERY_STRING value</u>]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED10703-10240	WARNING	POST Filter. Host:[%s:%d] Path:[%s] POSTDATA:[%s]	POSTDATA has been replaced because filter operation was performed. Output value: [Host:[host name:port number]] [Path:[URL path]] [POSTDATA:[client POSTDATA value]]
ED10705-10240	WARNING	POST Filter. Host:[%s:%d] Path:[%s] POSTDATA:[%s]	POSTDATA has been replaced because filter operation was performed. Output value: [Host:[host name:port number]] [Path:[URL path]] [POSTDATA:[client POSTDATA value]]
ED10804-10241	WARNING	SVR Filter. Host:[%s:%d] Path:[%s] FilterHost:[%s]	Content has been replaced because filter operation was performed. Output value: [Host:[host name:port number]] [Path:[URL path]] [FilterHost:[client filterhost value]]
ED10805-10241	WARNING	SVR Filter. Host:[%s:%d] Path:[%s] FilterHost:[%s]	SVR filter error page has been created because filter operation was performed. Output value: [Host:[host name:port number]] [Path:[URL path]] [FilterHost:[client filterhost value]]
ED11004-10242	WARNING	DFW_ReplaceFilterData() Error.	Failed in filter operation.
ED11007-10090	WARNING	Decode Error.	Failed in decoding of filter target.
ED11102-10241	WARNING	SVR Filter. Host:[%s:%d] Path:[%s] FilterHost:[%s]	Filter operation was performed. Output value: [Host:[host name:port number]] [Path:[URL path]] [FilterHost:[client filterhost value]]
ED11103-10241	WARNING	SVR Filter. Host:[%s:%d] Path:[%s] FilterHost:[%s]	SVR filter error page has been created because filter operation was performed. Output value: [Host:[host name:port number]] [Path:[URL path]] [FilterHost:[client filterhost value]]
ED12003-10259	WARNING	Create ExternalLibraryPage Failed.	Failed to create the password change page or system error page.
ED12102-10183	WARNING	Post Data Decode Error.	Failed to decode POST data.
ED12103-10183	WARNING	Post Data Decode Error.	Failed to decode POST data.
ED12104-10183	WARNING	Post Data Decode Error.	Failed to decode POST data.
ED12202-10002	WARNING	Alpha Numeric Include Error. UserID=%s	Password contains characters other than alphanumeric characters. Output value: [UserID=user ID]
ED12203-10227	WARNING	Numeric Include Error. UserID=%s	Password contains characters other than numbers. Output value: [UserID=user ID]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED12204-10228	WARNING	Alpha Include Error. UserID=%s	Password contains characters other than alphabetical characters. Output value: [UserID= <u>user ID</u>]
ED12205-10229	WARNING	Sign Include Error. UserID=%s	Password contains characters other than symbols. Output value: [UserID= <u>user ID</u>]
ED12206-10230	WARNING	Numeric Sign Include Error. UserID=%s	Password contains characters other than numbers and symbols. Output value: [UserID= <u>user ID</u>]
ED12207-10231	WARNING	Alpha Sign Include Error. UserID=%s	Password contains characters other than alphabetical characters and symbols. Output value: [UserID= <u>user ID</u>]
ED12208-10232	WARNING	Alpha Numeric Sign Include Error. UserID=%s	Password contains characters other than alphabetical characters, symbols, and numbers. Output value: [UserID= <u>user ID</u>]
ED12209-10261	WARNING	Alpha Numeric No Include Error. UserID=%s	Password contains neither numbers nor alphabetical characters. Output value: [UserID= <u>user ID</u>]
ED12210-10262	WARNING	Numeric No Include Error. UserID=%s	Password does not contain numbers. Output value: [UserID= <u>user ID</u>]
ED12211-10263	WARNING	Alpha No Include Error. UserID=%s	Password does not contain alphabetical characters. Output value: [UserID= <u>user ID</u>]
ED12212-10264	WARNING	Sign No Include Error. UserID=%s	Password does not contain symbols. Output value: [UserID= <u>user ID</u>]
ED12213-10265	WARNING	Numeric Sign No Include Error. UserID=%s	Password contains neither numbers nor symbols. Output value: [UserID= <u>user ID</u>]
ED12214-10266	WARNING	Alpha Sign No Include Error. UserID=%s	Password contains neither alphabetical characters nor symbols. Output value: [UserID= <u>user ID</u>]
ED12215-10267	WARNING	ALPHANUM Invalid Entry.	ALPHANUM parameter value is an invalid value.
ED12216-10002	WARNING	Alpha Numeric Include Error. UserID=%s	Password contains characters other than alphanumeric characters. Output value: [UserID= <u>user ID</u>]
ED12217-10129	WARNING	DFW_SetPasswordPage() Error.	Failed in the update error page operation.
ED12218-10323	WARNING	Forbidden Character Include Error. UserID=%s	Invalid characters in password. Output value: [UserID= <u>user ID</u>]
ED12219-10322	WARNING	DFW_PwForbidCharCheck() Error.	An error occurred in verifying invalid characters for password change.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED12302-10438	WARNING	DFW_CreateErrorInfo() Error.	An error occurred during the ERRORINFO string creation operation.
ED13002-10100	WARNING	DFW_GetBackendInfo() Error.	An error occurred during backend server information retrieval.
ED14003-00029	WARNING	Not Include '='.	Cannot find “=”.
ED14004-10122	WARNING	DFW_SetBasicInfo() Error.	Could not store basic information in structure.
ED14202-10285	WARNING	DFW_FormSelectAutoForm() Error.	Failed in Automatic Form Authentication verification in direct transmission method.
ED14203-10285	WARNING	DFW_FormSelectAutoForm() Error.	Failed in Automatic Form Authentication verification in automatic HTML transmission method.
ED14204-10284	WARNING	DFW_FormHTMLCheck() Error.	Failed in Automatic Form Authentication target verification.
ED14206-10303	WARNING	DFW_ReadFormConf() Error.	Failed in loading form configuration file.
ED14208-10353	WARNING	DFW_GetHTTPHeader() Error.	An error occurred during Set-cookie header retrieval for form authentication.
ED14209-10392	WARNING	Can't Get Status Code.	Status code was not included in the content retrieved from the Backend Web Server.
ED14210-10446	WARNING	FORM_FormMain() Error.	Failed in Automatic Form Authentication operation.
ED14211-10359	WARNING	DFW_AddCharsetCtype() Error.	An error occurred when adding charset to template HTML.
ED14302-10286	WARNING	FormMethod is not defined.[%s]	FormMethod is not defined. Output value: [alias name]
ED14304-10288	WARNING	FormTargetURL is not defined.[%s]	FormTargetURL is not defined. Output value: [alias name]
ED14305-10289	WARNING	FormTargetKeyword is not defined.[%s]	FormTargetKeyword is not defined. Output value: [alias name]
ED14307-10299	WARNING	DFW_GetTagList() Error.	Could not acquire INPUT tag from HTML.
ED14604-10290	WARNING	FormConfig Format Error.[%s]	Form authentication configuration format is invalid. Output value: [alias name]
ED14605-10291	WARNING	DFW_FormSetSendData() Error.	Could not set data structure of acquired send data.
ED14606-10290	WARNING	FormConfig Format Error.[%s]	Form authentication configuration format is invalid. Output value: [alias name]
ED14607-10293	WARNING	DFW_FormGetUserData() Error.	Could not set data structure of acquired send data.
ED14610-10290	WARNING	FormConfig Format Error.[%s]	Form authentication configuration format is invalid. Output value: [alias name]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED14611-10300	WARNING	Can't get value from HTMLTag.(Alias:[%s] Name:[%s])	Could not retrieve value of Value from INPUT tag. Output value: [Alias:[<u>alias name</u>]] [Name:[<u>tag name</u>]]
ED14612-10291	WARNING	DFW_FormSetSendData() Error.	Could not set to structure for acquired send data.
ED14614-10292	WARNING	DFW_FormSetDirectSendData() Error.	Failed to create QUERY_STRING.
ED14616-10292	WARNING	DFW_FormSetDirectSendData() Error.	Failed to create POSTDATA.
ED14617-10294	WARNING	DFW_FormDirectSend() Error.	Failed to send using the direct transfer method.
ED14618-10302	WARNING	DFW_FormPageSend() Error.	Failed in page loading.
ED15103-10295	WARNING	" " of header separator is not found.	Could not retrieve change position.
ED15104-10295	WARNING	" " of header separator is not found.	Could not retrieve change position.
ED15113-10298	WARNING	DFW_GetContents() Error.	Failed to send request.
ED15114-10220	WARNING	DFW_SetTemplateHost() Error.	Cannot retrieve connection information.
ED15119-10235	WARNING	DFW_ModifyHeaderValue() Error.	An error occurred in changing request header value.
ED15126-10220	WARNING	DFW_SetTemplateHost() Error.	Cannot retrieve connection information.
ED15127-10353	WARNING	DFW_GetHTTPHeader() Error.	An error occurred during Set-cookie header retrieval for form authentication.
ED15128-10354	WARNING	DFW_FormatChangeSetCookie() Error.	An error occurred during Set-cookie header conversion for form authentication.
ED15130-10352	WARNING	DFW_InsertManyHeader() Error.	An error occurred during HTTP header insertion for form authentication.
ED15131-10352	WARNING	DFW_InsertManyHeader() Error.	An error occurred during HTTP header insertion for form authentication.
ED15202-10045	WARNING	Can't Find End of Header.	Cannot find end of header.
ED15203-10154	WARNING	IW_StrInsertBuf() Error.	An error occurred in header insertion operation.
ED15204-10045	WARNING	Can't Find End of Header.	Cannot find end of header.
ED15302-10047	WARNING	Can't Find Separator.	Cannot find separator.
ED15303-10045	WARNING	Can't Find End of Header.	Cannot find end of header.
ED15304-10045	WARNING	Can't Find End of Header.	Cannot find end of header.
ED15603-00014	WARNING	IW_CreateHTML() Error.	Failed to load HTML.
ED15604-10078	WARNING	Change Keyword Failed	Failed to convert keyword.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED15605-10078	WARNING	Change Keyword Failed	Failed to convert keyword.
ED15611-10078	WARNING	Change Keyword Failed	Failed to convert keyword.
ED15612-10352	WARNING	DFW_InsertManyHeader() Error.	An error occurred during HTTP header insertion for form authentication.
ED15702-10344	WARNING	DFW_ReadFile() Error.	An error occurred during file loading.
ED15703-10345	WARNING	DFW_SplitConf() Error.	An error occurred while splitting configuration file.
ED16103-10307	WARNING	There is no header end in a buffer.	Failed in search for end of header.
ED16107-10308	WARNING	A header end is inaccurate.	Header end is invalid.
ED16602-10157	WARNING	LoginCheck Failed.	Failed in valid SessionID verification.
ED16603-10316	WARNING	DFW_CreateAgentRedirectHeader() Error.	Failed to create redirect page.
ED16607-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred during output of normal login page.
ED16608-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred during output of certificate login page.
ED16611-10316	WARNING	DFW_CreateAgentRedirectHeader() Error.	Failed to create redirect page.
ED16612-10213	WARNING	Wrong Response Data.	Response data is invalid.
ED16705-10032	WARNING	Can't Divide Response Message.[UserQuery]	Failed to retrieve response message.
ED16710-10419	WARNING	ICP_SetUserInfoRequest() Error.	Failed in creation of ICP 2.0 user query request message.
ED16711-10032	WARNING	Can't Divide Response Message.[UserQuery]	Failed to retrieve response message.
ED16713-10424	WARNING	DFW_OptimizeResponse() Error.	Failed in ICP 2.0 response message optimization.
ED16811-10070	WARNING	Can't Set Error Page.	Redirect header created.
ED17001-10318	WARNING	Catch Signal.[%d]	Received signal. Output value: [signal]
ED17304-10325	WARNING	DFW_InsertHeader() Error.	Failed to insert session ID header.
ED17402-10307	WARNING	There is no header end in a buffer.	Failed to retrieve header end position in header insertion.
ED17403-10308	WARNING	A header end is inaccurate.	Failed to retrieve header end position in header insertion.
ED17606-10327	WARNING	DFW_CertAgent() Error.	An error occurred during operation to allow Agent connection.
ED17612-10367	WARNING	QUERY_STRING Encryption Judgment Failed.	Failed to determine whether encryption has been performed.
ED17613-10368	WARNING	QUERY_STRING Decrypt Failed.(No Encryption Key.)	Failed to decrypt QUERY_STRING because the encryption key is not set.
ED17614-10370	WARNING	QUERY_STRING Decrypt Failed.	Failed to decrypt QUERY_STRING.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED17619-10183	WARNING	Post Data Decode Error.	Failed to decode URL for PROC retrieved from POSTDATA.
ED17703-10341	WARNING	Return AgentURL Error.(host=%s)	Agent return URL parameter is invalid. Output value: [host= <u>Agent host name</u> : <u>port number</u>]
ED17706-10220	WARNING	DFW_SetTemplateHost() Error.	Cannot retrieve connection information.
ED17707-10336	WARNING	DFW_CheckHost() Error.	An error occurred during Agent host connection verification.
ED17708-10337	WARNING	DFW_CheckDomain() Error.	An error occurred during Agent domain connection verification.
ED17710-10335	WARNING	DFW_CheckIpAddr() Error.	An error occurred during Agent IP address connection verification.
ED17711-10340	WARNING	Access deny.(host=%s)	Target Agent connection was denied. Output value: [host= <u>Agent host name</u>]
ED17713-10464	WARNING	getaddrinfo() error. Can't get network address. errno=[%d] errmsg=[%s] host=[%s:%d]	Failed to retrieve network address. Output value: [errno=[error number output from OS]] [errmsg=[error message received from OS]] [host=[<u>host name</u> : <u>port number</u>]]
ED17714-10465	WARNING	Can't get IPv4 Address.(AGENT_PERMIT,IP) host=[%s:%d]	Could not retrieve IPv4 address with connection control in which AGENT_PERMIT parameter is specified with IP. Output value: [host=[<u>host name</u> : <u>port number</u>]]
ED17715-10335	WARNING	DFW_CheckIpAddr() Error.	Failed in IP address verification.
ED17716-10466	WARNING	Can't get IPv6 Address.(AGENT_PERMIT,IPV6) host=[%s:%d]	Could not retrieve IPv6 address with connection control in which AGENT_PERMIT parameter is specified with IPV6. Output value: [host=[<u>host name</u> : <u>port number</u>]]
ED17717-10340	WARNING	Access deny.(host=%s)	Request from Agent not permitted. Output value: [host= <u>Agent host name</u> : <u>port number</u>]
ED17718-10479	WARNING	Return AgentPath Error.(host=%s)	Agent return path parameter is invalid. Output value: [path= <u>Agent return path</u>]
ED18402-10090	WARNING	Decode Error.	Failed in AGENT_KEY decoding.
ED18602-10334	WARNING	DFW_ComplIPAddr() Error.	Failed in Agent IP connection control.
ED18605-10334	WARNING	DFW_ComplIPAddr() Error.	Failed in Agent IP connection control.
ED18606-10334	WARNING	DFW_ComplIPAddr() Error.	Failed in Agent IP connection control.
ED18609-10468	WARNING	IPAddress format error. ip=[%s]	Agent IP address is invalid. Output value: [ip=[<u>IP address</u>]]
ED18610-10468	WARNING	IPAddress format error. ip=[%s]	Agent IP address is invalid. Output value: [ip=[<u>IP address</u>]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED18611-10468	WARNING	IPAddress format error. ip=[%s]	The IPv4 address specified in the AGENT_PERMIT parameter with IP is not valid. Output value: [ip=[<u>IP address</u>]]
ED18612-10468	WARNING	IPAddress format error. ip=[%s]	The IPv4 address specified in the AGENT_PERMIT parameter with IP is not valid. Output value: [ip=[<u>IP address</u>]]
ED18613-10468	WARNING	IPAddress format error. ip=[%s]	The IPv6 address specified in the AGENT_PERMIT parameter with IPv6 is not valid. Output value: [ip=[<u>IP address</u>]]
ED18614-10468	WARNING	IPAddress format error. ip=[%s]	The IPv6 address specified in the AGENT_PERMIT parameter with IPv6 is not valid. Output value: [ip=[<u>IP address</u>]]
ED18615-10467	WARNING	inet_pton() Error. errno=[%d] errmsg=[%s] ip=[%s]	Failed to convert IP address. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message received from OS</u>]] [ip=[<u>IP address</u>]]
ED18616-10469	WARNING	inaccurate IPAddress. ip=[%s]	Invalid IP address. Output value: [ip=[<u>IP address</u>]]
ED18617-10467	WARNING	inet_pton() Error. errno=[%d] errmsg=[%s] ip=[%s]	Failed to convert IP address. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message received from OS</u>]] [ip=[<u>IP address</u>]]
ED18618-10469	WARNING	inaccurate IPAddress. ip=[%s]	Invalid IP address. Output value: [ip=[<u>IP address</u>]]
ED18619-10467	WARNING	inet_pton() Error. errno=[%d] errmsg=[%s] ip=[%s]	Failed to convert IP address. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message received from OS</u>]] [ip=[<u>IP address</u>]]
ED18620-10469	WARNING	inaccurate IPAddress. ip=[%s]	Invalid IP address. Output value: [ip=[<u>IP address</u>]]
ED18621-10467	WARNING	inet_pton() Error. errno=[%d] errmsg=[%s] ip=[%s]	Failed to convert IP address. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message received from OS</u>]] [ip=[<u>IP address</u>]]
ED18622-10469	WARNING	inaccurate IPAddress. ip=[%s]	Invalid IP address. Output value: [ip=[<u>IP address</u>]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED18623-10467	WARNING	inet_pton() Error. errno=[%d] errmsg=[%s] ip=[%s]	Failed to convert IP address. Output value: [errno=[error number output from OS]] [errmsg=[error message received from OS]] [ip=[IP address]]
ED18624-10469	WARNING	inaccurate IPAddress. ip=[%s]	Invalid IP address. Output value: [ip=[IP address]]
ED18625-10467	WARNING	inet_pton() Error. errno=[%d] errmsg=[%s] ip=[%s]	Failed to convert IP address. Output value: [errno=[error number output from OS]] [errmsg=[error message received from OS]] [ip=[IP address]]
ED18626-10469	WARNING	inaccurate IPAddress. ip=[%s]	Invalid IP address. Output value: [ip=[IP address]]
ED18903-00029	WARNING	Not Include '='.	The symbol “=” is not included in AGENT-related configuration.
ED18904-10122	WARNING	DFW_SetBasicInfo() Error.	Could not store basic information in structure.
ED18911-10343	WARNING	AgentConfig Format Error.[%s]	AGENT configuration file format error. Output value: [configuration parameter]
ED18914-10343	WARNING	AgentConfig Format Error.[%s]	AGENT configuration file format error. Output value: [configuration parameter]
ED19202-10126	WARNING	DFW_SetHostInfo() Error.	Could not store HOST information in structure.
ED19203-10126	WARNING	DFW_SetHostInfo() Error.	Could not store SHOST information in structure.
ED19204-10127	WARNING	DFW_SetKeyInfo() Error.	Could not store SVRFILE information in structure.
ED19205-10127	WARNING	DFW_SetKeyInfo() Error.	Could not store URLKEY information in structure.
ED19206-10127	WARNING	DFW_SetKeyInfo() Error.	Could not store REPKEY information in structure.
ED19207-10124	WARNING	DFW_SetChainInfo() Error.	Could not store CTYPE information in structure.
ED19208-10124	WARNING	DFW_SetChainInfo() Error.	Could not store HEADER_FILTER information in structure.
ED19209-10124	WARNING	DFW_SetChainInfo() Error.	Could not store COOKIE_FILTER information in structure.
ED19210-10124	WARNING	DFW_SetChainInfo() Error.	Could not store LOCATION information in structure.
ED19211-10123	WARNING	DFW_SetCertInfo() Error.	Could not store CERT information in structure.
ED19212-10124	WARNING	DFW_SetChainInfo() Error.	Could not store GETFILTER information in structure.
ED19213-10124	WARNING	DFW_SetChainInfo() Error.	Could not store POSTFILTER information in structure.
ED19214-10124	WARNING	DFW_SetChainInfo() Error.	Could not store HTMLFILTER information in structure.
ED19215-10124	WARNING	DFW_SetChainInfo() Error.	Could not store GETEXCEPTION information in structure.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED19216-10124	WARNING	DFW_SetChainInfo() Error.	Could not store POSTEXCEPTION information in structure.
ED19217-10124	WARNING	DFW_SetChainInfo() Error.	Could not store SVREXCEPTION information in structure.
ED19218-10124	WARNING	DFW_SetChainInfo() Error.	Could not store REV_PATH information in structure.
ED19219-10124	WARNING	DFW_SetChainInfo() Error.	Could not store AGENT-related information in structure.
ED19220-10122	WARNING	DFW_SetBasicInfo() Error.	Could not store basic configuration information in structure.
ED19221-10127	WARNING	DFW_SetKeyInfo() Error.	Could not store ERRKEY information in structure.
ED19222-10376	WARNING	DFW_SetNoCheckInfo() Error.	Failed to set extension information not requiring authentication or authorization.
ED19224-10374	WARNING	DFW_SplitBufferCahin() Error.	Could not store SECEXCPAGE information in structure.
ED19225-10127	WARNING	DFW_SetKeyInfo() Error.	Could not store VIRTUALURL_ALIAS information in structure.
ED19226-10477	WARNING	CONF_SetCertInfo() Error.	Failed to store Authentication Module configuration information.
ED19227-10476	WARNING	CONF_SetKeyInfo() Error.	Could not store REPKEY_EXT information in structure.
ED19228-10459	WARNING	CONF_SetFailBackInfo() Error.	Could not store CERTFAILBACK information in structure.
ED19229-10459	WARNING	CONF_SetFailBackInfo() Error.	Could not store CERTLBFAILBACK information in structure.
ED19302-10127	WARNING	DFW_SetKeyInfo() Error.	Could not store URLKEY information in structure.
ED19303-10127	WARNING	DFW_SetKeyInfo() Error.	Could not store REPKEY information in structure.
ED19304-10124	WARNING	DFW_SetChainInfo() Error.	Could not store CTYPE information in structure.
ED19305-10124	WARNING	DFW_SetChainInfo() Error.	Could not store HTTPDATA information in structure.
ED19306-10124	WARNING	DFW_SetChainInfo() Error.	Could not store LOCATIONURL information in structure.
ED19307-10124	WARNING	DFW_SetChainInfo() Error.	Could not store HADER_FILTER information in structure.
ED19308-10124	WARNING	DFW_SetChainInfo() Error.	Could not store COOKIE_FILTER information in structure.
ED19309-10127	WARNING	DFW_SetKeyInfo() Error.	Could not store ERRKEY information in structure.
ED19310-10127	WARNING	DFW_SetKeyInfo() Error.	Could not store HEADER information in structure.
ED19311-10124	WARNING	DFW_SetChainInfo() Error.	Could not store GETFILTER information in structure.
ED19312-10124	WARNING	DFW_SetChainInfo() Error.	Could not store POSTFILTER information in structure.
ED19313-10124	WARNING	DFW_SetChainInfo() Error.	Could not store GETEXCEPTION information in structure.
ED19314-10124	WARNING	DFW_SetChainInfo() Error.	Could not store POSTEXCEPTION information in structure.
ED19315-10124	WARNING	DFW_SetChainInfo() Error.	Could not store SVREXCEPTION information in structure.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED19316-10124	WARNING	DFW_SetChainInfo() Error.	Could not store FORM-related information in structure.
ED19317-10122	WARNING	DFW_SetBasicInfo() Error.	Could not store basic configuration information in structure.
ED19318-10124	WARNING	DFW_SetChainInfo() Error.	Could not store HTMLFILTER information in structure.
ED19319-10127	WARNING	DFW_SetKeyInfo() Error.	Could not store RES_HEADER information in structure.
ED19320-10476	WARNING	CONF_SetKeyInfo() Error.	Could not store REPKEY_EXT information in structure.
ED19402-10124	WARNING	DFW_SetChainInfo() Error.	Could not store FORM-related information in structure.
ED19602-10307	WARNING	There is no header end in a buffer.	Failed to retrieve header end position during header addition.
ED19603-10308	WARNING	A header end is inaccurate.	Header end is invalid.
ED19702-10045	WARNING	Can't Find End of Header.	Failed to retrieve header end position during header retrieval.
ED19707-10045	WARNING	Can't Find End of Header.	Failed to retrieve header end position during header retrieval.
ED21102-10157	WARNING	LoginCheck Failed.	Failed in valid SessionID verification.
ED21103-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred during login page creation in relogin from Agent.
ED21104-10125	WARNING	DFW_SetForwarderPage() Error.	An error occurred during creation of client certificate login page in relogin from Agent.
ED21105-10217	WARNING	Wrong Value [w_uid].	Failed to extract Uid from POSTDATA in relogin from Agent.
ED21106-10090	WARNING	Decode Error.	Failed to decode Uid in relogin from Agent.
ED21108-10216	WARNING	Wrong Value [w_password].	Failed to extract Password from POSTDATA in relogin from Agent.
ED21109-10090	WARNING	Decode Error.	Failed to decode Password in relogin from Agent.
ED21110-10215	WARNING	Wrong Value [w_hideurl].	Failed to extract HIDEURL from POSTDATA in relogin from Agent.
ED21111-10090	WARNING	Decode Error.	Failed to decode HIDEURL in relogin from Agent.
ED21112-10072	WARNING	Can't Set Page.	An error occurred in creating the Uid error page in relogin from Agent.
ED21113-10072	WARNING	Can't Set Page.	An error occurred in creating the Pwd error page in relogin process from Agent.
ED21114-10316	WARNING	DFW_CreateAgentRedirectHeader() Error.	Failed in creating redirect buffer for successful relogin from Agent.
ED21204-10374	WARNING	DFW_SplitBufferCahin() Error.	Failed to create extension list.
ED21305-00035	WARNING	IW_ModifyFlagConfigValue() Error.	An error occurred during change of configuration value with flag.
ED21606-10379	WARNING	Can't Get REQUEST_URI. Using PATH_INFO instead.	The environment variable PATH_INFO is used because the environmental variable REQUEST_URI could not be retrieved.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED22102-10398	WARNING	DFW_PostFwCreateHideurl() Error.	Failed during creation of HIDEURL in POST data inheritance.
ED22103-10075	WARNING	DFW_SetForwarderPage() Error.	Failed in creation of POST data inheritance login page.
ED22104-10075	WARNING	DFW_SetForwarderPage() Error.	Failed in creation of POST data inheritance login page.
ED22202-10075	WARNING	DFW_SetForwarderPage() Error.	Failed in creation of POST data inheritance login page.
ED22203-10396	WARNING	DFW_PostFwPostCheck() Error.	Failed in method verification during POST data inheritance.
ED22204-10395	WARNING	DFW_PostFwCreateLoginPage() Error.	Failed in creation of POST data inheritance login page.
ED22302-10075	WARNING	DFW_SetForwarderPage() Error.	Failed in creation of POST data inheritance login page.
ED22303-10396	WARNING	DFW_PostFwPostCheck() Error.	Failed in method verification during POST data inheritance.
ED22603-10075	WARNING	DFW_SetForwarderPage() Error.	Failed in creation of error page for maximum length of POST data inheritance.
ED22604-10396	WARNING	DFW_PostFwPostCheck() Error.	Failed in POST data inheritance verification.
ED22614-10402	WARNING	DFW_PostFwPageSend() Error.	Failed in creation of response page for POST data inheritance login.
ED22703-10104	WARNING	DFW_GetIceWallHTML() Error.	Failed in automatic creation of login page for POST data inheritance.
ED22711-10078	WARNING	Change Keyword Failed	Failed to convert keyword.
ED22809-00012	WARNING	IW_CreateConfigEntry() Error.	Failed to create filtering target data entry.
ED22810-10132	WARNING	Entry Add Error.	Failed to add filtering target data entry.
ED22811-10361	WARNING	DFW_DFWFilter() Error.	Failed in filter operation.
ED23003-00012	WARNING	IW_CreateConfigEntry() Error.	Failed to create ICP 2.0 addition information entry.
ED23004-00007	WARNING	IW_AddConfigEntry() Error.	Failed in addition of ICP 2.0 information entry.
ED23005-00007	WARNING	IW_AddConfigEntry() Error.	Failed in addition of ICP 2.0 information entry.
ED23006-00007	WARNING	IW_AddConfigEntry() Error.	Failed in addition of ICP 2.0 information entry.
ED23007-00007	WARNING	IW_AddConfigEntry() Error.	Failed in addition of ICP 2.0 information entry.
ED23008-00018	WARNING	IW_ModifyConfigValue() Error.	Failed in change of ICP 2.0 information entry.
ED23009-00018	WARNING	IW_ModifyConfigValue() Error.	Failed in change of ICP 2.0 information entry.
ED23010-00018	WARNING	IW_ModifyConfigValue() Error.	Failed in change of ICP 2.0 information entry.
ED23011-00018	WARNING	IW_ModifyConfigValue() Error.	Failed in change of ICP 2.0 information entry.
ED23012-10030	WARNING	Can't Delete Entry.[%s]	Failed in deletion of ICP 2.0 information. Output value: [delete target information name]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED23013-10030	WARNING	Can't Delete Entry.[%s]	Failed in deletion of ICP 2.0 information. Output value: <u>[delete target information name]</u>
ED23014-10030	WARNING	Can't Delete Entry.[%s]	Failed in deletion of ICP 2.0 information. Output value: <u>[delete target information name]</u>
ED23015-10030	WARNING	Can't Delete Entry.[%s]	Failed in deletion of ICP 2.0 information. Output value: <u>[delete target information name]</u>
ED23104-10257	WARNING	External Library Error.	An external routine error occurred.
ED23105-10257	WARNING	External Library Error.	An external routine error occurred.
ED23107-10458	WARNING	DFW_FailBackCert() Error.	An error occurred during the certd failback operation.
ED23203-10405	WARNING	ICP_JoinBuffer() Error.	Failed in operation to link ICP 2.0 body.
ED23207-10408	WARNING	ICP_SetWriteBuf() Error.	Failed in creation of ICP 2.0 request message.
ED23303-10409	WARNING	ICP_GetBodyLength() Error.	Failed to retrieve encrypted body information.
ED23307-10412	WARNING	ICP_GetReadBuf() Error.	Failed to split ICP 2.0 response message.
ED23504-00012	WARNING	IW_CreateConfigEntry() Error.	Failed in creation of Description information entry.
ED23505-00007	WARNING	IW_AddConfigEntry() Error.	Failed in addition of Description information entry.
ED23506-00018	WARNING	IW_ModifyConfigValue() Error.	Failed in change of Description information entry value.
ED23509-00012	WARNING	IW_CreateConfigEntry() Error.	Failed in creation of Description information entry.
ED23510-00007	WARNING	IW_AddConfigEntry() Error.	Failed in addition of Description information entry.
ED23511-00018	WARNING	IW_ModifyConfigValue() Error.	Failed in change of Description information entry value.
ED23602-10399	WARNING	DFW_PostFwGetParmFromQuery() Error.	Could not extract inheritance POST data from inheritance data.
ED23603-10399	WARNING	DFW_PostFwGetParmFromQuery() Error.	Could not extract path information from inheritance data.
ED23604-10402	WARNING	DFW_PostFwPageSend() Error.	Failed in creation of login response page for POST data inheritance.
ED24105-10090	WARNING	Decode Error.	Failed to decode the URL of the QUERY_STRING.
ED24106-10432	WARNING	Keyword Decrypto Error.[%s]	Failed to decrypt QUERY_STRING. (High strength encryption method) Output value: <u>[string before decryption]</u>
ED24107-10432	WARNING	Keyword Decrypto Error.[%s]	Failed to decrypt QUERY_STRING. (Traditional encryption method) Output value: <u>[string before decryption]</u>
ED24202-10430	WARNING	DFW_CreateVirtualURL() Error.	An error occurred during URL conversion of the original URL.
ED24203-00018	WARNING	IW_ModifyConfigValue() Error.	An error occurred during conversion.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED24204-10430	WARNING	DFW_CreateVirtualURL() Error.	An error occurred during URL conversion of the original URL.
ED24205-00018	WARNING	IW_ModifyConfigValue() Error.	An error occurred during conversion.
ED25102-10444	WARNING	CMN_CreateParamEntry() Error.	Failed to create response header control information structure entry.
ED25103-10445	WARNING	CMN_AddParamEntry() Error.	Failed to add response header control information structure entry.
ED25302-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25303-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25304-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25305-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25306-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25307-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25308-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25309-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25310-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25311-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25312-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25313-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25314-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25315-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25316-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25317-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25318-10449	WARNING	CMN_GetElapsedTimeString	An error occurred during retrieval of elapsed time.
ED25403-10453	WARNING	CMN_DistributesFromStr() Error.	Failed in the procedure to assign Authentication Module.
ED25503-10440	WARNING	CONF_ModifyConfigFile() Error.	Could not change configuration file.
ED25504-00045	WARNING	failback.[%s]	Authentication Module configuration failback was performed. Output value: <u>[Authentication module failback configuration lines where failback was performed]</u>
ED25505-00041	WARNING	configuration file updated.	Configuration file was updated.
ED25603-10374	WARNING	DFW_SplitBufferCahin() Error.	Could not store REQUESTFILTER information in structure.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ED25604-10075	WARNING	DFW_SetForwarderPage() Error.	An error occurred when creating the request filter error page.
ED25832-00034	WARNING	Configuration format error.[%s]	Configuration values for TRANSID_STR paramaters are invalid. Output value: [TRANSID_STR]
ED25833-00034	WARNING	Configuration format error.[%s]	Configuration values for TRANSID_STR paramaters are invalid. Output value: [TRANSID_STR]
ED25834-10454	WARNING	CMN_CreateTIDString() Error.	Failed in operation to generate transaction ID.
EI10408-16026	WARNING	CMN_UrlCmpIPv6() Error.	Failed in URL comparison operation.
EI10409-16021	WARNING	SVR Filter TEST. Host:[%s:%d] Path:[%s] FilterHost:[%s]	Filter target host exists. Output value: [Host:[<u>host name</u> : <u>port number</u>]] [Path:[<u>URL path</u>]] [FilterHost:[<u>filter target host</u>]]
EI30603-11067	WARNING	CMN_UnEscapeString() Error.	An error occurred during the string unescape operation.
EI30604-11067	WARNING	CMN_UnEscapeString() Error.	An error occurred during the string unescape operation.
EI32102-11063	WARNING	gettimeofday() Error. Errno=%d	Failed to retrieve the time. Output value: [Errno= <u>error number output from OS</u>]
EI32502-11064	WARNING	CMN_Timersub() Error.	An error occurred while subtracting the time value.
EI32604-11065	WARNING	CMN_GetElapsedTime() Error.	An error occurred during retrieval of elapsed time.
EI32605-11066	WARNING	CMN_TimevalToString() Error.	An error occurred during the string conversion operation of the time value.
EI33002-11070	WARNING	inet_pton() Error. host:[%s] errno:[%d] errmsg:[%s]	Failed to convert IP address. Output value: [host:[<u>host name</u>]] [errno:[<u>error number output from OS</u>]] [errmsg:[<u>error message received from OS</u>]]
EI33003-11070	WARNING	inet_pton() Error. host:[%s] errno:[%d] errmsg:[%s]	Failed to convert IP address. Output value: [host:[<u>host name</u>]] [errno:[<u>error number output from OS</u>]] [errmsg:[<u>error message received from OS</u>]]
EI33202-11056	WARNING	CMN_CreateURLHost() Error.	Failed to split and store the URL information.
EI33203-11056	WARNING	CMN_CreateURLHost() Error.	Failed to split and store the URL information.
EI33402-11044	WARNING	CMN_ExtendBuf() Error.	Failed to expand buffer area.
EI33403-11007	WARNING	CMN_StrInsertBuf() Error.	Failed in inserting data to buffer.
EI40702-12016	WARNING	Not Include '='.	Cannot find “=”.
EI45302-13003	WARNING	Can't Find End of Header.	Cannot find end of header.
EI45303-13003	WARNING	Can't Find End of Header.	Cannot find end of header.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI45402-13005	WARNING	Can't Find Separator.	Cannot find separator.
EI45403-13003	WARNING	Can't Find End of Header.	Cannot find end of header.
EI46043-13095	WARNING	recv() Timeout. [CLOSETIME] [%s:%d]	Communication disconnected by CLOSETIME. Output value: [host name:port number]
EI46203-13026	WARNING	Path Not Include '//'.	Cannot find "//".
EI46204-13026	WARNING	Path Not Include '//'.	Cannot find "//".
EI46611-13061	WARNING	HTTP_ModifyHeaderstring() Error.	Failed in the header string conversion operation.
EI46613-13061	WARNING	HTTP_ModifyHeaderstring() Error.	Failed in the header string conversion operation.
EI56422-17060	WARNING	FORM_ConvertCharRef() Error.	Failed in entity reference conversion during FORM authentication.
EI57332-17061	WARNING	CMN_CreateConnectHost() Error.	Failed to create connection URL.
EI57333-17054	WARNING	Server Down(http). [%s:%d]	Backend web server is down. Output value: [host name:port number]
EI57334-17055	WARNING	Server Down(SSL). [%s:%d]	Backend web server is down. Output value: [host name:port number]
EI57335-17056	WARNING	HTTP_CreateSessionInfoEntry() Error.	Failed to create session information.
EI57337-17058	WARNING	failed to negotiate SSL algorithm. host=[%s:%d]	Failed in SSL negotiations due to invalid encryption method. Output value: [host=[host name:port number]]
EI57604-11007	WARNING	CMN_StrInsertBuf() Error.	Failed in inserting data to buffer.
EI75704-16023	WARNING	GET Filter TEST. Host:[%s:%d] Path:[%s] QUERY_STRING:[%s] Tag:[<%s]	Filter target tag exists. Output value: [Host:[host name:port number]] [QUERY_STRING:[client QUERY_STRING value]] [Tag:[filter target tag]]
EI75705-16024	WARNING	POST Filter TEST. Host:[%s:%d] Path:[%s] POSTDATA:[%s] Tag:[<%s]	Filter target tag exists. Output value: [Host:[host name:port number]] [POSTDATA:[client POSTDATA value]] [Tag:[filter target tag]]
EI75706-16022	WARNING	HTML Filter TEST. Host:[%s:%d] Path:[%s] Tag:[<%s]	Filter target tag exists. Output value: [Host:[host name:port number]] [Path:[URL path]] [Tag:[filter target tag]]
EI90412-19017	WARNING	ICP_JoinBuffer() Error.	Failed to link send data body.
EI90506-19014	WARNING	ICP_CutBuffer() Error.	Failed to split receive data header.
EI90507-19014	WARNING	ICP_CutBuffer() Error.	Failed to parse receive data body.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI92003-19013	WARNING	ICP_CreateParseData() Error.	Failed to create structure for parsed receive data of response mode.
EI92004-19013	WARNING	ICP_CreateParseData() Error.	Failed to create structure for parsed send data of request mode.
EI92102-19010	WARNING	IW_CreateConfig() Error.	Cannot create header structure.
EI92103-19010	WARNING	IW_CreateConfig() Error.	Cannot create body structure.
EI94102-19011	WARNING	IW_ModifyConfigValue() Error.	Failed to convert error number.
EI94103-19012	WARNING	IW_CreateConfigEntry() Error.	An error occurred when adding entry.
EI94104-19012	WARNING	IW_CreateConfigEntry() Error.	An error occurred when adding entry.
EI94303-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create entry of Authentication Module assignment key.
EI94304-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create request type entry.
EI94305-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create session ID entry.
EI94307-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create access control URL entry.
EI94308-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create entry of request sender type.
EI94310-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create client IP address entry.
EI94311-19018	WARNING	Not Found. [%s]	Cannot retrieve method. Output value: <u>[unretrievable data]</u>
EI94312-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create method entry.
EI94313-19018	WARNING	Not Found. [%s]	Cannot retrieve User_Agent. Output value: <u>[unretrievable data]</u>
EI94314-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create User_Agent entry.
EI94503-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create entry of Authentication Module assignment key.
EI94504-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create request type entry.
EI94505-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create session ID entry.
EI94507-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create access control URL entry.
EI94509-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create information entry for client certificate expiration date.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI94510-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create request type entry.
EI94512-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create client IP address entry.
EI94513-19018	WARNING	Not Found. [%s]	Cannot retrieve method. Output value: [unretrievable data]
EI94514-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create method entry.
EI94515-19018	WARNING	Not Found. [%s]	Cannot retrieve User_Agent. Output value: [unretrievable data]
EI94516-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create User_Agent entry.
EI94517-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create entry for client certificate serial number and issuer.
EI94518-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create information entry for client certificate expiration date.
EI94705-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create Loginuniquekey information entry.
EI94706-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create request type entry.
EI94707-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create user ID information entry.
EI94708-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create password information entry.
EI94709-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create AGENT_ID information entry.
EI94710-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create remote address information entry.
EI94712-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create User-Agent information entry.
EI94905-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create Loginuniquekey information entry.
EI94906-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create request type entry.
EI94907-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create user ID information entry.
EI94908-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create password information entry.
EI94909-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create client certificate information entry.
EI94910-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create information entry for client certificate expiration date.
EI94911-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create AGENT_ID information entry.
EI94912-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create remote address information entry.
EI94914-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create User-Agent information entry.
EI95104-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create Certuniquekey information entry.
EI95105-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create request type entry.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI95106-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create session ID information entry.
EI95107-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create user ID information entry.
EI95108-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create client certificate information entry.
EI95109-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create information entry for client certificate expiration date.
EI95110-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create AGENT_ID information entry.
EI95111-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create remote address information entry.
EI95113-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create User-Agent information entry.
EI95306-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create Certuniquekey information entry.
EI95307-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create request type entry.
EI95308-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create session ID information entry.
EI95309-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create user ID information entry.
EI95310-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create client certificate information entry.
EI95311-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create information entry for client certificate expiration date.
EI95312-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create password information entry after change.
EI95313-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create information entry for password expiration date.
EI95314-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create AGENT_ID information entry.
EI95315-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create remote address information entry.
EI95317-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create User-Agent information entry.
EI95504-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create Certuniquekey information entry.
EI95505-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create request type entry.
EI95506-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create session ID information entry.
EI95507-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create user ID information entry.
EI95508-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create client certificate information entry.
EI95509-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create information entry for client certificate expiration date.
EI95510-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create AGENT_ID information entry.
EI95511-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create remote address information entry.
EI95513-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create User-Agent information entry.
EI95702-19011	WARNING	IW_ModifyConfigValue() Error.	Failed to convert error number.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI95703-19019	WARNING	IW_CreateBuf() Error.	Failed to allocate work area for Description information.
EI95704-19008	WARNING	IW_SetBuf() Error.	Failed to create Description information.
EI95705-19008	WARNING	IW_SetBuf() Error.	Failed to create Description information.
EI95706-19008	WARNING	IW_SetBuf() Error.	Failed to create Description information.
EI95707-19008	WARNING	IW_SetBuf() Error.	Failed to create Description information.
EI95708-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to allocate Description information entry.
EI95709-19021	WARNING	IW_AddConfigEntry() Error.	Failed to add Description information entry.
EI95710-19011	WARNING	IW_ModifyConfigValue() Error.	Failed to change Description information.
EI95711-19007	WARNING	Bad Response Data.	Response type is invalid.
EI95712-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create user ID information entry.
EI95713-19012	WARNING	IW_CreateConfigEntry() Error.	Failed to create password information entry.
EI96210-19046	WARNING	getaddrinfo() error. Can't get network address. errno=[%d] errmsg=[%s] host=[%s:%d]	Failed to retrieve network address. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]] [host=[<u>host name:port number</u>]]
EI96211-19047	WARNING	Priority IPVerInfo was not able to be acquired. host=[%s:%d]	Failed to retrieve network address of the prioritized version. Output value: [host=[<u>host name:port number</u>]]
EI96212-19047	WARNING	Priority IPVerInfo was not able to be acquired. host=[%s:%d]	Failed to retrieve network address of the prioritized version. Output value: [host=[<u>host name:port number</u>]]
EI96213-19048	WARNING	All IPVerInfo was not able to be acquired. host=[%s:%d]	Failed to retrieve network address for all versions. Output value: [host=[<u>host name:port number</u>]]
EI96214-19049	WARNING	getnameinfo() error. errno=[%d] errmsg=[%s]	Failed to convert network address. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]]
EI96215-19050	WARNING	if_nametoindex() error. errno=[%d] errmsg=[%s]	Failed to convert interface. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]]
EIF0501-26012	WARNING	Send IW_SSLSelect() Error.	An error occurred during the connection operation.
EIF0502-26017	WARNING	SSL_write() Error.	An error occurred during data send operation via SSL communication.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EIF0503-26018	WARNING	send() Error. errno=[%d] errmsg=[%s]	Failed in send() operation. Output value: [errno=[error number output from OS]] [errmsg=[error message corresponding to error number output from OS]]
EIF0701-26021	WARNING	SSL_shutdown() Error.	An error occurred while ending SSL communication.
EIF0706-26023	WARNING	close() Error. errno=[%d] errmsg=[%s]	Failed to close socket. Output value: [errno=[error number output from OS]] [errmsg=[error message corresponding to error number output from OS]]
EIF2704-26016	WARNING	SSL_CTX_set_cipher_list() Error.	Failed to set encryption method for SSL communication.
EIF3101-26015	WARNING	SSL_new() Error.	Failed to generate SSL object.
EIF3305-26007	WARNING	ioctl() Error. errno=[%d] errmsg=[%s]	Could not change descriptor to non-blocking mode. Output value: [errno=[error number output from OS]] [errmsg=[error message corresponding to error number output from OS]]
EIF3305-26008	WARNING	fcntl() Error. errno=[%d] errmsg=[%s]	Could not change descriptor to non-blocking mode. Output value: [errno=[error number output from OS]] [errmsg=[error message corresponding to error number output from OS]]
EIF3308-26014	WARNING	getsockopt() Error. errno=[%d] errmsg=[%s]	Failed to retrieve socket option. Output value: [errno=[error number output from OS]] [errmsg=[error message corresponding to error number output from OS]]
EIF3309-26011	WARNING	Connect IW_SSLSelect() Error.	An error occurred during the connection operation.
EIF3310-26009	WARNING	connect() Error. errno=[%d] errmsg=[%s] host=[%s:%d]	Failed in connect() operation. Output value: [errno=[error number output from OS]] [errmsg=[error message corresponding to error number output from OS]] [host=[host name:port number]]
EIF3311-26007	WARNING	ioctl() Error. errno=[%d] errmsg=[%s]	Could not change descriptor to blocking mode. Output value: [errno=[error number output from OS]] [errmsg=[error message corresponding to error number output from OS]]
EIF3311-26008	WARNING	fcntl() Error. errno=[%d] errmsg=[%s]	Could not change descriptor to blocking mode. Output value: [errno=[error number output from OS]] [errmsg=[error message corresponding to error number output from OS]]
EIF3315-26006	WARNING	getaddrinfo() error. Can't get network address. errno=[%d] errmsg=[%s] host=[%s:%d]	Failed to convert address. Output value: [errno=[error number output from OS]] [errmsg=[error message corresponding to error number output from OS]] [host=[host name:port number]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EIF3316-26024	WARNING	Priority IPVerInfo was not able to be acquired. host=[%s:%d]	Failed to retrieve network address of the prioritized version. Output value: [host=[<u>host name</u> : <u>port number</u>]]
EIF3317-26024	WARNING	Priority IPVerInfo was not able to be acquired. host=[%s:%d]	Failed to retrieve network address of the prioritized version. Output value: [host=[<u>host name</u> : <u>port number</u>]]
EIF3318-26025	WARNING	All IPVerInfo was not able to be acquired. host=[%s:%d]	Failed to retrieve network address for all versions. Output value: [host=[<u>host name</u> : <u>port number</u>]]
EIF3319-26026	WARNING	getnameinfo() error. errno=[%d] errmsg=[%s]	Failed to convert network address. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]]
EIF3320-26028	WARNING	if_nametoindex() error. errno=[%d] errmsg=[%s]	Failed to convert interface. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]]
EIF3321-26029	WARNING	socket() error. errno=[%d] errmsg=[%s]	Socket error occurred. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]]
EIF3501-26010	WARNING	select() Error. errno=[%d] errmsg=[%s]	Failed in select() operation. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]]
EIF5601-26007	WARNING	ioctl() Error. errno=[%d] errmsg=[%s]	Could not change descriptor to non-blocking mode. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]]
EIF5601-26008	WARNING	fcntl() Error. errno=[%d] errmsg=[%s]	Could not change descriptor to non-blocking mode. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]]
EIF5604-26007	WARNING	ioctl() Error. errno=[%d] errmsg=[%s]	Could not change descriptor to blocking mode. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]]
EIF5701-26013	WARNING	Recv IW_SSLSelect() Error.	An error occurred while receiving.
EIF5702-26019	WARNING	SSL_read() Error.	An error occurred while receiving SSL communication data.
EIF5703-26020	WARNING	recv() Error. errno=[%d] errmsg=[%s]	Failed in recv() operation. Output value: [errno=[<u>error number output from OS</u>]] [errmsg=[<u>error message corresponding to error number output from OS</u>]]
EL01502-00022	WARNING	IW_ReplaceBuf() Error.	An error occurred during buffer release.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL03803-00004	WARNING	Configuration Invalid Entry.	No entry name found.
EL03804-00003	WARNING	Configuration Invalid Entry. Entry=%s	No entry name value found. Output value: [Entry= <u>entry name value</u>]
EL03903-00004	WARNING	Configuration Invalid Entry.	No entry name found.
EL03904-00003	WARNING	Configuration Invalid Entry. Entry=%s	No entry name value found. Output value: [Entry= <u>entry name value</u>]
EL04404-40022	WARNING	gethostbyname() Error: %s	Failed in gethostbyname(). Output value: [<u>host name</u>]
EL04701-00031	WARNING	Parameter is NULL.	Parameter is NULL.
EL04703-40028	WARNING	IW_CreateHostData() Error.	An error occurred during host data creation.
EL04704-40025	WARNING	IW_AddHostData() Error.	An error occurred when adding host data.
EL05202-40005	WARNING	Bad Response Data.	Response data is invalid.
EL05402-40005	WARNING	Bad Response Data.	Response data is invalid.
EL05602-40005	WARNING	Bad Response Data.	Response data is invalid.
EL05603-40005	WARNING	Bad Response Data.	Response data is invalid.
EL05604-40005	WARNING	Bad Response Data.	Response data is invalid.
EL05802-40005	WARNING	Bad Response Data.	Response data is invalid.
EL05803-40005	WARNING	Bad Response Data.	Response data is invalid.
EL05804-40005	WARNING	Bad Response Data.	Response data is invalid.
EL06002-40005	WARNING	Bad Response Data.	Response data is invalid.
EL06202-40005	WARNING	Bad Response Data.	Response data is invalid.
EL06402-40005	WARNING	Bad Response Data.	Response data is invalid.
EL10302-00024	WARNING	IW_SockNonblock() Error.	Cannot set socket to non-blocking mode.
EL10305-40012	WARNING	connect() Error: %s(errno=%d)	Connection error occurred. Output value: [Error: <u>message corresponding to error number output from OS</u>] [errno= <u>error number output from OS</u>]
EL10306-40023	WARNING	ioctl() Error: %s	An error occurred in executing operation to return to blocking. Output value: [Error: <u>message corresponding to error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL10307-40049	WARNING	fcntl() Error: %s	An error occurred in executing operation to return to state before non-blocking. Output value: [Error: <u>message corresponding to error number output from OS</u>]
EL10401-40047	WARNING	shutdown() Error: %s(errno=%d)	Failed to shut down socket. Output value: [Error: <u>message corresponding to error number output from OS</u>] [errno= <u>error number output from OS</u>]
EL10402-40011	WARNING	close() Error: %s(errno=%d)	Failed to close socket. Output value: [Error: <u>message corresponding to error number output from OS</u>] [errno= <u>error number output from OS</u>]
EL10601-40023	WARNING	ioctl() Error: %s	Cannot set socket to non-blocking mode. Output value: [Error: <u>message corresponding to error number output from OS</u>]
EL10602-40049	WARNING	fcntl() Error: %s	Cannot set socket to non-blocking mode. Output value: [Error: <u>message corresponding to error number output from OS</u>]
EL10901-40043	WARNING	Send Data is NULL.	Send data is NULL.
EL10902-40045	WARNING	send timeout.	Send operation timed out.
EL10903-40044	WARNING	send Error.	Send error.
EL10904-40046	WARNING	send() Error: %s(%d)	Send error. Output value: [Error: <u>message corresponding to error number output from OS</u>] [<u>error number output from OS</u>]
EL11101-00024	WARNING	IW_SockNonblock() Error.	Cannot set socket to non-blocking mode.
EL11102-00020	WARNING	IW_RecvSelect() Error.	An error occurred during data receive.
EL11103-00021	WARNING	IW_RecvSelect() Timeout.	Data receive operation timed out.
EL11104-00032	WARNING	recv() Error: %s	Receive error. Output value: [Error: <u>error number output from OS</u>]
EL11105-00023	WARNING	IW_SetBuf() Error.	An error occurred during buffer storage.
EL11201-40031	WARNING	IW_Recv() Error.	An error occurred during data receive.
EL11202-40029	WARNING	IW_CryptoBuf() Error.	An error occurred during data encryption.
EL12903-10154	WARNING	IW_StrInsertBuf() Error.	Failed in inserting data to buffer.
EL13001-40043	WARNING	Send Data is NULL.	Send data is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL13002-00015	WARNING	IW_CreateSocketData() Error.	Failed in creating socket structure.
EL13003-00023	WARNING	IW_SetBuf() Error.	An error occurred during buffer storage.
EL13004-40029	WARNING	IW_CryptoBuf() Error.	An error occurred during data encryption.
EL13005-00039	WARNING	IW_AddICPHeader() Error.	An error occurred during ICP header.
EL13006-40032	WARNING	IW_Send() Error.	An error occurred during data send.
EL70301-40015	WARNING	Data is NULL.	Parameter is NULL.
EL70601-40015	WARNING	Data is NULL.	Parameter is NULL.
EL70701-40015	WARNING	Data is NULL.	Parameter is NULL.
ED03304-10170	INFO	Not Found Header.[%s]	Environment variable name written to header has not been retrieved. Output value: [entry name]
ED03320-10170	INFO	Not Found Header.[%s]	Cannot retrieve header specified in HEADER parameter. Output value: [header name]
ED03321-10170	INFO	Not Found Header.[%s]	Cannot retrieve header specified in HEADER parameter. Output value: [header name]
ED03322-10170	INFO	Not Found Header.[%s]	Cannot retrieve header specified in HEADER parameter. Output value: [header name]
ED21609-10383	INFO	Can't get virtualpath from env.[%s]	Could not obtain VIRTUALPATH from environment variable. Output value: [environment variable]
EI90204-19015	INFO	ICP Format Error.	ICP communication data fixed format is invalid. (Line separator is not line feed code.)
EI90206-19015	INFO	ICP Format Error.	ICP communication data format is invalid. (Name is NULL.)
EI90302-19001	INFO	Parameter is NULL.	Argument parameter is NULL.
EI94711-19018	INFO	Not Found. [%s]	No User-Agent found. Output value: [unretrievable data]
EI94913-19018	INFO	Not Found. [%s]	No User-Agent found. Output value: [unretrievable data]
EI95112-19018	INFO	Not Found. [%s]	No User-Agent found. Output value: [unretrievable data]
EI95316-19018	INFO	Not Found. [%s]	Failed to create User-Agent information entry. Output value: [OUTPUT AGENT]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EI95512-19018	INFO	Not Found. [%s]	Failed to create User-Agent information entry. Output value: [OUTPUT AGENT]

7.2.2 Authentication Module error log (same for all authentication databases)

Code ID	Level	Message	Description
EC00422-20046	FATAL	PID File Open Error. File=[%s]	Failed to open pid file. Output value: [File=[PID file name]]
EC00801-20058	FATAL	Replication Server Down. Server=[%s] Port=[%d]	Failed to connect to replication server. Output value: [Server=[replication server IP address]] [Port=[port number]]
EC01001-20058	FATAL	Replication Server Down. Server=[%s] Port=[%d]	Failed to connect to replication server. Output value: [Server=[replication server IP address]] [Port=[port number]]
EC01201-20048	FATAL	Pool Queue Enqueue Error.	Failed to insert data to request queue.
EC01202-25078	FATAL	Pool Queue is Full	Request queue is full.
EC01408-20031	FATAL	Download Response Error.	Failed in download response.
EC02101-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing access control list. Output value: [Errno= <u>error number output from OS</u>]
EC02201-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing access control information. Output value: [Errno= <u>error number output from OS</u>]
EC02203-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate URL area for access control.
EC02501-00001	FATAL	Configuration File Open Error. File=[%s]	Failed to open access control file. Output value: [File= <u>access control file name</u>]
EC03001-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing access control URL conversion buffer. Output value: [Errno= <u>error number output from OS</u>]
EC03201-20065	FATAL	Max BTree Index. Insert Error.	Failed in internal index operation because no nodes were available.
EC03501-20064	FATAL	Index Destroyed.	B-Tree index is corrupted.
EC03601-20064	FATAL	Index Destroyed.	B-Tree index is corrupted.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC05401-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing user cache. Output value: [Errno= <u>error number output from OS</u>]
EC05402-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing user cache information list. Output value: [Errno= <u>error number output from OS</u>]
EC05403-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing session ID B-Tree. Output value: [Errno= <u>error number output from OS</u>]
EC05404-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing userID B-Tree. Output value: [Errno= <u>error number output from OS</u>]
EC05604-20067	FATAL	BTree Index Delete Error. Key=%s	Failed to delete session ID B-Tree index when deleting user cache. Output value: [Key= <u>session ID</u>]
EC05605-20067	FATAL	BTree Index Delete Error. Key=%s	Failed to delete UserID B-Tree index when deleting the user cache because duplicate login was prohibited. Output value: [Key= <u>user ID</u>]
EC05606-20066	FATAL	BTree Index Insert Error. Key=%s	Failed to register session ID B-Tree index when registering user cache. Output value: [Key= <u>session ID</u>]
EC05607-20066	FATAL	BTree Index Insert Error. Key=%s	Failed to register UserID B-Tree index when registering user cache. Output value: [Key= <u>user ID</u>]
EC05608-20067	FATAL	BTree Index Delete Error. Key=%s	Failed to delete session ID B-Tree index when registering user cache. Output value: [Key= <u>session ID</u>]
EC06003-20025	FATAL	CS_ModClientCert() Error. Cert=%d	Failed to update serial number for login by certificate. Output value: [Cert= <u>certificate number</u>]
EC06005-20025	FATAL	CS_ModClientCert() Error. Cert=%d	Failed to update serial number for login by certificate. Output value: [Cert= <u>certificate number</u>]
EC06309-20040	FATAL	Log Database Load Error.	Failed to load log column information.
EC06313-20030	FATAL	Database Load Error.	Failed to load authentication database column information.
EC06318-20035	FATAL	Group Load Error.	Failed to load group configuration information file.
EC06322-20007	FATAL	Acl Load Error.	Failed to load access control information file.
EC06324-20036	FATAL	Group File ACL No Match Error.	Group and access information do not match.
EC08401-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing group information list. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC05401-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing user cache. Output value: [Errno= <u>error number output from OS</u>]
EC05402-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing user cache information list. Output value: [Errno= <u>error number output from OS</u>]
EC05403-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing session ID B-Tree. Output value: [Errno= <u>error number output from OS</u>]
EC05404-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing userID B-Tree. Output value: [Errno= <u>error number output from OS</u>]
EC05604-20067	FATAL	BTree Index Delete Error. Key=%s	Failed to delete session ID B-Tree index when deleting user cache. Output value: [Key= <u>session ID</u>]
EC05605-20067	FATAL	BTree Index Delete Error. Key=%s	Failed to delete UserID B-Tree index when deleting the user cache because duplicate login was prohibited. Output value: [Key= <u>user ID</u>]
EC05606-20066	FATAL	BTree Index Insert Error. Key=%s	Failed to register session ID B-Tree index when registering user cache. Output value: [Key= <u>session ID</u>]
EC05607-20066	FATAL	BTree Index Insert Error. Key=%s	Failed to register UserID B-Tree index when registering user cache. Output value: [Key= <u>user ID</u>]
EC05608-20067	FATAL	BTree Index Delete Error. Key=%s	Failed to delete session ID B-Tree index when registering user cache. Output value: [Key= <u>session ID</u>]
EC06003-20025	FATAL	CS_ModClientCert() Error. Cert=%d	Failed to update serial number for login by certificate. Output value: [Cert= <u>certificate number</u>]
EC06005-20025	FATAL	CS_ModClientCert() Error. Cert=%d	Failed to update serial number for login by certificate. Output value: [Cert= <u>certificate number</u>]
EC06309-20040	FATAL	Log Database Load Error.	Failed to load log column information.
EC06313-20030	FATAL	Database Load Error.	Failed to load authentication database column information.
EC06318-20035	FATAL	Group Load Error.	Failed to load group configuration information file.
EC06322-20007	FATAL	Acl Load Error.	Failed to load access control information file.
EC06324-20036	FATAL	Group File ACL No Match Error.	Group and access information do not match.
EC08401-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing group information list. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC05401-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing user cache. Output value: [Errno= <u>error number output from OS</u>]
EC05402-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing user cache information list. Output value: [Errno= <u>error number output from OS</u>]
EC05403-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing session ID B-Tree. Output value: [Errno= <u>error number output from OS</u>]
EC05404-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing userID B-Tree. Output value: [Errno= <u>error number output from OS</u>]
EC05604-20067	FATAL	BTree Index Delete Error. Key=%s	Failed to delete session ID B-Tree index when deleting user cache. Output value: [Key= <u>session ID</u>]
EC05605-20067	FATAL	BTree Index Delete Error. Key=%s	Failed to delete UserID B-Tree index when deleting the user cache because duplicate login was prohibited. Output value: [Key= <u>user ID</u>]
EC05606-20066	FATAL	BTree Index Insert Error. Key=%s	Failed to register session ID B-Tree index when registering user cache. Output value: [Key= <u>session ID</u>]
EC05607-20066	FATAL	BTree Index Insert Error. Key=%s	Failed to register UserID B-Tree index when registering user cache. Output value: [Key= <u>user ID</u>]
EC05608-20067	FATAL	BTree Index Delete Error. Key=%s	Failed to delete session ID B-Tree index when registering user cache. Output value: [Key= <u>session ID</u>]
EC06003-20025	FATAL	CS_ModClientCert() Error. Cert=%d	Failed to update serial number for login by certificate. Output value: [Cert= <u>certificate number</u>]
EC06005-20025	FATAL	CS_ModClientCert() Error. Cert=%d	Failed to update serial number for login by certificate. Output value: [Cert= <u>certificate number</u>]
EC06309-20040	FATAL	Log Database Load Error.	Failed to load log column information.
EC06313-20030	FATAL	Database Load Error.	Failed to load authentication database column information.
EC06318-20035	FATAL	Group Load Error.	Failed to load group configuration information file.
EC06322-20007	FATAL	Acl Load Error.	Failed to load access control information file.
EC06324-20036	FATAL	Group File ACL No Match Error.	Group and access information do not match.
EC08401-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing group information list. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC08501-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing group information. Output value: [Errno= <u>error number output from OS</u>]
EC08502-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing the group name of the group information. Output value: [Errno= <u>error number output from OS</u>]
EC08801-00001	FATAL	Configuration File Open Error. File=[%s]	Failed to open group configuration file. Output value: [File= <u>group configuration file name</u>]
EC10114-25079	FATAL	Login Password Hash Error. UserID=%s	Failed to hash password entered at login. Output value: [UserID= <u>user ID</u>]
EC10401-20024	FATAL	CS_DBModData() Error.	Could not update login successful information in authentication database.
EC10501-20024	FATAL	CS_DBModData() Error.	Could not update password failure information in authentication database.
EC10601-20024	FATAL	CS_DBModData() Error.	Could not update login failure information in authentication database.
EC11302-20013	FATAL	Cookie : %s is Locked by Another Thread.	Cannot delete session ID because it is locked. Output value: [Cookie: <u>session ID</u>]
EC11303-20012	FATAL	Cookie : %s Delete Failed.	Failed to delete session ID. Output value: [Cookie: <u>session ID</u>]
EC11408-25080	FATAL	New Password Hash Error. UserID=%s	Failed to encrypt new password. Output value: [UserID= <u>user ID</u>]
EC11414-20024	FATAL	CS_DBModData() Error.	Failed to change authentication database password data.
EC11601-00001	FATAL	Configuration File Open Error. File=[%s]	Failed to open forbidden password configuration file. Output value: [File=[<u>forbidden password configuration file</u>]]
EC13401-25078	FATAL	Pool Queue is Full	Replication queue is full.
EC13402-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC13403-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC13404-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC13405-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC13406-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC13407-20055	FATAL	Replication Pool Queue Enqueue Error.	Failed to insert data to replication queue.
EC13408-25078	FATAL	Pool Queue is Full	Replication queue is full.
EC16407-25114	FATAL	Content-Length is 0.	ICP communication data format is invalid ("Content-length" header value is "0").
EC16408-25115	FATAL	Not Found Content-Length.	ICP communication data format is invalid ("Content-length" header value missing).
EC16409-05013	FATAL	Content-length Error. [%d] Body=[%d]	Data with value larger than "Content-length" was received in ICP communication. Output value: [length set to Content-length] [Body= <u>actual body length</u>]
EC18009-00023	FATAL	IW_SetBuf() Error.	An error occurred during buffer storage.
EC18701-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate column name area. Output value: [Errno= <u>error number output from OS</u>]
EC18702-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate column value area. Output value: [Errno= <u>error number output from OS</u>]
EC18801-00026	FATAL	malloc() Error. Errno=%d	Failed to create work area. Output value: [Errno= <u>error number output from OS</u>]
EC18901-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate unreferenced information area. Output value: [Errno= <u>error number output from OS</u>]
EC19101-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate entry area. Output value: [Errno= <u>error number output from OS</u>]
EC19102-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate column name area. Output value: [Errno= <u>error number output from OS</u>]
EC19103-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate column value area. Output value: [Errno= <u>error number output from OS</u>]
EC19201-00026	FATAL	malloc() Error. Errno=%d	Failed to create column value area. Output value: [Errno= <u>error number output from OS</u>]
EC19301-00011	FATAL	IW_CreateConfig() Error.	An error occurred during allocation of authentication database column area.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC19304-00011	FATAL	IW_CreateConfig() Error.	An error occurred during allocation of reference database column area.
EC19401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC19402-00012	FATAL	IW_CreateConfigEntry() Error.	Failed to create entry.
EC19601-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate record structure area. Output value: [Errno= <u>error number output from OS</u>]
EC19602-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate column name area. Output value: [Errno= <u>error number output from OS</u>]
EC19603-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate column value area. Output value: [Errno= <u>error number output from OS</u>]
EC19701-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate record structure area. Output value: [Errno= <u>error number output from OS</u>]
EC19702-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate column value area. Output value: [Errno= <u>error number output from OS</u>]
EC19703-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate column name area. Output value: [Errno= <u>error number output from OS</u>]
EC19801-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate record structure area. Output value: [Errno= <u>error number output from OS</u>]
EC20101-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for storing database information. Output value: [Errno= <u>error number output from OS</u>]
EC20201-00026	FATAL	malloc() Error. Errno=%d	Could not allocate record structure area. Output value: [Errno= <u>error number output from OS</u>]
EC25501-20092	FATAL	AclRequest Load Error.	Argument parameter passed to function that sets the request control configuration file is NULL.
EC25502-20092	FATAL	AclRequest Load Error.	Failed to create request control information structure for setting request control configuration file.
EC25503-20092	FATAL	AclRequest Load Error.	Failed to load request control configuration file.
EC25504-20093	FATAL	Bad Format AclRequest Configuration. Line=[%d]	Request control configuration file format is invalid. Output value: [Line= <u>error location line number</u>]
EC25505-20093	FATAL	Bad Format AclRequest Configuration. Line=[%d]	Request control configuration file format is invalid. Output value: [Line= <u>error location line number</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC25506-20093	FATAL	Bad Format AclRequest Configuration. Line=[%d]	Request control configuration file format is invalid. Output value: [Line= <u>error location line number</u>]
EC25507-20093	FATAL	Bad Format AclRequest Configuration. Line=[%d]	Request control configuration file format is invalid. Output value: [Line= <u>error location line number</u>]
EC25508-20093	FATAL	Bad Format AclRequest Configuration. Line=[%d]	Request control configuration file format is invalid. Output value: [Line= <u>error location line number</u>]
EC30301-20059	FATAL	RA Serial does Not Exist. (Database Configuration) Cert=%d	Could not retrieve RA serial column name from column configuration information of authentication database. Output value: [Cert= <u>certificate number</u>]
EC30302-20039	FATAL	IW Serial does Not Exist. (Database Configuration) Cert=%d	Could not retrieve IW serial column name from column configuration information of authentication database. Output value: [Cert= <u>certificate number</u>]
EC30303-20096	FATAL	Client Certificate Expire does Not Exist. (Database Configuration) Cert=%d	Could not retrieve expiration date column name from column configuration information of authentication database. Output value: [Cert= <u>certificate number</u>]
EC31002-20097	FATAL	IW_ExCreateSid Error. UserID=%s Result=%d	Failed in session ID generation routine. Output value: [UserID= <u>user ID</u>] [Result= <u>session ID generation routine return value</u>]
EC31003-20098	FATAL	Bad SessionID. UserID=%s IW_INFO=%s	Session ID with invalid length was generated. Output value: [UserID= <u>user ID</u>] [IW_INFO= <u>session ID</u>]
EC34601-40014	FATAL	Create Socket Failed.	Failed to create client socket.
EC34801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC35001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC35301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC35401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC35501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC35601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70006-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70007-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70010-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70011-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70012-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70013-20115	FATAL	Config format error. HOST:PORT (%s)	CERT parameter format is invalid. Output value: [HOST:PORT (<u>set value</u>)]
EC70014-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70015-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70016-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70017-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70018-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70019-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70020-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70021-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70022-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70023-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70024-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70025-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70026-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70027-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70028-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70029-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70030-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70031-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70032-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70033-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70034-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70035-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70036-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70037-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70038-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70039-20136	FATAL	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>]] [ErrCode= <u>error number output from OS</u>]] [ErrMsg= <u>system call error message</u>]]
EC70040-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70041-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70042-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70043-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70044-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70045-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70046-20137	FATAL	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70047-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70048-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70049-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70051-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70052-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70054-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70056-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70058-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70060-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70062-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70063-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70065-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70066-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70068-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70069-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70071-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70073-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70076-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70078-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70081-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70082-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70084-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70086-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70088-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70090-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70093-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70094-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70096-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70097-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70098-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70099-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70100-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70101-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70102-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70103-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70104-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70105-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70106-20136	FATAL	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70107-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70108-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70109-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70110-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70111-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70112-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70115-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70119-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70122-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70125-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70126-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70129-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70133-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70138-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70143-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70148-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70153-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70182-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70185-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70186-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70187-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70188-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70189-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70190-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70191-20116	FATAL	DB interface library setup routine failed	Failed to set up authentication database library interface.
EC70192-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70193-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70194-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70195-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70196-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70197-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70198-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70199-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70200-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70202-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70204-00012	FATAL	IW_CreateConfigEntry() Error.	Failed to add entry to the TARGET parameter of the request control configuration.
EC70205-00012	FATAL	IW_CreateConfigEntry() Error.	Failed to add entry to the TARGET parameter of the request control configuration.
EC70206-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70207-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70208-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70210-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70214-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70215-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70216-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70217-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>[error code]</u>]
EC70218-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70219-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70220-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70221-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70222-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>[error code]</u>]
EC70223-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70224-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>[error code]</u>]
EC70225-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70226-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>[error code]</u>]
EC70227-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70228-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>[error code]</u>]
EC70229-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70230-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70231-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70232-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70234-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70235-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70237-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70238-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70240-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70241-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70242-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70245-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70248-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70250-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70252-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70254-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70256-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70258-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70260-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70261-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70262-20137	FATAL	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70263-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70266-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70267-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70268-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70274-20140	FATAL	CS_StringAlloc() Error.	Failed to allocate memory area.
EC70275-20139	FATAL	CS_EntriesAlloc() Error.	Failed to allocate group affiliation conditions list area.
EC70276-20141	FATAL	CS_StrListAlloc() Error.	Failed to allocate group information list structure area.
EC70277-20140	FATAL	CS_StringAlloc() Error.	Failed to allocate memory area.
EC70278-20140	FATAL	CS_StringAlloc() Error.	Failed to allocate memory area.
EC70279-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70280-20140	FATAL	CS_StringAlloc() Error.	Failed to allocate memory area.
EC70281-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70287-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70288-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70289-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70291-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70293-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70294-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70295-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70296-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70297-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70298-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70299-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70300-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70301-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70302-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70303-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70304-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70305-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70306-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70307-20098	FATAL	Bad SessionID. UserID=%s IW_INFO=%s	Failed to validate session ID. The generated session ID violates either the length, character type, or unique key. Output value: [UserID= <u>user ID</u>] [IW_INFO= <u>session ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70308-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70309-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70310-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70316-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70317-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70318-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70319-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70320-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70321-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70322-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70323-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70324-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70325-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70328-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70331-20106	FATAL	Locked by another thread. Index=[%d]	Failed to retry the logout operation because the user is being used in a different thread. Output value: [Index=[user cache index]]
EC70332-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70335-20101	FATAL	All User Logout Error. UserID=%s	Failed to process one user during the logout sequence for all users. Output value: [UserID= <u>user ID</u>]
EC70337-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70338-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70339-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70340-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70341-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70342-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70343-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70344-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70345-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70346-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70347-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70350-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70351-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70352-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70353-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70354-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70356-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70358-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70359-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70360-20143	FATAL	Failed to update database information on the user cache. column name =[%s].	Failed to update database information with the user cache data. Output value: [column name= <u>column name</u>]
EC70361-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70362-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70363-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70364-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70365-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70366-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70367-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70368-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70370-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70371-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70372-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70373-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70374-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70375-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70376-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70377-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70378-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70380-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70381-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70383-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70384-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70385-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70386-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70387-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70388-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70389-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70390-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70391-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70392-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70393-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70394-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70395-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70396-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70397-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70398-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70399-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70400-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70401-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70402-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70403-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70404-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70405-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70406-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70407-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70408-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70413-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70415-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70421-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70423-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70425-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70426-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70428-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70430-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70431-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70432-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70433-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70434-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70435-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70436-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70437-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70438-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70439-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70440-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70441-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70442-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70443-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70444-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70445-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70446-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70447-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70448-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70449-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70450-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70451-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70452-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70453-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70454-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70455-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70456-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70466-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70475-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70478-20144	FATAL	Failed to initialize session ID generator. ErrCode=[%d].	Failed to initialize session ID. Output value: [ErrCode= <u>error code</u>]
EC70479-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70480-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70481-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70482-20145	FATAL	Failed to generate session ID. ErrCode=[%d].	Failed in session ID generation operation. Output value: [ErrCode= <u>error number output from OS</u>]
EC70483-20145	FATAL	Failed to generate session ID. ErrCode=[%d].	Failed in session ID generation operation. Output value: [ErrCode= <u>error number output from OS</u>]
EC70485-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70486-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70487-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70488-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70497-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70498-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70499-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70500-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70501-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70502-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70503-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70504-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70505-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70506-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70507-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70508-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70509-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70510-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70511-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70512-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70513-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70514-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70516-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70517-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70518-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70519-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70520-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70521-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70522-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70524-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70526-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70528-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70529-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70530-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70531-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70532-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70533-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70534-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[<u>error code</u>]]
EC70535-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70536-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[<u>error code</u>]]
EC70537-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70538-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[<u>error code</u>]]
EC70539-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70540-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[<u>error code</u>]]
EC70541-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70542-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[<u>error code</u>]]
EC70543-20116	FATAL	DB interface library setup routine failed	Failed to set up authentication database library interface.
EC70544-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70545-20046	FATAL	PID File Open Error. File=[%s]	Failed to open pid file. Output value: [File=[<u>PID file name</u>]]
EC70546-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70547-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70548-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[<u>error code</u>]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70549-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70550-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70551-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70554-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70555-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70556-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70557-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70558-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70559-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70560-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70561-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70562-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70563-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70564-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70565-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70566-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70567-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70568-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70569-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70570-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70571-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70572-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70573-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70574-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70575-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70576-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70577-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70578-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70579-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70588-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70597-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70598-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70599-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70601-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70602-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70603-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70604-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70605-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70606-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70608-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70610-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70612-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70614-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70615-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70616-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70617-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70618-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70619-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70620-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70622-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70624-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70625-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70626-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70627-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70628-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70629-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70630-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70631-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70632-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70633-20146	FATAL	Failed to allocate memory for %s. ErrCode=[%d].	Failed to assign memory. Output value: [message context] [ErrCode=[error code]]
EC70634-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70636-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70638-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70640-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70642-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70643-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70644-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70645-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70646-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70647-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70648-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70649-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70650-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70651-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70652-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70653-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70654-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70655-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70656-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70657-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70658-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70659-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70660-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70661-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70662-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70663-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70664-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70665-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70666-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70668-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70669-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70670-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70673-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70674-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70684-20146	FATAL	Failed to allocate memory for %s. ErrCode=[%d].	Failed to assign memory. Output value: [<u>response message</u>] [ErrCode= <u>error code</u>]
EC70685-20146	FATAL	Failed to allocate memory for %s. ErrCode=[%d].	Failed to assign memory. Output value: [<u>socket message</u>] [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70687-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70689-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70691-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70692-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70693-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70694-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70695-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70697-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70708-25114	FATAL	Content-Length is 0.	HTTP communication data format is invalid ("Content-length" header value is "0").
EC70709-25115	FATAL	Not Found Content-Length.	HTTP communication data format is invalid ("Content-length" header value missing).
EC70710-05013	FATAL	Content-length Error. [%d] Body=[%d]	More data than the value in "Content-length" was received in HTTP communication. Output value: [<u>length set to Content-length</u>] [Body= <u>actual body length</u>]
EC70718-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70719-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70721-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70722-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70723-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70724-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70725-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70726-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70727-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70762-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70765-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70769-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70773-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70776-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70780-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70782-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70783-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70786-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70788-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70789-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70791-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC70830-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70837-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70838-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70839-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70840-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70841-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70842-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70843-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70844-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70845-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70846-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70847-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70848-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70850-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70851-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70852-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70853-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70860-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70861-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70862-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70863-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70865-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70869-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70871-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70891-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70892-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70893-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70894-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70895-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70896-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70897-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70898-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70899-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70900-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70907-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70901-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70902-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70903-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70904-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70905-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70906-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70908-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70909-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70910-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70911-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70912-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70913-20123	FATAL	DBCrypto is not configured correctly; Not Found [DBIWCRYPTOSEED]	Configuration parameter DBIWCRYPTOSEED value is NULL.
EC70914-20124	FATAL	DBCrypto is not configured correctly; Invalid [DBIWCRYPTOSEED]	Configuration parameter DBIWCRYPTOSEED value is invalid.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70915-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70920-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70921-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70924-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70937-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70938-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70947-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70948-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70958-20128	FATAL	PWDLOGINHASH must set to other than AUTO-MD5 or AUTO-PLAIN. PWDLOGINHASH=[%s].	Set PWDLOGINHASH to a value other than an AUTO-based value. Output value: [PWDLOGINHASH=[configuration value]]
EC70959-20129	FATAL	PWDCHGHASH must set to other than AUTO-MD5 or AUTO-PLAIN. PWDCHGHASH=[%s].	Set PWDCHGHASH to a value other than an AUTO-based value. Output value: [PWDCHGHASH=[configuration value]]
EC70986-20132	FATAL	HTTPPORT cannot set a port number of the same PORT	The port numbers for configuration parameters HTTPPORT and PORT are duplicated.
EC70991-20163	FATAL	All User Logout Error. ErrMsg=[%s]	Failed in logout operation for all users. Output value: [ErrMsg=[Out Of Memory]]
EC70992-20163	FATAL	All User Logout Error. ErrMsg=[%s]	Failed in logout operation for all users. Output value: [ErrMsg=[Cannot logout some users locked by another thread]]
EC70994-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70995-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70996-20133	FATAL	PWDLOGINHASH and PWDCHGHASH have different settings. PWD LOGINHASH=[%s] PWDCHGHASH=[%s]	The hash method set for PWDLOGINHASH and PWDCHGHASH is different. Output value: [PWDLOGINHASH= <u>configuration value</u>] [PWDCHGHASH= <u>configuration value</u>]
EC71003-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71005-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71017-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71018-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71020-20164	FATAL	Create Thread Error. Name=[%s], ErrCode=[%d], ErrMsg=[%s]	Failed to generate thread. Output value: [Name=[<u>thread name</u>]], [ErrCode= <u>error code</u>], [ErrMsg=[<u>system call error message</u>]]
EC71021-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71022-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71023-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71024-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71025-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71026-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71027-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71028-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71029-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC71030-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC71031-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71032-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC71033-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC71034-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71035-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC71036-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71037-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC71038-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71039-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71040-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71042-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71044-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71046-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71047-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71048-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC71049-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71050-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71051-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC71052-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71053-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC71054-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71055-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC71056-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71057-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71058-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71059-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71060-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71061-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71066-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71067-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71068-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC71069-20168	FATAL	Failed to initialize request. ErrCode=[%d]	Failed to initialize request. Output value: [ErrCode= <u>error code</u>]
EC71070-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71071-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71106-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EC71111-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71112-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71114-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71131-20171	FATAL	LogDB Queue is Full	Log database queue is full.
EC71156-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71157-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71158-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71160-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71164-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71176-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71177-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71178-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71179-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC71180-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC71181-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71183-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71184-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71185-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC71186-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71187-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC71188-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71189-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC71191-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EL03802-00005	FATAL	File Open Error. File=%s	File open error occurred. Output value: [File=file name]
EL09902-20111	FATAL	Argument is out of range.	Configuration value for IPV6LISTEN is out of range.
EL09902-40048	FATAL	socket() Error: %s	Failed to create server socket. Output value: [error message output from OS]
EL09903-40006	FATAL	bind() port=%d Error: %s	Failed to bind socket. Output value: [port=port number] [Error: error message output from OS]
EL09904-40035	FATAL	listen() Error: %s	Failed in socket listening. Output value: [Error: message corresponding to error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL10301-40048	FATAL	socket() Error: %s	Socket error occurred. Output value: [Error: <u>message corresponding to error number output from OS</u>]
EL60101-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area for URL encoding. Output value: [Errno= <u>error number output from OS</u>]
EL60201-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate buffer area for URL decoding. Output value: [Errno= <u>error number output from OS</u>]
EL60605-05012	FATAL	ICP Format Error.	ICP communication data format is invalid. (No header separator found.)
EL60606-05013	FATAL	Content-length Error. [%d] Body=[%d]	Data length of request message header is invalid. Output value: [<u>length set to Content-length</u>] [Body= <u>actual body length</u>]
EL60607-05013	FATAL	Content-length Error. [%d] Body=[%d]	Data length of request message header is invalid. Output value: [<u>length set to Content-length</u>] [Body= <u>actual body length</u>]
EL70001-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EL70002-20112	FATAL	Failed to create address information structure. ErrCode=[%d]	Failed to create ICP protocol address structure. Output value: [ErrCode= <u>error status code</u>]
EL70003-20112	FATAL	Failed to create address information structure. ErrCode=[%d]	Failed to create HTTP protocol address structure. Output value: [ErrCode= <u>error status code</u>]
EL70004-20110	FATAL	Unable to set socket option ErrMsg=[%s].	Failed to set socket options. Output value: [ErrMsg= <u>error message output from OS</u>]
EL70005-20110	FATAL	Unable to set socket option ErrMsg=[%s].	Failed to set socket options. Output value: [ErrMsg= <u>error message output from OS</u>]
EL70269-05001	FATAL	%s IW_EXCRYPTO is NULL.	Failed to encrypt or decrypt request data or response data. Output value: [<u>encryption method</u>]
EL70270-05002	FATAL	%s ErrNo[%d] ErrMsg[%s]	Failed to encrypt or decrypt. Output value: [<u>encryption method</u>] [ErrNo= <u>error code</u>] [ErrMsg= <u>error message</u>]
EC00401-20011	WARNING	Configuration File Setting Error.	Failed in environment configuration of Authentication Module.
EC00420-20081	WARNING	CS_DownloadUsrCache Download Start.	Cache information download request has started.
EC00421-20082	WARNING	CS_DownloadUsrCache Download End.	Cache information download request has ended.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC00423-20002	WARNING	*** IceWall Certification Server Stop. ***	Authentication Module is stopped.
EC00902-20089	WARNING	CS_DecryptoRecv() Error.	Failed to decrypt receive data.
EC00905-00016	WARNING	IW_CryptoSend() Error.	Failed to send ICP 1.0 encryption data.
EC00907-05006	WARNING	ICP_EncryptoSend() Error.	Failed to send ICP 2.0 encryption data.
EC01302-20085	WARNING	*** Config File Reloaded. ***	Reload succeeded.
EC01303-20095	WARNING	Config File Reload Error. [%s]	Failed to reload request control configuration file. Output value: [AclRequest]
EC01304-20095	WARNING	Config File Reload Error. [%s]	Failed in reload because group and access information did not match. Output value: [Group & Acl]
EC01305-20095	WARNING	Config File Reload Error. [%s]	Failed in reload because request did not go into standby status. Output value: [Time Over (No Wait RequestThread)]
EC01306-20095	WARNING	Config File Reload Error. [%s]	Failed to reload Authentication Module configuration file. Output value: [CertConf]
EC01307-20095	WARNING	Config File Reload Error. [%s]	Failed to reload forbidden password configuration file. Output value: [PWDFORBID]
EC01411-20084	WARNING	*** Memory Dump Success. ***	Dump succeeded
EC01413-20086	WARNING	*** Cert Information Output. ***	Outputs the operation information.
EC01415-20061	WARNING	Unknown RequestID Error. ID=[%c]	Receive data type is abnormal. Output value: [ID=[data type]]
EC01501-20062	WARNING	Unknown RequestID Error.	Could not retrieve the data type from receive data.
EC02601-20006	WARNING	Acl Data is NULL.	Access control area is NULL.
EC02602-20005	WARNING	Acl Data Format Error.	Access control buffer format is abnormal ("=" not found).
EC02603-20004	WARNING	Acl Data Format Error. (URL)	URL not found in access control buffer.
EC03002-20068	WARNING	Replace Error. Key=%s	Failed to convert access control URL. Output value: [Key=conversion target URL]
EC06304-20001	WARNING	*** IceWall Certification Server Startup. ***	Started the Authentication Module.
EC06335-00003	WARNING	Configuration Invalid Entry. Entry=%s	Parameter is invalid. Output value: [Entry=SAML]
EC06336-00003	WARNING	Configuration Invalid Entry. Entry=%s	Parameter is invalid. Output value: [Entry=FEDERATION]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC06337-00003	WARNING	Configuration Invalid Entry. Entry=%s	Parameter is invalid. Output value: [Entry= <u>FORCELOGOUT</u>]
EC07903-20082	WARNING	CS_DownloadUsrCache Download End.	Cache information download request has ended.
EC08901-20034	WARNING	Group Data is NULL.	CS_AddGrpProc function parameter is NULL.
EC08902-20033	WARNING	Group Data Format Error.	Group information format is invalid.
EC08903-20032	WARNING	Group Data Format Error.(Group)	Group name is not found in group information.
EC08908-20038	WARNING	IP address Format Error. IP address=[%s]	IP address format is invalid. Output value: [IP address= <u>IP address</u>]]
EC09301-20008	WARNING	Bad Result Code. [position,code=%d]	Return value from UserExit at login is invalid. Output value: [code= <u>UserExit return value</u>]
EC09401-20008	WARNING	Bad Result Code. [position,code=%d]	Return value from UserExit at logout is invalid. Output value: [code= <u>UserExit return value</u>]
EC09501-20008	WARNING	Bad Result Code. [position,code=%d]	Return value from UserExit during access control is invalid. Output value: [code= <u>UserExit return value</u>]
EC11301-20014	WARNING	Cookie : %s Search Failed.	Cannot delete session ID because it is not registered. Output value: [Cookie : <u>session ID</u>]
EC12601-20085	WARNING	*** Config File Reloaded. ***%s	Successfully reloaded group configuration file. Output value: [GROUP]
EC12603-20085	WARNING	*** Config File Reloaded. ***%s	Successfully reloaded forbidden password configuration file. Output value: [PWDFORBID]
EC12604-20085	WARNING	*** Config File Reloaded. ***%s	Successfully reloaded access control file. Output value: [ACL]
EC12803-20095	WARNING	Config File Reload Error. [%s]	Failed in reload because request did not go into standby status when group configuration file was reloaded. Output value: [Time Over (No Wait RequestThread)]
EC12903-20095	WARNING	Config File Reload Error. [%s]	Failed in reload because request did not go into standby status when access control configuration file was reloaded. Output value: [Time Over (No Wait RequestThread)]
EC14603-20095	WARNING	Config File Reload Error. [%s]	Failed in reload because request did not go into standby status when forbidden password configuration file was reloaded. Output value: [<u>error cause</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC15702-20044	WARNING	No Regular Expression. Data=[%s]	Format of regular expression is abnormal. Output value: [Data= <u>regular expression data</u>]
EC16401-00024	WARNING	IW_SockNonblock() Error.	Failed in non-blocking mode operation.
EC16402-00020	WARNING	IW_RecvSelect() Error.	An error occurred in the socket receive wait operation.
EC16403-40039	WARNING	recv() Error (%d): %s	Failed in socket data receive operation. Output value: [error number output from OS] [error message output from OS]
EC16404-00023	WARNING	IW_SetBuf() Error.	Could not store receive data in receive buffer.
EC16410-05012	WARNING	ICP Format Error.	ICP communication data format is invalid (ICP header format has an error).
EC17501-20008	WARNING	Bad Result Code. [position,code=%d]	Return value from UserExit during password change is invalid. Output value: [code= <u>UserExit return value</u>]
EC18001-00012	WARNING	IW_CreateConfigEntry() Error.	Could not retrieve column value from cache.
EC19302-00012	WARNING	IW_CreateConfigEntry() Error.	An error occurred when adding column_name=NULL.
EC19303-00012	WARNING	IW_CreateConfigEntry() Error.	An error occurred when adding column_name=NULL.
EC19305-50041	WARNING	Reference Table UserID does not Exist.	Cannot find user ID in reference database.
EC19306-00012	WARNING	IW_CreateConfigEntry() Error.	An error occurred when adding column_name=NULL.
EC20708-20095	WARNING	Config File Reload Error. [%s]	Failed in reload because request did not go into standby status when request control configuration file was reloaded. Output value: [Time Over (No Wait RequestThread)]
EC23001-20026	WARNING	CS_Recv() Error.	Failed to receive data.
EC23002-05009	WARNING	ICP_DecryptoBuf() Error.	Failed to decrypt ICP 2.0 data.
EC24101-20094	WARNING	Unknown RequestID Error. ID=[%s]	The receive data type is an unknown data type. Output value: [ID= <u>data type</u>]
EC25601-20034	WARNING	Group Data is NULL.	Argument parameter passed to function that analyzes TARGET parameter of request control configuration file is NULL.
EC25606-20038	WARNING	IP address Format Error. IP address=[%s]	Format of IP address set by TARGET parameter in request control configuration file is invalid. Output value: [IP address= <u>IP address</u>]
EC30101-00010	WARNING	IW_CreateChain() Error.	Failed to allocate column information list Info structure.
EC30102-00011	WARNING	IW_CreateConfig() Error.	Failed to allocate column information list Entry structure.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC30401-00010	WARNING	IW_CreateChain() Error.	Failed to allocate SAML request control list Info structure.
EC30402-30023	WARNING	IW_CreateChainEntry() Error.	Failed to allocate SAML request control list Entry structure.
EC34705-10154	WARNING	IW_StrInsertBuf() Error.	Failed to decrypt data.
EC70000-20127	WARNING	Download only user cache.	Configuration data is not downloaded, only user information (cache) is downloaded.
EC70008-20114	WARNING	Failed to get socket IP address. ErrCode=[%d] ErrMsg=[%s]	Failed to retrieve socket IP address. Output value: [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70009-20114	WARNING	Failed to get socket IP address. ErrCode=[%d] ErrMsg=[%s]	Failed to retrieve socket IP address. Output value: [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70050-20138	WARNING	Failed to read data from file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to load file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70053-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70055-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70057-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70059-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70061-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70064-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70067-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70070-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70072-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70074-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70075-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[<u>file name</u>]] [ErrCode=[<u>error number output from OS</u>]] [ErrMsg=[<u>system call error message</u>]]
EC70077-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70079-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70080-20138	WARNING	Failed to read data from file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to load file. Output value: [filename=[<u>file name</u>]] [ErrCode=[<u>error number output from OS</u>]] [ErrMsg=[<u>system call error message</u>]]
EC70083-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70085-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70087-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70089-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70091-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70092-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[<u>file name</u>]] [ErrCode=[<u>error number output from OS</u>]] [ErrMsg=[<u>system call error message</u>]]
EC70113-20142	WARNING	Exceeded maximum nest level of ACL logical operation.	The number of logical conditional expressions in the access control file exceeds 32.
EC70114-20026	WARNING	CS_Recv() Error.	Failed to receive data.
EC70116-20142	WARNING	Exceeded maximum nest level of ACL logical operation.	The number of logical conditional expressions in the access control file exceeds 32.
EC70120-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70121-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70123-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70124-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70127-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70128-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70130-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70131-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70132-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70134-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70135-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70136-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70137-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70139-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70140-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70141-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70142-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70144-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70145-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[<u>file name</u>]] [ErrCode=[<u>error number output from OS</u>]] [ErrMsg=[<u>system call error message</u>]]
EC70146-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70147-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70149-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70150-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[<u>file name</u>]] [ErrCode=[<u>error number output from OS</u>]] [ErrMsg=[<u>system call error message</u>]]
EC70151-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70152-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70154-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70155-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[<u>file name</u>]] [ErrCode=[<u>error number output from OS</u>]] [ErrMsg=[<u>system call error message</u>]]
EC70177-20102	WARNING	AutoLogout Thread Start	Started the automatic logout thread.
EC70178-20104	WARNING	AutoLogout Thread Wait	Stop the automatic logout thread.
EC70179-20105	WARNING	AutoLogout Thread Active	Start the automatic logout thread.
EC70180-20103	WARNING	AutoLogout Thread Stop	The automatic logout thread finished.
EC70203-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70211-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70212-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70213-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70233-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70236-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70239-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode=error code]
EC70243-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70244-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70246-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70247-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70249-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70251-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70253-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70255-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70257-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70259-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70264-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70265-20113	WARNING	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC70271-00003	WARNING	Configuration Invalid Entry. Entry=%s	Parameter is invalid. Output value: [Entry= <u>parameter name</u>]
EC70273-00003	WARNING	Configuration Invalid Entry. Entry=%s	Parameter is invalid. Output value: [Entry= <u>parameter name</u>]
EC70282-20134	WARNING	Cannot compile regular expression. Value=[%s] ErrMsg=[%s]	Cannot use regular expressions for the forbidden password string. Output value: [Value= <u>regular expression data</u>] [ErrMsg= <u>system call error message</u>]
EC70290-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70292-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70327-20109	WARNING	AutoLogout failed. cannot retry. Index=[%d]	Failed to stock the user locked by logging out in the retry list. Output value: [Index= <u>user cache index</u>]
EC70330-20108	WARNING	Unable to lock user, so retry later. Index=[%d]	The user is being used in a different thread. Retry the logout operation. Output value: [Index= <u>user cache index</u>]
EC70334-20100	WARNING	Database Update Error. (All User Logout) UserID=%s	Failed to update authentication database for one user during the log-out sequence for all users. Output value: [UserID= <u>user ID</u>]
EC70348-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70349-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= <u>error code</u>]
EC70355-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70357-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70409-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70410-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70411-20113	WARNING	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70412-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70414-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70416-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70417-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70418-20113	WARNING	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode=[error code]]
EC70419-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70420-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70422-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70424-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70427-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70429-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70457-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70458-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70459-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70460-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70461-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70462-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70463-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70464-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70465-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70467-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70469-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70470-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70471-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70472-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EC70473-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70474-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70476-20095	WARNING	Config File Reload Error. [%s]	Failed in reload because request did not go into standby status. Output value: [Time Over (No Wait RequestThread)]
EC70477-20085	WARNING	*** Config File Reloaded. ***%s	Reload command (reload-cert) succeeded. Output value: [BASE]
EC70484-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70489-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70490-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70491-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70492-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70493-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70494-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70495-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70525-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70527-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70552-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70553-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70580-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70581-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70582-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70583-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70584-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70585-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70586-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70587-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]
EC70589-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70590-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70591-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70592-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70593-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70594-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70595-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70596-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70607-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70609-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70611-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70613-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70621-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70635-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70637-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70639-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70641-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70671-20094	WARNING	Unknown RequestID Error. ID=[%s]	The receive data type is an unknown data type. Output value: [ID= <u>[data type]</u>]
EC70675-20117	WARNING	Failed to register for Dump event. event=[%s]. ErrCode=[%d].	Failed to register a configuration output event. Output value: [event=ReqprocDumpConfig] [ErrCode= <u>[error code]</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70676-20118	WARNING	Failed to register for DumpConfig event. event=[%s]. ErrCode=[%d].	Failed to register storing configuration event. Output value: [event=ReqprocDumpConfig] [ErrCode= <u>error code</u>]
EC70677-20119	WARNING	Failed to register for Reload event. event=[%s]. ErrCode=[%d].	Failed to register a configuration retrieval event. Output value: [event=ReqprocDumpConfig] [ErrCode= <u>error code</u>]
EC70678-20120	WARNING	Failed to write data for dumpconfig. config=[%s]	Failed to output Authentication Module configuration file data to a file. Output value: [config=cert.conf]
EC70679-20120	WARNING	Failed to write data for dumpconfig. config=[%s]	Failed to output access control file data to a file. Output value: [config=cert.conf]
EC70680-20120	WARNING	Failed to write data for dumpconfig. config=[%s]	Failed to output group configuration file data to a file. Output value: [config=cert.conf]
EC70681-20120	WARNING	Failed to write data for dumpconfig. config=[%s]	Failed to output request control configuration data to a file. Output value: [config=cert.conf]
EC70682-20120	WARNING	Failed to write data for dumpconfig. config=[%s]	Failed to output Authentication DB column information file data to a file. Output value: [config=dbattr.conf]
EC70683-20120	WARNING	Failed to write data for dumpconfig. config=[%s]	Failed to output log column information file data to a file. Output value: [config=logdbattr.conf]
EC70686-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70688-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70690-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70696-20026	WARNING	CS_Recv() Error.	Failed to receive data.
EC70698-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70699-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70700-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70701-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70702-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70703-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70704-00024	WARNING	IW_SockNonblock() Error.	Failed in non-blocking mode operation.
EC70705-00020	WARNING	IW_RecvSelect() Error.	An error occurred in the socket receive wait operation.
EC70706-40039	WARNING	recv() Error (%d): %s	Failed in socket data receive operation. Output value: [error number output from OS] [error message output from OS]
EC70707-00023	WARNING	IW_SetBuf() Error.	Could not store receive data in receive buffer.
EC70711-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70712-20136	WARNING	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70732-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode=[error code]]
EC70733-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode=[error code]]
EC70734-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode=[error code]]
EC70735-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode=[error code]]
EC70736-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode=[error code]]
EC70737-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode=[error code]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70738-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]
EC70739-20151	WARNING	Failed to update user information on cache. ErrCode=[%d].	Failed to update user cache information. Output value: [ErrCode= error code]
EC70740-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]
EC70743-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]
EC70744-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]
EC70745-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]
EC70746-20147	WARNING	Failed to delete an user on cache. ErrCode=[%d].	Failed to delete user cache information. Output value: [ErrCode= error code]
EC70747-20149	WARNING	Failed to change a cookie expiration time on cache. ErrCode=[%d].	Failed to reconfigure the session ID expiration date for the user cache information. Output value: [ErrCode= error code]
EC70747-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]
EC70748-20149	WARNING	Failed to change a cookie expiration time on cache. ErrCode=[%d].	Failed to reconfigure the session ID expiration date for the user cache information. Output value: [ErrCode= error code]
EC70751-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]
EC70752-20147	WARNING	Failed to delete an user on cache. ErrCode=[%d].	Failed to delete user cache information. Output value: [ErrCode= error code]
EC70753-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]
EC70754-20147	WARNING	Failed to delete an user on cache. ErrCode=[%d].	Failed to delete user cache information. Output value: [ErrCode= error code]
EC70755-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70756-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]]
EC70757-20147	WARNING	Failed to delete an user on cache. ErrCode=[%d].	Failed to delete user cache information. Output value: [ErrCode= error code]]
EC70758-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]]
EC70759-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]]
EC70760-20148	WARNING	Failed to change a password on cache. ErrCode=[%d].	Failed to change password for user cache information. Output value: [ErrCode= error code]]
EC70761-20149	WARNING	Failed to change a cookie expiration time on cache. ErrCode=[%d].	Failed to reconfigure the session ID expiration date for the user cache information. Output value: [ErrCode= error code]]
EC70763-20147	WARNING	Failed to delete an user on cache. ErrCode=[%d].	Failed to delete user cache information. Output value: [ErrCode= error code]]
EC70764-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]]
EC70766-20147	WARNING	Failed to delete an user on cache. ErrCode=[%d].	Failed to delete user cache information. Output value: [ErrCode= error code]]
EC70767-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]]
EC70768-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]]
EC70770-20151	WARNING	Failed to update user information on cache. ErrCode=[%d].	Failed to update user cache information. Output value: [ErrCode= error code]]
EC70771-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]]
EC70772-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]]
EC70774-20147	WARNING	Failed to delete an user on cache. ErrCode=[%d].	Failed to delete user cache information. Output value: [ErrCode= error code]]
EC70775-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= error code]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70777-20147	WARNING	Failed to delete an user on cache. ErrCode=[%d].	Failed to delete user cache information. Output value: [ErrCode= <u>error code</u>]
EC70778-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= <u>error code</u>]
EC70779-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= <u>error code</u>]
EC70781-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= <u>error code</u>]
EC70784-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= <u>error code</u>]
EC70785-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= <u>error code</u>]
EC70787-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= <u>error code</u>]
EC70794-20120	WARNING	Failed to write data for dumpconfig. config=[%s]	Failed to output forbidden password configuration file data to a file. Output value: [config= <u>cert.conf</u>]
EC70795-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70796-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70797-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70798-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70799-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70800-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70801-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70802-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70803-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70804-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70805-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70806-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70807-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70808-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70809-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70810-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70811-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70812-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70813-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70814-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70815-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70816-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70817-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70818-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70819-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70820-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70821-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70822-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70823-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70824-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70825-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70826-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70827-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70828-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70829-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]
EC70864-20089	WARNING	CS_DecryptoRecv() Error.	Failed to decrypt request.
EC70866-05006	WARNING	ICP_EncryptoSend() Error.	Could not send response data due to an error while sending.
EC70867-05006	WARNING	ICP_EncryptoSend() Error.	Could not send response data due to response encryption failure.
EC70868-05006	WARNING	ICP_EncryptoSend() Error.	Failed to send HTTP encryption data.
EC70870-20106	WARNING	Locked by another thread. Index=[%d]	Failed to retry the automatic logout operation because the user is being used in a different thread. Output value: [Index=user cache index]
EC70916-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno=error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70917-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70918-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70919-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70922-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70923-20113	WARNING	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70925-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>]] [ErrCode= <u>error number output from OS</u>]] [ErrMsg= <u>system call error message</u>]]
EC70929-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70930-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC70939-20125	WARNING	Different DB password value and Hash type. UserID=[%s]. DB=[%s] PWDLOGINHASH=[%s].	The password prefix registered in the authentication database and the login hash method are different. Output value: [UserID= <u>user ID</u>]] [DB= <u>MD5</u>]] [PWDLOGINHASH= <u>configuration value</u>]]
EC70940-20125	WARNING	Different DB password value and Hash type. UserID=[%s]. DB=[%s] PWDLOGINHASH=[%s].	The password prefix registered in the authentication database and the login hash method are different. Output value: [UserID= <u>user ID</u>]] [DB= <u>MD5</u>]] [PWDLOGINHASH= <u>configuration value</u>]]
EC70941-20125	WARNING	Different DB password value and Hash type. UserID=[%s]. DB=[%s] PWDLOGINHASH=[%s].	The password prefix registered in the authentication database and the login hash method are different. Output value: [UserID= <u>user ID</u>]] [DB= <u>MD5</u>]] [PWDLOGINHASH= <u>configuration value</u>]]
EC70942-20125	WARNING	Different DB password value and Hash type. UserID=[%s]. DB=[%s] PWDLOGINHASH=[%s].	The password prefix registered in the authentication database and the login hash method are different. Output value: [UserID= <u>user ID</u>]] [DB= <u>MD5</u>]] [PWDLOGINHASH= <u>configuration value</u>]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70943-20126	WARNING	Different DB password value and Hash type. UserID=[%s]. DB=[%s] PWDCHGHASH=[%s].	The password prefix registered in the authentication database and the hash method for changing the password are different. Output value: [UserID=[user ID]] [DB=[MD5]] [PWDCHGHASH= <u>configuration value</u>]]
EC70944-20126	WARNING	Different DB password value and Hash type. UserID=[%s]. DB=[%s] PWDCHGHASH=[%s].	The password prefix registered in the authentication database and the hash method for changing the password are different. Output value: [UserID=[user ID]] [DB=[MD5]] [PWDCHGHASH= <u>configuration value</u>]]
EC70945-20126	WARNING	Different DB password value and Hash type. UserID=[%s]. DB=[%s] PWDCHGHASH=[%s].	The password prefix registered in the authentication database and the hash method for changing the password are different. Output value: [UserID=[user ID]] [DB=[MD5]] [PWDCHGHASH= <u>configuration value</u>]]
EC70946-20126	WARNING	Different DB password value and Hash type. UserID=[%s]. DB=[%s] PWDCHGHASH=[%s].	The password prefix registered in the authentication database and the hash method for changing the password are different. Output value: [UserID=[user ID]] [DB=[MD5]] [PWDCHGHASH= <u>configuration value</u>]]
EC70952-20154	WARNING	PWDLOGINHASH should be AUTO-MD5 or AUTO-PLAIN if no hash type prefix on DB password. UserID=[%s]. PWDLOGINHASH=[%s].	No prefix in the authentication database password, and PWDLOGINHASH is configured to a value other than an AUTO-based value. Output value: [UserID=[user ID]] [PWDLOGINHASH= <u>configuration value</u>]]
EC70953-20155	WARNING	Invalid Base64 format. Input=[%s].	The decryption value of authentication database column is not a valid Base64 format. Output value: [Input= <u>data to be decrypted</u>]]
EC70954-20156	WARNING	Failed to decode Base64. Input=[%s].	Failed in Base64 decoding during authentication database column decryption. Output value: [Input= <u>data to be decrypted</u>]]
EC70955-20157	WARNING	Failed to set AES decrypt key.	Failed to generate AES common key during authentication database column decryption.
EC70956-20158	WARNING	Failed to decrypt column. Input=[%s].	Failed in the authentication database column decryption. Output value: [Input= <u>data to be decrypted</u>]]
EC70957-20159	WARNING	Crypto type not found; Input=[%s].	The prefix of the value retrieved from the authentication database column is not IWCRYPTO128 or IWCRYPTO256. Output value: [Input= <u>data to be decrypted</u>]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70960-20095	WARNING	Config File Reload Error. [%s]	Failed to to reload request control configuration file. Output value: [AcIRequest]
EC70961-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70962-20113	WARNING	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70963-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]]
EC70964-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]]
EC70965-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]]
EC70966-20137	WARNING	Failed to write data to file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to write file. Output value: [filename= <u>file name</u>] [ErrCode= <u>error number output from OS</u>] [ErrMsg= <u>system call error message</u>]]
EC70968-20130	WARNING	Processing request cannot be made at this time because there are already as many processing request as ACCTHREAD can accept.	Cannot process requests which require database connection due to too many requests. The requests which can be handled with ACCTHREAD are acceptable.
EC70970-20130	WARNING	Processing request cannot be made at this time because there are already as many processing request as ACCTHREAD can accept.	Cannot process requests which require database connection due to too many requests. The requests which can be handled with ACCTHREAD are acceptable.
EC70971-20160	WARNING	Session ID generation failed. ICP is 1.x but SESSIONIDLEN is not 32.	Failed to generate session ID. For ICP 1.x communication, SESSIONIDLEN is configured to a value other than 32.
EC70972-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70973-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70974-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70975-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70976-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70977-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70978-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70979-20131	WARNING	*** Config File Output. ***%s	Outputs Authentication Module configuration file data to a dump file. Output value: [BASE]
EC70980-20131	WARNING	*** Config File Output. ***%s	Outputs access control file data to a dump file. Output value: [ACL]
EC70981-20131	WARNING	*** Config File Output. ***%s	Outputs group configuration file data to a dump file. Output value: [GROUP]
EC70982-20131	WARNING	*** Config File Output. ***%s	Outputs forbidden password configuration file data to a dump file. Output value: [PWDFORBID]
EC70983-20131	WARNING	*** Config File Output. ***%s	Outputs request control configuration file data to a dump file. Output value: [ACLREQUEST]
EC70984-20131	WARNING	*** Config File Output. ***%s	Outputs authentication database column file data to a dump file. Output value: [DBATTR]
EC70985-20131	WARNING	*** Config File Output. ***%s	Outputs log column information file data to a dump file. Output value: [DBATTR]
EC70989-00003	WARNING	Configuration Invalid Entry. Entry=%s	Parameter is invalid. Output value: [Entry= <u>parameter name</u>]
EC70990-20095	WARNING	Config File Reload Error. [%s]	Failed in the validation check for the configuration value of the parameters to reload. Output value: [CertConf]
EC70993-20162	WARNING	*** All User Logout Succeed. ***	The logout operation for all users succeeded.
EC70997-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC70998-20113	WARNING	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]]
EC70999-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC71000-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71001-20113	WARNING	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EC71002-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71004-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71006-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71007-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71008-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71009-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71010-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71011-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71012-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71013-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71014-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71015-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71016-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EC71041-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC71043-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= <u>error code</u>]]
EC71045-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC71072-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC71073-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC71074-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC71119-20170	WARNING	DB Queue is Full, So Failed to Update.	Failed to update the authentication database due to no available space in the authentication database queue.
EC71128-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC71129-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC71130-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC71162-20173	WARNING	LogDB Queue forced output to be delivered to the file.	Forcibly outputs data accumulated in the log database queue to an access log file.
EC71165-20147	WARNING	Failed to delete an user on cache. ErrCode=[%d].	Failed to delete user cache information. Output value: [ErrCode= <u>error code</u>]]
EC71166-20150	WARNING	Failed to unlock a record on cache. ErrCode=[%d].	Cannot lock the user cache information record. Output value: [ErrCode= <u>error code</u>]]
EC71182-20173	WARNING	LogDB Queue forced output to be delivered to the file.	Forcibly outputs data accumulated in the log database queue to an access log file.
EC71190-00026	WARNING	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EC71192-20173	WARNING	LogDB Queue forced output to be delivered to the file.	Forcibly outputs data accumulated in the log database queue to an access log file.
EL10001-40001	FATAL	accept() Error: %s	Failed in accept. Output value: [Error: <u>message corresponding to error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL10302-00024	WARNING	IW_SockNonblock() Error.	Cannot set socket to non-blocking mode.
EL10305-40012	WARNING	connect() Error: %s(errno=%d)	Connection error occurred. Output value: [Error: <u>message corresponding to error number output from OS</u>] [errno= <u>error number output from OS</u>]
EL10401-40047	WARNING	shutdown() Error: %s(errno=%d)	Failed to shut down socket. Output value: [Error: <u>message corresponding to error number output from OS</u>] [errno= <u>error number output from OS</u>]
EL10402-40011	WARNING	close() Error: %s(errno=%d)	Failed to close socket. Output value: [Error: <u>message corresponding to error number output from OS</u>] [errno= <u>error number output from OS</u>]
EL10601-40023	WARNING	ioctl() Error: %s	Cannot set socket to non-blocking mode. Output value: [<u>message corresponding to error number output from OS</u>]
EL10602-40049	WARNING	fcntl() Error: %s	Cannot set socket to non-blocking mode. Output value: [<u>error message output from OS</u>]
EL10901-40043	WARNING	Send Data is NULL.	Send data is NULL.
EL10902-40045	WARNING	send timeout.	Send operation timed out.
EL10903-40044	WARNING	send Error.	Send error.
EL10904-40046	WARNING	send() Error: %s(%d)	Send error. Output value: [Error: <u>message corresponding to error number output from OS</u>] [errno= <u>error number output from OS</u>]
EL11101-00024	WARNING	IW_SockNonblock() Error.	Cannot set socket to non-blocking mode.
EL11102-00020	WARNING	IW_RecvSelect() Error.	An error occurred in the socket receive wait operation.
EL11103-00021	WARNING	IW_RecvSelect() Timeout.	Data receive operation timed out.
EL11104-00032	WARNING	recv() Error: %s	Receive error. Output value: [Errno= <u>error number output from OS</u>]
EL11105-00023	WARNING	IW_SetBuf() Error.	An error occurred during buffer storage.
EC02801-00031	INFO	Parameter is NULL.	Argument parameter is NULL.
EC06305-20069	INFO	CS_DownloadClient Download Start.	Started downloading configuration information in the Authentication Module configuration file.
EC06306-20070	INFO	CS_DownloadClient Download End.	Finished downloading configuration information in the Authentication Module configuration file.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC06307-20071	INFO	CS_DownloadCIm LogCIm Download Start.	Started downloading configuration information in the log column information file.
EC06308-20072	INFO	CS_DownloadCIm LogCIm Download End.	Finished downloading configuration information in the log column information file.
EC06311-20073	INFO	CS_DownloadCIm Download Start.	Started downloading configuration information in the Authentication DB column information file.
EC06312-20074	INFO	CS_DownloadCIm Download End.	Finished downloading configuration information in the Authentication DB column information file.
EC06316-20075	INFO	CS_DownloadGroup Download Start.	Started downloading configuration information in the group configuration information file.
EC06317-20076	INFO	CS_DownloadGroup Download End.	Finished downloading configuration information in the group configuration information file.
EC06320-20077	INFO	CS_DownloadAcl Download Start.	Started downloading configuration information in the access control information file.
EC06321-20078	INFO	CS_DownloadAcl Download End.	Finished downloading configuration information in the access control information file.
EC06325-20079	INFO	CS_DownloadBid Download Start.	Started downloading configuration information in the forbidden password configuration file.
EC06326-20080	INFO	CS_DownloadBid Download End.	Finished downloading configuration information in the forbidden password configuration file.
EC06327-20050	INFO	Password Forbidden Load Error.	Failed to load forbidden password configuration file.
EC06330-20090	INFO	CS_DownloadAclRequest Download Start.	Downloading configuration information in the request control configuration file started.
EC06331-20091	INFO	CS_DownloadAclRequest Download End.	Downloading configuration information in the request control configuration file finished.
EC15701-00031	INFO	Parameter is NULL.	Argument parameter is NULL.
EC24102-20052	INFO	Recv UserID Max Length Error. UserID=[%s]	Retrieved UserID exceeds the maximum length. Output value: [UserID=[user ID]]
EC24103-20051	INFO	Recv Password Max Length Error. Len=[%d]	Retrieved password exceeds the maximum length. Output value: [Len=[password length]]
EC70285-25079	INFO	Login Password Hash Error. UserID=%s	Failed in password hashing during BIND authentication. Output value: [UserID=user ID]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EC70311-20136	INFO	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70312-20136	INFO	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70313-20136	INFO	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70314-20136	INFO	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70315-20136	INFO	Failed to open file. filename=[%s] ErrCode=[%d], ErrMsg=[%s]	Failed to open file. Output value: [filename=[file name]] [ErrCode=[error number output from OS]] [ErrMsg=[system call error message]]
EC70600-20052	INFO	Recv UserID Max Length Error. UserID=[%s]	User ID of receive data is too long. Output value: [UserID=[user ID]]
EC70793-20062	INFO	Unknown RequestID Error.	Receive data type is NULL.
EC70933-20153	INFO	Thread commonly used for logging %s exits. LOGMULTITHREAD=[%d].	LOGMULTITHREAD is enabled and not all logs are output by a single thread. Output value: [logging Error, Access and Perf] [LOGMULTITHREAD=1] * Logs are output by individual threads.
EC70934-20152	INFO	Thread used for logging %s exits. LOGMULTITHREAD=[%d].	LOGMULTITHREAD is disabled, and logs are not output by individual threads. Output value: [logging Access] [LOGMULTITHREAD=0]
EC70935-20152	INFO	Thread used for logging %s exits. LOGMULTITHREAD=[%d].	LOGMULTITHREAD is disabled, and logs are not output by individual threads. Output value: [logging Error] [LOGMULTITHREAD=0]
EC70936-20152	INFO	Thread used for logging %s exits. LOGMULTITHREAD=[%d].	LOGMULTITHREAD is disabled, and logs are not output by individual threads. Output value: [logging Perf] [LOGMULTITHREAD=0]
EC71161-20172	INFO	Failed to update LOGINSTAT.	Failed to update LOGINSTAT parameters.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EL60304-05012	INFO	ICP Format Error.	ICP communication data format is invalid (separator between name and value has an error).
EL60306-05012	INFO	ICP Format Error.	ICP communication data format is invalid (name is NULL).

7.2.3 Authentication Module error log (for ORACLE edition only)

Code ID	Level	Message	Description
EO00902-50013	FATAL	No Database Host.	Authentication database host name is not set.
EO00903-50011	FATAL	No Database Attach UserID.	User ID for connecting to authentication database is not set.
EO00905-50010	FATAL	No Database Attach Password.	Password for connecting to authentication database is not set.
EO00907-50016	FATAL	No Database Table Name.	Table name for connecting to authentication database is not set.
EO00908-50017	FATAL	No Database UserID Column.	User ID column name for connecting to authentication database is not set.
EO00909-50014	FATAL	No Database Password Column.	Password column name for connecting to authentication database is not set.
EO00910-50038	FATAL	No Reference UserID Column.	User ID column name for connecting to authentication database is not set.
EO00911-50037	FATAL	No Reference Attribute.	Attribute name for connecting to authentication database is not set.
EO01101-50015	FATAL	No Database Sequence Name .	Sequential object is not set.
EO01403-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing SQL descriptor. Output value: [Errno= <u>error number output from OS</u>]
EO01404-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing SQL descriptor. Output value: [Errno= <u>error number output from OS</u>]
EO01405-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required when initializing SQLDA structure. Output value: [Errno= <u>error number output from OS</u>]
EO01406-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required when initializing SQLDA structure. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EO01407-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required when initializing SQLDA structure. Output value: [Errno= <u>error number output from OS</u>]
EO01408-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required when initializing SQLDA structure. Output value: [Errno= <u>error number output from OS</u>]
EO01409-50039	FATAL	Out of Buffer. [SQL > %d]	SQL statement is too long. Output value: [<u>16576</u>]
EO01411-50045	FATAL	SQL CONTEXT USE Error.	Failed to select context.
EO01412-50052	FATAL	SQL PREPARE Error.	Failed to analyze SQL statement.
EO01413-50046	FATAL	SQL DECLARE Error.	Failed to declare cursor.
EO01414-50047	FATAL	SQL DESCRIBE BIND VARIABLES Error.	Failed to initialize bind descriptor.
EO01415-50050	FATAL	SQL Item Overflow.	Number of bind descriptor variables is invalid.
EO01416-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate VALUE area. Output value: [Errno= <u>error number output from OS</u>]
EO01417-50051	FATAL	SQL OPEN CURSOR Error.	Failed in OPEN cursor.
EO01418-50048	FATAL	SQL DESCRIBE SELECT LIST Error.	Failed in DESCRIBE for selection list.
EO01419-50054	FATAL	SQL Select List Overflow.	Too many parameters are selected.
EO01420-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required to verify retrieved VALUE. Output value: [Errno= <u>error number output from OS</u>]
EO01422-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required to verify retrieved VALUE type. Output value: [Errno= <u>error number output from OS</u>]
EO01423-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required to verify retrieved VALUE type. Output value: [Errno= <u>error number output from OS</u>]
EO01424-00018	FATAL	IW_ModifyConfigValue() Error.	Failed to set retrieved VALUE to IW_CONF structure. Output value: [Errno= <u>error number output from OS</u>]
EO01425-50043	FATAL	SQL CLOSE Error.	Failed in CLOSE of SQL cursor.
EO01427-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate an area to store the FETCH results. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EO01501-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for Select List data area. Output value: [Errno=error number output from OS]
EO01502-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory for Select List data area. Output value: [Errno=error number output from OS]
EO01801-50003	FATAL	CONTEXT ALLOCATE Error. (conn=%d/%d) (errno=%d) [%s]	Could not retrieve context. Output value: [conn=number of connections] [number of connection pools] [errno=authentication database error code] [authentication database error message]
EO01901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO01902-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO01903-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO01904-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO02001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO02002-50002	FATAL	CONNECT USE Error. (conn=%d/%d) (errno=%d) [%s]	Failed to select context. Output value: [conn=number of connections] [number of connection pools] [errno=authentication database error code] [authentication database error message]
EO02003-50007	FATAL	DISCONNECT Error. (conn=%d/%d) (errno=%d) [%s]	Disconnection failed. Output value: [conn=number of connections] [number of connection pools] [errno=authentication database error code] [authentication database error message]
EO02101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO02103-00008	FATAL	IW_ClearBuf() Error.	An error occurred during buffer clearing.
EO02104-50029	FATAL	IW_DBSetColumn() Error.	Failed to retrieve column string.
EO02105-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing SQL statement. Output value: [Errno=error number output from OS]
EO02201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO02203-00008	FATAL	IW_ClearBuf() Error.	An error occurred during buffer clearing.
EO02204-50029	FATAL	IW_DBSetColumn() Error.	Failed to retrieve column string.
EO02205-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing SQL statement. Output value: [Errno=error number output from OS]
EO02301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EO02303-00008	FATAL	IW_ClearBuf() Error.	An error occurred during buffer clearing.
EO02304-00008	FATAL	IW_ClearBuf() Error.	An error occurred during buffer clearing.
EO02305-50029	FATAL	IW_DBSetColumn() Error.	Failed to retrieve column string (NAME).
EO02306-50029	FATAL	IW_DBSetColumn() Error.	Failed to retrieve column string (VALUE).
EO02307-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate area for storing SQL statement. Output value: [Errno=error number output from OS]
EO02401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO02402-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO02403-50040	FATAL	Process flag Error.	flg parameter value is invalid.
EO02404-50040	FATAL	Process flag Error.	flg parameter value is invalid.
EO02501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO02502-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO02504-50045	FATAL	SQL CONTEXT USE Error.	Failed to select context.
EO02505-50052	FATAL	SQL PREPARE Error.	Failed to analyze SQL statement.
EO02506-50049	FATAL	SQL EXECUTE Error.	Failed to execute SQL statement.
EO02507-50044	FATAL	SQL COMMIT Error.	Database commit failed.
EO02601-50053	FATAL	SQL ROLLBACK Error.	Failed in rollback.
EO02701-50006	FATAL	DBErrNo[%d] DBErrMsg[%s] UserID[%s] Table[%s]	Authentication database error is a system error. Output value: [authentication database error code], [authentication database error message], [user ID], [table name]
EO02801-50018	FATAL	Database Connection is Busy.	No idle database connections found.
EO03001-50009	FATAL	CONTEXT USE Error. [%s]	Failed to select context. Output value: [authentication database error message]
EO03002-50008	FATAL	CONNECT Error. [%s]	Connection failed. Output value: [authentication database error message]
EO70717-20167	FATAL	CS_ExReleaseDBConnection() failed. ret=[%d]	Failed to release the database connection. Output value: [ret=error code]
EO70729-50019	FATAL	Database Connection Pool Busy.	No idle database connection found.
EO70730-50019	FATAL	Database Connection Pool Busy.	No idle database connection found.
EO70731-50019	FATAL	Database Connection Pool Busy.	No idle database connection found.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EO71075-20165	FATAL	CS_ExInitDBConnection() failed. ret=[%d]	Failed to initialize database connection. Output value: [ret= <u>error code</u>]
EO71076-20166	FATAL	CS_ExRegisterDBConnection() failed. ret=[%d]	Failed to register database connection. Output value: [ret= <u>error code</u>]
EO71077-20167	FATAL	CS_ExReleaseDBConnection() failed. ret=[%d]	Failed to release the database connection. Output value: [ret= <u>error code</u>]
EO71078-20167	FATAL	CS_ExReleaseDBConnection() failed. ret=[%d]	Failed to release the database connection. Output value: [ret= <u>error code</u>]
EO71079-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EO00401-50030	WARNING	IW_DBUpdate() Error. UserID=%s.	Failed to update authentication database. Output value: [UserID= <u>user ID</u>]
EO01001-50022	WARNING	Get Database Context Error.	Failed to search for idle database connections.
EO01202-50028	WARNING	IW_DBInsert() Error.	Failed to insert row to access log table.
EO02106-50026	WARNING	IW_DBFetch() Error. Retry SQL.	Failed to execute SQL statement (FETCH). Statement will be re-executed.
EO02107-50027	WARNING	IW_DBFetch() Error.	Failed to execute SQL statement (FETCH).
EO02206-50024	WARNING	IW_DBExecute() Error. Retry SQL.	Failed to execute SQL statement (UPDATE).
EO02207-50025	WARNING	IW_DBExecute() Error.	Failed to execute SQL statement (UPDATE).
EO02308-50024	WARNING	IW_DBExecute() Error. Retry SQL.	Failed to execute SQL statement (Insert).
EO02309-50025	WARNING	IW_DBExecute() Error.	Failed to execute SQL statement (Insert).
EO03003-50021	WARNING	Database Reconnect succeeded.	Successfully reconnected to authentication database.
EO70720-20028	WARNING	Database Connection Error.	Failed to connect Authentication DB.
EO01421-50036	INFO	No Data Found. KEY=[%s].	No records found. Output value: [Key= <u>user ID</u>]

7.2.4 Authentication Module error log (LDAP, OpenLDAP, MSAD, and NED editions only)

Code ID	Level	Message	Description
EP10601-50031	FATAL	LDAP Server Down. Host=[%s]	Authentication database server is down. Output value: [Host=[host name:port number]]
EP10602-50031	FATAL	LDAP Server Down. Host=[%s]	Authentication database server is down. Output value: [Host=[host name:port number]]
EP10603-50006	FATAL	DBErrNo[%d] DBErrMsg[%s] UserID[%s] Table[%s]	Failed to connect to authentication database server. Output value: [authentication database error code] [authentication database error message] [user ID] [table name]
EP10801-50056	FATAL	IW_DBSelect() Error. Retry Select.	Server down error. Reconnection to authentication database will be attempted.
EP10802-50055	FATAL	ldap_search_s() Error. [%s]	Failed to search for user using ldap_search_s function. Output value: [authentication database error message]
EP10804-50058	FATAL	ldap_first_entry() Error.	Failed to retrieve user information using ldap_first_entry function.
EP10807-50061	FATAL	ldap_get_dn() Error.	Failed to retrieve user DN using ldap_get_dn function.
EP10809-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for storing DN. Output value: [Errno=error number output from OS]
EP10811-50032	FATAL	ldap_first_attribute() Error.	Failed to retrieve first attribute name using ldap_first_attribute function.
EP10813-50033	FATAL	ldap_get_values() Error.	Failed to retrieve attribute value using ldap_get_values function.
EP10818-00018	FATAL	IW_ModifyConfigValue() Error.	An error occurred when modifying configuration value.
EP10820-00011	FATAL	IW_CreateConfig() Error.	Failed to allocate structure area.
EP10901-50057	FATAL	IW_DBUpdate() Error. Retry Modify.	An attempt was made to change the user information, but a server down error occurred. Reconnection to authentication database will be attempted.
EP10902-50034	FATAL	ldap_modify_s() Error. [%s]	Failed to change user information. Output value: [database error message]
EP11001-50006	FATAL	DBErrNo[%d] DBErrMsg[%s] UserID[%s] Table[%s]	Failed to retrieve authentication database error information. Output value: [authentication database error code] [authentication database error message] [user ID] [table name]
EP14001-50031	FATAL	LDAP Server Down. Host=[%s]	Authentication database server is down. Output value: [Host=[host name:port number]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EP14003-50001	FATAL	CONNECT Error. (conn(%d/%d)=[%s]) (errno=%d) [%s]	Failed to connect to LDAP server for bind authentication. Output value: [0] [0] [user DN] [errno=authentication database error code] [authentication database error message]
EP14301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP14401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP14601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP14603-50057	FATAL	IW_DBUpdate() Error. Retry Modify.	An attempt was made to change the user information, but a server down error occurred. Reconnection to authentication database will be attempted.
EP14701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP14801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP14802-00011	FATAL	IW_CreateConfig() Error.	Failed to allocate structure area.
EP14803-20099	FATAL	CS_AddConfigEntry() Error.	Failed to create entry.
EP14901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP14902-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EP15001-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP15002-00011	FATAL	IW_CreateConfig() Error.	Failed to allocate structure area.
EP15101-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP15201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP15202-50018	FATAL	Database Connection is Busy.	No idle database connections found.
EP15203-50056	FATAL	IW_DBSelect() Error. Retry Select.	Server down error. Reconnection to authentication database will be attempted.
EP15204-50055	FATAL	ldap_search_s() Error. [%s]	Failed to search for the authentication database. Output value: [database error message]
EP15205-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EP15206-00011	FATAL	IW_CreateConfig() Error.	Failed to allocate structure area.
EP15301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EP15403-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EP15501-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP15601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP15602-00012	FATAL	IW_CreateConfigEntry() Error.	Failed to add entry for group information.
EP15801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP15901-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP15902-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EP16001-20015	FATAL	Create Thread Error. (%d) [%s]	Failed to generate the AD group retrieval thread. Output value: [ErrCode= <u>error code</u>] [<u>system call error message</u>]
EP19201-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for converting to UTF-8. Output value: [Errno= <u>error number output from OS</u>]
EP70926-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EP70927-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EP70928-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EP70932-50013	FATAL	No Database Host.	Authentication database host name is not set.
EP70949-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EP70950-20115	FATAL	Config format error. HOST:PORT (%s)	DBHOST parameter format is invalid. Output value: [HOST:PORT (<u>set value</u>)]
EP70951-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EP71087-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71088-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71089-20165	FATAL	CS_ExInitDBConnection() failed. ret=[%d]	Failed to initialize database connection. Output value: [ret= <u>error code</u>]
EP71090-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EP71091-20166	FATAL	CS_ExRegisterDBConnection() failed. ret=[%d]	Failed to register database connection. Output value: [ret= <u>error code</u>]
EP71092-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71093-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71094-20167	FATAL	CS_ExReleaseDBConnection() failed. ret=[%d]	Failed to release the database connection. Output value: [ret= <u>error code</u>]
EP71095-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71096-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71097-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71098-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71099-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71100-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71101-20167	FATAL	CS_ExReleaseDBConnection() failed. ret=[%d]	Failed to release the database connection. Output value: [ret= <u>error code</u>]
EP71102-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71103-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71104-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71105-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EP71107-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EP71108-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EP71109-00026	FATAL	malloc() Error. Erno=%d	Failed to allocate memory area. Output value: [Erno= <u>error number output from OS</u>]
EP71110-20113	FATAL	Internal error. ErrCode=[%d]	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EP10102-50059	WARNING	Conv Code Error. [%s]	Failed in reassignment of conversion descriptor for converting UTF-8 to the default conversion character encoding "sjis." Output value: [<u>conversion character encoding</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EP10202-50059	WARNING	Conv Code Error. [%s]	Failed in reassignment of conversion descriptor for converting UTF-8 to the default conversion character encoding "sjis." Output value: [conversion character encoding]
EP10604-50073	WARNING	Database Connected. Host=[%s]	Successfully connected to LDAP server. Output value: [Host=[LDAP server name]]
EP10812-50060	WARNING	Conv Change Error. [%s] (errno=%d)	Could not convert attribute value from UTF-8 to an arbitrary character encoding. Output value: [first attribute] [errno=error number output from OS]
EP10814-50035	WARNING	ldap_next_attribute() Error.	Failed to retrieve next attribute name using ldap_next_attribute function.
EP10821-50060	WARNING	Conv Change Error. [%s] (errno=%d)	Failed to convert code. Output value: [Attribute value] [errno=error number output from OS]
EP10822-20099	WARNING	CS_AddConfigEntry() Error.	Failed to create entry.
EP10823-50075	WARNING	IW_DBModifyConfigMultiValue() Error.	Failed to update database information.
EP11601-50030	WARNING	IW_DBUpdate() Error. UserID=%s.	Failed to update authentication database. Output value: [UserID=user ID]
EP12201-50023	WARNING	IW_CreateDBInfo() Error.	Failed to allocate area for DB INFO structure.
EP12202-50013	WARNING	No Database Host.	Authentication database host name is not set.
EP12203-50011	WARNING	No Database Attach UserID.	User ID for connecting to authentication database is not set.
EP12205-50010	WARNING	No Database Attach Password.	User password for connecting to authentication database is not set.
EP12208-50012	WARNING	No Database Directory Entry.	Authentication database directory search position is not set.
EP12209-50017	WARNING	No Database UserID Column.	Authentication database user ID column is not set.
EP12210-50014	WARNING	No Database Password Column.	Authentication database password column is not set.
EP12401-50022	WARNING	Get Database Context Error.	Failed to search for idle database connections.
EP13403-50021	WARNING	Database Reconnect succeeded.	Successfully reconnected to authentication database.
EP13405-50074	WARNING	Database Reconnected. Host=[%s]	Successfully reconnected to LDAP server. Output value: [Host=[LDAP server name]]
EP14602-50018	WARNING	Database Connection is Busy.	No idle database connections found.
EP15207-50060	WARNING	Conv Change Error. [%s] (errno=%d)	Failed to convert code. Output value: [Attribute value] [errno=error number output from OS]
EP15208-20099	WARNING	CS_AddConfigEntry() Error.	Failed to create entry.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EP15402-50076	WARNING	Cannot parse DN. Not Found=[%c]	Failed to analyze DN value. Output value: [Not Found=[=]]
EP16102-50080	WARNING	IW_DBGetADGroupObject() Error. Cannot get group.	Failed to retrieve group information.
EP16402-50081	WARNING	Timeout waiting for thread. Thread=[%s].	The thread finished due to a timeout. Output value: [Thread=[ADGROUP]]
EP70713-20028	WARNING	Database Connection Error.	Failed to connect authentication database.
EP70714-50083	WARNING	IW_DBSelect() Error.	Failed to search for the authentication database.
EP70715-50084	WARNING	IW_DBUpdate() Error.	Failed to update authentication database.
EP70716-20167	WARNING	CS_ExReleaseDBConnection() failed. ret=[%d]	Failed to release the database connection. Output value: [ret=[error code]]
EP70987-20161	WARNING	LDAP search result is NULL. Server is regarded as DOWN state.	LDAP search results are successful, but the server is assumed to be down, as the structure to store the retrieved data is NULL.
EP70988-20161	WARNING	LDAP search result is NULL. Server is regarded as DOWN state.	LDAP search results are successful, but the server is assumed to be down, as the structure to store the retrieved data is NULL.
EP10101-50059	INFO	Conv Code Error. [%s]	Failed to assign conversion descriptor for converting from an arbitrary character encoding to UTF-8. Output value: [conversion character encoding]
EP10201-50059	INFO	Conv Code Error. [%s]	Failed to assign conversion descriptor for converting from UTF-8 to an arbitrary character encoding. Output value: [conversion character encoding]
EP10808-50061	INFO	ldap_get_dn() Error.	Failed to retrieve user DN using ldap_get_dn function.
EP10819-50036	INFO	No Data Found. KEY=[%s].	Cannot find data. Output value: [Key=[user ID]]
EP12207-00026	INFO	malloc() Error. Errno=%d	Failed to allocate Unicode conversion area. Output value: [Errno=error number output from OS]
EP14002-50001	INFO	CONNECT Error. (conn(%d/%d)=[%s]) (errno=%d) [%s]	Failed in bind authentication. Output value: [0] [0] [user DN] [errno=authentication database error code] [authentication database error message]
EP14402-50077	INFO	DBErrMsg[%s] UserID[%s]	Failed in certificate-base authentication. Output value: [authentication database error message] [user ID]
EP15401-00031	INFO	Parameter is NULL.	Argument parameter is NULL.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EP16101-50079	INFO	Saving group cache succeed. Entry=[%d]	Failed to retrieve group information. Output value: [number of groups retrieved]
EP16401-50082	INFO	Cannot get group cache.	Failed to retrieve group information.
EP16403-50082	INFO	Cannot get group cache.	Failed to retrieve group information.
EP71113-20169	INFO	ADGroup thread stopped. ADGroup get one-time-only	Stop the AD group information retrieval thread. AD group is retrieved only once.

7.2.5 Authentication Module error log (for CSV edition only)

Code ID	Level	Message	Description
EF05401-00026	FATAL	malloc() Error. Errno=%d	Could not allocate memory area for allocating pointer to user cache. Output value: [Errno=error number output from OS]
EF05402-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area as a user cache information list area. Output value: [Errno=error number output from OS]
EF05404-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area for UserID B-Tree. Output value: [Errno=error number output from OS]
EF32105-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area required for setting value. Output value: [Errno=error number output from OS]
EF33201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
EF33203-20021	FATAL	CS_CreateCache() Error.	CSV file is empty.
EF33204-20021	FATAL	CS_CreateCache() Error.	Failed to allocate cache area.
EF33205-50063	FATAL	No Database File. File=%s	File open error occurred. Output value: [File=file name]
EF70854-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
EF70856-00011	FATAL	IW_CreateConfig() Error.	Failed to retrieve the authentication column position information area.
EF70857-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EF70858-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EF70872-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EF70873-20113	FATAL	Internal error. ErrCode=%d	An internal error occurred. Output value: [ErrCode= <u>error code</u>]
EF71019-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EF32104-50064	WARNING	No Column. Column=%s	No column found. Output value: [Column= <u>column name</u>]
EF32301-50065	WARNING	No User. UserID=%s	No user found. Output value: [UserID= <u>user ID</u>]
EF32302-00011	WARNING	IW_CreateConfig() Error.	Failed to create information before change.
EF32303-50064	WARNING	No Column. Column=%s	No column found. Output value: [Column= <u>column name</u>]
EF32708-50012	WARNING	No Database Directory Entry.	No database entry found.
EF32709-50017	WARNING	No Database UserID Column.	No database user ID column found.
EF32710-50014	WARNING	No Database Password Column.	No database password column found.
EF32711-50062	WARNING	Create Database Table.	Failed to create table.
EF33202-50063	WARNING	No Database File. File=%s	File OPEN error occurred. Output value: [File= <u>file name</u>]
EF33209-50066	WARNING	Line Overflow. %s=[%s]	User information is too large. Output value: [<u>Line</u>] [<u>64 characters at line start</u>]
EF33301-50066	WARNING	Line Overflow. %s=[%s]	Overflow occurred while writing file. Output value: [<u>UserID</u>] [<u>user ID</u>]
EF33302-50063	WARNING	No Database File. File=%s	CSV file open error occurred. Output value: [File= <u>CSV file name</u>]
EF70855-50017	WARNING	No Database UserID Column.	No user ID column found in CSV.
EF71062-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EF71063-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
EF71064-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EF71065-00026	WARNING	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno= <u>error number output from OS</u>]
EF32103-50036	INFO	No Data Found. KEY=[%s].	Target user not found in search of user cache information. Output value: [KEY= <u>user ID</u>]

7.2.6 Authentication Module error log (for MySQL edition only)

Code ID	Level	Message	Description
ES41402-50013	FATAL	No Database Host.	Authentication database host name is not set.
ES41403-50013	FATAL	No Database Host.	Authentication database host name is not set.
ES41404-50011	FATAL	No Database Attach UserID.	User ID for connecting to authentication database is not set.
ES41406-50010	FATAL	No Database Attach Password.	Password for connecting to authentication database is not set.
ES41408-50016	FATAL	No Database Table Name.	Table name for connecting to authentication database is not set.
ES41409-50017	FATAL	No Database UserID Column.	User ID column for connecting to authentication database is not set.
ES41410-50014	FATAL	No Database Password Column.	Password column for connecting to authentication database is not set.
ES41411-50038	FATAL	No Reference UserID Column.	The column name used as the user ID in the reference table is not set.
ES41412-50037	FATAL	No Reference Attribute.	The column names for the reference table are not set.
ES45001-50067	FATAL	SQLAllocHandle Error. (conn=%d/%d) (errno=%d) [%s]	Failed to allocate SQL handle area. Output value: [conn= <u>0</u>] [<u>0</u>] [errno= <u>authentication database error code</u>] [<u>authentication database error message</u>]
ES45002-50069	FATAL	SQLSetEnvAttr Error. (errno=%d) [%s]	ODBC environment configuration failed. Output value: [errno= <u>authentication database error code</u>] [<u>authentication database error message</u>]
ES45003-50067	FATAL	SQLAllocHandle Error. (conn=%d/%d) (errno=%d) [%s]	Failed to allocate SQL handle area. Output value: [conn= <u>number of connections</u>] [<u>number of connection pools</u>] [errno= <u>authentication database error code</u>] [<u>authentication database error message</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ES45201-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ES45301-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ES45302-00008	FATAL	IW_ClearBuf() Error.	An error occurred during buffer clearing.
ES45303-50029	FATAL	IW_DBSetColumn() Error.	Failed to retrieve column string.
ES45304-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate SQL statement area. Output value: [Errno= <u>error number output from OS</u>]
ES45401-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ES45402-00008	FATAL	IW_ClearBuf() Error.	An error occurred during buffer clearing.
ES45403-50029	FATAL	IW_DBSetColumn() Error.	Failed to retrieve column string.
ES45404-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate SQL statement area. Output value: [Errno= <u>error number output from OS</u>]
ES45601-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ES45602-50040	FATAL	Process flag Error.	flg parameter value is invalid.
ES45603-50040	FATAL	Process flag Error.	flg parameter value is invalid.
ES45701-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ES45702-50019	FATAL	Database Connection Pool Busy.	No idle database connections found.
ES45703-50068	FATAL	SQLAllocHandle Error.	Failed to allocate SQL handle area.
ES45704-50070	FATAL	SQLExecDirect Error.	Failed to execute SQL statement.
ES45801-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ES45802-50019	FATAL	Database Connection Pool Busy.	No idle database connections found.
ES45803-50068	FATAL	SQLAllocHandle Error.	Failed to allocate SQL handle area.
ES45804-50070	FATAL	SQLExecDirect Error.	Failed to execute SQL statement.
ES45806-50071	FATAL	SQLFetch Error.	Failed in data fetch.
ES45807-50072	FATAL	SQLGetData Error.	Failed to retrieve length of column value.
ES45808-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate column value area. Output value: [Errno= <u>error number output from OS</u>]
ES45901-50006	FATAL	DBErrNo[%d] DBErrMsg[%s] UserID[%s] Table[%s]	Authentication database error is a system error. Output value: [<u>authentication database error code</u>] [<u>authentication database error message</u>] [<u>user ID</u>] [<u>table name</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ES46001-50018	FATAL	Database Connection is Busy.	No idle database connections found.
ES46201-50008	FATAL	CONNECT Error. [%s]	Connection failed. Output value: [authentication database error message]
ES70874-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
ES70876-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
ES70878-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
ES70879-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
ES70880-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
ES70882-50013	FATAL	No Database Host.	Authentication database host name is not set.
ES71080-20165	FATAL	CS_ExInitDBConnection() failed. ret=%d]	Failed to initialize database connection. Output value: [ret=[error code]]
ES71081-20166	FATAL	CS_ExRegisterDBConnection() failed. ret=%d]	Failed to register database connection. Output value: [ret=[error code]]
ES71082-20167	FATAL	CS_ExReleaseDBConnection() failed. ret=%d]	Failed to release the database connection. Output value: [ret=[error code]]
ES71083-20167	FATAL	CS_ExReleaseDBConnection() failed. ret=%d]	Failed to release the database connection. Output value: [ret=[error code]]
ES71084-00026	FATAL	malloc() Error. Errno=%d	Failed to allocate memory area. Output value: [Errno=error number output from OS]
ES71085-20113	FATAL	Internal error. ErrCode=%d]	An internal error occurred. Output value: [ErrCode=[error code]]
ES71086-00031	FATAL	Parameter is NULL.	Argument parameter is NULL.
ES41201-50030	WARNING	IW_DBUpdate() Error. UserID=%s.	Failed to update authentication database. Output value: [UserID=user ID]
ES41501-50022	WARNING	Get Database Context Error.	Failed to search for idle database connections.
ES45305-50026	WARNING	IW_DBFetch() Error. Retry SQL.	Failed to execute SQL statement (FETCH). Statement will be re-executed.

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Level	Message	Description
ES45306-50027	WARNING	IW_DBFetch() Error.	Failed to execute SQL statement (FETCH).
ES45405-50024	WARNING	IW_DBExecute() Error. Retry SQL.	Failed to execute SQL statement (UPDATE). Statement will be re-executed.
ES45406-50025	WARNING	IW_DBExecute() Error.	Failed to execute SQL statement (UPDATE).
ES46202-50021	WARNING	Database Reconnect succeeded.	Successfully reconnected to authentication database.
ES70523-20167	WARNING	CS_ExReleaseDBConnection() failed. ret=[%d]	Failed to release the database connection. Output value: [ret= <u>error code</u>]
ES70931-20028	WARNING	Database Connection Error.	Failed to connect authentication database.
ES45805-50036	INFO	No Data Found. KEY=[%s].	No records found. Output value: [KEY= <u>user ID</u>]
ES70875-50073	INFO	Database Connected. Host=[%s]	Successfully connected to MySQL server. Output value: [Host= <u>MySQL server name</u>]
ES70877-50085	INFO	Database Connect Error. Host=[%s]	Failed to connect to MySQL server. Output value: [Host= <u>MySQL server name</u>]
ES70881-50074	INFO	Database Reconnected. Host=[%s]	Successfully reconnected to MySQL server. Output value: [Host= <u>MySQL server name</u>]

7.3 Audit log message list

History type	Operation result	IP address	Message	Status
1	1	○	Can Not Access For Uid/Password. UserID=%s	Cannot log in with Uid/Password. Output value: [UserID= <u>user ID</u>]
1	1	○	Client Certificate Error. UserID=%s	Failed to check the Client Certificate used for certificate login. Output value: [UserID= <u>user ID</u>]
1	0	○	Duplicate Login. UserID=%s	Duplicate login. Output value: [UserID= <u>user ID</u>]
1	1	○	IW Serial Exist. But RA Serial Not Exist. UserID=%s Cert=%d	RA serial does not exist, but IW serial exists. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
1	1	○	Login Lock. UserID=%s	Login is locked. Output value: [UserID= <u>user ID</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

History type	Operation result	IP address	Message	Status
1	1	○	Max User Login. Login Failed. UserID=%s	Could not log in because the number of user logins reached the maximum count. Output value: [UserID= <u>user ID</u>]
1	1	○	Password Error. UserID=%s	Password error occurred. Output value: [UserID= <u>user ID</u>]
1	1	○	Password is NULL. UserID=%s	Password is NULL. Output value: [UserID= <u>user ID</u>]
1	1	○	Password Lock. UserID=%s	Password is locked. Output value: [UserID= <u>user ID</u>]
1	1	○	RA Serial And Receive Serial Not Match. UserID=%s Cert=%d	RA serial and received serial do not match. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
1	0	○	RA Serial Exist & IW Serial Exist. UserID=%s Cert=%d	RA serial, IW serial, and received serial matched. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
1	0	○	RA Serial Exist. IW Serial Not Exist. UserID=%s Cert=%d	RA serial exists, but IW serial does not exist. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
1	1	○	RA Serial is Not Registered. UserID=%s Cert=%d	RA serial is not registered in authentication database. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
1	1	○	Receive Unknown Serial. UserID=%s Cert=%d	Received serial is abnormal. Output value: [UserID= <u>user ID</u>] [Cert= <u>certificate number</u>]
1	1	×	Unknown Cookie. Cookie=%s	Not logged in. Output value: [Cookie= <u>session ID</u>]
1	1	○	Unknown UserID. UserID=%s	User ID is not registered in the authentication database. Output value: [UserID= <u>user ID</u>]
1	0	○	User Login. UserID=%s	User logged in. Output value: [UserID= <u>user ID</u>]
1	1	○	UserID Not Exist.	User ID does not exist.
2	1	○	User Logout Error. UserID=%s	Could not delete the user information from the user cache. Output value: [UserID= <u>user ID</u>]
2	0	○	User Logout. UserID=%s %s	User logged out. Output value: [UserID= <u>user ID</u>] [<u>logged in period</u>]

IceWall SSO Version 10.0 / Troubleshooting Guide

History type	Operation result	IP address	Message	Status
2	0	○	User Logout. (All User Logout) UserID=%s %s	User logged out. Output value: [UserID=user ID] [logged in period]
3	0	○	Login Timeout. UserID=%s %s	User logged out due to a timeout. Output value: [UserID=user ID] [logged in period]
4	0	○	Forced to Logout. UserID=%s %s	Forced logout occurred. Output value: [UserID=user ID] [logged in period]
4	0	○	Reference User Logout. UserID=%s %s	User logged out. Output value: [UserID=user ID] [logged in period]

7.4 Security log message list

SECINFO	User ID	IP address	AGENT_KEY	Message	Description
LOGIN	○	○	×	Userid login.	Login by user ID authentication was successful.
	○	○	○	ClientCert login.	Login by client certificate authentication was successful.
LOGOUT	×	○	×	Logout.	Logout was successful.
PWDCHG	○	○	×	PasswordChange.	Password change was successful.
AGENT	○	○	○	Agent userid login. agent=xxxx	Agent login link operation by user ID authentication was successful. Output value: [agent=agent server host name]
	○	○	○	Agent ClientCert login. agent=xxxx	Agent login link operation by client certificate authentication was successful. Output value: [agent=agent server host name]
	○	○	○	Agent sid reissue. agent=xxxx	Agent session ID reissuing link operation was successful. Output value: [agent=agent server host name]
	○	○	○	Agent userid re-login. agent=xxxx	Agent relogin link operation by user ID authentication was successful. Output value: [agent=agent server host name]
	○	○	○	Agent ClientCert re-login. agent=xxxx	Agent relogin link operation by client certificate authentication was successful. Output value: [agent=agent server host name]
PAGE	○ *2	○	○ *2	Output page.[xxxx] path=xxxx	Template HTML for request from client displayed. Output value: [template HTML name] [path=requested URL]

The output message is for SECLEVEL=0. Information like “uid=xxx” for SECLEVEL 1, and “key=xxx uid=xxx ip=xxx.xxx.xxx.xxx” for SECLEVEL 2 is added.

*1 The user ID is not output, but “uid=” is output in the message.

*2 There may be no output for certain operations.

Each parameter name in the HTML configuration file (html.conf) is output as the HTML template name when PAGE is set as the SECINFO parameter. However, if a preset page is displayed when the system error page cannot be displayed, “DFWERROR” is output.

7.5 Information log message list

Code ID	Message	Description
AC17001-29999	CERTINFO USER: Used[%d] / Max[%d] = %2.0f%%	Log for checking the number of login users Output value: [Used[number of users currently logged in] / Max[number of users that can log in] = [percentage of users that can log in]]
AC17002-29999	CERTINFO REQUEST_QUEUE : Used[%d] / Max[%d] = %2.0f%% Over[%d]	Log for checking the status of the request queue Output value: [Used[number of request queues currently in use] / Max[request queue size] = [request queue usage rate] Over[request queue overflow count]]
AC17004-29999	CERTINFO REPRICA_QUEUE : Used[%d] / Max[%d] = %2.0f%% Over[%d]	Log for checking the status of the replication queue Output value: [Used[number of replication queues currently in use] / Max[replication queue size] = [replication queue usage rate] Over[replication queue overflow count]]
AC17007-29999	CERTINFO REPRICA_THREAD : Used[%d] / Max[%d] = %2.0f%%	Log for checking the status of the replication threads Output value: [Used[number of thread currently in use] / Max[total number of threads] = [thread usage rate]]
AC17008-29999	CERTINFO DBCONNECT : Used[%d] / Max[%d] = %2.0f%% Over[%d]	Log for checking the status of connections to the authentication database Output value: [Used[number of connections currently in use] / Max[total number of connections] = [connection usage rate] Over[wait count for an open connection]]

IceWall SSO Version 10.0 / Troubleshooting Guide

Code ID	Message	Description
AC17009-29999	CERTINFO REQUEST_THREAD : Used[%d] / Max[%d] = %2.0f%%	Log for checking the status of the request threads Output value: [Used[number of thread currently in use] / Max[total number of threads] = [thread usage rate]]
AC17010-29999	CERTINFO ACCTHREAD : Used[%d] / Max[%d] = %2.0f%%	Log for checking the number of access dedicated threads Output value: [Used[number of access thread currently in use] / Max[number of request thread] = [request thread usage rate]]
AC17011-29999	CERTINFO CACHE: Used[%d] / Max[%d] = %2.0f%%	Log for checking the status of cache usage Output value: [Used[number of users currently logged in] / Max[cache size] = [cache usage rate]]
AC71115-29999	CERTINFO DB_QUEUE : Used[%d] / Max[%d] = %2.0f%% Over[%d]	Log for checking the status of the authentication database queue Output value: [Used[number of authentication DB queue currently in use] / Max[authentication DB queue size] = [authentication DB queue usage rate] Over[authentication DB queue overflow count]]
AC71116-29999	CERTINFO LOGDB_QUEUE : Used[%d] / Max[%d] = %2.0f%% Over[%d]	Log for checking the status of the log database queue Output value: [Used[number of log DB queue currently in use] / Max[log DB queue size] = [log DB queue usage rate] Over[log DB queue overflow count]]