

Extraction in detail, Delta Mechanisms and few challenges faced during implementation

Summary:

The article articulates the step by step procedure for the generation of the COPA Data Source at the ECC R/3 back-end level along with Delta mechanisms and talk about the few challenges faced while extracting the data during implementation.

Table of Contents:

1. Introduction
2. Following is the Scenarios with explanation:
 - a. Generating the COPA Data Source,
 - b. Issues/Errors faced while extraction and building the Summarization Levels,
 - c. Transporting the Summarization Levels to the next level,
 - d. Delta mechanism and how it works, and
 - e. How to change the safety interval limit for COPA Data Source
3. Describing the Test Scenarios
4. Related content

Introduction:

Initially we had generated the COPA Data Source using the standard procedure and while extracting the data in RSA3, unable to extract the data due to few issues at ECC R/3 back-end level. Therefore describing such scenarios in this document.

Terms

Data Source	SAP BW Data Extraction Object
T-code	SAP Transaction
CO-PA	Controlling – Profitability Analysis
Operating Concern	An operating concern represents an organizational unit in your company for which the sales market has a uniform structure. It is the valuation level for Profitability Analysis (CO-PA).

Scenario:

Part – A). Generating the COPA Data Source:

Below are the simple steps for generating the COPA Data Source.

Basically COPA Data Source generation is a generic extraction, and we can create the generic Data Source depending on the KPI's for the Profitability Analysis.

Go to T-Code:

SBIW → Settings for Application-Specific Data Sources (PI) → Profitability Analysis → Create Transaction Data Source → Create a Data Source.

or

KEBO → define the Data Source with the necessary details as below.

Generally, we use the naming convention for the COPA Data Source is: {1_CO_PA_(SYSTEM ID)_(CLIENT)_(OPERATING CONCERN)}.

Select the Operating concern and choose the option **Costing/Account-based** (as per the business requirement), execute (F8).

If the COPA Data Source is “**Costing based**” then it will extract the data from below four tables:

CE1XXXX – Actual line items

CE2XXXX – Plan line items

CE3XXXX – Summary table

CE4XXXX – Segment table

where “XXXX” is the Operating Concern.

Or

If the COPA Data Source is “**Account based**” then it will pull the data from the following tables:

COEP & COBK – CO Object: (Line Items (by Period) & Document Header)

COEJ – CO Object: Line Items (by Fiscal Year)

COSP & COSS – CO Object: (Cost Totals for Internal & External Postings)

CE4XXXX – Segment table

Program Edit Goto System Help

CO-PA / SAP BW: DataSource for Transaction Data

Control Parameters

CO-PA DataSource 1_CO_PA_DS2

Function

☐ Display

☒ Create

Operating concern S001 Example

☒ Costing-based

☐ Account-based

☐ Delete

Select the below fields which you want to display/as a part of the Data Source.

Note: When we generate the COPA Data Source basically the Data Structure (Characteristics and Value fields) is based on/proposed by the Operating Concern (OC).

{If we want to check/view the total number of fields based on the Operating Concern and other etc. details. Then, Go to the T-Code: **KEA0**.

The T-Code: **KEA0** is used for to maintain/create the Operating Concern.}

CO-PA / SAP BW: DataSource for Transaction Data

DataSource: 1_CO_PA_COEP

Delta Method: Generic Delta

Logical System: [REDACTED]

Operating concern: AR00

Type of Profit. Analysis: Costing-Based Prof. Analysis

Extract structure (DDIC):

Short text: COPA EXTRACTION

Medium-Length Text: COPA EXTRACTION

Long text: COPA EXTRACTION

Field Name for Partitioning: BUKRS

Characteristics from the segment level

Characteristic	Field	Length	Unit
✓ Currency type	PALEDGER	CHAR	2
✓ Fiscal Year	GJAHR	NUMC	4
✓ Period/year	PERIO	NUMC	7
✓ Plan/Act. Indicator	PLIKZ	CHAR	1
✓ Record Type	VRGAR	CHAR	1
✓ Version	VERSI	CHAR	3
✓ Week/year	ALTPERIO	NUMC	7

Characteristics from the segment table

Characteristic	Field	Length	Unit
✓ Company Code	BUKRS	CHAR	4
✓ Business Area	GSBER	CHAR	4
✓ CO Area	KOKRS	CHAR	4
✓ Cost center	COPA_KOSTL	CHAR	10
✓ Customer	KUNNR	CHAR	10
✓ Distr. Channel	VTWEG	CHAR	2

After field selection, check & choose the Info Catalog (F7) option for the Data Source generation.

InfoSource	Edit	Goto	System
Accept entries			Enter
Summarization Level			Ctrl+F3
Check			Ctrl+F2
InfoCatalog			F7
Generate			
Print			Ctrl+P
Save to PC file...			
Exit			Shift+F3

Then provide the Transport Request number and select the fields for the input selection.

DataSource: Customer version Edit

Header Data

DataSource: 1_CO_PA_COEP Package:

Description: COPA EXTRACTION

Extraction

ExtractStruct.: ZOXID30541

Direct Access: D

Delta Update: ☒ DataSource for Reconciliation: ☐

Field Name	Short text	Selection	Hide field	Inversion	Field only..
ARTNR	Product number	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
PRCTR	Profit Center	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
VKORG	Sales Organization	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
SEGMENT	Segment for Segmental Reporting	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
ABSMG_ME	Un Sales quantity	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
REC_WAERS	Currency of the data record	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
FADAT	Invoice date (date created)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
FKART	Billing Type	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
STO_BELNR	Canceled document	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
STO_POSNR	Canceled document item	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
KSTAR	Cost Element	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
KTOPL	Chart of Accounts	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
KSTRG	Cost Object	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Click on Save button.

Data Source "1_CO_PA_DS2" created successfully.


Note: After generating the COPA Data Source, we will not be able to edit/enhance the COPA Data Source. In case if we need to add the new fields, then we need to delete and recreate the Data Source again using the same naming convention.

Go to the T-Code: **RSA3** and try to extract the data.

Part – B). Issues/Errors faced while extraction and building the Summarization Levels:


In some situations, you might get the following issues during the data extraction in **RSA3**:

Case. 1: During the data extraction probably you will get "0" records in **RSA3**. Or




Case. 2: The Data Source is giving a below error while extracting the data in **RSA3**.

'Errors occurred during the extraction' (Message no. RJ012).




or check the error logs.




To overcome from this error, we need to define/maintain the following few steps.

Go to the T-Code: **KEB0** and check if the Summarization Levels are maintained or not using option (**CTRL+F3**).



Or go directly to the T-Code: **KEDV** (CO-PA: Maintain Summarization Levels). Select the Operating Concern.

And then, check the Summarization levels are maintained or not. If not, then choose the option to create entries (**F5**).



While creating the Summary Levels, kindly consult with your functional consultant for more details/about the requirement.

New Entries: Details of Added Entries

Variable list

Summariz. Level: 1 [Test Summarization level1 for COPA extractor]

Status: To be created

Data from: 05.08.15 12:34:54

Come back and select your Summ. Levels.

New Entries: Overview of Added Entries

Variable list

Navigation

- Summarization Levels (AA00 Costing-based)
- Characteristics
- Indexes

Level	Text	Status
1	Test Summarization level1 for COPA extractor	To be created
2	Test Summarization level2 for COPA extractor	To be created

Choose the Characteristics option and assign the characteristic Values '*' or 'etc... value' as below.

Change View "Summarization levels - fields": Overview

Variable list

Navigation

- Summarization Levels (AA00 Costing-based)
- Characteristics
- Indexes

Summarization level: 3 Summarization level for COPA extractor COEP Level3

Field	Name	Characteristic Value	Text
ARINR	Product	*	
BUKRS	Company Code		
COPA_KOSTL	Cost center	*	
GJAHR	Fiscal Year	*	
GSBER	Business Area	*	
KMMAKL	Material Group	*	
KNDNR	Customer	*	
KOKRS	CO Area	*	
PALEDGER	Currency type	*	
PERDE	Period	*	
PLIKZ	Plan/Act. Indic	*	
PRCTR	Profit Center	*	

Save the entries and assign the TR.

Change View "Summarization levels": Overview

60% Test mode... New entries Variable list

Navigation

- Summarization Levels (AA00 Costing-based)
- Characteristics
- Indexes

Level	Text	Status
1	Test Summarization level1 for COPA extractor	Active, without data
2	Test Summarization level2 for COPA extractor	Active, without data

Now, the status of Summary levels are **Active, without data**.

Then go to the T-Code: **KEDU** (CO-PA: Build Summarization Levels) refill the same using below option.

Select your Operating Concern (AA00), Type of Profitability Analysis "Costing-based (1) or Account-based" (2) and Choose Summarization Level (1 to 2).

Build Summarization Levels for Profitability Analysis

Selections

Operating concern: AA00

Type of Profitability Analysis: 1

Summarization levels: 1 to 2

Data in the summarization levels

☐ Build new levels
☐ Refresh
☒ Rebuild

Choose the option **Rebuild/Build new levels** and Execute (F8).

Build Summarization Levels for Profitability Analysis

Call parameter

Operating concern: AA00
 Type: Costing-based
 Summarization levels:
 I BI 000001 000002
 Data in summarization levels: Rebuild

Statistics

The data was read from the segment level. Data from the last 30 minutes was ignored for reasons of consistency.

The summarization levels have been supplied with data.
 The processed levels now contain the data up to
 05.08.2015, 12:34:54.
 Program started: 05.08.2015 13:04:54
 Program completed: 05.08.2015 13:04:55
 Runtime: 00:00:01

Again, go to the T-Code: **KEDV** and check the status of Summary levels. now the status is **Active** with data.


Change View "Summarization levels": Overview

Navigation


- Summarization Levels (AA00 Costing-based)
- Characteristics
- Indexes

Level	Text	Status
1	Test Summarization level1 for COPA extractor	Active
2	Test Summarization level2 for COPA extractor	Active


After refilling the Summarization levels, go to the T-Code: **RSA3** and extract the data.



If still issue occurs then, go to the T-Code: **SE38** and run the Report program “**RKETREGN**” (Summarization Levels: Generate Tables for Summarization Levels) generate the same.




And again Go to the T-Code: **RSA3** and extract the data.



Now data are available.

Part-C). Transporting the Summarization Levels to the next level:


Now transporting the changes/settings to the other system/next level. Go to the T-Code: **KE3I** (CO-PA: Transport tool) to collect all settings in the TR.



Execute **(F8)** it and mention your both TR Customizing and Workbench TR.



Select the relevant object classes and continue **(OK)**.



Release the TR from **SE09**. Go to the T-Code: **SCC1** (Client Copy – Special Selections), basically this T-Code is used for to import the TR from one client to another client within a system, for example: ECCCLNT800 (Pre-DEV) to ECCCLNT900 (DEV/QUA system).


Note: Check if the above transport procedure is applicable in your case. Otherwise, follow the normal transport procedure for transporting the objects from one system to another system, for example: from development (DEVCLNT100) to quality (QUACLNT500) system.

Part-D). Delta mechanism and how it works:

The COPA Data Source is based BW Delta process type: **“CUBE”** (Info Cube Extraction).

Note: The BW Delta process type **“CUBE”** is exactly similar as **“ADD”**.

Explaining the Delta mechanism of **“ADD/CUBE”** with below example and how it works.



Example:

When BW Delta process type: **ADD** → which provides the additive Image.

A simple Doc Number as below: Existing Target document's quantity value is 30.

Document	Status	Quantity	U/M
11111	O	30	KG

Now let us assume the quantity has changed from 30 to 40 in the SAP ECC source.

If the Data Source is based on **ADD/CUBE**: it will bring only additive image i.e. quantity as 10.

Document	Status	Quantity	U/M
11111	O	10	KG

In the final target it will reflect as below: adding the value (30+10 = 40).

Document	Status	Quantity	U/M
11111	O	40	KG


Note: If the data that fills the BI system with an additive (**ADD/CUBE**) image, the data can be written to an Info Cube or a Data Store object.

However, in-case of Data Store object, the update type of key figures must be set to add and not overwrite.

Delta Process type		DSO/ODS	CUBE
ADD/CUBE	Additive Image	Yes (Add Only)	Yes (Add)

Part-E). How to change the Delta safety interval limit for COPA Data Source:

When data is extracted from the COPA Data Source, a "safety delta" of half an hour (30 minutes) is used with the initialization and the delta upload. This always ensures that only records that are already half an hour old, since the start of the upload are loaded into SAP BW. Half an hour was chosen as the safety delta to overcome any time differences between the clocks on the different application servers.




The above standard upper limit for COPA is already set to 1800 i.e. (30 Mins) provided by SAP.

Steps for changing the Delta Safety intervals for the COPA Data Source:

Note: It is not recommended to change the safety intervals. But sometimes we need to change the Intervals based on the Business/Project requirements.

Go to the T-Code: **RSA2**, check the existing value.



The Data Source safety upper limit is: 1800.

Also, we can check the interval values for individual Data Source in the table **"ROOSOURCE"** where the field **"DELTASAFE2"** holds the Safety Upper limit Value and **"DELTASAFE1"** holds Lower limit.

Table ROOSOURCE Display

Check Table...

TSTPDAT	03.08.2015
TSTPTIM	14:56:23
INVFIELD	
GENDELTAFD	TIMESTAMP
GENDELATAP	T
DELTASAFE1	
DELTASAFE2	1800
DLTAGETMAX	

Below are the simple steps for changing the safety interval limit value.

Now, again Go to the T-Code: **SE11**, open the table “**ROOSOURCE**” and select the Data Source, click on display button.

Then we will use the ABAP Debugging trick to change the interval value.

Data Browser: Table ROOSOURCE: Selection Screen

Number of Entries

OLTPSOURCE	1_CO_PA_COEP	to	
OBJVERS	A	to	

Data Browser: Table ROOSOURCE Select Entries 1

OLTPSOURCE	OBJVERS	TYPE	APPLNM	BASOSOURCE	DELTA	STOCKUPD	UPDF
1_CO_PA_COEP	A	TRAN	CO-PA		CUBE		

Table Entry Edit Goto Settings Environment

/H

Table ROOSOURCE Display

Check Table...

OLTPSOURCE	1_CO_PA_COEP
OBJVERS	A
TYPE	TRAN
APPLNM	CO-PA
BASOSOURCE	
DELTA	CUBE

Select the relevant field and press **Enter** button → Double Click on the **CODE** and replace the word “**SHOW**” with “**EDIT**” → press **ENTER** → Execute (**F8**).

It will open in edit mode, then change the value based on the requirement (for example: here replacing 1800 Seconds with 600), save and go back to check the changed value in the table/Go to the T-Code: **RSA2**.

The image shows two screenshots from the SAP BI Service API configuration interface, connected by red arrows indicating a workflow.

Top Screenshot: Table ROOSOURCE Change

This window shows a table with two rows: DELTASAFE1 and DELTASAFE2. The DELTASAFE2 row has a value of 600 in a highlighted yellow cell. Above the table, there is a section for 'S... Variable' and 'V... Val.' with a dropdown menu set to 'EDIT'.

Bottom Screenshot: BI Service API: Display DataSource 1_CO_PA_COEP

This window shows the configuration for a data source. The 'General' tab is active, and the 'Generic Delta' section is expanded. The 'DataSource' is set to '1_CO_PA_COEP'. The 'Delta-Specific Field' is set to 'TIMESTAMP'. The 'Settings' section shows 'Safety Interval Upper Limit' set to 600 seconds. The 'Delta Extraction' section shows 'CUBE InfoCube Extraction' and 'Generic Delta' selected.

Refer SAP Note: (0000392876 – Safety delta for extraction from the CO-PA) for more details.

Replicate/Import the Data Source in the BW/etc. Targets (Destination) and load the data into respective Data Targets.