



Exercise 5.6: Start a VNC server

Install VNC server.

Use the **vncserver** command to create a VNC session.

Solution 5.6

1. Ensure VNC server is installed.

- **CentOS**

```
# yum install tigervnc-server tigervnc
```

- **Ubuntu**

```
# apt-get install tightvncserver xtightvncviewer
```

- **OpenSUSE**

```
# zypper install tigervnc
```

2. Start the server.

```
$ vncserver
```

3. Test the server with **vncviewer**.

```
$ vncviewer localhost:1
```

Note: For Ubuntu users, the default `$HOME/.vnc/xstartup` file may contain references to program options that are not available. This is copy of a **xstartup** file that can be used if the vnc client only displays a gray screen. This example uses the **mwm** window manager, you may have to install the **mwm** package.

```
#!/bin/sh

xrdb $HOME/.Xresources
xsetroot -solid grey
x-terminal-emulator -geometry 80x24+10+10 &
#x-window-manager &
# Fix to make GNOME work
mwm &
export XKL_XMODMAP_DISABLE=1
/etc/X11/Xsession
```