

Unified Assurance and Analytics **Upgrade MOP**

Release 23.08.64

Issue 2.0 | November 21, 2023 | 450-3704-326-2308

Table of Contents

Publication History	4
System Requirements	5
Patch Install Instructions (Non-GR)	6
Pre-requisites	6
Downloading Installation Files	7
Updating the Hosts File	8
Modifying the Volume Group Name (Optional)	9
Updating Configured Parameters.....	10
Transferring the Installation Files to Host	11
Setting Up Users	13
Modifying System Logging Path (Optional)	14
Updating Site Configurations	15
Upgrading BPUAA Platform and Solution.....	17
Patch Install Instructions (GR).....	19
Pre-requisites	19
Upgrade with Geographical Redundancy.....	20
Updating Site for Upgrade	21
Downloading Installation Files	21
Transferring the Installation Files to Host	22
Disabling Geographical Redundancy Configuration	24
Activating Site B (standby) Optional.....	26
Preparing Hosts for Upgrade (on site A)	27
Updating the Hosts File	27
Modifying the Volume Group Name (Optional)	28
Updating Configured Parameters.....	28
Setting Up Users (Site A)	29
Modifying System Logging Path (Optional)	30
Updating Site Configurations	31
Upgrading BPUAA Platform and Solution on Site A (Active)	33
Upgrading site B and setting up geographical redundancy (Automatic Procedure)	35
Preparing Site B (standby) for Upgrade	35
Getting Site B Information for upgrade.....	35
Updating Hosts File on Site A (active)	36
Setting Up Users of Site B (standby).....	37
Purging solutions from Site B (standby) on Pre-upgrade BPUAA.....	38

Updating Site Configurations on Site B (standby)	38
Installing Core Platform and Platform Solution for BPUAA 23.08 on Site B (standby)	40
Connecting Site A and Site B for Geographical Redundancy (automatic procedure)	40
Logstash Configuration.....	44
Creating a New Standby Site for Geographical Redundancy	46
Cleaning up Old Georedundancy Settings	46
Updating Hosts File.....	47
Modifying the Volume Group Name.....	48
Configuring a Time Source	49
Configuring Geographical Redundancy.....	51
Configuring the Blue Planet email Service	52
Modifying the ILAN NET Interface	53
Modifying the Default UAA Interface	54
Specifying the External License Server	54
Setting Up Users	55
Validating the Hosts.....	56
Configuring UAA Hosts on Active and Standby Sites	57
Setup Overrides Configuration for Postgres	58
Installing Core Platform and Extended Platform Solution on Active and Standby Sites.....	59
Installing UAA and Configuring Georedundancy on Active and Standby Sites (automatic procedure)	59
Revert Override Configuration in Postgres	63
Backup and Restore of UAA PM DB	64
Contacting Blue Planet.....	65
LEGAL NOTICES	66
Security.....	66

Publication History

The following table lists the 23.08.64 UAA Upgrade history.

DATE	VERSION	NOTES
14-Dec-2023	2.0	Maintenance Release 23.08.64 Updated the below section with swagger API details: <ul style="list-style-type: none">• Connecting Site A and Site B for Geographical Redundancy (automatic procedure)• Installing BPUAA and configuring georedundancy on active and standby sites (automatic procedure)
13-Dec-2023	2.0	Maintenance Release 23.08.64 <ul style="list-style-type: none">• Added a backup step for proxy in the pre-requisites section.• Added in the Upgrading BPUAA Platform and Solution also after execute step.
11-Dec-2023	2.0	Maintenance Release 23.08.64 Added Tron restart step in the post upgrade common steps (under GR and Non-GR Sections).
21-Nov-2023	2.0	Maintenance Release 23.08.64
17-Nov-2023	2.0	Maintenance Release 23.08.61 <ul style="list-style-type: none">• Added new section for Remote Data Collector (RDC) Upgrade.• Fixed minor typos.
25-Oct-2023	1.0	Maintenance Release 23.08.61
24-Aug-2023	1.0	Initial 23.08 Release

System Requirements

BPUAA supports the following versions of Operating Systems:

BPUAA version	Supported OS and versions		
Upgrade from 23.04.xx 23.08.xx to 23.08.64	CentOS versions	RHEL versions	Oracle Enterprise Linux versions
	CentOS 7.9	RHEL 7.9	OEL 7.9

Patch Install Instructions (Non-GR)

Pre-requisites

1. Make sure you have reviewed the Blue Planet Release Notes for information about features and functions and any requirements not listed below.
2. Make sure Solution Manager authentication (proxyauth) is not enabled.
3. Make sure you have Ciena Portal access (<http://my.ciena.com>). This is required to download the new Linux system bundle and the UAA software.
4. Make sure you can use your existing license file to download the new software release. If you have not installed the Standalone License Server or do not have an active software license, refer **BP Engineering Guide** for the licensing procedure.
5. Ensure that the server meets the requirements for BPUAA as provided in the **BP Engineering Guide**.
6. All the commands should be run with root or sudo privileges.
7. Make sure to follow the **Creating a Site Backup Using the Solution Manager** section (Under *System Backups > Backing up and restoring software*) in the **UAA Administration Guide** to take the **Site** backup of the working **UAA setup**. This can be used in case of failed upgrade to restore the system to its previously working condition.
8. If proxy is being used for RA downloads from bphub, make sure to note down the content of file `"/etc/yum.conf"` from **uaa-core leader** which contains proxy configuration. Follow the instructions provided in **Proxy Setup to Access Bphub** (Under *UAA Administration* section) In the **UAA Administration Guide**.
9. The user should be able to SSH to all the UAA servers without password (password-less authentication must be set) from the server where the upgrade is planned to be executed.
10. It is recommended to run the upgrade from host (*leader instance*).
11. Make sure to update all RAs/Plugins to latest (8.x) version before proceeding.
12. Make sure to have at least 50% free disk space before upgrading.
13. Make sure to have at least 40+ GB free disk space under `/opt/ciena` before upgrading.
14. Make sure that the user group names are not exceeding 30 characters before upgrading else the upgrade will fail.
15. Make sure **No LAG** exists between Leader and Replica/Stand by instances of uaa-core-db instances. Execute `"ctl list"` to check the LAG.
16. Capture the UAA components JVM settings from UAA UI available under menu option "System → Application Configuration → Value column". To filter the uaa components, enter "uaa" in the "Application" search field.

NOTE

Capture the System → Application Configuration settings for uaa components and reconfigure the same JVM settings post UAA upgrade.

Downloading Installation Files

To install the BPUAA 23.08 platform and solutions, you need the following files:

- bp_uaa_23.08.xx-xx.tar - Contains the BPUAA solutions specific for customer installation.
- bpi_23.08-xx.sh - Contains the Blue Planet installer scripts and commands that will install BPUAA 23.08.
- LinuxIntel_2023_xx_x.tar - Contains Blue planet platform files required for installation/upgrade.

Before you begin, verify that you have:

- A computer with web access separates from the host server where you will install UAA.
- Ciena portal (<https://my.ciena.com>) account for your organization and the ability to log in as a registered user. If you do not have an account, visit <https://my.ciena.com/CienaPortal/s/SelfRegisterForm>.

To download files

1. As a registered user, log in to <https://my.ciena.com>.
2. Navigate to your web browser's preferences and configure it to allow popups for my.ciena.com. *(Files will not download if popups are blocked)*
3. Click the **Support** tab and select **Software**.
4. Select the company name from the download list and click **Proceed**.
5. In the **AVAILABLE DOWNLOADS** list, select **Blue Planet Unified Assurance and Analytics (UAA)** to download the following solutions -
 - a. BPUAA_MR2_23_08
 - b. BPI_23_08
 - c. LINUX_2023_xx_x
6. In the **RELEASE INFO** column, click the PDF icon to display, then save this file to your computer for future reference.
7. Retain the files in their current location. You need to transfer them to the UAA host in the next procedure: [Transferring software installation files](#).

Updating the Hosts File

Perform the following procedure to update the hosts file parameters as per the existing, pre-upgrade UAA setup.

Requirements

Before you update the hosts file, ensure you complete the following procedure: [Transferring the installation files to host](#).

Steps

1. Log in to host 0 as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to the **/home/bpadmin/bpi** directory.
3. Update the host or hosts in the hosts file as per the existing pre-upgrade setup. Get the hosts file:

```
get-hosts-config
```

Example system output:

```
[bpadmin@bp-prod-test-1 bpi]$ get-hosts-config
```

Host	Ip	Interface	sched_labels
0	10.186.32.101	ens192	controller=True
1	10.186.33.14	ens192	controller=True
2	10.186.32.108	ens192	controller=True

```
[bpadmin@bp-prod-test-1 bpi]$
```

4. Update `site_ip` parameter in the hosts file as per the existing pre-upgrade setup. Get the site IP details:

```
get-site-ip
```

5. Update `site_name` parameter in the hosts file if it's defined on the existing pre-upgrade setup. Get the site name details:

```
get-site-name
```


Modifying the Volume Group Name (Optional)

Blue Planet recommends using unique names for volume group that can be recognized and avoid name conflicts across multiple virtual groups.

Complete this procedure to modify the volume group name where the unallocated physical extents space is left free for BPUAA to create and configure the Docker thin pool. This procedure is needed if you want to change the default values.

Before you begin, verify that you know the name of the volume group where the unallocated physical extents space is available for BPUAA to create and configure the Docker thin pool.

NOTE | You can use the Linux `vgdisplay` command to display volume group information.

To modify the volume group name

1. Log in to host 0 as `bpadmin` and navigate to the `/home/bpadmin/bpi/playbooks/group_vars` directory.
2. Using a text editor, open the `all.yml` file.
3. Uncomment and set the `vgdockerpool` to the name of your volume group.

```
#bpdockerdevs: /dev/xvdb  
#vgdockerpool: blueplanet
```

Example *after* the edit with `vgdockerpool` set to `my_vgname`.

```
#bpdockerdevs: /dev/xvdb  
vgdockerpool: my_vgname
```

4. Save the `all.yml` file.

Updating Configured Parameters

Perform the following procedure to configure the parameters of a site. These parameters are defined in the file: **/home/bpadmin/bpi/playbooks/group_vars/all.yml**.

Requirements

Before you start updating the configured parameters, ensure you complete the following procedures:

- Renaming the bpi directory
- Updating the hosts file

Steps

1. Log in to host 0 as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to the **/home/bpadmin/bpi/playbooks/group_vars**.
3. Record the ilannet configured value:

```
get-ilannet
```

Example system output:

```
[bpadmin@bp-prod-test-1 group_vars]$  
get-ilannet 172.28.0.0/16/24  
[bpadmin@bp-prod-test-1 group_vars]$
```

4. Open the **all.yml** file with a text editor and perform the following:
 - a. Uncomment the following line and replace a.b.c.d with your license server IP address, for example:

```
#license_server:a.b.c.d
```

```
license_server:10.10.10.10
```

NOTE | IP address that is, 10.10.10.10 can be onxv0288.ott.ciena.com or license server IP address of the customer.

- b. Enter the `ilannet` configured value recorded in step 3.

```
ilannet: 172.28.0.0/16/24
```

- c. Save the file and exit.

IMPORTANT

Once the changes to the new all.yml file is done, make sure to compare the parameters in new all.yml file with the old all.yml file which is backed up while transferring the files to host [here](#) and manually update any further changes as per the old all.yml file.

Transferring the Installation Files to Host

Log in to the computer where you downloaded the UAA files in the [Downloading the installation files](#) procedure.

NOTE

This procedure assumes you extracted the bpi installer and the upgrade tar file into the directory listed above. If you use other directories for installation, modify the steps to point to your directories, as required.

To extract files –

1. Log in to the UAA host 0 as the bpadmin user. Do not use the site IP; use the IP address of host 0.
2. Change to the `/opt/ciena/loads/23.08` directory:

```
sudo mkdir -p /opt/ciena/loads/23.08  
sudo chown bpadmin:bpadmin /opt/ciena/loads/23.08  
cd /opt/ciena/loads/23.08
```

3. As bpadmin user, perform the following steps,
 - a. the `bp_uaa_23.08.xx-xx.tar` file to the `/opt/ciena/loads/23.08` directory.
 - b. the `bpi-23.08-xx.sh` file to the `/home/bpadmin` directory.
 - c. the `LinuxIntel_2023_xx_x.tar` file to the `/opt/ciena/loads/23.08` directory.

4. Extract the `bp_uaa_23.08.xx-xx.tar` file:

```
tar -xf bp_uaa_23.08.xx-xx.tar
```

The extraction creates an `bp_uaa_23.08.xx.x` folder containing a `bp_uaa_23.08.xx.xx.tar.gz.bin` file and required YML files.

NOTE

Do **NOT** untar the `bp_uaa_23.08.xx-xx.tar.gz.bin` file; it will be untarred by the Blue Planet installer during installation.

5. Change to the `/home/bpadmin/bpi` directory:

```
cd /home/bpadmin/bpi
```

6. Record the current bpi version:

```
./bpi --version
```

In the following example, the version is recorded as 23.08-10.

```
[bpadmin@bp-prod-test-1 bpi]$ ./bpi --version  
bpi version 23.08-10  
ansible-playbook 2.9.27  
  config file = /home/bpadmin/bpi/ansible.cfg  
  configured module search path =  
[u'/home/bpadmin/.ansible/plugins/modules',  
u'/usr/share/ansible/plugins/modules']  
  ansible python module location =  
/home/bpadmin/bpi/venv/lib/python2.7/site-  
packages/ansible  
  executable location = venv/bin/ansible-playbook
```

```
python version = 2.7.5 (default, Apr 2 2020,  
13:16:51) [GCC 4.8.5 20150623 (Red Hat 4.8.5-39)]
```

7. Enter the following command to clean up the bpi virtual environment:

```
./scripts/cleanup.sh
```

8. Change the directory to **/home/bpadmin/**:

```
cd /home/bpadmin
```

9. Rename the bpi directory:

```
mv bpi bpi-<version>
```

Here, version recorded in step 6.

10. Remove the old bpi installer if it exists:

```
rm bpi-<version>.sh
```

Here, version recorded in step 6.

11. Extract the latest bpi version, which is transferred to **/home/bpadmin/** directory

```
bash bpi-23.08-xx.sh
```

The extraction creates the bpi directory for the latest bpi version.

Setting Up Users

This procedure performs the following tasks:

- Manages keys of the badmin user
- Manages keys of the root user
- Creates the bpuser (sudo-restricted Docker install user) and manages the bpuser sudo permissions and keys. The setup script skips this step, if the bpuser is already created.

Requirements

Before setting up the users, ensure you complete the following:

- Know the badmin user password
- Know the bpuser password, which is provided to the bpuser

Steps

1. Log in to host 0 as badmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to the **/home/badmin/bpi** directory.
3. Start the `setup-users` script:

```
./bpi --setup-users
```

4. Enter the badmin user password, *if applicable*.
5. Enter the bpuser user password, *if applicable*.

Modifying System Logging Path (Optional)

By default, the path to the system logging (syslog) file for the Blue Planet UAA applications is **/var/log/ciena/blueplanet.log**. If you want to modify this path, perform the following optional procedure: To keep current release logs separate, this procedure can be followed.

Steps

1. Log in to host 0 as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to directory **/home/bpadmin/bpi/playbooks/group_vars**.
3. Update the **all.yml** file located at **/home/bpadmin/bpi/playbooks/group_vars/** by removing the commenting and editing the bp_log_file option.

Here is an example before the edit:

```
## Logging
# BluePlanet apps log file location
# '/var/log/syslog' is an invalid choice for RedHat/Oracle Linux/CentOS systems
# '/var/log/messages' is an invalid choice for Ubuntu systems
bp_log_dir: /var/log/Ciena
#bp_log_file: "{{ bp_log_dir }}/blueplanet.log"
```

Here is an example after the edit:

```
## Logging
# BluePlanet apps log file location
# '/var/log/syslog' is an invalid choice for RedHat/Oracle Linux/CentOS systems
# '/var/log/messages' is an invalid choice for Ubuntu systems
bp_log_dir: /var/log/Ciena
#bp_log_file: "{{ bp_log_dir }}/bp_syslog.log"
```

4. Save the **all.yml** file and exit the text editor.
5. To enable changes, navigate to directory **/home/bpadmin/bpi**:

```
nohup ./bpi --site /opt/ciena/loads/23.08/lineupfile &
```

Updating Site Configurations

This procedure describes how to install the Ciena Linux system bundle, PostgreSQL and license files update on an existing, pre-upgraded setup.

Requirements

Before you start to install the Ciena Linux system bundle, complete the following procedures:

- Downloading the UAA software installation files
- Transferring software installation files
- Updating the hosts file
- Setting up users on site A
- Modifying system logging path (Optional)

Steps

1. Log in to host 0 as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to **/opt/ciena/loads/23.08/**.
3. Ensure that the LinuxIntel_2023_xx_x.tar Ciena Linux bundle tar file is available in the **/opt/ciena/loads/23.08/** directory:

```
ls -lrt LinuxIntel_2023_xx_x.tar
```

4. Change the directory to **/home/bpadmin/bpi**:

```
cd /home/bpadmin/bpi
```

5. Select the appropriate lineup file for your deployment, lineup file to update the Ciena Linux bundle:

```
nohup ./bpi --site /opt/ciena/loads/23.08/lineupfile &
```

If you are provisioning your own NTP timing, add the following playbook arguments by executing command (on single line) -

```
nohup ./bpi --site <lineup file> --playbook-args='--skip-tags ntp --limit standby_cluster' &
```

6. Verify the cienabundle.<DATE>.<TIME>.log located in **/var/opt/ciena/logs/** directory to ensure that no errors occurred in host or hosts during the Linux bundle installation.
7. Verify the Ciena Linux bundle is updated on all hosts:

```
sudo su -
```

```
bpssh checkOSversion
```

Example system output:

```
[bpadmin@bp-prod-test-1 ~]$ sudo su -
Last login: Thu Feb 13 11:41:57 UTC 2020 on pts/0
[root@bpprodtest-1 ~]# bpssh checkOSversion
host-0 ec: 0

Base Operating System Version:      Red Hat Enterprise Linux Server release 7.9 (Maipo)
                                   Oracle Linux Server release 7.9 64-bit

Operating System Bundle:            2020.35.0
host-1 ec:                           0

Base Operating System Version:      Red Hat Enterprise Linux Server release 7.9 (Maipo)
                                   Oracle Linux Server release 7.9 64-bit

Operating System Bundle:            2020.35.0
host-2 ec:                           0

Base Operating System Version:      Red Hat Enterprise Linux Server release 7.9 (Maipo)
                                   Oracle Linux Server release 7.9 64-bit

Operating System Bundle:            2020.35.0
[root@bp-prod-test-1 ~]#
```

8. Verify chetak config file:

```
sudo su -  
  
bpssh ls /etc/bp2/postgres/private/users.json  
  
bpssh ls /etc/bp2/uaa-core-db/private/users.json  
  
bpssh ls /etc/bp2/uaa-pm-db/private/users.json  
  
bpssh ls /etc/bp2/uaa-graph-db/private/users.json
```

Example system output:

```
root@bp-prod-test-1:~# bpssh ls /etc/bp2/postgres/private/users.json  
host-0 ec: 0  
/etc/bp2/postgres/private/users.json  
host-1 ec: 0  
/etc/bp2/postgres/private/users.json  
host-2 ec: 0  
/etc/bp2/postgres/private/users.json
```

9. Verify license server configuration. It must have the same server defined earlier.

```
sudo su -  
  
bpssh cat /etc/bp2/solutionmanager/nbis.d/licsvr.yaml
```

Example system output:

```
root@bp-prod-test-1:~# bpssh cat  
/etc/bp2/solutionmanager/nbis.d/licsvr.yaml  
host-0 ec: 0  
url:          https://onxv0288.ott.ciena.com:7071  
ip:           onxv0288.ott.ciena.com  
port:         7071  
publish:      true  
# Created by bpi --site  
host-1 ec: 0  
url:          https://onxv0288.ott.ciena.com:7071  
ip:           onxv0288.ott.ciena.com  
port:         7071  
publish:      true  
# Created by bpi --site  
host-2 ec: 0  
url:          https://onxv0288.ott.ciena.com:7071  
ip:           onxv0288.ott.ciena.com  
port:         7071  
publish:      true  
# Created by bpi -site
```


Upgrading BPUAA Platform and Solution

The following table shows different BPUAA install options and the corresponding lineup files available –

BPAA SOLUTION	LINEUP FILE NAME (SINGLE HOST)	LINEUP FILE NAME (MULTI HOST)
Unified Assurance and Analytics	lineup-uaa-single-rhel.yml	lineup-uaa-multi-rhel.yml

- **lineup-uaa-single-rhel.yml:** This lineup file is meant to install only UAA without integrators on a single host machine.
- **lineup-uaa-multi-rhel.yml:** This lineup file is meant to install only UAA without integrators on a multi host machine.

NOTE

Make sure **/opt/ciena/loads/** have enough free space (Recommended 60GB).
Make sure LinuxIntel bundle, bp installer and latest bpaa tar files are in the same location (host 0).

For installing optional solutions on 23.08.xx server, copy the required solutions along with its version from *lineup-uaa-<multi/single>-optional-solutions.yml* present in BP_UAA-TAR file to the main lineup file *lineup-uaa-<single/multi>-rhel.yml*

Example:

For installing upgrade solution along with normal lineup, copy below snippet from *lineup-uaa-<multi/single>-optional-solutions.yml* and paste in *lineup-uaa-<single/multi>-rhel.yml*

NOTE

```
uaa_upgrade_from_20_02:
  name: uaa_upgrade_from_20_02
  vendor: blueplanet
  version: 23.08.xx
  scale: false
```

Make sure to add the solution name under *order_additional_solution attributes*

```
order_additional_solutions:
  - uaa_upgrade_from_20_02
```

1. Log in to host 0 as bpadmin and navigate to the **/home/bpadmin/bpi** directory.
2. Execute the following command to audit solution (change the lineup file as per the requirement)

```
nohup ./bpi --upgrade-audit /opt/ciena/loads/23.08/lineupfile &
```

Verify the upgrade audit summary is accurate – new solution(s) and app(s) to be upgraded, etc.

3. Execute the following command to upgrade the desired solution (change the lineup file as per the requirement) –

```
nohup ./bpi --upgrade-execute /opt/ciena/loads/23.08/lineupfile &
```

Verify the system is in the desired state: new apps are deployed, deprecated apps are undeployed and non-upgraded apps are unaffected. Previous versions of containers still exist in the system in stopped state.

This step is service affecting. UAA will not be available during this step.

4. Open your browser and navigate to Nagios by entering the following:

<https://<site IP address>/nagios>

- a. Enter the host username and password. Nagios displays the current network, host, and service status.
 - b. Navigate to **Current Status** from the list on the left and select **Services**.
 - c. Wait for the status of all services to display OK (green).
 - d. If any service displays WARNING, UNKNOWN, PENDING, or CRITICAL as a status, then resolve the issue before proceeding further.
5. If upgrading from earlier versions of UAA (22.12, 23.04), and observe the below mentioned critical error in the environment under UAA-SBC container:

```
Failed to create policies: check-policies-failed - Exception while creating
policies not able to get the response for policies api, Exit code 1
```

Follow the below steps to overcome the error:

- a. Login to host 0 as root user.
 - b. Execute the following commands to restart the uaa-sbc container –


```
sudo solman
```

```
solution_app_restart artifactory.ciena.com.blueplanet.uaa_collector:ha-23.08.xx uaa-sbc
```
 6. If upgrading from earlier versions of 23.08, restart tron container under XP solution.
- Execute the following command:
- ```
solution_app_restart artifactory.ciena.com.blueplanet.xp:ha_23.08.xx tron
```
7. If proxy is being used for RA downloads from bphub, restore the noted content to file **"/etc/yum.conf"** in all **uaa-core instances** which contains proxy configuration. Follow the instructions provided in **Proxy Setup to Access Bphub** (Under *UAA Administration* section) In the **UAA Administration Guide**.
  8. Verify all data after the upgrade, by logging into UAA application. If you find any issues, follow the **Restoring a site backup using the bpi utility** section (Under *System Backups > Backing up and restoring software*) in the **UAA Administration Guide** to restore the software to its previously working condition.
  9. Execute the following command to commit the desired solution (change the lineup file as per the requirement)

**NOTE** | Once the commit is done, the system **cannot be restored**. Make sure that the upgrade was completely successful before proceeding.

```
nohup ./bpi --upgrade-commit /opt/ciena/loads/23.08/<lineup file> &
```

# Patch Install Instructions (GR)

## Pre-requisites

1. Make sure you have reviewed the Blue Planet Release Notes for information about features and functions and any requirements not listed below.
2. Make sure Solution Manager authentication (proxyauth) is not enabled.
3. Make sure you have Ciena Portal access (<http://my.ciena.com>). This is required to download the new Linux system bundle and the UAA software.
4. Make sure you can use your existing license file to download the new software release. If you have not installed the Standalone License Server or do not have an active software license, refer **BP Engineering Guide** for the licensing procedure.
5. Ensure that the server meets the requirements for BPUAA as provided in the **BP Engineering Guide**.
6. All the commands should be run with root or sudo privileges.
7. Make sure to follow the **Creating a Site Backup Using the Solution Manager** section (Under *System Backups > Backing Up Restoring the Software*) in the **UAA Administration Guide** to take the **Site** backup of the working **UAA setup**. This can be used in case of failed upgrade to restore the system to its previously working condition.
8. If proxy is being used for RA downloads from bphub, make sure to note down the content of file **"/etc/yum.conf"** from **uaa-core leader** which contains proxy configuration. Follow the instructions provided in **Proxy Setup to Access Bphub** (Under *UAA Administration* section) In the **UAA Administration Guide**.
9. The user should be able to SSH to all the UAA servers without password (password-less authentication must be set) from the server where the upgrade is planned to be executed.
10. It is recommended to run the upgrade from host (*leader instance*).
11. Make sure to update all RAs/Plugins to latest (8.x) version before proceeding.
12. Make sure to have at least 50% free disk space before upgrading.
13. Make sure to have at least 40+ GB free disk space under */opt/ciena* before upgrading.
14. Make sure that the user group names are not exceeding 30 characters before upgrading else the upgrade will fail.
15. Make sure **No LAG** exists between Leader and Replica/Stand by instances of uaa-core-db instances. Execute `"ctl list"` to check the LAG.
16. Recommended network guidelines Between GR sites are less than 20ms latency but GR is supported up to 100ms.  
Note that having more than 20ms latency will have an impact on time taken to setup new standby site. It might take up to couple of days depending on FM data size.
17. The BPUAA 23.08 upgrade workflows for multi-host deployment with geographic redundancy uses the following designations:
  - Site A (active)
  - Site B (standby)
18. Capture the UAA components JVM settings from UAA UI available under menu option "System → Application Configuration → Value column". To filter the uaa components, enter "uaa" in the Application" search field.

### NOTE

Capture the System → Application Configuration settings for uaa components and reconfigure the same JVM settings post UAA upgrade.

# Upgrade with Geographical Redundancy

To upgrade the single-host or multi-host deployment with geographic redundancy, you need to perform the following procedures -

- [Updating Site for Upgrade](#)
- [Upgrading Site A \(Active\) to 23.08](#)
- [Upgrading site B and setting up geographical redundancy](#)

# Updating Site for Upgrade

You need to update the site and bring it to the state from where you can start the upgrade. Following are the steps to update site.

- [Downloading the BPUAA software installation files](#)
- [Transferring the Installation Files to Host](#)
- [Disabling geographical redundancy configuration](#)
- [Activating site B \(standby\) \(optional\)](#)
- [Preparing hosts for upgrade \(on site A\)](#)

## Downloading Installation Files

To install the BPUAA 23.08 platform and solutions, you need the following files:

- bp\_uaa\_23.08.xx-xx.tar - Contains the BPUAA solutions specific for customer installation.
- bpi\_23.08-xx.sh - Contains the Blue Planet installer scripts and commands that will install BPUAA 23.08.
- LinuxIntel\_2023\_xx\_x.tar - Contains Blue planet platform files required for installation/upgrade.

Before you begin, verify that you have:

- A computer with web access separate from the host server where you will install UAA.
- Ciena portal (<https://my.ciena.com>) account for your organization and the ability to log in as a registered user. If you do not have an account, visit <https://my.ciena.com/CienaPortal/s/SelfRegisterForm>.

### To download files

1. As a registered user, log in to <https://my.ciena.com>.
2. Navigate to your web browser's preferences and configure it to allow popups for my.ciena.com. (*Files will not download if popups are blocked*)
3. Click the **Support** tab and select **Software**.
4. Select the company name from the download list and click **Proceed**.
5. In the **AVAILABLE DOWNLOADS** list, select **Blue Planet Unified Assurance and Analytics (UAA)** to download the following solutions -
  - a. BPUAA\_MR2\_23\_08
  - b. BPI\_23\_08
  - c. LINUX\_2023\_xx\_x
6. In the **RELEASE INFO** column, click the PDF icon to display, then save this file to your computer for future reference.
7. Retain the files in their current location. You need to transfer them to the UAA host in the next procedure: [Transferring software installation files](#).

## Transferring the Installation Files to Host

Log in to the computer where you downloaded the UAA files in the [Downloading the installation files](#) procedure.

### NOTE

This procedure assumes you extracted the bpi installer and the upgrade tar file into the directory listed above. If you use other directories for installation, modify the steps to point to your directories, as required.

### To extract files –

1. Log in to the UAA host 0 as the bpadmin user. Do not use the site IP; use the IP address of host 0.
2. As bpadmin user, perform the following steps,
  - a. the bp\_uaa\_23.08.xx-xx.tar file to the **/opt/ciena/loads/23.08** directory.
  - b. the bpi-23.08-xx.sh file to the **/home/bpadmin** directory.
  - c. the LinuxIntel\_2023\_xx\_x.tar file to the **/opt/ciena/loads/23.08** directory.

3. Extract the bp\_uaa\_23.08.xx-xx.tar file:

```
tar -xf bp_uaa_23.08.xx-xx.tar
```

The extraction creates an bp\_uaa\_23.08.xx.x folder containing a bp\_uaa\_23.08.xx.xx.tar.gz.bin file and required YML files.

### NOTE

Do **NOT** untar the bp\_uaa\_23.08.xx-xx.tar.gz.bin file; it will be untarred by the Blue Planet installer during installation.

4. Change to the /home/bpadmin/bpi directory:

```
cd /home/bpadmin/bpi
```

5. Record the current bpi version:

```
./bpi --version
```

In the following example, the version is recorded as 23.08-10.

```
[bpadmin@bp-prod-test-1 bpi]$./bpi --version
bpi version 23.08-10
ansible-playbook 2.3.0.0
config file = /home/bpadmin/bpi/ansible.cfg configured
module search path = Default w/o overrides
python version = 2.7.5 (default, Nov 1 2018, 03:12:47) [GCC 4.8.5 20150623
(Red Hat 4.8.5-36.0.1)]
[bpadmin@bp-prod-test-1 bpi]$
```

6. Enter the following command to clean up the bpi virtual environment:

```
./scripts/cleanup.sh
```

7. Change the directory to /home/bpadmin/:

```
cd /home/bpadmin
```

8. Rename the bpi directory:

```
mv bpi bpi-<version>
```

Here, version recorded in step 5.

9. Remove the old bpi installer, if it exists:

```
rm bpi-<version>.sh
```

Here, version recorded in step 5.

10. Extract the latest bpi version, which is transferred to **/home/bpadmin/** directory

```
bash bpi-23.08-xx.sh
```

The extraction creates the bpi directory for the latest bpi version.

## Disabling Geographical Redundancy Configuration

To prepare for BPUAA upgrade, you need to disable geographical redundancy (GR) between site A (active) and site B (standby).

Use this procedure to disable GR. This procedure includes following tasks:

- Removing the standby configuration from site A (active)
- Removing the active configuration from site B (standby)
- Disabling the tunnel between site A (active) and site B (standby)

### Steps

1. Log in to host 0 of site A (active) as bpadmin (*Do not use the site IP; use the IP address of host 0*).
2. Change the directory to **/home/bpadmin/bpi**

```
cd /home/bpadmin/bpi
```

3. Start disabling geographical redundancy by executing the below command –

```
nohup ./bpi --remove-geored <siteB_IP_address> --playbook-args='-e geo_user=<user> -e geo_password=<password>' &
```

4. Fetch a valid token from tron by executing the below command (*make sure to execute the whole command in one line*) –

```
curl -sSk -X POST https://<siteA_IP_address>/tron/api/v1/tokens -d 'username=<username>&password=<password>' | python -m json.tool
```

### Example

```
curl -sSk -X POST https://localhost/tron/api/v1/tokens -d 'username=admin&password=adminpw' | python -m json.tool
```

Record the token value. The token value is 825697e4c6475d0887e1 in the following example.

```
{
 "createdTime": "2021.12-24T05:47:27Z",
 "failedLoginAttempts": 0,
 "inactiveExpirationTime": null,
 "isSuccessful": true,
 "lastSuccessIpAddress": "172.16.0.1",
 "lastSuccessLogin": "2021.12-24 05:45:00+00:00",
 "loginDetail": {
 "ipAddress": "172.16.0.1",
 "sessionId": "ccd8879c-4264-4606-bb80-49e210c5c5fe",
 "sessionType": "Machine",
 "time": "2021.12-24T05:47:27Z",
 "userAgent": "curl/7.29.0"
 },
 "timeout": 86400,
 "token": "825697e4c6475d0887e1",
 "user": "7a9ca679-59f3-4c6e-a31f-1a505cf7218a",
 "userTenantUuid": "056c8d72-2e14-49e5-85c7-5e65ec086567"
}
```



5. Verify the configured remote site from site A (active) –

```
curl -sSk -X GET -H 'Authorization: Bearer <token>'
https://<siteA_IP_address>/geored/site/remotes | python -m json.tool
```

**Example**

```
curl -sSk -X GET -H 'Authorization: Bearer 825697e4c6475d0887e1'
https://10.186.32.187/geored/site/remotes?site_id=Chennai | python -m json.tool
```

The system provides the configured remote site and other information.

```
{
 "message": "Listing all currently configured sites",
 "remote_sites": null,
 "success": true
}
```

6. remote\_sites from the above command should be reported as null as show in the system response as shown in the above example. If site B is listed under remote\_sites, execute the following command to remove it from site A configuration –

```
curl -sSk -X DELETE -H 'Authorization: Bearer <token>'https://<siteA_IP_address>/geored/site/remotes?site_id=<remote_site_id>
```

7. Repeat step 5 to verify the configured remote site again. If the response is null, proceed to Activating site B (standby).

## Activating Site B (standby) Optional

Before you activate site B (standby), ensure you complete the following procedure: Disabling geographical redundancy configuration.

### Steps

To activate site B (standby) using Blue Planet UI, use the following

1. Open your web browser and access the geographical redundancy window for site B (standby) by entering the following:

<https://<siteB IP address>/bp-platform-ui/#/geored-ui>

2. When the dialog box displays, perform the following steps:
  - a. Enter your username and password.
  - b. Click Sign in. The Geographical Redundancy window displays.
  - c. Verify that site B (standby) is the only site listed as standby.
  - d. Click the checkbox next to the site B (standby).
  - e. Click Activate.
3. Wait for site B (standby) to become fully active. This activation can take a few minutes to complete, as the process activates all applications.
4. Use Nagios to monitor the system applications on site B (standby). Wait for the status of all services to display OK (green)
  - a. Open your browser and go to Nagios by entering: <https://<siteB IP address>/nagios>.
  - b. Enter the Nagios username and password. The system displays the Nagios window. The Nagios dashboard displays the container status and status information.
  - c. Navigate to Current Status from the list on the left and select Services.
  - d. Wait for the status of all services to display OK (green).
  - e. When the status of all services displays OK (green), login to the Blue Planet UI to verify that all data exists, and all applications work as expected.

# Preparing Hosts for Upgrade (on site A)

This section provides information to prepare the hosts for performing upgrade. To prepare the hosts for upgrade, you need to perform the following procedures:

- [Updating the hosts file](#)
- [Modifying the volume group name \(Optional\)](#)
- [Updating configured parameters](#)
- [Setting up users on site A \(Active\)](#)
- [Modifying system logging path \(Optional\)](#)
- [Updating Site Configuration](#)

## Updating the Hosts File

Perform the following procedure to update the hosts file parameters as per the existing, pre-upgrade UAA setup.

### Requirements

Before you update the hosts file, ensure you complete the following procedure: [Transferring the installation files to host](#).

### Steps

1. Log in to host 0 as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to the **/home/bpadmin/bpi** directory.
3. Update the host or hosts in the hosts file as per the existing pre-upgrade setup. Get the hosts file:

```
get-hosts-config
```

Example system output:

```
[bpadmin@bp-prod-test-1 bpi]$ get-hosts-config
```

| Host | Ip            | Interface | sched_labels    |
|------|---------------|-----------|-----------------|
| 0    | 10.186.32.101 | ens192    | controller=True |
| 1    | 10.186.33.14  | ens192    | controller=True |
| 2    | 10.186.32.108 | ens192    | controller=True |

```
[bpadmin@bp-prod-test-1 bpi]$
```

4. Update `site_ip` parameter in the hosts file as per the existing pre-upgrade setup. Get the site IP details:

```
get-site-ip
```

5. Update `site_name` parameter in the hosts file, if it's defined on the existing pre-upgrade setup. Get the site name details:

```
get-site-name
```

## Modifying the Volume Group Name (Optional)

Blue Planet recommends using unique names for volume group that can be recognized and avoid name conflicts across multiple virtual groups.

Complete this procedure to modify the volume group name where the unallocated physical extents space is left free for BPUAA to create and configure the Docker thin pool. This procedure is needed if you want to change the default values.

Before you begin, verify that you know the name of the volume group where the unallocated physical extents space is available for BPUAA to create and configure the Docker thin pool.

**NOTE** | You can use the Linux `vgdisplay` command to display volume group information.

To modify the volume group name

1. Log in to host 0 as `bpadmin` and navigate to the `/home/bpadmin/bpi/playbooks/group_vars` directory.
2. Using a text editor, open the `all.yml` file.
3. Uncomment and set the `vgdockerpool` to the name of your volume group.

```
#bpdockerdevs: /dev/xvdb
#vgdockerpool: blueplanet
```

Example *after* the edit with `vgdockerpool` set to `my_vgname`.

```
#bpdockerdevs: /dev/xvdb
vgdockerpool: my_vgname
```

4. Save the `all.yml` file.

## Updating Configured Parameters

Perform the following procedure to configure the parameters of a site. These parameters are defined in the file: `/home/bpadmin/bpi/playbooks/group_vars/all.yml`.

### Requirements

Before you start updating the configured parameters, ensure you complete the following procedures:

- Renaming the `bpi` directory
- Updating the `hosts` file

### Steps

1. Log in to host 0 as `bpadmin`. Do not use the site IP; use the IP address of host 0.
2. Navigate to the `/home/bpadmin/bpi/playbooks/group_vars`.
3. Record the `ilannet` configured value:

```
get-ilannet
```

Example system output:

```
[bpadmin@bp-prod-test-1 group_vars]$
get-ilannet 172.28.0.0/16/24
[bpadmin@bp-prod-test-1 group_vars]$
```

4. Record the `siteld` and `siteState` configured values

```
cat /etc/bp2/geored/config.json | python -m json.tool
```

5. Open the **all.yml** file with a text editor and perform the following:
  - a. Uncomment the following line and replace a.b.c.d with your license server IP address, for example:

```
#license_server:a.b.c.d

license_server:10.10.10.10
```

**NOTE** | IP address that is, 10.10.10.10 can be onxv0288.ott.ciena.com or license server IP address of the customer.

- b. Enter the `ilannet` configured value recorded in step 3.

```
ilannet: 172.28.0.0/16/24
```

- c. Enter the `geored_site_id` value, recorded as the `siteld` configured value in

```
geored_site_id: siteA
```

- d. Enter the `geored_site_state` value, recorded as the `siteState` configured

```
geored_site_state: ACTIVE
```

**NOTE** | Setting the parameter to false requires more disk space but provides more flexibility to encounter the problems. Setting the parameter to true does not require additional disk space but limits the data recovery options. Do not set `bp_upgrade_host_volume_move` value in site B (standby).

- e. Save the file and exit.

## Setting Up Users (Site A)

This procedure performs the following tasks:

- Manages keys of the `bpadmin` user
- Manages keys of the root user
- Creates the `bpuser` (sudo-restricted Docker install user) and manages the `bpuser` sudo permissions and keys. The setup script skips this step, if the `bpuser` is already created.

### Requirements

Before setting up the users, ensure you complete the following:

- Know the `bpadmin` user password
- Know the `bpuser` password, which is provided to the `bpuser`

### Steps

1. Log in to host 0 as `bpadmin`. Do not use the site IP; use the IP address of host 0.
2. Navigate to the **/home/bpadmin/bpi** directory.
3. Start the `setup-users` script:

```
./bpi --setup-users
```

4. Enter the `bpadmin` user password, *if needed*.
5. Enter the `bpuser` user password, *if needed*.

## Modifying System Logging Path (Optional)

By default, the path to the system logging (syslog) file for the Blue Planet UAA applications is **/var/log/ciena/blueplanet.log**. If you want to modify this path, perform the following optional procedure: To keep current release logs separate, this procedure can be followed.

### Steps

1. Log in to host 0 as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to directory **/home/bpadmin/bpi/playbooks/group\_vars**.
3. Update the **all.yml** file located at **/home/bpadmin/bpi/playbooks/group\_vars/** by removing the commenting and editing the bp\_log\_file option.

Here is an example before the edit:

```
Logging
BluePlanet apps log file location
'/var/log/syslog' is an invalid choice for RedHat/Oracle Linux/CentOS systems
'/var/log/messages' is an invalid choice for Ubuntu systems
bp_log_dir: /var/log/Ciena
#bp_log_file: "{{ bp_log_dir }}/blueplanet.log"
```

Here is an example after the edit:

```
Logging
BluePlanet apps log file location
'/var/log/syslog' is an invalid choice for RedHat/Oracle Linux/CentOS systems
'/var/log/messages' is an invalid choice for Ubuntu systems
bp_log_dir: /var/log/Ciena
#bp_log_file: "{{ bp_log_dir }}/bp_syslog.log"
```

4. Save the **all.yml** file and exit the text editor.
5. To enable changes, navigate to directory **/home/bpadmin/bpi**:

```
nohup ./bpi --site lineupfile --playbook-args='--tags logging' &
```

## Updating Site Configurations

This procedure describes how to install the Ciena Linux system bundle, PostgreSQL and license files update on an existing, pre-upgraded setup.

### Requirements

Before you start to install the Ciena Linux system bundle, complete the following procedures:

- Downloading the UAA software installation files
- Transferring software installation files
- Updating the hosts file
- Setting up users on site A
- Modifying system logging path (Optional)

### Steps

1. Log in to host 0 as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to **/opt/ciena/loads/23.08/**.
3. Ensure that the LinuxIntel\_2023\_xx\_x.tar Ciena Linux bundle tar file is available in the **/opt/ciena/loads/23.08/** directory:

```
ls -lrt LinuxIntel_2023_xx_x.tar
```

4. Change the directory to /home/bpadmin/bpi:

```
cd /home/bpadmin/bpi
```

5. Select the appropriate lineup file for your deployment, lineup file to update the Ciena Linux bundle:

```
nohup ./bpi --site /opt/ciena/loads/23.08/lineupfile &
```

If you are provisioning your own NTP timing, add the following playbook arguments by executing command (on single line) -

```
nohup ./bpi --site <lineup file> --playbook-args='--skip-tags ntp --limit standby_cluster' &
```

6. Verify the cienabundle.<DATE>.<TIME>.log located in /var/opt/ciena/logs/ directory to ensure that no errors occurred in host or hosts during the Linux bundle installation.
7. Verify the Ciena Linux bundle is updated on all hosts:

```
sudo su -
```

```
bpssh checkOSversion
```

#### Example system output:

```
[bpadmin@bp-prod-test-1 ~]$ sudo su -
Last login: Thu Feb 13 11:41:57 UTC 2020 on pts/0
[root@bpprodtest-1 ~]# bpssh checkOSversion host-0 ec: 0
Base Operating System Version: Red Hat Enterprise Linux Server release 7.9 (Maipo)
 Oracle Linux Server release 7.9 64-bit
Operating System Bundle: 2020.35.0
host-1 ec: 0
Base Operating System Version: Red Hat Enterprise Linux Server release 7.9 (Maipo)
 Oracle Linux Server release 7.9 64-bit
Operating System Bundle: 2020.35.0
host-2 ec: 0
Base Operating System Version: Red Hat Enterprise Linux Server release 7.9 (Maipo)
 Oracle Linux Server release 7.9 64-bit
Operating System Bundle: 2020.35.0
```

8. Verify chetak config file:

```
sudo su -

bpssh ls /etc/bp2/postgres/private/users.json

bpssh ls /etc/bp2/uaa-core-db/private/users.json

bpssh ls /etc/bp2/uaa-pm-db/private/users.json

bpssh ls /etc/bp2/uaa-graph-db/private/users.json
```

Example system output:

```
root@bp-prod-test-1:~# bpssh ls /etc/bp2/postgres/private/users.json
host-0 ec: 0
/etc/bp2/postgres/private/users.json
host-1 ec: 0
/etc/bp2/postgres/private/users.json
host-2 ec: 0
/etc/bp2/postgres/private/users.json
```

9. Verify license server configuration. It must have the same server defined earlier.

```
sudo su -

bpssh cat /etc/bp2/solutionmanager/nbis.d/licsvr.yaml
```

Example system output:

```
root@bp-prod-test-1:~# bpssh cat
/etc/bp2/solutionmanager/nbis.d/licsvr.yaml
host-0 ec: 0
url: https://onxv0288.ott.ciena.com:7071
ip: onxv0288.ott.ciena.com
port: 7071
publish: true
Created by bpi --site
host-1 ec: 0
url: https://onxv0288.ott.ciena.com:7071
ip: onxv0288.ott.ciena.com
port: 7071
publish: true
Created by bpi --site
host-2 ec: 0
url: https://onxv0288.ott.ciena.com:7071
ip: onxv0288.ott.ciena.com
port: 7071
publish: true
Created by bpi --site
```



# Upgrading BPUAA Platform and Solution on Site A (Active)

The following table shows different BPUAA install options and the corresponding lineup files available –

| BPUAA SOLUTION                  | LINEUP FILE NAME (SINGLE HOST) | LINEUP FILE NAME (MULTI HOST) |
|---------------------------------|--------------------------------|-------------------------------|
| Unified Assurance and Analytics | lineup-uaa-single-rhel.yml     | lineup-uaa-multi-rhel.yml     |

- **lineup-uaa-single-rhel.yml:** This lineup file is meant to install only UAA without integrators on a single host machine.
- **lineup-uaa-multi-rhel.yml:** This lineup file is meant to install only UAA without integrators on a multi host machine.

## NOTE

Make sure **/opt/ciena/loads/** have enough free space (Recommended 60GB).  
Make sure LinuxIntel bundle, bp installer and latest bpuaa tar files are in the same location (host 0).

1. Log in to host 0 as bpadmin and navigate to the **/home/bpadmin/bpi** directory.
2. Execute the following command to audit solution (change the lineup file as per the requirement)

```
nohup ./bpi --upgrade-audit /opt/ciena/loads/23.08/lineupfile &
```

Verify the upgrade audit summary is accurate – new solution(s) and app(s) to be upgraded, etc.

3. Execute the following command to upgrade the desired solution (change the lineup file as per the requirement) –

```
nohup ./bpi --upgrade-execute /opt/ciena/loads/23.08/lineupfile &
```

Verify the system is in the desired state: new apps are deployed, deprecated apps are undeployed and non-upgraded apps are unaffected.

This step is service affecting. UAA will not be available during this step.

4. Open your browser and navigate to Nagios by entering the following:

<https://<site IP address>/nagios>

- a. Enter the host username and password. Nagios displays the current network, host, and service status.
- b. Navigate to **Current Status** from the list on the left and select **Services**.
- c. Wait for the status of all services to display OK (green).
- d. If any service displays WARNING, UNKNOWN, PENDING, or CRITICAL as a status, then resolve the issue before proceeding further.

5. If upgrading from earlier versions of UAA (22.12, 23.04), and observe the below mentioned critical error in the environment under UAA-SBC container:

```
Failed to create policies: check-policies-failed - Exception while creating policies not able to get the response for policies api, Exit code 1
```

Follow the below steps to overcome the error:

- a. Login to host 0 as root user.
- b. Execute the following commands to restart the uaa-sbc container –  

```
sudo solman
solution_app_restart artifactory.ciena.com.blueplanet.uaa_collector:ha-23.08.xx uaa-sbc
```

6. If upgrading from earlier versions of 23.08, restart tron container under XP solution.

Execute the following command:

```
solution_app_restart artifactory.ciena.com.blueplanet.xp:ha_23.08.xx tron
```

7. If proxy is being used for RA downloads from bphub, restore the noted content to file **"/etc/yum.conf"** in all **uaa-core instances** which contains proxy configuration. Follow the instructions provided in **Proxy Setup to Access Bphub** (Under *UAA Administration* section) In the **UAA Administration Guide**.
8. Verify all data after the upgrade, by logging into UAA application. If you find any issues, follow the **Restoring a site backup using the bpi utility on geo-redundancy setup** section (*Under System Backups > Backing up and restoring software*) in the **UAA Administration Guide** to restore the software to its previously working condition.
9. Execute the following command to commit the desired solution (change the lineup file as per the requirement)

**NOTE**

Once the commit is done, the system **cannot be restored**. Make sure that the upgrade was completely successful before proceeding.

```
nohup ./bpi --upgrade-commit /opt/ciena/loads/23.08/<lineup file> &
```

10. Proceed to [Upgrading site B and setting up geographical redundancy](#).

# Upgrading site B and setting up geographical redundancy (Automatic Procedure)

This section describes how to upgrade site B (standby) and set up a post-upgrade geographical redundancy (GR) between site A and site B.

To upgrade site B (standby) and set up a post-upgrade GR between site A and site B, you need to perform the following procedures -

- [Preparing site B \(standby\) for upgrade](#)
- [Installing core platform and platform solution for BPUAA on site B \(standby\)](#)
- [Connecting site A and site B for geographical redundancy](#)

## Preparing Site B (standby) for Upgrade

This section provides a procedure to prepare site B (standby) for upgrade. You need to perform the following procedures -

- [Getting site B information for upgrade](#)
- [Updating hosts file on site A \(Active\)](#)
- [Setting up users of site B \(standby\)](#)
- [Purging solutions from site B \(standby\) on pre-upgrade BPUAA](#)
- [Updating Site Configurations on Site B \(standby\)](#)

Before you prepare site B (standby) for upgrade, ensure you complete following procedures on site A.

- [Downloading the BPUAA software installation files](#)
- [Transferring software installation files](#)

## Getting Site B Information for upgrade

1. Log in to host 0 of site B (Standby) as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Get the server details of standby site and save it for later use.

```
get-hosts-config
```

### Example

```
bpadmin@bp-prod-test-1 bpi]$ get-hosts-config
host ip interface sched_labels
---- -
0 10.186.33.14 ens192 controller=True
1 10.186.32.108 ens192 controller=True
2 10.186.32.101 ens192 controller=True
bpadmin@bp-prod-test-1 bpi]$
```

3. Record the siteId and siteState configured values

```
cat /etc/bp2/geored/config.json | python -m json.tool
```

### Example

```
[bpadmin@bp-prod-test-1 group_vars]$ cat /etc/bp2/geored/config.json | python -m
json.tool
{
 "Address": "10.186.35.16",
 "siteId": "siteB", "siteState": "STANDBY"
}
[bpadmin@bp-prod-test-1 group_vars]$
```

In above example, the siteId configured value is siteB and siteState configured value is STANDBY.

4. Get the ilannet information of standby site and save it for later use.

```
get-ilannet
```

## Updating Hosts File on Site A (active)

1. Log in to host 0 of site A (Active) as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to /bpi/playbooks/group\_vars and modify standby\_cluster file.
3. Add ilannet information and site B information for upgrade section. geored\_site\_state must be STANDBY

```
Ilannet: 172.XX.XX.XX/XX/XX
geored_site_id: SiteB
geored_site_state: STANDBY
```

4. Navigate to the /home/bpadmin/bpi directory.
5. Copy hosts.gr file to hosts file enter.

```
cp -p hosts.gr hosts
```

6. Open the hosts file with a text editor, add Site A (Active) hosts IP, site IP and Site B (Standby) hosts IP, site IP.

Following is an example of hosts file of multi-host setup on host0 of site A

```

#
Lists the set of nodes that make up the cluster
The value of ansible_host should be an IP address
#
The controller label dictates what components (core platform/platform solutions) are to be deployed on a node
To set a host as a Controller node, either do not set the label (default), or set label "controller=True"
To set a host as a Non-Controller node, set label "controller=False"
#
To deploy one or more solutions on an isolated host (host segregation), set the host as a Non-Controller node,
set label "controller=False", add a solution label and provide a comma separated list of solution names.
e.g. "host3 ansible_host=a.b.c.d controller=False solution=<solution name 1>,<solution name 2>"
#
[cluster]
host0 ansible_host=10.107.3.7 controller=True
host1 ansible_host=10.107.3.27 controller=True
host2 ansible_host=10.107.3.44 controller=True
#host3 ansible_host=a.b.c.d controller=False
#host4 ansible_host=a.b.c.d controller=False

[cluster:vars]
If uncommented, the Site IP address will be set via the set-site-ip command
Format is IP Address/CIDR mask - e.g. 1.1.1.1/22
site_ip=10.107.3.15/26

If uncommented, the Site Name will be set via the set-site-name command
Valid characters for site_name are letters, numbers and dashes.
site_name=SiteA

Required for ubuntu 16.04, when python 2.x is not installed
#ansible_python_interpreter=/usr/bin/python3

[standby_cluster]
standby_host0 ansible_host=10.107.3.31 controller=True
standby_host1 ansible_host=10.107.3.17 controller=True
standby_host2 ansible_host=10.107.3.62 controller=True
##standby_host3 ansible_host=a.b.c.d controller=False
##standby_host4 ansible_host=a.b.c.d controller=False
##
[standby_cluster:vars]
If uncommented, the Site IP address will be set via the set-site-ip command
Format is IP Address/CIDR mask - e.g. 1.1.1.1/22
site_ip=10.107.3.38/26
##
If uncommented, the Site Name will be set via the set-site-name command
Valid characters for site_name are letters, numbers and dashes.
site_name=SiteB

```

## Setting Up Users of Site B (standby)

This procedure performs the following tasks -

- Manages keys of the bpadmin user
- Manage keys of the root user
- Creates the bpuser (sudo-restricted Docker install user) manage the bpuser sudo permissions and keys. The setup script skips this step, if the bpuser is already created.
- Creates the bpmaint user which manages the bpmaint sudo permissions and keys. The setup script skips this step, if the bpmaint is already created.

Before setting up the users, ensure you complete the following -

- Perform the Updating the hosts file on site A (Active) procedure
- Know the bpadmin user password
- Know the bpuser password, which is provided to the bpuser

## Steps

1. Log in to host 0 of siteA(Active) as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to the /home/bpadmin/bpi directory.
3. Start the setup-users script

```
./bpi --setup-users
```

4. Enter the bpadmin user password, if needed.
5. Enter the bpuser user password, if needed.

You will purge solutions from site B (standby) in the next procedure.

## Purging solutions from Site B (standby) on Pre-upgrade BPUAA

Before you purge the solutions from site B (standby), ensure you complete following procedure: Setting up users of site B (standby).

### Steps

1. Log in to host 0 of site A as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to /home/bpadmin/bpi.
3. To purge solutions

```
nohup ./bpi --utility playbooks/solution-undeploypurge.yml --playbook-args='--limit standby_cluster' &
```

This raises a query to the solution manager for all running solutions to purge solutions from the site and to remove related images and host volumes.

## Updating Site Configurations on Site B (standby)

Before you start to install the Ciena Linux system bundle, complete the following procedures:

- Getting site B information for upgrade
- Updating the hosts file on site A (Active)
- Setting up users on site B (standby)
- Purging solutions from site B (standby) on pre-upgrade BPUAA

### Steps

To update site configurations on site B (standby):

1. Log in to host 0 of site A (Active) as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Change the directory to /home/bpadmin/bpi

```
cd /home/bpadmin/bpi
```

3. Select the appropriate lineup file for your deployment, lineup file to update the Ciena Linux bundle (*make sure to enter the whole command in one line*)

```
nohup ./bpi --site /opt/ciena/loads/23.08/<lineup file> --playbook-args='--limit standby_cluster' &
```

If you are provisioning your own NTP timing, add the following playbook arguments by executing command (on single line) -

```
nohup ./bpi --site /opt/ciena/loads/23.08/<lineup file> --playbook-args='--skip-tags ntp --limit standby_cluster' &
```

4. Verify the cienabundle.<DATE>.<TIME>.log located in /var/opt/ciena/logs/ directory to ensure that no errors occurred in host or hosts during the Linux bundle installation
5. Copy credential files content of postgres,uaa-core-db,uaa-pm-db and uaa-graph-db in active site and replace credential files in standby site. Make sure credentials file must match in all hosts (active and standby), respective directories need to create (if not present).
  - a. /etc/bp2/postgres/private/users.json
  - b. /etc/bp2/uaa-core-db/private/users.json
  - c. /etc/bp2/uaa-pm-db/private/users.json
  - d. /etc/bp2/uaa-graph-db/private/users.json
6. Verify the Ciena Linux bundle is updated on all hosts of Site B. Login host0 of site B then run below commands -

```
sudo su -
```

```
bpssh checkOSversion
```

#### Example

```
[bpadmin@bp-prod-test-1 ~]$ sudo su -
Last login: Thu Feb 13 11:41:57 UTC 2020 on pts/0
[root@bpprodtest-1 ~]# bpssh checkOSversion host-0 ec: 0

Base Operating System Version: Red Hat Enterprise Linux Server release 7.6 (Maipo) Oracle Linux Server release 7.6 64-bit
Operating System Bundle: 2020.35.0
host-1 ec: 0
Base Operating System Version: Red Hat Enterprise Linux Server release 7.6 (Maipo) Oracle Linux Server release 7.6 64-bit
host-2 ec: 0
Base Operating System Version: Red Hat Enterprise Linux Server release 7.6 (Maipo) Oracle Linux Server release 7.6 64-bit
Operating System Bundle: 2020.35.0
[root@bp-prod-test-1 ~]#
```

7. Verify license server configuration of site B. It must have the same server defined earlier. Login host 0 of site B, then run below commands –

```
sudo su -
```

```
bpssh cat /etc/bp2/solutionmanager/nbis.d/licsvr.yaml
```

#### Example

```
root@bp-prod-test-1:~# bpssh cat /etc/bp2/solutionmanager/nbis.d/licsvr.yaml host-0 ec: 0
url: https://onxv0288.ott.ciena.com:7071 ip: onxv0288.ott.ciena.com
port: 7071
publish: true
Created by bpi --site
host-1 ec: 0
url: https://onxv0288.ott.ciena.com:7071 ip: onxv0288.ott.ciena.com
port: 7071
publish: true
Created by bpi --site
host-2 ec: 0
url: https://onxv0288.ott.ciena.com:7071 ip: onxv0288.ott.ciena.com
port: 7071
publish: true
Created by bpi --site
```

8. If no error is reported, reboot all standby hosts.

# Installing Core Platform and Platform Solution for BPUAA 23.08 on Site B (standby)

Before you install the core platform and platform solution, ensure you complete the following procedure: Preparing site B (standby) for upgrade.

## Steps

1. Log in to host 0 of site A (Active) as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to the /home/bpadmin/bpi directory
3. Install the core platform and extended-platform solution for BPUAA 23.08 on site B (standby) –

```
nohup ./bpi --install <lineup file> --playbook-args='--limit standby_cluster --skip-tags bp2-solution' &
```

## Connecting Site A and Site B for Geographical Redundancy (automatic procedure)

Before you connect site A and site B for geographical redundancy, ensure you complete the following procedure -

- Complete Installing core platform and platform solution for BPUAA 23.08 on site B (standby) procedure.
- Have the bpadmin user password.
- Can access the /home/bpadmin/bpi directory of host 0 of active site as the bpadmin user.

## Steps

1. Log in to host 0 of site A (active) as bpadmin. Do not use the site IP; use the IP address of host 0.
2. Navigate to the /home/bpadmin/bpi.
3. Start automatically geographical redundant configuration setup between active and standby sites by executing command (on single line) –

For OS hardened servers

```
nohup ./bpi --geo-keys <standby_siteIp> --playbook-args="--limit cluster" &

nohup ./bpi --autoinstall-geo <lineup file> --playbook-args='--skip-tags geowhitelist --skip-tags active-install -e geo_user=admin -e geo_password=adminpw' &
```

For Non-OS hardened servers


```
nohup ./bpi --autoinstall-geo <lineup file> --playbook-args='--skip-tags active-install -e geo_user=admin -e geo_password=adminpw'&
```

4. Execute below script to copy bpi directory to host 0 of standby site which enable standby site to keep its original bpi configuration for example hosts file and all.yml file


```
./setup-bpi-standby.sh
```

5. On the active host UI, select **System > Security > Geographical redundancy** to verify that the active and standby sites are visible and connected to the tunnel.
6. On the active host UI, select **System > Platform > Swaggar UI**.
7. Click Geographic Redundancy on the left panel.






8. On the right pane, expand POST /geored/credentials API.
9. Click **Try it out**.



The JSON data in the API body section becomes editable.



10. Enter the following data for the active site:

|               |                                                                                                             |
|---------------|-------------------------------------------------------------------------------------------------------------|
| where         |                                                                                                             |
| <SiteA_IP> is | is the site IP address of the active site.                                                                  |
| <user>        | Put the username that is used to login active site host to perform GR installation command.                 |
| <password>    | Put the password of the username that is used to login active site host to perform GR installation command. |

11. Click **Execute**.

Name

Description

**body** ★ required

The credentials to be added.

(body)

Edit Value | Model

```
{
 "data": {
 "ip": "<active site IP>",
 "username": "user1",
 "password": "userpw"
 }
}
```

Cancel

Parameter content type

application/json

Execute

12. Enter the data for the standby site:

|               |                                                                                                             |
|---------------|-------------------------------------------------------------------------------------------------------------|
| where         |                                                                                                             |
| <SiteA_IP> is | is the site IP address of the active site.                                                                  |
| <user>        | Put the username that is used to login active site host to perform GR installation command.                 |
| <password>    | Put the password of the username that is used to login active site host to perform GR installation command. |

13. Click **Execute**.

The screenshot shows a web interface for executing a command. It consists of a large text area for input, a 'Cancel' button, a 'Parameter content type' dropdown menu, and an 'Execute' button.

```
{
 "data": {
 "ip": "<standby site IP>",
 "username": "user1",
 "password": "userpw"
 }
}
```

Cancel

Parameter content type

application/json

Execute

# Logstash Configuration

**NOTE** | This step must be performed only once after upgrading to 23.08 and Logstash version is 8.x

Logstash package upgrade from v7 to v8, Elastic Common Schema (ECS) compatibility mode is enabled by default on v8. The availability of **host** field in the event input is changed accordingly. This field is required for Resource Adapter Log Translator.

The user must check whether the Logstash version is 8.x.

## Steps:

To check the Logstash Version

1. Login to `uaa-logstash` container (if it is HA instance login to all the `uaa-logstash` containers)
2. Type the below command.

```
versionroot@uaa-logstash:/bp2/src# logstash/bin/logstash --version
Using system java: /usr/bin/java
```

If the Logstash is for example:

```
logstash 8.6.2
```

3. To add host field in the input by taking from the fields available as per ECS compatibility mode. The following configuration must be added as a part of filter configuration in `/bp2/data/logstash-conf.conf` file.

```
v7 to v8 upgrade: ecs_compatibility mode is enabled by default on v8 and the
availability of 'host' field in the event input got changed.
Added 'host' field in the event input by taking it from the fields available
as per ECS compatibility mode. # TCP plugin input
if [@metadata][input][tcp][source] and ![host] {
 mutate {
 copy => {
 "[@metadata][input][tcp][source][name]" => "[host]"
 }
 }
}
UDP plugin input
if [host][ip] {
 mutate {
 copy => {
 "[host][ip]" => "[host]"
 }
 }
}
```

**NOTE** | Follow the **Example of complete Logstash Configuration File** provided below to paste the above content in the filter plugin {}.

4. Restart the Logstash container.

```
solution_app_restart artifactory.ciena.com.blueplanet.uaa_collector:23.08.XX uaa-
logstash
```

### Example of complete Logstash Configuration File:

```
#The changes to this configuration file should be copied to all the instances of
uaa-logstash container in case of HA
input {
 beats {
 port => 5044
 }
 tcp {
 port => 5514
 type => syslog
 }
 udp {
 port => 5514
 type => syslog
 #codec => plain {
 # charset => "ISO-8859-1"
 # }
 }
}
filter {
 # Spec handling of " characters in logs. Standard escape is stripped
 somewhere on the way to vsure
 # Msg shows logstash log like this "message txt \"quoted strng\" more
 message txt" (logstash log)
 # But in vsure log translator it is "message txt "quoted strng" more
 message txt" (med debug log)
 # So the mutate is required to make it "message txt \\\"quoted strng\\\" more
 message txt"
 # Not sure why, but when mutate is used, actually see \\\"quoted
 string\\\" in logstash log.
 # This ends up in med debug log as the desired \"quoted string\"
 mutate {
 gsub => ["message","\\"", "\\\""]
 }
 # v7 to v8 upgrade(BPUAA-17170): ecs_compatibility mode is enabled by
 default on v8 and the availability of 'host' field in the event input got
 changed.
 # Added 'host' field in the event input by taking it from the fields available
 as per ECS compatibility mode. # TCP plugin input
 if [@metadata][input][tcp][source] and ![host] {
 mutate {
 copy => {
 "[@metadata][input][tcp][source][name]" => "[host]"
 }
 }
 }
 # UDP plugin input
 if [host][ip] {
 mutate {
 copy => {
 "[host][ip]" => "[host]"
 }
 }
 }
}
output {
 file {
 path => "/bp2/log/logstash-plain.log"
 codec => rubydebug {
 metadata => true
 }
 }
 kafka {
 topic_id => "com.ciena.bp.uaa.logEvents"
 bootstrap_servers => "kafka.docker:9092"
 codec => line { format => "{\"message\": \"#{message}\", \"ipaddress\": \"#{host}\"}" }
 }
}
```

#### NOTE

After the above steps are performed user needs to run the steps for the [Backup and Restore of UAA PM DB](#).

---

# Creating a New Standby Site for Geographical Redundancy

After activating a Standby site during a geographical redundancy (GR) failover, use this procedure to create a new Standby site for GR (not the former Active site, referred to in the Activating a Standby site for a geographical redundancy failover procedure).

If you want to reuse the former Active site, then go to the Restoring the former Active site as the new Standby site.

## Cleaning up Old Georedundancy Settings

1. Clean up tunnel configuration on the new Active site, run the following command on host0 of new active site as a **badmin** user –

```
nohup ./bpi --utility playbooks/geo-clean.yml &
```

2. Clean up geored configuration files –
  - a. Delete contents of the `/etc/bp2/site/bpfirewall.conf` file on the new active site –

```
sudo bpssh "sudo truncate -s 0 /etc/bp2/site/bpfirewall.conf"
```

- b. Delete the `/etc/ipsec.d/GeoRed-*.conf` files on all hosts of the new active site –

```
sudo bpssh "rm -f /etc/ipsec.d/GeoRed-*.conf"
```

To set up a new Standby site, complete the following procedures available in the Blue Planet UAA Installation Guide.

- Creating the badmin user
- Configuring the Security-Enhanced Linux mode and disabling firewalld
- Downloading and installing the Ciena Linux system bundle
- Downloading software files for UAA installation

After the above procedures are completed, follow the below mentioned procedures to complete setting up the Standby site from the Active site –

- [Updating hosts file](#)
- [Modifying the volume group name](#)
- [Configuring a time source](#)
- [Configuring geographical redundancy](#)
- [Configuring the Blue Planet email service](#)
- [Modifying the ILAN NET interface](#)
- [Modifying the default UAA interface](#)
- [Specifying the external license server](#)
- [Setting up users](#)
- [Validating the hosts](#)
- [Configuring UAA hosts on active and standby sites](#)
- [Installing Core Platform and Extended Platform Solution on active and standby sites](#)
- [Installing UAA and configuring georedundancy on active and standby sites \(automatic procedure\)](#)

## Updating Hosts File

1. Log in to Host 0 of Site A (active site) as bpadmin. Do not use the Site IP, use the IP address of the host 0.
2. Navigate to /home/bpadmin/bpi.
3. Add the standby section on hosts file –

```
StandBy Cluster Details
#
#Lists the set of nodes that make up the cluster
#The value of ansible_host should be an IP address
#
#The controller label dictates what components (core platform/platform solutions) are to
be deployed on a node
To set a host as a Controller node, either do not set the label (default), or set label
"controller=True"
To set a host as a Non-Controller node, set label "controller=False"
#
#To deploy one or more solutions on an isolated host (host segregation), set the host as a
Non-Controller node,
set label "controller=False", add a solution label and provide a comma separated list of
solution names.
e.g. "host3 ansible_host=a.b.c.d controller=False solution=<solution name 1>,<solution
name 2>"
#
#
[standby_cluster]
#standby_host0 ansible_host=a.b.c.d controller=True
#standby_host1 ansible_host=a.b.c.d controller=True
#standby_host2 ansible_host=a.b.c.d controller=True
#standby_host3 ansible_host=a.b.c.d controller=False
#standby_host4 ansible_host=a.b.c.d controller=False
#

[standby_cluster:vars]

If uncommented, the Site IP address will be set via the set-site-ip command
Format is IP Address/CIDR mask - e.g. 1.1.1.1/22
#site_ip=a.b.c.d/XX
#
#If uncommented, the Site Name will be set via the set-site-name command
Valid characters for site_name are letters, numbers and dashes.
#site_name=mysite
#
#Required for ubuntu 16.04, when python 2.x is not installed
#ansible_python_interpreter=/usr/bin/python3
```

The following shows a sample of active host 0 file after the multi-host edits of active and standby sites are made for an installation where the subnet mask is 22 (255.255.252.0).

```
[cluster]
host0 ansible_host=10.186.34.246 controller=True
host1 ansible_host=10.186.33.108 controller=True
host2 ansible_host=10.186.32.60 controller=True
#host3 ansible_host=a.b.c.d controller=False
#host4 ansible_host=a.b.c.d controller=False
[cluster:vars]
If uncommented, the Site IP address will be set via the set-site-ip command
Format is IP Address/CIDR mask - e.g. 1.1.1.1/22
site_ip=10.186.35.15/22
StandBy Cluster Details
##
[standby_cluster]
standby_host0 ansible_host=10.186.34.235 controller=True
standby_host1 ansible_host=10.186.32.44 controller=True
standby_host2 ansible_host=10.186.33.120 controller=True
#standby_host3 ansible_host=a.b.c.d controller=False
#standby_host4 ansible_host=a.b.c.d controller=False
#
[standby_cluster:vars]
If uncommented, the Site IP address will be set via the set-site-ip command
Format is IP Address/CIDR mask - e.g. 1.1.1.1/22
```

```

site_ip=10.186.35.16/22
#
#If uncommented, the Site Name will be set via the set-site-name command
Valid characters for site_name are letters, numbers and dashes.
site_name=BPSite2
#
#Required for ubuntu 16.04, when python 2.x is not installed
#ansible_python_interpreter=/usr/bin/python3

```

4. Save the hosts file.

## Modifying the Volume Group Name

Blue Planet recommends using unique names that can be recognized and avoid name conflicts across multiple virtual groups.

Complete the following steps to modify the volume group name where the unallocated physical extents space is left free for UAA to create and configure the Docker thin pool.

### NOTE

This is the first of six procedures requiring edits to the all.yml file of the active site and to the standby\_cluster file of the standby site.

These files are located in the /home/bpadmin/bpi/playbooks/group\_vars directory of host 0 of the active site. Most of the edits are as required by your specific network environment and UAA installation.

You might not need to complete many of them unless you want to change the default values.

Remaining procedures include Configuring a time source, Configuring geographical redundancy, Configuring the Blue Planet email service, Modifying the ILAN NET interface, and Modifying the default UAA interface.

Before you begin, verify that you -

1. Know the name of the volume group where the unallocated physical extents (PE) space is available for UAA to create and configure the Docker thin pool.

### NOTE

You can use the Linux vgdisplay command to display volume group information.

To modify the volume group name -

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP; use the IP address of the host 0) and navigate to the /home/bpadmin/bpi/playbooks/group\_vars directory.
2. Using a text editor, open the standby\_cluster file.
3. Uncomment and set the vgdockerpool to the name of your volume group. Save the standby\_cluster file.

Example **before** the edit -

```

#bpdockerdevs: /dev/xvdb
#vgdockerpool: blueplanet

```

Example **after** the edit with vgdockerpool set to my\_vgname -

```

#bpdockerdevs: /dev/xvdb
vgdockerpool: my_vgname

```



## Configuring a Time Source

UAA hosts can use a local or remote time source. For example -

- In environments where an enterprise NTP source is available, you can configure the UAA hosts as NTP clients of the enterprise NTP host.
- If UAA hosts have internet access, you can use public NTP servers as the UAA timing source.
- If no enterprise NTP host is available and UAA hosts do not have internet access, you can configure one of the UAA VMs to act as an NTP server. See your operating system documentation for more information.

### NOTE

Configure NTP in accordance with your site timeserver infrastructure. The Blue Planet installer can apply a simple configuration with one, three, or four timeservers. If NTP is already configured on UAA host, skip this procedure.

By default, the UAA installer sets up four NTP servers –

```
ntp_servers_default:
- 0.rhel.pool.ntp.org
- 1.rhel.pool.ntp.org
- 2.rhel.pool.ntp.org
- 3.rhel.pool.ntp.org
```

While you can specify your own NTP servers, or use fewer servers, Ciena recommends that you always have a minimum of three—and preferably four—timing servers for optimal UAA timing synchronization. The number of upstream servers, in order from most to least preferred, is listed below.

- 4 - Allows for one or more servers to be a "false ticker" and for one server to be unreachable.
- 3 - The minimum number required to allow ntpd to detect if one is a false ticker.
- 2 - Are not allowed and will be blocked. With two NTP servers, you cannot determine which timing source is better because no reference exists to compare them to.
- 1 - Provides no debate as to which server is correct, but also provides no redundancy.

### NOTE

Disable all other timing synchronization methods including, but not limited to, VMware Tools periodic time synchronization.  
Following installation, you can use the bp2-site check-platform or bp2-site checkclockdrift commands to check UAA timing synchronization.

Complete this procedure to configure the Network Time Protocol (NTP) server(s) to serve as the timing source for UAA hosts. This is a mandatory procedure.

All UAA hosts must be synchronized to an accurate timing source. If you want to use a local time source or custom remote time sources (different than the default ones provided), then perform this procedure.

Before you begin this procedure, verify that you -

- Completed the Updating hosts file procedure.
- Can access the /home/bpadmin/bpi/playbooks/group\_vars directory of host 0 of active site as the bpadmin user.

To configure a time source -

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP, use the IP address of the host 0) and navigate to /home/bpadmin/bpi/playbooks/group\_vars directory.
2. Using a text editor, open the standby\_cluster file.

3. To use a local time source, uncomment `ntp_server_type` and change its value to `local` and save the `standby_cluster` file. The default `ntp_server_type` is `remote`.

Here is an NTP section before the edit for the local time source:

```
NTP
There are 2 options 'remote' (default) and 'local'. The default configuration (remote)
will set up NTP to connect
to a set of remote, Operating System specific, servers. If local is specified, host0
will be used as the ntp clock
reference for all nodes in the cluster. This is controlled via the 'ntp_server_type'
outlined below.
ntp_server_type: remote
```

Here is an NTP section after the edit for the local time source:

```
NTP
There are 2 options 'remote' (default) and 'local'. The default configuration (remote)
will set up NTP to connect
to a set of remote, Operating System specific, servers. If local is specified, host0
will be used as the ntp clock
reference for all nodes in the cluster. This is controlled via the 'ntp_server_type'
outlined below.
ntp_server_type: local
```

4. If you are working with only local time source, go to step 10. If not, go to step 7.
5. Using a text editor, open the `standby_cluster` file.
6. To use custom remote time sources, uncomment and edit the `ntp_servers_custom` list to include the NTP server URLs or IP addresses that you want used as the UAA host timing source in standby site.

Save the `standby_cluster` file. Example before the edit for the custom remote time sources.

The example focuses on the section to be edited.

```
In the 'remote' case, you can also override the set of remote servers by uncommenting
#and setting the
'ntp_servers_custom' variable and configuring 1,3 or 4 NTP servers to connect to. To do
#so, uncomment
the 'ntp_servers_custom' variable and uncomment and configure the appropriate number of
#hosts. e.g. change
'<host a>' (and optionally host b, host c and host d) to the IP address or hostname of a
#valid NTP server.
#ntp_servers_custom: # - <host a>
- <host b>
- <host c>
```

Example **after** the edit using hostnames. In this example, the first NTP server to be contacted will be the one with the fully qualified domain name of `0.mycustomer.ntp.com`:

```
In the 'remote' case, you can also override the set of remote servers by uncommenting
and setting the
'ntp_servers_custom' variable and configuring 1,3 or 4 NTP servers to connect to. To do
so, uncomment
the 'ntp_servers_custom' variable and uncomment and configure the appropriate number of
hosts. e.g. change
'<host a>' (and optionally host b, host c and host d) to the IP address or hostname of a
valid NTP server.
ntp_servers_custom:
- 0.mycustomer.ntp.com
- 1.mycustomer.ntp.com
- 2.mycustomer.ntp.com
```

Example **after** the edit using IP addresses. In this example the first NTP server to be contacted will be the one with an IP address of `10.128.8.89`:

```
In the 'remote' case, you can also override the set of remote servers by uncommenting
and setting the
```

```
'ntp_servers_custom' variable and configuring 1,3 or 4 NTP servers to connect to. To do
so, uncomment
the 'ntp_servers_custom' variable and uncomment and configure the appropriate number of
hosts. e.g. change
'<host a>' (and optionally host b, host c and host d) to the IP address or hostname of a
valid NTP server.
ntp_servers_custom:
- 0.10.128.8.89
```

7. By default, the `ntp_server_options` entry default is `iburst`. For details about the `ntp_server_options`, see <https://linux.die.net/man/5/ntp.conf>. If you want to change the default value, uncomment `ntp_server_options` and edit its value in `standby_cluster` and save the file.

## Configuring Geographical Redundancy

This section describes the configuration of geographical redundancy functions which are given below. These parameters need to be configured in `standby_cluster` file for standby site.

1. `geored_site_state` - It can be in `ACTIVE` or `STANDBY` state
2. `geored_site_id` – It identifies a site from a geographical context. You can use the variables such as `Toronto`, `DataCenter_1`, `Zone-East`. You You can use letters, numbers, underscores and, dashes and must be at least 3 characters in length to define it.

### NOTE

You must have `GR SiteId` and `SiteState`, before creating the `geored_site_id`. `geored_site_id` uniquely identifies a site from a GR context. This variable should be set to something meaningful for your deployment, for example, `Toronto`, `DataCenter_1`, `Zone-East`. Application deployments will not be fully functional until the `GR SiteId` and `SiteState` are configured. Valid characters for `geored_site_id` are letters, numbers, underscores and dashes and must be at least 3 characters in length. For example, `geored_site_id: SiteA`.

3. `geored_local_site_ip` - It is used with the `geored_site_id` and `geored_site_state` to provision the local site from a geographical point of view.

### NOTE

The specification of this variable is optional and if not set will default to `site_ip` defined in the host's file. This IP address is the same as the `site_ip` and will not need to be overridden. The IP is not functionally significant (no GR operations depend on it).

4. `geo_nagios_checks` – It is used to verify nagios checks for GeoRed installation. If it is set to `false`, nagios checks will not be verified for active and standby sites during auto GR configuration setup.

## Requirements

Before you begin this procedure, verify that you -

- Completed the Updating hosts file procedure.
- Can access the `/home/bpadmin/bpi/playbooks/group_vars` directory of host 0 of active site as the `bpadmin` user

## Steps

1. Log in to Host 0 of Site A (active site) as `bpadmin` (do not use the Site IP, use the IP address of the host 0) and navigate to the `/home/bpadmin/bpi/playbooks/group_vars` directory.
2. Using a text editor, open the `standby_cluster` file.
3. Edit `geored_site_id`, `geored_site_state`, `geored_local_site_ip` and `geo_nagios_checks` in `standby_cluster` file and save it. `geored_site_state` is always set to `STANDBY` in `standby_cluster` file.

# Configuring the Blue Planet email Service

UAA requires that you configure a Simple Mail Transfer Protocol (SMTP) server so UAA can send system email to users. Emails are used for alarm notifications and forgotten password assistance.

## NOTE

If password expirations are enabled and the SMTP server is not configured, users will not be able to log in after their password expires. Blue Planet recommends if you cannot complete the configuration now, ensure you do it within 60 days to avoid causing users to be locked out with no way to reset their passwords.

Complete the following procedure to configure Blue Planet email service. This is a mandatory procedure.

Before you begin this procedure, verify that you -

- Completed the Updating hosts file procedure.
- Can access the /home/bpadmin/bpi/playbooks/group\_vars directory of host 0 of active site as the bpadmin user.
- Understand the SMTP server requirements at your site.

To configure the Blue Planet email service -

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP, use the IP address of the host 0) and navigate to the /home/bpadmin/bpi/playbooks/group\_vars directory.
2. Using a text editor, open the standby\_cluster file and edit the SMTP parameters mentioned in table SMTP parameters. Save the standby\_cluster file.

| ISSUE            | DESCRIPTION                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| smtp_username    | The SMTP server account username used for sending emails.                                                                                                                                                                                                                                                                                                                                                                                             |
| smtp_password    | The SMTP server account password.                                                                                                                                                                                                                                                                                                                                                                                                                     |
| smtp_staticPath  | The staticPath value must be /bp2/src/static. Do not change this value.                                                                                                                                                                                                                                                                                                                                                                               |
| smtp_authen      | The SMTP server authentication. Set the value to true.                                                                                                                                                                                                                                                                                                                                                                                                |
| smtp_transport   | The SMTP server transport security. Set the value to true or false, as applicable.                                                                                                                                                                                                                                                                                                                                                                    |
| smtp_mail_server | The SMTP server fully qualified domain name (FQDN), such as smtp.gmail.com or, if                                                                                                                                                                                                                                                                                                                                                                     |
| smtp_mailer_name | Must be set to Blue Planet Mailer. Do not change this value.                                                                                                                                                                                                                                                                                                                                                                                          |
| smtp_port        | The SMTP server port number. Depending on the server, this port can be 25, 465, or 587.                                                                                                                                                                                                                                                                                                                                                               |
| smtp_email       | The SMTP server email account from which reset password emails will be sent. Some SMTP servers, such as Gmail, allow you to use an alias that is not set on the server. For example, the account could be "bphostmonitor@abccompany.com", but the value could be "api- crinoid@ciena.com". Of course, you can enter the true value, bphostmonitor@abccompany.com. The Amazon Web Services (AWS) SMTP server restricts the entry to the correct value. |

Example **before** the edit –

```
SMTP configuration details for 'Forgot Password' feature
smtp_username: USERNAME
smtp_password: PASSWORD
smtp_staticPath: /bp2/src/static
smtp_authen: SMTP_AUTHENTICATION
smtp_transport: SMTP_TRANSPORTSECURITY
smtp_mail_server: MAILSERVER.COM
```

```
smtp_mailer_name: MAILER_NAME
smtp_port: SMTP_PORT
smtp_email: MAILER@EMAIL.COM
```

**Example after the edit –**

```
SMTP configuration details for 'Forgot Password' feature
smtp_username: GmailUser
smtp_password: AnyPassword
smtp_staticPath: /bp2/src/static
smtp_authen: true
smtp_transport: true
smtp_mail_server: smtp.gmail.com
smtp_mailer_name: Blue Planet Mailer
smtp_port: 587
smtp_email: api-crinoid@AnyCompany.com
```

## Modifying the iLAN NET Interface

UAA uses the address 172.16.0.0/16/24 for its internal LAN (iLAN). Complete this procedure if -

- Your network uses 172.16.0.0/16/24, in which case, a conflict with the UAA iLAN will occur, or,
- You are implementing georedundancy. Georedundancy requires different iLAN addresses for the active and standby sites.

Before you begin this procedure, verify that you -

- Completed the Updating hosts file procedure.
- Have a new address for the iLAN

To modify the iLAN interface -

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP, use the IP address of the host 0) and navigate to /home/bpadmin/bpi/playbooks/group\_vars directory.
2. Using a text editor, open the standby\_cluster file.
3. Uncomment the ilannet option, then enter the IP network address you want UAA to use, for example, 172.29.0.0/16/24. Save the standby\_cluster file.

**Example before the edit –**

```
#####
install #
The ilannet to use on hosts
ilannet: 172.16.0.0/16/24
```

**Example after the edit –**

```
#####
install #
The ilannet to use on hosts
ilannet: 172.19.0.0/16/24
```

**NOTE**

If you are installing georedundancy, the active and standby sites must have different iLAN addresses. The active site can use the default (or user-assigned) address. The standby site must be on a different network.

**For example:** Active → ilannet:172.19.0.0/16/24 (default) and Standby → ilannet: 172.29.0.0/16/24. Do not modify the /24 subnet value.

---

## Modifying the Default UAA Interface

By default, UAA uses the first network interface, eth0, for Blue Planet activities. Complete the following steps if you want to set a new default interface. Otherwise, you can skip this procedure and continue with the Specifying the external license server procedure.

Before you begin this procedure, verify that you -

- Completed the Updating hosts file procedure.

**NOTE** | To display a list of interfaces, use the "ip a" command.

To modify the default UAA interface -

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP, use the IP address of the host 0) and navigate to /home/bpadmin/bpi/playbooks/group\_vars directory.
2. Using a text editor, open the standby\_cluster file.
3. Uncomment the bp\_interface option and replace eth0 with the interface you want used for example eth3. Save the standby\_cluster file.

Example **before** the edit –

```
specify the Blue Planet Interface
if not defined, the ansible default interface
will be used, which is typically your first interface
#bp_interface: eth0
```

Example **after** the edit –

```
specify the Blue Planet Interface
if not defined, the ansible default interface
will be used, which is typically your first interface
bp_interface: eth3
```

4. Save the file.

## Specifying the External License Server

Use this procedure to set up the external license server IP address in cluster and standby\_cluster files.

### Requirements

Before you begin this procedure, verify that you -

- Completed the Updating hosts file procedure.

### Steps

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP, use the IP address of the host 0) and navigate to /home/bpadmin/bpi/playbooks/group\_vars directory.
2. Using a text editor, open the standby\_cluster file.
3. Uncomment the **license\_server** parameter and replace a.b.c.d with external license server IP.
4. Uncomment the **license\_server\_backup** parameter and replace a.b.c.d with external backup license server IP.
5. Save the standby\_cluster file.

Example **before** the edit –

```
License Server details for unbundling encrypted offline archives and runtime
#requirements
#license_server: a.b.c.d
#license_server_backup: a.b.c.d
```

Example **after** the edit –

```
License Server details for unbundling encrypted offline archives and runtime
#requirements
license_server: 10.10.10.10
license_server_backup: 12.12.12.12
```

## Setting Up Users

Complete this procedure to manage keys of the bpadmin user and the root user, and to create the bpuser user (sudo restricted Docker install user) and manage its sudo permissions and keys. This is a mandatory procedure. The setup script skips this step if you have previously manually created the bpuser user.

Before you begin this procedure, verify that you -

- Completed the Updating hosts file procedure.
- Know the bpadmin user password
- Can access the /home/bpadmin/bpi directory of host 0 of active site as the bpadmin user

To set up users -

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP, use the IP address of the host 0) and navigate to /home/bpadmin/bpi/ directory.
2. To start the setup users' script enter -

```
./bpi --setup-users
```

3. If prompted, enter the bpadmin user password.

**NOTE** | For multi-host deployments, you must enter the bpadmin password for each host.

4. If you have not previously completed the procedure to manually create the bpuser user, then:
  - a. When prompted, enter the bpuser password. The same password is set on all hosts.
  - b. Re-enter the password for the bpuser user.

The script sets the bpadmin and bpuser authentication keys as well as several sudo privileges for the bpuser user. See the files in /home/bpadmin/bpi/roles/setup-users/sudoers/templates to see the settings.

---

## Validating the Hosts

This procedure verifies that the host hardware and software where you will install the UAA meet Blue Planet requirements. The validation is based upon requirements described in the Hardware and software requirements chapter.

The validation phase checks the following areas and related requirements -

- Hardware (CPU, RAM, and SWAP)
- Operating system (type, architecture, version, system-level packages for bpi execution, and SELinux mode)
- Disk (mountpoints, size, and Docker volume group [if required])
- Network (ports and unique hostnames)

Before you begin this procedure, verify that you -

- Completed Setting up users procedure.
- Can access the /home/bpadmin/bpi directory of host 0 of active site as the bpadmin user.

To validate the hosts -

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP, use the IP address of the host 0) and navigate to /home/bpadmin/bpi/ directory.
2. Validate the system by executing command.

```
nohup ./bpi --validate <profile> &
```

where,

<profile> is the validation profile. Possible values are: uaa-dev (lab environment) or uaa-prod (production environment).

3. If prompted, enter the bpadmin user password.

**NOTE** | For multi-host deployments, you must enter the bpadmin password for each host.

The system displays various task-related outputs as the validation progresses. At the end of the validation process, the system displays a summary.

4. If elements display a Failed status, correct them, then repeat step 2 and 3 until all elements display a Passed status.
5. If all elements display a Passed status and "failed=0" at the end of the summary, continue with the next procedure.



---

## Configuring UAA Hosts on Active and Standby Sites

Complete this procedure to configure the UAA host(s) on active and standby sites for the UAA software installation from host 0 of active site.

Configuring the UAA hosts creates the following directories on active and standby sites. It also ensures they are owned by bpuser on both active and standby sites -

- /etc/bp2
- /etc/bp2/site
- /etc/bp2/solutionmanager

This procedure also performs minor configuration changes including updates to syslog, rsyslog, sshd, and NTP to prepares the hosts for UAA installation on active and standby sites.

Before you begin this procedure, verify that you -

- Completed Setting up users procedure.
- Know the bpadmin user password.
- Can access the /home/bpadmin/bpi directory of host 0 of Site A (active site) site as the bpadmin user
- If you chose not to implement the Blue Planet NTP option in the Configuring a time source procedure and will use your network NTP for UAA host timing, add the playbook arguments shown in step 2.

To configure the UAA hosts –

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP, use the IP address of the host 0) and navigate to /home/bpadmin/bpi/ directory.
2. Execute one of the following commands, depending on whether your installation is single-host or multi-host and your NTP timing preference.

```
nohup ./bpi --site <lineup file> --playbook-args='--limit standby_cluster' &
```

- a. If you are provisioning your own NTP timing, add the following playbook arguments by executing command (on single line) -

```
nohup ./bpi --site <lineup file> --playbook-args='--skip-tags ntp --limit standby_cluster' &
```

If no failures occur, indicated by failed=0, continue with the next step. If failures occurred, contact Blue Planet Customer Support for guidance.

--

## Setup Overrides Configuration for Postgres

Use this procedure to setup the override configuration for the postgres application.

Before you begin this procedure, verify that you -

- Completed the Specifying the external license server procedure.

To setup overrides configuration -

1. Log in to Host 0 of Site B (Standby site) as bpadmin (do not use the Site IP, use the IP address of the host 0).
2. Using a text editor, open /etc/bp2/postgres/overrides.json.
3. Add the monitor\_task\_startup\_wait\_time\_in\_mins entry –

```
{
 "PG_CFG_OVERRIDE":
 {
 "PG_BOOTSTRAP_max_connections":"600",
 "monitor_task_startup_wait_time_in_mins": "stop",
 "MANAGED_DB_LIST":"postgres tron"
 }
}
```

4. Verify that you have the right json in these files by running the following commands -

```
cat /etc/bp2/postgres/overrides.json | python -m json.tool
```

**NOTE** | These commands should not return error, it will print back the JSON content.

5. Copy credential files content of postgres, uaa-core-db, uaa-pm-db, and uaa-graph-db in active site and replace credential files in standby site. Make sure credentials file must match in all hosts (*active and standby*), respective directories need to create (*if not present*).

```
/etc/bp2/postgres/private/users.json
/etc/bp2/uaa-core-db/private/users.json
/etc/bp2/uaa-pm-db/private/users.json
/etc/bp2/uaa-graph-db/private/users.json
```

6. Execute the below command to sync it to all hosts -

```
sudo bp2-site sync-site-config
```

---

## Installing Core Platform and Extended Platform Solution on Active and Standby Sites

Complete this procedure to install core platform and platform solution on active and standby sites from host 0 of the active site.

Before you begin this procedure, verify that you -

- Completed the Configuring UAA hosts on active and standby sites procedure.
- Know the bpadmin user password.
- Can access the /home/bpadmin/bpi directory of host 0 of active site as the bpadmin user.

To install UAA platform and solutions -

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP, use the IP address of the host 0) and navigate to /home/bpadmin/bpi/ directory.
2. Install the Core Platform and Platform Solution for UAA 23.08 on standby site by entering (on a single line)

```
nohup ./bpi --install <lineup file> --playbook-args='--limit standby_cluster --skip -tags bp2-solution' &
```

If all elements display a Passed status and "failed=0" at the end of the summary, continue with Installing UAA and configuring georedundancy on active and standby sites (automatic procedure).

## Installing UAA and Configuring Georedundancy on Active and Standby Sites (automatic procedure)

Complete this procedure to install UAA solution on active and standby sites. This procedure also automatically sets up geographical redundant configuration between active and standby.

This procedure performs -

- Share the keys with standby site.
- Create an IP security tunnel between the active and standby sites.
- Install and deploy the UAA application solution & additional solutions on active and standby sites.
- Verify system health of active and standby sites.
- Configure geographical redundancy on active site.
- Configure geographical redundancy on standby site.

Before you begin this procedure, verify that you -

- Completed the Installing Core Platform and Extended Platform Solution on active and standby sites procedure.
- Know the bpadmin user password.
- Can access the /home/bpadmin/bpi directory of host 0 of active site as the bpadmin user.

To install UAA and configure georedundancy -

1. Log in to Host 0 of Site A (active site) as bpadmin (do not use the Site IP, use the IP address of the host 0) and navigate to /home/bpadmin/bpi/ directory.
2. Start automatically geographical redundant configuration setup between active and standby sites by executing command (on single line) –

a. For OS hardened servers:

```
nohup ./bpi --geo-keys <standby_siteIp> --playbook-args="--limit cluster" &
```

```
nohup ./bpi --autoinstall-geo <lineup_file> --playbook-args='--skip-tags geowhitelist --skip-tags active-install -e geo_user=admin -e geo_password=adminpw' &
```

This is the default password you use for the first time. If you forget to specify the password here, then you are asked for the password.

b. For non-OS hardened servers -

```
nohup ./bpi --autoinstall-geo <lineup_file> --playbook-args='--skip-tags active-install -e geo_user=admin -e geo_password=adminpw' &
```

If all elements display a Passed status and "failed=0" at the end of the summary, continue with the next step. If failures occurred, contact Blue Planet Customer Support for guidance.

3. Execute below script to copy bpi directory to host 0 of standby site which enable standby site to keep its original bpi configuration for example hosts file and all.yml file.

```
./setup-bpi-standby.sh
```

4. Verify the system health by logging into Nagios for both active and standby sites.


```
https://<active_site_IP_address>/nagios
```

```
https://<standby_site_IP_address>/nagios
```

**NOTE**

Ignore the containers showing an Unknown status. Nagios can take up to 30 minutes to display the status of all services as GREEN.


5. On the active host UI, select **System > Security > Geographical redundancy** to verify that the active and standby sites are visible and connected to the tunnel.
6. On the active host UI, select **System > Platform > Swaggar UI**.
7. Click Geographic Redundancy on the left panel.



- 8. On the right pane, expand POST /geored/credentials API.
- 9. Click Try it out.



The JSON data in the API body section becomes editable.



- 10. Enter the following data for the active site:

|               |                                                                                                             |
|---------------|-------------------------------------------------------------------------------------------------------------|
| where         |                                                                                                             |
| <SiteA_IP> is | is the site IP address of the active site.                                                                  |
| <user>        | Put the username that is used to login active site host to perform GR installation command.                 |
| <password>    | Put the password of the username that is used to login active site host to perform GR installation command. |

- 11. Click **Execute**.

| Name                          | Description                                                                                                                                                                                                                                                                   |
|-------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>body</b> ★ <i>required</i> | The credentials to be added.                                                                                                                                                                                                                                                  |
| (body)                        | <div> <div>Edit Value</div> <div>Model</div> </div> <pre> {   "data": {     "ip": "&lt;active site IP&gt;",     "username": "user1",     "password": "userpw"   } } </pre> <div>Cancel</div> <div>Parameter content type</div> <div>application/json</div> <div>Execute</div> |

12. Enter the data for the standby site:

|               |                                                                                                             |
|---------------|-------------------------------------------------------------------------------------------------------------|
| where         |                                                                                                             |
| <SiteA_IP> is | is the site IP address of the active site.                                                                  |
| <user>        | Put the username that is used to login active site host to perform GR installation command.                 |
| <password>    | Put the password of the username that is used to login active site host to perform GR installation command. |

13. Click **Execute**.

|                                                                                                                         |
|-------------------------------------------------------------------------------------------------------------------------|
| <pre> {   "data": {     "ip": "&lt;standby site IP&gt;",     "username": "user1",     "password": "userpw"   } } </pre> |
| <div>Cancel</div> <div>Parameter content type</div> <div>application/json</div> <div>Execute</div>                      |

---

## Revert Override Configuration in Postgres

To revert override configuration in postgres -

1. Log in to Host 0 of Site B (Standby site) as bpadmin (do not use the Site IP, use the IP address of the host 0).
2. Remove /etc/bp2/bpopg/overrides.json.
3. Delete monitor\_task\_startup\_wait\_time\_in\_mins entry from the /etc/bp2/postgres/overrides.json file.
4. Confirm that you have the right json in these files by running the following command –

```
cat /etc/bp2/postgres/overrides.json | python -m json.tool
```

This command should not return an error, it will display the JSON content.

5. Execute the below command to sync it to all hosts –

```
sudo bp2-site sync-site-config
```

### NOTE

After the above steps are performed user needs to run the steps for the [Backup and Restore of UAA PM DB](#).

# Backup and Restore of UAA PM DB

Following are the steps for the backup and restore of UAA PM DB:

1. Login to host 0 of the current active cluster.

**NOTE** | Make sure not to use site IP.

2. Enter solman using command 'sudo solman'.
3. Execute the below command to take backup of the UAA PM DB:

```
site_backup --apps=uaa-pm-db --label=<label_name>
```

**NOTE** | label\_name is the name that is used while creating a snapshot file for backup.

Example: `site_backup --apps=uaa-pm-db --label=pmdbbbackup`

4. Make note of the file name displayed on the screen after the backup is successful.
5. Exit **Solman**.
6. Download the snapshot file by executing the below command (*in a single line*):

```
curl -o <snapshot_file_name_noted>.snap
http://127.0.0.1/solutionmanager/api/v1/snapshots/<snapshot_file_name_noted>/download
```

"snapshot\_file\_name\_noted" is the file name noted down in **Step 4**.

7. Copy the downloaded snapshot file to host 0 of the current standby server by executing the below command (*in a single line*):

```
scp ./<snapshot_file_name_noted>.snap
bpadmin@<host0_of_current_standby_ip>:<destination_directory_to_which_snapshot_will_be_copied>
```

8. Log in to host 0 of the current standby server and navigate to the directory where the snapshot file is copied.
9. Upload the snapshot file to the **Solman** on host 0 of the current standby using the below command (*in a single line*):

```
curl -i -X POST -H "Content-Type: multipart/form-data" -F "data=@<snapshot_file_name_noted>.snap"
http://localhost/solutionmanager/api/v1/snapshots/upload?snapshot=<snapshot_file_name_noted>
```

10. Enter solman using command 'sudo solman' on host 0 of the current standby server:
11. Restore the UAA PM DB app by executing the below command:

```
site_restore --apps=uaa-pm-db <snapshot_file_name_noted>
```



---

## Contacting Blue Planet

|                                   |                                                                                       |
|-----------------------------------|---------------------------------------------------------------------------------------|
| Blue Planet Division Headquarters | 7035 Ridge Road<br>Hanover, MD 21076<br>+1 800-921-1144                               |
| Blue Planet Support               | <a href="https://www.blueplanet.com/support">https://www.blueplanet.com/support</a>   |
| Sales and General Information     | <a href="https://www.blueplanet.com/contact">https://www.blueplanet.com/contact</a>   |
| Training                          | <a href="https://www.blueplanet.com/learning">https://www.blueplanet.com/learning</a> |

For additional information, please visit <https://www.blueplanet.com>.

---

## LEGAL NOTICES

THIS DOCUMENT CONTAINS CONFIDENTIAL AND TRADE SECRET INFORMATION OF CIENA CORPORATION, INCLUDING ITS SUBSIDIARY, BLUE PLANET SOFTWARE, INC., AND ITS RECEIPT OR POSSESSION DOES NOT CONVEY ANY RIGHTS TO REPRODUCE OR DISCLOSE ITS CONTENTS, OR TO MANUFACTURE, USE, OR SELL ANYTHING THAT IT MAY DESCRIBE. REPRODUCTION, DISCLOSURE, OR USE IN WHOLE OR IN PART WITHOUT THE SPECIFIC WRITTEN AUTHORIZATION OF CIENA CORPORATION OR BLUE PLANET SOFTWARE, INC IS STRICTLY FORBIDDEN.

EVERY EFFORT HAS BEEN MADE TO ENSURE THAT THE INFORMATION IN THIS DOCUMENT IS COMPLETE AND ACCURATE AT THE TIME OF PUBLISHING; HOWEVER, THE INFORMATION CONTAINED IN THIS DOCUMENT IS SUBJECT TO CHANGE.

While the information in this document is believed to be accurate and reliable, except as otherwise expressly agreed to in writing, BLUE PLANET PROVIDES THIS DOCUMENT “AS IS” WITHOUT WARRANTY OR CONDITION OF ANY KIND, EITHER EXPRESS OR IMPLIED. The information and/or products described in this document are subject to change without notice. For the most up-to-date technical publications, visit <https://my.ciena.com>.

Copyright© 2023 Ciena® Corporation. All Rights Reserved

The material contained in this document is also protected by copyright laws of the United States of America and other countries. It may not be reproduced or distributed in any form by any means, altered in any fashion, or stored in a data base or retrieval system, without express written permission of Blue Planet.

Ciena®, the Ciena logo, Blue Planet®, and other trademarks and service marks of Ciena, Blue Planet, and/or their affiliates appearing in this publication are the property of Ciena and Blue Planet. Trade names, trademarks, and service marks of other companies appearing in this publication are the property of the respective holders.

## Security

Ciena® cannot be responsible for unauthorized use of equipment and will not make allowance or credit for unauthorized use or access.