


Automating Snowpipe for Microsoft Azure Blob Storage



Snowflake supports the following types of blob storage accounts:

1. Blob storage
2. Data Lake Storage Gen2
3. General-purpose v2

How to create External Stage and Load Data Into snowflake Table without snow pipe?

- 1) creating External Stage
- 2) Creating FileFormat

```
-- *****
-- create azure blob storage external stage
-- *****

CREATE OR REPLACE STAGE azure_blob_stage
URL = 'azure://storageaccount.blob.core.windows.net/container/folder/'
CREDENTIALS = (AZURE_SAS_TOKEN = 'z32bt4FIFQ5NTkY%3D&sdd=1');

list @azure_blob_stage;

-- *****
-- Create CSV File Format
-- *****

create or replace file format my_csv_format
type = csv
field_delimiter = '|'
skip_header = 1
null_if = ('NULL', 'null')
empty_field_as_null = true
compression = none;

-- *****
-- -- copy into table using external stage
-- *****

copy into dept from @azure_blob_stage file_format = my_csv_format;

-- verify target table.
select * from dept;
```

How to create External Stage and Load Data Into snowflake Table with snow pipe?

- 1) STORAGE INTEGRATION
- 2) NOTIFICATION INTEGRATION
- 3) Creating External Stage
- 4) Creating File Format

```
-- *****  
-- Create External Storage Integration  
-- *****
```



```
CREATE OR REPLACE STORAGE INTEGRATION AZURE_INT  
  TYPE = EXTERNAL_STAGE  
  STORAGE_PROVIDER = 'AZURE'  
  ENABLED = TRUE  
  AZURE_TENANT_ID = '89556edd--43c1'  
  storage_allowed_locations = (*);
```

```
desc integration AZURE_INT;
```

```
DESC STORAGE INTEGRATION AZURE_INT;
```

property	property_type	property_value	property_default
ENABLED	Boolean	true	false
STORAGE_PROVIDER	String	AZURE	
STORAGE_ALLOWED_LOCATIONS	List	*	[]
STORAGE_BLOCKED_LOCATIONS	List		[]
AZURE_TENANT_ID	String		
AZURE_CONSENT_URL	String	https://login.microsoftonline.com/	
AZURE_MULTI_TENANT_APP_NAME	String	ngumqcsnowflakepacint_	
COMMENT	String		

Creating Queue in storage account.



-- Create External Queue Integration

-- *****

```
CREATE OR REPLACE NOTIFICATION INTEGRATION azure_data_event
ENABLED = TRUE
TYPE = QUEUE
NOTIFICATION_PROVIDER = AZURE_STORAGE_QUEUE
AZURE_STORAGE_QUEUE_PRIMARY_URI = 'https://snowflakeravi.queue.core.windows.net/
snowflakequeue'
AZURE_TENANT_ID = '89556edd-0e4a-43c1';
```


```
desc notification INTEGRATION azure_data_event;
```

	property	property_type	property_value	property_default
1	ENABLED	Boolean	true	false
2	AZURE_STORAGE_QUEUE_PRIMARY_URI	String	[REDACTED]	
3	AZURE_CONSENT_URL	String	https://login.microsoftonline.com/[REDACTED]o	
4	AZURE_MULTI_TENANT_APP_NAME	String	pgv3qvsnowflakepacint-[REDACTED]	
5	COMMENT	String		

```
-- *****
-- Create CSV File Format
-- *****
```

```
create or replace file format my_csv_format
type = csv
field_delimiter = ','
skip_header = 1
null_if = ('NULL', 'null')
empty_field_as_null = true
compression = none;
```

Create Storage Account -> Container->folder



snowflakeravi | Containers

Storage account

[+ Container](#)
[Change access level](#)
[Restore containers](#)
[Refresh](#)
[Delete](#)
[Give feedback](#)

Overview

Activity log

Tags

Diagnose and solve problems

Access Control (IAM)

Data migration

Events

Storage browser

Data storage

Containers

File shares

☐ Show deleted containers

Name	Last modified	Public access level	Lease state
<input type="checkbox"/> \$logs		Private	Available
<input type="checkbox"/> datalake		Private	Available

```

__*****
-- Create External Storage
__*****

create or replace stage my_azure_stage
url='azure://snowflakeravi.blob.core.windows.net/datalake/landing/'
file_format = my_csv_format
STORAGE_INTEGRATION = AZURE_INT;

list @my_azure_stage;

__*****
-- Create snow pipe for external storage read
__*****

-- create pipeline
create or replace pipe dept_snowpipe
auto_ingest=true
integration='AZURE_DATA_EVENT'
as
copy into dept from @my_azure_stage;

--https://snowflakeravi.queue.core.windows.net/queue

--truncate table dept;

select * from dept;

ALTER PIPE dept_snowpipe refresh;

-- Verify pipe is paused and has pendingFileCount 0
SELECT SYSTEM$PIPE_STATUS('dept_snowpipe');

-- Pause pipe
ALTER PIPE dept_snowpipe SET PIPE_EXECUTION_PAUSED = false

```