

StratusLab Administrator's Guide

StratusLab Collaboration

Version 13.05.0.RC1



Contents

1 Preface	5
1.1 Organization	5
1.2 Typographic Conventions	5
2 Introduction	7
3 Installation	9
3.1 Installation Overview	9
3.2 Prerequisites	10
3.2.1 Physical Machines	10
3.2.2 Operating System	10
3.2.3 Disable SELinux	10
3.2.4 Python Version	11
3.2.5 Disk Configuration	11
3.2.6 Package Repositories	11
3.2.7 DNS and Hostname	12
3.2.8 SSH Configuration	12
3.2.9 DHCP Server	14
3.2.10 Network Bridge	14
3.3 Front End Deployment	14
3.3.1 Deployment tool installation	14
3.3.2 Configuration file customization	15
3.3.3 VM Management Service	15

3.3.4 Storage Service	16
3.3.5 Network configuration	16
3.3.6 DHCP Configuration	17
3.3.7 Finalize Front End Installation	17
3.4 Node Deployment	18
3.5 User Configuration	18
3.6 StratusLab Client	19
3.7 Conclusions	21
4 Running a Cloud	23
4.1 Service Logging Information	23
4.2 Monitoring Activity	23
4.3 Security Concerns	23
5 Troubleshooting	25

Chapter 1

Preface

1.1 Organization

1.2 Typographic Conventions

Chapter 2

Introduction

Describe all of the services and how they fit together in detail. Provide a detailed view of a cloud deployment.

How StratusLab fits into the various cloud service models. It is a IaaS!

Different types of deployments: public, private, and community.

Chapter 3

Installation

This tutorial demonstrates how to install manually a StratusLab cloud infrastructure using the StratusLab system administrator command line utilities. A minimal StratusLab cloud consists of two physical machines, although additional machines may be necessary if the internet cannot be accessed.

3.1 Installation Overview

The StratusLab distribution provides a simple command line client to install, configure and start the StratusLab Cloud services and components.

The default deployment has two types of machines:

1. **Front-End** - machine for VM management and storage services
2. **Node** - machine that hosts virtual machines

A quick overview of the procedure is:

1. Ensure all prerequisites are satisfied.
2. Define all of the StratusLab service parameters.
3. Install and configure the Front End, containing the VM management service (OpenNebula) and the storage management (Persistent Disk) service.

4. Install and configure the Node(s) via SSH from the Front End. By default [KVM](#) is used for the hypervisor on the Node(s).
5. Validate the installation by starting a virtual machine.

FIXME: [Minimal StratusLab Cloud][install-diagram]

3.2 Prerequisites

3.2.1 Physical Machines

This tutorial demonstrates a minimal installation of a StratusLab cloud on two physical machines. The physical machines should be relatively modern machines with the following **minimum** characteristics:

- 1 **64-bit multicore** CPU (≥ 4 cores) with **VT-x extensions**
- 4 GB of RAM
- 200 GB local disk space

The hardware virtualization extensions must be enabled in the BIOS on the “Node” machine. Many vendors ship machines with these extensions disabled.

In general cloud infrastructures prefer “fat” machines, that is machines that have a maximum number of CPUs, RAM, and disk space as possible. This is because the maximum size of a single virtual machine is limited by the size of the largest physical machine.

3.2.2 Operating System

Install a minimal version of [CentOS 6](#) on the two physical machines that will be used for the cloud infrastructure.

3.2.3 Disable SELinux

The SELinux system must be disabled on **all of the machines**. Normally this is enabled by default. To disable SELinux, ensure that the file `/etc/selinux/config` has the following line:

```
SELINUX=disabled
```

You must reboot the machine for this to take effect.

3.2.4 Python Version

The default version of Python installed with CentOS should be correct. StratusLab requires a version of Python 2 with a version **2.6 or later**. The StratusLab command line tools **do not work with Python 3**.

Verify that the correct version of Python is installed:

```
$ python --version
Python 2.6.6
```

3.2.5 Disk Configuration

StratusLab allows for a variety of storage options behind the persistent disk service. The tutorial uses the defaults using LVM and iSCSI.

The machines must be configured to use LVM for the disk storage.

The Front End must be configured with two LVM groups: one for the base operating system (~20 GB) and one for the StratusLab storage service (remaining space).

The “Node” machine can be configured with a single LVM group.

Below, we assume that the volume group names are “vg.01” for the operating system and “vg.02” for the StratusLab storage service. You can use other names, but then change the commands below as necessary.

3.2.6 Package Repositories

The StratusLab installation takes packages from three yum repositories:

1. The standard CentOS repository,
2. The [EPEL 6](#) repository, and
3. The [StratusLab repository](#).

The configuration for the CentOS repository is done when the system is installed. The others require additional configuration.

To configure **both** the Front End and Node for the EPEL repository, do the following:

```
$ wget -nd http://mirrors.ircam.fr/pub/fedora/epel/6/i386
/epel-release-6-8.noarch.rpm
$ yum install -y epel-release-6-8.noarch.rpm
```

This will add the necessary files to the `/etc/yum.repos.d/` directory.

To configure **both** the Front End and Node for the StratusLab repository, put the following into the file `/etc/yum.repos.d/stratuslab.repo`:

```
[StratusLab-Releases]
name=StratusLab-Releases
baseurl=http://yum.stratuslab.eu/releases/centos-6.2-v13
        .02/
gpgcheck=0
```

replacing the URL with the version you want to install.

Although not strictly necessary, it is advisable to clear all of the yum caches and upgrade the packages to the latest versions:

```
$ yum clean all
$ yum upgrade -y
```

This may take some time if you installed the base operating system from old media.

3.2.7 DNS and Hostname

Ensure that the **hostname** is properly setup on the Front End and the Node. The DNS must provide both the forward and reverse naming of the nodes. This is required for critical services to start.

You can verify this on both the Front End and the Node with the command:

```
$ hostname -f
```

Set the hostname if it is not correct.

Throughout this tutorial we use the variables `FRONTEND_HOST`(`FRONTEND_IP`) and `NODE_HOST`(`NODE_IP`) for the Front End and Node hostnames (IP addresses), respectively. Change these to the proper names for your physical machines when running the commands.

3.2.8 SSH Configuration

The installation scripts will automate most of the work, but the scripts require **password-less root access**:

- From the Front End to each Node and
- From the Front End to the Front End itself

Check to see if there is already an SSH key pair in `/root/.ssh/id_rsa` *. If not, then you need to create a new key pair **without a password**:

```
$ ssh-keygen -q
Enter file in which to save the key (/root/.ssh/id_rsa):
/root/.ssh/id_rsa already exists.
Overwrite (y/n)? y
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
```

Now ensure that you can log into the Front End from the Front End without needing a password. Do the following:

```
$ ssh-copy-id $FRONTEND_HOST
The authenticity of host 'onehost-5.lal.in2p3.fr_
(134.158.75.5)' can't be established.
RSA_key_fingerprint_is_e9:04:03:02:e5:2e:f9:a1:0e:ae:9f:9
f:e4:3f:70:dd.
Are_you_sure_you_want_to_continue_connecting_(yes/no)?_
yes
Warning:_Permanently_added_'onehost-5.lal.in2p3.fr
,134.158.75.5'_(RSA)_to_the_list_of_known_hosts.
root@onehost-5.lal.in2p3.fr's password:
Now try logging into the machine, with "ssh_'onehost-5.
lal.in2p3.fr'", and check in:

    .ssh/authorized_keys

to make sure we haven't added extra keys that you weren't
expecting.
```

Do the same thing for the node:

```
$ ssh-copy-id $NODE_HOST
...
```

And verify that the password-less access works as expected.

```
$ ssh $FRONTEND_HOST

Last login: Mon May 27 14:26:29 2013 from mac-91100.lal.
in2p3.fr
#
# exit
logout
Connection to onehost-5.lal.in2p3.fr closed.

$ ssh $NODE_HOST
```

```
Last login: Mon May 27 14:26:43 2013 from mac-91100.lal.  
in2p3.fr  
#  
# exit  
logout  
Connection to onehost-6.lal.in2p3.fr closed.
```

Now that SSH is properly configured, the StratusLab scripts will be able to install software on both the Front End and the Node.

3.2.9 DHCP Server

A DHCP server must be configured to assign static IP addresses corresponding to known MAC addresses for the virtual machines. These IP addresses must be publicly visible if the cloud instances are to be accessible from the internet.

If an external DHCP server is not available, the StratusLab installation command can be used to properly configure a DHCP server on the Front End for the virtual machines.

This uses a DHCP server on the Front End.

3.2.10 Network Bridge

A network bridge must be configured on the Node to allow virtual machines access to the internet. You can do this manually if you want, but the StratusLab installation scripts are capable of configuring this automatically.

This tutorial allows the installation scripts to configure the network bridge.

3.3 Front End Deployment

3.3.1 Deployment tool installation

The first step is to install the StratusLab system administrator command line client from the [StratusLab repository on the Front End](#):

```
$ yum install -y stratuslab-cli-sysadmin
```

This will install the system administrator client and all of the necessary dependencies. You can verify that it is correctly installed by doing the following:

```
$ stratus-config --help

Usage: stratus-config [options] [key [value]]
If the [value] is not provided, the command returns the
    current value
of the key.
...
```

3.3.2 Configuration file customization

The entire StratusLab Cloud is configured from a single configuration file `/etc/stratuslab/stratuslab.cfg`. This file contains many options, but only a few are required.

StratusLab ships with a default configuration file in the standard location and a reference configuration file located in `/etc/stratuslab/stratuslab.cfg.ref`.

To simplify viewing the configuration parameters and changing them, the `stratus-config` command can be used.

To list the content of the configuration, and show the differences between the `stratuslab.cfg` file and the reference configuration, you can use the `-k` or `--keys` option:

```
$ stratus-config -k

... lots of parameter values! ...
```

To change a value, specify the key and the new value. To view a single value, simply specify the key.

We will use this command to set the various configuration parameters below.

3.3.3 VM Management Service

The parameters for the frontend and VM management:

```
$ stratus-config frontend_system centos
$ stratus-config frontend_ip $FRONTEND_IP
```

3.3.4 Storage Service

Similar parameters must also be set for the Persistent Disk service.

For this tutorial, this service is installed on the Front End, so the same IP address should be used.

```
$ stratus-config persistent_disk_system centos
$ stratus-config persistent_disk_ip $FRONTEND_IP
$ stratus-config persistent_disk_merge_auth_with_proxy
    True
```

The Persistent Disk service and the Nodes communicate using a strategy defined by the `persistent_disk_storage` and `persistent_disk_share` parameters. The default values (“lvm” and “iscsi”, respectively) will be used for this tutorial.

One needs to specify what device will be used for the physical storage for the Persistent Disk service:

```
$ stratus-config persistent_disk_lvm_device /dev/vg.02

# Provide detailed parameters for storage backend plugins
.
# (NOTE: The opening and closing single quotes!)
$ stratus-config persistent_disk_backend_sections '
[% (persistent_disk_ip)s]
    type=LVM
    volume_name=_/dev/vg.02
    lun_namespace=_stratuslab
    volume_snapshot_prefix=_pdisk_clone
    initiator_group_=
'
```

If you’ve used another name for the LVM volume group, then change the above command.

3.3.5 Network configuration

Use the frontend as the general gateway for the cloud:

```
$ stratus-config default_gateway $FRONTEND_IP
```

Set the IP and mac addresses for virtual machines:

```
$ stratus-config one_public_network_addr \
    134.158.xx.yy 134.158.xx.yy 134.158.xx.yy
```



```
$ stratus-config one_public_network_mac \  
    0a:0a:86:9e:49:2a 0a:0a:86:9e:49:2b 0a:0a:86:9e:49:2c
```

In this example, the Front-End is configured on IP address \$FRONTEND_IP and three IP/MAC address pairs are defined for virtual machines.

You must use the real values for the Front End IP addresses and for the range of addresses you will use for the virtual machines.

More network parameters are described in the “one-network” section in the reference configuration file.

3.3.6 DHCP Configuration

Allow the script to automatically configure and start the DHCP server on the Front End. Do the following:

```
$ stratus-config dhcp True  
$ stratus-config dhcp_subnet 134.158.75.0  
$ stratus-config dhcp_netmask 255.255.255.0  
$ stratus-config dhcp_lease_time 3600  
  
$ stratus-config dhcp_one_public_network True  
$ stratus-config dhcp_one_local_network_routers  
    $FRONTEND_IP  
$ stratus-config dhcp_one_local_network_domain_name lal.  
    in2p3.fr  
$ stratus-config  
    dhcp_one_local_network_domain_name_servers \  
        134.158.91.80, 134.158.88.149
```

Use **your** values for these parameters!

3.3.7 Finalize Front End Installation

Now that we have defined all of the configuration parameters, you can now do the full Front End installation by issuing the following command:

```
$ stratus-install -vv
```

To get more details on what the command is (because of curiosity or errors), use the option `-v`, `-vv`, or `-vvv`.

If you run into errors, the `stratus-install` command can simply be rerun after adjusting the configuration parameters.

3.4 Node Deployment

The deployment of the StratusLab Nodes is done from the Front End, thus, **all the commands below should be run from the Front End.**

To add a Node to the cloud, specify the Linux distribution of the machine and indicate that the bridge should be configured:

```
$ stratus-config node_system centos
```

Request the automatic configuration of the network bridge:

```
$ stratus-config node_bridge_configure True
$ stratus-config node_bridge_name br0
$ stratus-config node_network_interface eth0
```

Check carefully the name of the interface on the node!

Invoke installation by

```
stratus-install -vv -n $NODE_IP
```

As before, you can increase the verbosity level by adding the option `-v` or `-vv`.

3.5 User Configuration

At this point, you have both the Front End and one Node installed. This is a functional installation, but you have not yet authorized any users for the cloud. Here we will create a new StratusLab user account. Note that StratusLab accounts are independent of the Unix accounts on the machine itself.

Add the following line to the end of the file `/etc/stratuslab/authn/login-pswd.properties`.

```
$ cat >> /etc/stratuslab/authn/login-pswd.properties
sluser=slpass,cloud-access
```

This creates a new StratusLab user 'sluser' with a password 'slpass'. The group 'cloud-access' is mandatory for the user to have access to the cloud services. (Crypted or hashed password values are also allowed in the configuration.)

The StratusLab distribution supports other authentication methods (LDAP, X509 certificates, X509 proxies, etc.), but a username/password pair is the simplest for this tutorial.

3.6 StratusLab Client

Now we will test that the cloud functions correctly by starting a new virtual machine instance and logging into it. We'll test the cloud service from a normal Unix user account on the Front End.

First, ensure that the StratusLab user client is installed on the machine. Do the following as root:

```
$ yum install -y stratuslab-cli-user
```

It is very likely that the user client commands are already installed.

(Note: For normal client installations, it is strongly recommended to use pip or easy_install with virtualenv. See the usual [client installation instructions](#).)

Now create a normal Unix user for testing:

```
$ adduser sluser
```

Now log in as the user and setup the account for using StratusLab. An SSH key pair is required to log into your virtual machines and the client requires that a complete client configuration file.

Log in as the user and create an SSH key pair. This is similar to the process used for the root account on the machine.

```
$ su - sluser
$ ssh-keygen -q
...
```

Now copy the reference configuration file into place and edit the parameters.

```
$ mkdir ~/.stratuslab
$ cd ~/.stratuslab
$ cp /etc/stratuslab/stratuslab-user.cfg.ref ~/.stratuslab/stratuslab-user.cfg
$ vi ~/.stratuslab/stratuslab-user.cfg # endpoint, username, password
```

You will need to set the “endpoint”, “username”, and “password” parameters in this file. For the “endpoint” use the hostname or IP address of your Front End. For the “username” and “password” use “sluser” and “slpass”, respectively.

Everything should be setup now. So try deploying a virtual machine. You can look in the Marketplace to find an interesting machine to deploy. We'll use a ttylinux image here. This is a micro distribution that boots very quickly and is ideal for tests.

```
# Deploy a ttylinux virtual machine.
$ stratus-run-instance BNlEEkPiBx87_uLj2-sdybSI-Xb

::::::::::::::::::::::::::::
:: Starting machine(s) ::
::::::::::::::::::::::::::::
:: Starting 1 machine
:: Machine 1 (vm ID: 1)
Public ip: 134.158.75.42
:: Done!
```

Check the status of the machine as it starts:

```
# Check its status. Pending -> not yet assigned to a
Node
$ stratus-describe-instance
id state      vcpu memory      cpu% host/ip
    name
1   Pending   1    0            0    vm-42.lal.stratuslab.eu
    one-1

# Check again. Prolog -> resources for VM are being
initialized
$ stratus-describe-instance
id state      vcpu memory      cpu% host/ip
    name
1   Prolog    1    0            0    vm-42.lal.stratuslab.eu
    one-1

# Check again. Running -> hypervisor has started machine
$ stratus-describe-instance
id state      vcpu memory      cpu% host/ip
    name
1   Running   1    0            0    vm-42.lal.stratuslab.eu
    one-1
```

When the machine reaches the ‘running’ status, the virtual machine is running in the hypervisor on the Node. It will probably take some additional time for the operating system to boot.

Verify that the machine has fully booted and is accessible from the network:

```
# Ping the virtual machine to see if it is accessible.
$ ping vm-42.lal.stratuslab.eu
PING vm-42.lal.stratuslab.eu (134.158.75.42) 56(84) bytes
of data.
```

```

From onehost-5.lal.in2p3.fr (134.158.75.5) icmp_seq=2
  Destination Host
  Unreachable
...
From onehost-5.lal.in2p3.fr (134.158.75.5) icmp_seq=8
  Destination Host
  Unreachable
64 bytes from vm-42.lal.stratuslab.eu (134.158.75.42):
  icmp_seq=9
  ttl=64 time=1.44 ms
...

# Now login to the machine as root.
$ ssh root@vm-42.lal.stratuslab.eu

The authenticity of host 'vm-42.lal.stratuslab.eu
(134.158.75.42)'
can't be established.
RSA_key_fingerprint_is
_6a:bd:f7:2d:b6:82:39:61:e6:ca:3f:c7:61:9d:72:31.
Are_you_sure_you_want_to_continue_connecting_(yes/no)?_
yes
Warning:_Permanently_added_'vm-42.lal.stratuslab.eu
,134.158.75.42'
_(RSA)_to_the_list_of_known_hosts.

#_#<-_we're logged into the ttylinux virtual
machine
# exit # just logout of the session
logout
Connection to vm-42.lal.stratuslab.eu closed.

```

Now the machine can be terminated:

```
$ stratus-kill-instance 1
```

Going through the full lifecycle of a machine shows that all of the services are working.

3.7 Conclusions

You've successfully installed a minimal StratusLab cloud. You can checkout the [documentation](#) to see what other configuration parameters

are available or try the user tutorials to discover more of the StratusLab services.

You can get help on the installation or use of StratusLab through the [support mailing list](#). You can also report bugs and provide feedback on the same list.

Chapter 4

Running a Cloud

Information on running the cloud as a service.

4.1 Service Logging Information

Where are the service logs?

4.2 Monitoring Activity

Where to find monitoring information.

4.3 Security Concerns

Various topics.

Chapter 5

Troubleshooting

Information about common problems.