

You're reading the documentation for an older, but still supported, version of ROS 2. For information on the latest version, please have a look at [Iron](#).

# Understanding parameters

**Goal:** Learn how to get, set, save and reload parameters in ROS 2.

**Tutorial level:** Beginner

**Time:** 5 minutes

## Contents

- [Background](#)
- [Prerequisites](#)
- [Tasks](#)
  - [1 Setup](#)
  - [2 ros2 param list](#)
  - [3 ros2 param get](#)
  - [4 ros2 param set](#)
  - [5 ros2 param dump](#)
  - [6 ros2 param load](#)
  - [7 Load parameter file on node startup](#)
- [Summary](#)
- [Next steps](#)

## Background

A parameter is a configuration value of a node. You can think of parameters as node settings. A node can store parameters as integers, floats, booleans, strings, and lists. In ROS 2, each node maintains its own parameters. For more background on parameters, please see [the concept document](#).

## Prerequisites

This tutorial uses the [turtlesim](#) package.

As always, don't forget to source ROS 2 in every new terminal you open.

# Tasks

## 1 Setup

Start up the two turtlesim nodes, `/turtlesim` and `/teleop_turtle`.

Open a new terminal and run:

```
ros2 run turtlesim turtlesim_node
```

Open another terminal and run:

```
ros2 run turtlesim turtle_teleop_key
```

## 2 ros2 param list

To see the parameters belonging to your nodes, open a new terminal and enter the command:

```
ros2 param list
```

You will see the node namespaces, `/teleop_turtle` and `/turtlesim`, followed by each node's parameters:

```
/teleop_turtle:
  qos_overrides./parameter_events.publisher.depth
  qos_overrides./parameter_events.publisher.durability
  qos_overrides./parameter_events.publisher.history
  qos_overrides./parameter_events.publisher.reliability
  scale_angular
  scale_linear
  use_sim_time
/turtlesim:
  background_b
  background_g
  background_r
  qos_overrides./parameter_events.publisher.depth
  qos_overrides./parameter_events.publisher.durability
  qos_overrides./parameter_events.publisher.history
  qos_overrides./parameter_events.publisher.reliability
  use_sim_time
```

Every node has the parameter `use_sim_time`; it's not unique to turtlesim.

Based on their names, it looks like `/turtlesim`'s parameters determine the background color of the turtlesim window using RGB color values.

To determine a parameter's type, you can use `ros2 param get`.

### 3 `ros2 param get`

To display the type and current value of a parameter, use the command:

```
ros2 param get <node_name> <parameter_name>
```

Let's find out the current value of `/turtlesim`'s parameter `background_g`:

```
ros2 param get /turtlesim background_g
```

Which will return the value:

```
Integer value is: 86
```

Now you know `background_g` holds an integer value.

If you run the same command on `background_r` and `background_b`, you will get the values `69` and `255`, respectively.

### 4 `ros2 param set`

To change a parameter's value at runtime, use the command:

```
ros2 param set <node_name> <parameter_name> <value>
```


Let's change `/turtlesim`'s background color:

```
ros2 param set /turtlesim background_r 150
```

Your terminal should return the message:

```
Set parameter successful
```

And the background of your turtlesim window should change colors:



Setting parameters with the `set` command will only change them in your current session, not permanently. However, you can save your settings and reload them the next time you start a node.

## 5 ros2 param dump

You can view all of a node's current parameter values by using the command:

```
ros2 param dump <node_name>
```

The command prints to the standard output (stdout) by default but you can also redirect the parameter values into a file to save them for later. To save your current configuration of `/turtlesim`'s parameters into the file `turtlesim.yaml`, enter the command:

```
ros2 param dump /turtlesim > turtlesim.yaml
```

You will find a new file in the current working directory your shell is running in. If you open this file, you'll see the following content:

```
/turtlesim:
  ros__parameters:
    background_b: 255
    background_g: 86
    background_r: 150
    qos_overrides:
      /parameter_events:
        publisher:
          depth: 1000
          durability: volatile
          history: keep_last
          reliability: reliable
    use_sim_time: false
```

Dumping parameters comes in handy if you want to reload the node with the same parameters in the future.

## 6 ros2 param load

You can load parameters from a file to a currently running node using the command:

```
ros2 param load <node_name> <parameter_file>
```

To load the `turtlesim.yaml` file generated with `ros2 param dump` into `/turtlesim` node's parameters, enter the command:

```
ros2 param load /turtlesim turtlesim.yaml
```

Your terminal will return the message:

```
Set parameter background_b successful
Set parameter background_g successful
Set parameter background_r successful
Set parameter qos_overrides./parameter_events.publisher.depth failed: parameter
'qos_overrides./parameter_events.publisher.depth' cannot be set because it is read-only
Set parameter qos_overrides./parameter_events.publisher.durability failed: parameter
'qos_overrides./parameter_events.publisher.durability' cannot be set because it is read-only
Set parameter qos_overrides./parameter_events.publisher.history failed: parameter
'qos_overrides./parameter_events.publisher.history' cannot be set because it is read-only
Set parameter qos_overrides./parameter_events.publisher.reliability failed: parameter
'qos_overrides./parameter_events.publisher.reliability' cannot be set because it is read-only
Set parameter use_sim_time successful
```

### Note

Read-only parameters can only be modified at startup and not afterwards, that is why there are some warnings for the “qos\_overrides” parameters.

## 7 Load parameter file on node startup

To start the same node using your saved parameter values, use:

```
ros2 run <package_name> <executable_name> --ros-args --params-file <file_name>
```

This is the same command you always use to start turtlesim, with the added flags `--ros-args` and `--params-file`, followed by the file you want to load.

Stop your running turtlesim node, and try reloading it with your saved parameters, using:

```
ros2 run turtlesim turtlesim_node --ros-args --params-file turtlesim.yaml
```

The turtlesim window should appear as usual, but with the purple background you set earlier.

### Note

When a parameter file is used at node startup, all parameters, including the read-only ones, will be updated.

## Summary

Nodes have parameters to define their default configuration values. You can `get` and `set` parameter values from the command line. You can also save the parameter settings to a file to reload them in a future session.

## Next steps

Jumping back to ROS 2 communication methods, in the next tutorial you'll learn about [actions](#).