

libsfmt44497 Reference

© 2011 Sony Computer Entertainment Inc.
All Rights Reserved.
SCE Confidential

Table of Contents

Constants	3
SCE_SFMT44497_ARRAY_SIZE.....	4
Datatypes.....	5
SceSfmt44497Context	6
Functions.....	7
sceSfmt44497InitGenRand	8
sceSfmt44497InitByArray	9
sceSfmt44497GenRand32.....	10
sceSfmt44497GenRand64.....	11
sceSfmt44497FillArray32.....	12
sceSfmt44497FillArray64.....	13

Constants

000004892117

SCE CONFIDENTIAL

SCE_SFMT44497_ARRAY_SIZE

Array size for SFMT44497 pseudo random number calculation

Definition

```
#include <libsfmt44497.h>
#define SCE_SFMT44497_ARRAY_SIZE    348    /* (44497 / 128) + 1 */
```

Description

This constant defines the array size for pseudo random numbers in conformance with SFMT44497. In addition to indicating the array size that is maintained as state in the `SceSfmt44497Context` structure, this constant is also used by the `sceSfmt44497FillArray32()` and `sceSfmt44497FillArray64()` functions to indicate the minimum size for generating random numbers.

See Also

`SceSfmt44497Context`, `sceSfmt44497FillArray32()`, `sceSfmt44497FillArray64()`

Datatypes

000004892117

SceSfmt44497Context

Context information for SFMT44497 pseudo random number calculation

Definition

```
#include <libsfmt44497.h>
typedef struct SceSfmt44497Context {
    unsigned int idx;
    unsigned int sfmt[SCE_SFMT44497_ARRAY_SIZE][4];
} SceSfmt44497Context;
```

Description

This structure is a work area for calculating pseudo random numbers in conformance with SFMT44497.

One instance of this work area must be prepared for each random number sequence.

See Also

SCE_SFMT44497_ARRAY_SIZE, sceSfmt44497InitGenRand(), sceSfmt44497InitByArray()

Functions

000004892117

sceSfmt44497InitGenRand

Initialize SFMT44497 pseudo random number work area

Definition

```
#include <libsfmt44497.h>
SceInt32 sceSfmt44497InitGenRand (
    SceSfmt44497Context *pCtx,
    SceUInt32 seed
);
```

Calling Conditions

Multithread safe

Arguments

pCtx Pointer to an `SceSfmt44497Context` structure, which represents a random number sequence as a context.
seed Specifies a random number sequence.

Return Values

If an error occurs, a negative value is returned.

Value	Result
SCE_OK	Normal completion

Description

This function uses a 32-bit seed to initialize an SFMT44497 random number sequence, which is represented by the `SceSfmt44497Context` structure. This function must be executed before the `sceSfmt44497GenRand32()`, `sceSfmt44497GenRand64()`, `sceSfmt44497FillArray32()`, and `sceSfmt44497FillArray64()` functions.

Since only the `SceSfmt44497Context` structure indicated by *pCtx* is initialized, multiple random number sequences can be handled simultaneously by having multiple `SceSfmt44497Context` structures.

See Also

`SceSfmt44497Context`, `sceSfmt44497InitByArray()`

sceSfmt44497InitByArray

Initialize SFMT44497 pseudo random number work area

Definition

```
#include <libsfmt44497.h>
SceInt32 sceSfmt44497InitByArray (
    SceSfmt44497Context *pCtx,
    const SceUInt32 initkey[],
    SceUInt32 keylength
);
```

Calling Conditions

Multithread safe

Arguments

<i>pCtx</i>	Pointer to an <code>SceSfmt44497Context</code> structure, which represents a random number sequence as a context.
<i>initkey</i>	Specifies the array to be used for initializing.
<i>keylength</i>	Number of elements in <i>initkey</i> .

Return Values

If an error occurs, a negative value is returned.

Value	Result
SCE_OK	Normal completion

Description

This function uses an array of 32-bit seeds to initialize an SFMT44497 random number sequence, which is represented by the `SceSfmt44497Context` structure. This function must be executed before the `sceSfmt44497GenRand32()`, `sceSfmt44497GenRand64()`, `sceSfmt44497FillArray32()`, and `sceSfmt44497FillArray64()` functions.

Since only the `SceSfmt44497Context` structure indicated by *pCtx* is initialized, multiple random number sequences can be handled simultaneously by having multiple `SceSfmt44497Context` structures.

See Also

`SceSfmt44497Context`, `sceSfmt44497InitGenRand()`

sceSfmt44497GenRand32

Generate an SFMT44497 32-bit pseudo random number

Definition

```
#include <libmt44497.h>
SceUInt32 sceSfmt44497GenRand32 (
    SceSfmt44497Context *pCtx
);
```

Calling Conditions

Multithread safe

Arguments

pCtx Pointer to an `SceSfmt44497Context` structure, which represents a random number sequence as a context.

Return Values

32-bit pseudo random number

Description

This function generates a 32-bit pseudo random number that conforms to SFMT44497.

Before using this function, the `SceSfmt44497Context` structure must be initialized by calling the `sceSfmt44497InitGenRand()` or `sceSfmt44497InitByArray()` functions.

See Also

`SceSfmt44497Context`, `sceSfmt44497InitGenRand()`, `sceSfmt44497InitByArray()`

sceSfmt44497GenRand64

Generate an SFMT44497 64-bit pseudo random number

Definition

```
#include <libmt44497.h>
SceUInt64 sceSfmt44497GenRand64 (
    SceSfmt44497Context *pCtx
);
```

Calling Conditions

Multithread safe

Arguments

pCtx Pointer to an `SceSfmt44497Context` structure, which represents a random number sequence as a context.

Return Values

64-bit pseudo random number

Description

This function generates a 64-bit pseudo random number that conforms to SFMT44497.

Before using this function, the `SceSfmt44497Context` structure must be initialized by calling the `sceSfmt44497InitGenRand()` or `sceSfmt44497InitByArray()` functions.

Note that if the `sceSfmt44497GenRand32()` and `sceSfmt44497GenRand64()` functions are used together and the `sceSfmt44497GenRand64()` function is called after the `sceSfmt44497GenRand32()` function has been called an odd number of times, a full 64-bit random number will not be obtained. Instead, this function will return a 64-bit value in which the upper 32 bits are zero.

See Also

`SceSfmt44497Context`, `sceSfmt44497InitGenRand()`, `sceSfmt44497InitByArray()`

sceSfmt44497FillArray32

Generate an array of SFMT44497 32-bit pseudo random numbers

Definition

```
#include <libmt44497.h>
SceInt32 sceSfmt44497FillArray32 (
    SceSfmt44497Context *pCtx,
    SceUInt32 array[],
    SceUInt32 size
);
```

Calling Conditions

Multithread safe

Arguments

pCtx Pointer to an `SceSfmt44497Context` structure, which represents a random number sequence as a context.

array Buffer for receiving the generated random numbers

size Number of elements in *array* (multiple of 4 that is larger than `SCE_SFMT44497_ARRAY_SIZE*4`)

Return Values

If an error occurs, a negative value is returned.

Value	Result
<code>SCE_OK</code>	Normal completion

Description

This function generates an arbitrary number of 32-bit pseudo random numbers that conform to SFMT44497. *size* specifies the number of elements in *array* and must be a multiple of 4 that is larger than `(SCE_SFMT44497_ARRAY_SIZE * 4)`.

Before using this function, the `SceSfmt44497Context` structure must be initialized by calling the `sceSfmt44497InitGenRand()` or `sceSfmt44497InitByArray()` functions.

When the `sceSfmt44497FillArray32()` function is used together with the `sceSfmt44497GenRand32()` function, the `sceSfmt44497FillArray32()` function can be called only after the `sceSfmt44497GenRand32()` function has been called `(SCE_SFMT44497_ARRAY_SIZE * 4)` times.

When the `sceSfmt44497FillArray32()` function is used together with the `sceSfmt44497GenRand64()` function, the `sceSfmt44497FillArray32()` function can be called only after the `sceSfmt44497GenRand64()` function has been called `(SCE_SFMT44497_ARRAY_SIZE * 2)` times.

See Also

`SceSfmt44497Context`, `sceSfmt44497InitGenRand()`, `sceSfmt44497InitByArray()`

sceSfmt44497FillArray64

Generate an array of SFMT44497 64-bit pseudo random numbers

Definition

```
#include <libmt44497.h>
SceInt32 sceSfmt44497FillArray64 (
    SceSfmt44497Context *pCtx,
    SceUInt64 array[],
    SceUInt32 size
);
```

Calling Conditions

Multithread safe

Arguments

pCtx Pointer to an `SceSfmt44497Context` structure, which represents a random number sequence as a context.

array Buffer for receiving the generated random numbers

size Number of elements in *array* (multiple of 2 that is larger than `SCE_SFMT44497_ARRAY_SIZE*2`)

Return Values

If an error occurs, a negative value is returned.

Value	Result
<code>SCE_OK</code>	Normal completion

Description

This function generates an arbitrary number of 64-bit pseudo random numbers that conform to SFMT44497. *size* specifies the number of elements in *array* and must be a multiple of 2 that is larger than `(SCE_SFMT44497_ARRAY_SIZE * 2)`.

Before using this function, the `SceSfmt44497Context` structure must be initialized by calling the `sceSfmt44497InitGenRand()` or `sceSfmt44497InitByArray()` functions.

When the `sceSfmt44497FillArray64()` function is used together with the `sceSfmt44497GenRand32()` function, the `sceSfmt44497FillArray64()` function can be called only after the `sceSfmt44497GenRand32()` function has been called `(SCE_SFMT44497_ARRAY_SIZE * 4)` times.

When the `sceSfmt44497FillArray64()` function is used together with the `sceSfmt44497GenRand64()` function, the `sceSfmt44497FillArray64()` function can be called only after the `sceSfmt44497GenRand64()` function has been called `(SCE_SFMT44497_ARRAY_SIZE * 2)` times.

See Also

`SceSfmt44497Context`, `sceSfmt44497InitGenRand()`, `sceSfmt44497InitByArray()`