

# Physics Effects Reference

© 2012 Sony Computer Entertainment Inc.  
All Rights Reserved.  
SCE Confidential

# Table of Contents

<b>Sort Data</b>	<b>11</b>
Structures	12
PfxSortData16, PfxSortData32	12
Public Methods	13
get8, get16, get32	13
set8, set16, set32	14
Functions	15
pfxGetKey	15
pfxSetKey	16
<b>Broadphase Proxy</b>	<b>17</b>
Structures	18
PfxBroadphaseProxy	18
<b>Broadphase Pair</b>	<b>19</b>
Structures	20
PfxBroadphasePair	20
Functions	21
pfxGetObjectldA, pfxGetObjectldB	21
pfxSetObjectldA, pfxSetObjectldB	22
pfxGetActive	23
pfxSetActive	24
pfxGetContactld	25
pfxSetContactld	26
<b>Constraint Pair</b>	<b>27</b>
Structures	28
PfxConstraintPair	28
Functions	29
pfxGetObjectldA, pfxGetObjectldB	29
pfxSetObjectldA, pfxSetObjectldB	30
pfxGetActive	31
pfxSetActive	32
pfxGetConstraintld	33
pfxSetConstraintld	34
<b>Rigid Body State</b>	<b>35</b>
Classes	36
PfxRigidState	36
Public Methods	38
reset	38
getRigidBodyld	39
setRigidBodyld	40
getContactFilterSelf	41
setContactFilterSelf	42
getContactFilterTarget	43
setContactFilterTarget	44
getMotionType	45

setMotionType .....	46
getLinearDamping .....	47
setLinearDamping .....	48
getAngularDamping .....	49
setAngularDamping .....	50
getPosition .....	51
setPosition .....	52
getOrientation .....	53
setOrientation .....	54
getLinearVelocity .....	55
setLinearVelocity .....	56
getAngularVelocity .....	57
setAngularVelocity .....	58
movePosition .....	59
moveOrientation .....	60
isAsleep .....	61
isAwake .....	62
wakeup .....	63
sleep .....	64
getUseSleep .....	65
setUseSleep .....	66
incrementSleepCount .....	67
resetSleepCount .....	68
getSleepCount .....	69
getMaxLinearVelocity .....	70
setMaxLinearVelocity .....	71
getMaxAngularVelocity .....	72
setMaxAngularVelocity .....	73
getUserData .....	74
setUserData .....	75
getUserParam .....	76
setUserParam .....	77
<b>Rigid Body Attributes .....</b>	<b>78</b>
Classes .....	79
PfxRigidBody .....	79
Public Methods .....	80
reset .....	80
getMass .....	81
setMass .....	82
getInertia .....	83
setInertia .....	84
getRestitution .....	85
setRestitution .....	86
getFriction .....	87
setFriction .....	88
<b>Rigid Body Shape .....</b>	<b>89</b>
Classes .....	90
PfxCollidable .....	90

Public Methods .....	91
reset .....	91
reset .....	92
finish .....	93
addShape .....	94
getNumShapes .....	95
getMaxNumShapes .....	96
getShape .....	97
getShapeld .....	98
getHalf .....	99
getCenter .....	100
<b>Shape .....</b>	<b>101</b>
Classes .....	102
PfxShape .....	102
Public Methods .....	103
reset .....	103
getType .....	104
getAabb .....	105
getSphere .....	106
setSphere .....	107
getBox .....	108
setBox .....	109
getCapsule .....	110
setCapsule .....	111
getCylinder .....	112
setCylinder .....	113
getConvexMesh .....	114
setConvexMesh .....	115
getLargeTriMesh .....	116
setLargeTriMesh .....	117
getOffsetTransform .....	118
setOffsetTransform .....	119
getOffsetPosition .....	120
setOffsetPosition .....	121
getOffsetOrientation .....	122
setOffsetOrientation .....	123
getContactFilterSelf .....	124
setContactFilterSelf .....	125
getContactFilterTarget .....	126
setContactFilterTarget .....	127
<b>Sphere .....</b>	<b>128</b>
Classes .....	129
PfxSphere .....	129
Constructors and Destructors .....	130
PfxSphere .....	130
<b>Box .....</b>	<b>131</b>
Classes .....	132

PfxBox .....	132
Constructors and Destructors .....	133
PfxBox .....	133
<b>Capsule .....</b>	<b>134</b>
Classes .....	135
PfxCapsule .....	135
Constructors and Destructors .....	136
PfxCapsule .....	136
<b>Cylinder .....</b>	<b>137</b>
Classes .....	138
PfxCylinder .....	138
Constructors and Destructors .....	139
PfxCylinder .....	139
<b>Convex Mesh .....</b>	<b>140</b>
Structures .....	141
PfxConvexMesh .....	141
Constructors and Destructors .....	142
PfxConvexMesh .....	142
Public Methods .....	143
updateAABB .....	143
<b>Large Mesh .....</b>	<b>144</b>
Structures .....	145
PfxQuantize, PfxQuantize2, PfxQuantize3 .....	145
Constructors and Destructors .....	146
PfxQuantize, PfxQuantize2, PfxQuantize3 .....	146
Structures .....	147
PfxEdge .....	147
Structures .....	148
PfxExpandedFacet, PfxQuantizedFacet .....	148
Structures .....	149
PfxExpandedFacetBvh, PfxQuantizedFacetBvh .....	149
Structures .....	150
PfxExpandedTriMesh, PfxQuantizedTriMesh .....	150
Structures .....	151
PfxExpandedTriMeshBvh, PfxQuantizedTriMeshBvh .....	151
Structures .....	152
PfxLargeTriMesh .....	152
Constructors and Destructors .....	154
PfxLargeTriMesh .....	154
Public Methods .....	155
getLocalPosition .....	155
getWorldPosition .....	156
quantizePosition .....	157
quantizeVector .....	158
quantizeNormal .....	159
quantizeFloat .....	160
decodePosition .....	161

decodeVector .....	162
decodeNormal .....	163
decodeFloat .....	164
isUsingBvh .....	165
isQuantized .....	166
<b>Solver Body .....</b>	<b>167</b>
Structures .....	168
PfxSolverBody .....	168
<b>Joint .....</b>	<b>169</b>
Structures .....	170
PfxJointConstraint .....	170
PfxJoint .....	171
<b>Sub Data of Collision .....</b>	<b>172</b>
Structures .....	173
PfxSubData .....	173
Constructors and Destructors .....	175
PfxSubData .....	175
Public Methods .....	176
getIslandId .....	176
setIslandId .....	177
getFacetId .....	178
setFacetId .....	179
getFacetLocalS, getFacetLocalT .....	180
setFacetLocalS, setFacetLocalT .....	181
getUserData .....	182
setUserData .....	183
<b>Collision Data .....</b>	<b>184</b>
Structures .....	185
PfxContactPoint .....	185
Classes .....	186
PfxContactManifold .....	186
Public Methods .....	187
reset .....	187
addContactPoint .....	188
removeContactPoint .....	189
getNumContacts .....	190
getContactPoint .....	191
refresh .....	192
merge .....	193
getDuration .....	194
getRigidBodyIdA, getRigidBodyIdB .....	195
<b>Ray .....</b>	<b>196</b>
Structures .....	197
PfxRayInput .....	197
PfxRayOutput .....	198
<b>Simulation Island .....</b>	<b>199</b>
Structures .....	200

PfxIslandUnit .....	200
PfxIsland .....	201
<b>Task Manager.....</b>	<b>202</b>
Classes.....	203
PfxPsp2TaskManager .....	203
Constructors and Destructors .....	204
PfxPsp2TaskManager .....	204
~PfxPsp2TaskManager .....	205
Public Methods .....	206
getWorkBytes .....	206
getNumTasks .....	207
setNumTasks.....	208
initialize .....	209
finalize .....	210
<b>Heap Manager .....</b>	<b>211</b>
Classes.....	212
PfxHeapManager .....	212
Constructors and Destructors .....	213
PfxHeapManager .....	213
~PfxHeapManager .....	214
Public Methods .....	215
allocate .....	215
deallocate .....	216
clear .....	217
getAllocated .....	218
getRest .....	219
<b>Joint APIs .....</b>	<b>220</b>
pfxUpdateJointPairs .....	221
PfxBallJointInitParam .....	222
pfxInitializeBallJoint.....	223
PfxSwingTwistJointInitParam.....	224
pfxInitializeSwingTwistJoint.....	225
PfxHingeJointInitParam .....	226
pfxInitializeHingeJoint .....	227
PfxSliderJointInitParam.....	228
pfxInitializeSliderJoint.....	229
PfxFixJointInitParam .....	230
pfxInitializeFixJoint .....	231
PfxUniversalJointInitParam .....	232
pfxInitializeUniversalJoint.....	233
<b>Broad Phase APIs.....</b>	<b>234</b>
pfxUpdateBroadphaseProxy .....	235
pfxUpdateBroadphaseProxy .....	236
PfxUpdateBroadphaseProxiesParam .....	237
PfxUpdateBroadphaseProxiesResult.....	238
pfxGetWorkBytesOfUpdateBroadphaseProxies .....	239
pfxUpdateBroadphaseProxies .....	240

PfxFindPairsParam .....	241
PfxFindPairsResult .....	242
pfxGetWorkBytesOfFindPairs .....	243
pfxGetPairBytesOfFindPairs .....	244
pfxFindPairs .....	245
PfxDecomposePairsParam .....	246
PfxDecomposePairsResult .....	247
pfxGetWorkBytesOfDecomposePairs .....	248
pfxGetPairBytesOfDecomposePairs .....	249
pfxDecomposePairs .....	250
<b>Collision Detection APIs .....</b>	<b>251</b>
PfxDetectCollisionParam .....	252
pfxDetectCollision .....	253
<b>Constraint Solver APIs .....</b>	<b>254</b>
PfxSetupSolverBodiesParam .....	255
pfxSetupSolverBodies .....	256
PfxSetupContactConstraintsParam .....	257
pfxSetupContactConstraints .....	258
PfxSetupJointConstraintsParam .....	259
pfxSetupJointConstraints .....	260
PfxSolveConstraintsParam .....	261
pfxGetWorkBytesOfSolveConstraints .....	262
pfxSolveConstraints .....	263
<b>External Force and Position Calculation APIs .....</b>	<b>264</b>
pfxApplyExternalForce .....	265
pfxIntegrate .....	266
PfxUpdateRigidStatesParam .....	267
pfxUpdateRigidStates .....	268
<b>Simulation Island APIs .....</b>	<b>269</b>
PfxGenerateIslandParam .....	270
PfxGenerateIslandResult .....	271
pfxGetIslandBytesOfGenerateIsland .....	272
pfxGenerateIsland .....	273
pfxAppendPairs .....	274
pfxGetNumIslands .....	275
pfxGetFirstUnitInIsland .....	276
pfxGetNextUnitInIsland .....	277
pfxGetUnitId .....	278
pfxGetIslandId .....	279
pfxResetIsland .....	280
<b>Raycast APIs .....</b>	<b>281</b>
PfxRayCastParam .....	282
pfxCastSingleRay .....	283
pfxCastRays .....	284
<b>Sort APIs .....</b>	<b>285</b>
pfxParallelSort .....	286



<b>Utility APIs .....</b>	<b>287</b>
pfxCalcMassBox .....	288
pfxCalcInertiaBox .....	289
pfxCalcMassSphere .....	290
pfxCalcInertiaSphere .....	291
pfxCalcMassCylinder .....	292
pfxCalcInertiaCylinderX, pfxCalcInertiaCylinderY, pfxCalcInertiaCylinderZ .....	293
pfxMassTranslate .....	294
pfxMassRotate .....	295
PfxCreateConvexMeshParam .....	296
pfxCreateConvexMesh .....	297
pfxReleaseConvexMesh .....	298
PfxCreateLargeTriMeshParam .....	299
pfxCreateLargeTriMesh .....	300
pfxReleaseLargeTriMesh .....	301
pfxSetUtilityAllocator .....	302
<b>Serialization APIs .....</b>	<b>303</b>
Structures .....	304
PfxSerializeCapacity .....	304
PfxSerializeBuffer .....	305
Functions .....	306
pfxSerializeRead .....	306
pfxSerializeWrite .....	308
Callback Functions .....	309
PfxSerializeInitFunc .....	309
PfxSerializeTermFunc .....	310
PfxSerializeResizeFunc .....	311
PfxSerializeUpdateFunc .....	312
PfxSerializeErrorFunc .....	313
<b>Debug Rendering APIs .....</b>	<b>314</b>
Structures .....	315
PfxLargeMeshFlagTable .....	315
Classes .....	316
PfxDebugRender .....	316
Constructors and Destructors .....	317
PfxDebugRender .....	317
~PfxDebugRender .....	318
Public Methods .....	319
setDebugRenderPointFunc .....	319
setDebugRenderLineFunc .....	320
setDebugRenderArcFunc .....	321
setDebugRenderAabbFunc .....	322
setDebugRenderBoxFunc .....	323
resetVisible .....	324
getVisible .....	325
setVisible .....	326
renderWorld .....	327
renderAabb .....	328

---

renderLocalAxis .....	329
renderIsland .....	330
renderContact .....	331
renderLargeMesh .....	332
renderLargeMeshInFrustum .....	333
renderLargeMeshByFlag .....	334
renderJoint .....	335
resetLargeMeshFlagTables .....	336
getLargeMeshFlag .....	337
setLargeMeshFlag .....	338
getScale .....	339
setScale .....	340
Callback Functions .....	341
PfxDebugRenderPointFunc .....	341
PfxDebugRenderLineFunc .....	342
PfxDebugRenderArcFunc .....	343
PfxDebugRenderAabbFunc .....	344
PfxDebugRenderBoxFunc .....	345

**Sort Data**

000004892117

# Structures

## PfxSortData16, PfxSortData32

### Sort data structure

#### Definition

```
#include <physics_effects/base_level/sort/pfx_sort_data.h>
struct SCE_PFX_ALIGNED(16) PfxSortData16 {
    union {
        PfxUInt8  i8data[16];
        PfxUInt16 i16data[8];
        PfxUInt32 i32data[4];
    };
};
struct SCE_PFX_ALIGNED(16) PfxSortData32 {
    union {
        PfxUInt8  i8data[2][16];
        PfxUInt16 i16data[2][8];
        PfxUInt32 i32data[2][4];
    };
};
```

#### Description

This is a sort data structure used to perform sorting with the `pfxParallelSort()` sort function. `PfxSortData16` has either 8-bit value x 16, 16-bit value x 8, or 32-bit value x 4 slots. `PfxSortData32` has either 8-bit value x 32, 16-bit value x 16, or 32-bit x 8 slots. The last 32 bits are always used to save the key value for sorting.

16-byte alignment is required.

#### Method List

Method	Description
<code>get8</code>	Gets an 8-bit value from the specified slot.
<code>set8</code>	Sets an 8-bit value into the specified slot.
<code>get16</code>	Gets a 16-bit value from the specified slot.
<code>set16</code>	Sets a 16-bit value into the specified slot.
<code>get32</code>	Gets a 32-bit value from the specified slot.
<code>set32</code>	Sets a 32-bit value into the specified slot.

#### List of Functions

Function	Description
<code>pfxGetKey()</code>	Get sort key value
<code>pfxSetKey()</code>	Set sort key value

# Public Methods

## get8, get16, get32

Get value of specified slot

### Definition

```
#include <physics_effects/base_level/sort/pfx_sort_data.h>
struct SCE_PFX_ALIGNED(16) PfxSortData16 {
    PfxUInt8  get8(int slot) const;
    PfxUInt16 get16(int slot) const;
    PfxUInt32 get32(int slot) const;
};
struct SCE_PFX_ALIGNED(16) PfxSortData32 {
    PfxUInt8  get8(int slot) const;
    PfxUInt16 get16(int slot) const;
    PfxUInt32 get32(int slot) const;
};
```

### Arguments

*slot* Slot whose value is to be retrieved

### Return Values

Returns the value of the specified slot.

### Description

This public method gets the value of the specified slot.  
The supported *slot* ranges are listed below.

Sort Data	Method	<i>slot</i> Range
PfxSortData16	get8()	0 to 15
	get16()	0 to 7
	get32()	0 to 3
PfxSortData32	get8()	0 to 31
	get16()	0 to 15
	get32()	0 to 7

SCE CONFIDENTIAL

## set8, set16, set32

Set value into specified slot

### Definition

```
#include <physics_effects/base_level/sort/pfx_sort_data.h>
struct SCE_PFX_ALIGNED(16) PfxSortData16 {
    void set8(int slot, PfxUInt8 data);
    void set16(int slot, PfxUInt16 data);
    void set32(int slot, PfxUInt32 data);
};
struct SCE_PFX_ALIGNED(16) PfxSortData32 {
    void set8(int slot, PfxUInt8 data);
    void set16(int slot, PfxUInt16 data);
    void set32(int slot, PfxUInt32 data);
};
```

### Arguments

*slot* Slot into which value is to be set  
*data* Value to be set

### Return Values

None

### Description

This public method sets the value into the specified slot.  
 The supported *slot* ranges are listed below.

Sort Data	Method	<i>slot</i> Range
PfxSortData16	set8()	0 to 15
	set16()	0 to 7
	set32()	0 to 3
PfxSortData32	set8()	0 to 31
	set16()	0 to 15
	set32()	0 to 7

# Functions

## pfxGetKey

Get value of sort key

### Definition

```
#include <physics_effects/base_level/sort/pfx_sort_data.h>
SCE_PFX_FORCE_INLINE PfxUInt32 pfxGetKey(
    const PfxSortData16 &sortData
);
SCE_PFX_FORCE_INLINE PfxUInt32 pfxGetKey(
    const PfxSortData32 &sortData
);
```

### Arguments

*sortData* Sort data

### Return Values

Returns the value of the sort key.

### Description

This function gets the value of the sort key.

SCE CONFIDENTIAL

---

# pfxSetKey

---

Set value of sort key

## Definition

---

```
#include <physics_effects/base_level/sort/pfx_sort_data.h>
SCE_PFX_FORCE_INLINE void pfxSetKey(
    const PfxSortData16 &sortData,
    PfxUInt32 key
);
SCE_PFX_FORCE_INLINE void pfxSetKey(
    const PfxSortData32 &sortData,
    PfxUInt32 key
);
```

## Arguments

---

<i>sortData</i>	Sort data
<i>key</i>	Value of sort key

## Return Values

---

None

## Description

---

This function sets the value of the sort key.



# Broadphase Proxy

000004892117

# Structures

## PfxBroadphaseProxy

### Broadphase proxy structure

#### Definition

```
#include <physics_effects/base_level/broadphase/pfx_broadphase_proxy.h>
typedef PfxSortData32 PfxBroadphaseProxy;
```

#### Description

This is the `PfxBroadphaseProxy` structure, which is the simple expression of the objects (rigid bodies) handled in the broad phase. It sets parameters from the rigid body data to the broadphase proxy using the `pfxUpdateBroadphaseProxy()` function. Updating before the broad phase is required if the position, shape, behavior, or contact filters of rigid bodies have changed.

16-byte alignment is required.

## Broadphase Pair

000004892117

# Structures

## PfxBroadphasePair

### Broadphase pair structure

#### Definition

```
#include <physics_effects/base_level/broadphase/pfx_broadphase_pair.h>
typedef PfxSortData16 PfxBroadphasePair;
```

#### Description

This is the `PfxBroadphasePair` structure, which expresses a pair of objects that are highly likely to collide detected from broad phase. A copy of the two broadphase proxy data forming the pair is kept and given as the input parameter for detection of the next collision. The index to the collision data must be set prior to the execution of collision detection.

16-byte alignment is required.

#### List of Functions

Function	Description
<code>pfxGetObjectIdA()</code>	Get index of object A
<code>pfxSetObjectIdA()</code>	Set index of object A
<code>pfxGetObjectIdB()</code>	Get index of object B
<code>pfxSetObjectIdB()</code>	Set index of object B
<code>pfxGetActive()</code>	Get active flag
<code>pfxSetActive()</code>	Set active flag
<code>pfxGetContactId()</code>	Get index to collision data
<code>pfxSetContactId()</code>	Set index to collision data

# Functions

## pfxGetObjectIdA, pfxGetObjectIdB

Get index of objects that form a pair

### Definition

```
#include <physics_effects/base_level/broadphase/pfx_broadphase_pairy.h>
SCE_PFX_FORCE_INLINE PfxUInt16 pfxGetObjectIdA(
    const PfxBroadphasePair &pair
);
SCE_PFX_FORCE_INLINE PfxUInt16 pfxGetObjectIdB(
    const PfxBroadphasePair &pair
);
```

### Arguments

*pair* Broadphase pair structure

### Return Values

Returns the index of the objects.

### Description

This function gets the index of the objects that form a pair.

SCE CONFIDENTIAL

---

## pfxSetObjectIdA, pfxSetObjectIdB

---

Set index of objects forming a pair

### Definition

---

```
#include <physics_effects/base_level/broadphase/pfx_broadphase_pairy.h>
SCE_PFX_FORCE_INLINE void pfxSetObjectIdA(
    const PfxBroadphasePair &pair,
    PfxUInt16 i
);
SCE_PFX_FORCE_INLINE void pfxSetObjectIdB(
    const PfxBroadphasePair &pair,
    PfxUInt16 i
);
```

### Arguments

---

*pair*    Broadphase pair structure  
*i*       Index of objects

### Return Values

---

None

### Description

---

This function sets the index of the objects that form a pair.

SCE CONFIDENTIAL

---

# pfxGetActive

---

## Get active flag

### Definition

---

```
#include <physics_effects/base_level/broadphase/pfx_broadphase_pairy.h>
SCE_PFX_FORCE_INLINE PfxBool pfxGetActive(
    const PfxBroadphasePair &pair
);
```

### Arguments

---

*pair* Broadphase pair structure

### Return Values

---

Returns the active flag.

### Description

---

This function gets the active flag.

SCE CONFIDENTIAL

---

# pfxSetActive

---

Set active flag

## Definition

---

```
#include <physics_effects/base_level/broadphase/pfx_broadphase_pairy.h>
SCE_PFX_FORCE_INLINE void pfxSetActive(
    const PfxBroadphasePair &pair,
    PfxBool b
);
```

## Arguments

---

*pair* Broadphase pair structure  
*b* true if active, false if inactive

## Return Values

---

None

## Description

---

This function sets the active flag. If the active flag is false, the constraint solver operation is canceled.



SCE CONFIDENTIAL

---

## pfxGetContactId

---

Get index to collision data

### Definition

---

```
#include <physics_effects/base_level/broadphase/pfx_broadphase_pairy.h>
SCE_PFX_FORCE_INLINE PfxUInt32 pfxGetContactId(
    const PfxBroadphasePair &pair
);
```

### Arguments

---

*pair* Broadphase pair structure

### Return Values

---

Returns the index to the collision data.

### Description

---

This function gets the index to the collision data.

SCE CONFIDENTIAL

---

## pfxSetContactId

---

Set index to collision data

### Definition

---

```
#include <physics_effects/base_level/broadphase/pfx_broadphase_pairy.h>
SCE_PFX_FORCE_INLINE void pfxSetContactId(
    const PfxBroadphasePair &pair,
    PfxUInt32 i
);
```

### Arguments

---

<i>pair</i>	Broadphase pair structure
<i>i</i>	Index to collision data

### Return Values

---

None

### Description

---

This function sets the index to the collision data.

# Constraint Pair

000004892117

# Structures

## PfxConstraintPair

### Constraint pair structure

#### Definition

```
#include <physics_effects/base_level/solver/pfx_constraint_pair.h>
typedef PfxSortData16 PfxConstraintPair;
```

#### Description

This is the `PfxConstraintPair` structure, which expresses the target pair of the constraint solver operation. Since This is compatible with `PfxBroadphasePair`, `PfxBroadphasePair` detected from the broad phase can be handled as is as `PfxConstraintPair`. Only collision data `PfxContactManifold` or joint `PfxJoint` can be handled as constraints.

16-byte alignment is required.

#### List of Functions

Function	Description
<code>pfxGetObjectIdA()</code>	Get index of object A
<code>pfxSetObjectIdA()</code>	Set index of object A
<code>pfxGetObjectIdB()</code>	Get index of object B
<code>pfxSetObjectIdB()</code>	Set index of object B
<code>pfxGetActive()</code>	Get active flag
<code>pfxSetActive()</code>	Set active flag
<code>pfxGetConstraintId()</code>	Get index to constraint
<code>pfxSetConstraintId()</code>	Set index to constraint

# Functions

## pfxGetObjectIdA, pfxGetObjectIdB

Get index of objects that form a pair

### Definition

```
#include <physics_effects/base_level/solver/pfx_constraint_pair.h>
SCE_PFX_FORCE_INLINE PfxUInt16 pfxGetObjectIdA(
    const PfxConstraintPair &pair
);
SCE_PFX_FORCE_INLINE PfxUInt16 pfxGetObjectIdB(
    const PfxConstraintPair &pair
);
```

### Arguments

*pair* Constraint pair structure

### Return Values

Returns the index of the objects.

### Description

This function gets the index of the objects that form a pair.

SCE CONFIDENTIAL

---

## pfxSetObjectIdA, pfxSetObjectIdB

---

Set index of objects that form a pair

### Definition

---

```
#include <physics_effects/base_level/solver/pfx_constraint_pair.h>
SCE_PFX_FORCE_INLINE void pfxSetObjectIdA(
    const PfxConstraintPair &pair,
    PfxUInt16 i
);
SCE_PFX_FORCE_INLINE void pfxSetObjectIdB(
    const PfxConstraintPair &pair,
    PfxUInt16 i
);
```

### Arguments

---

*pair*    Constraint pair structure  
*i*        Index of objects

### Return Values

---

None

### Description

---

This function sets the index of the objects that form a pair.

SCE CONFIDENTIAL

---

# pfxGetActive

---

## Get active flag

### Definition

---

```
#include <physics_effects/base_level/solver/pfx_constraint_pair.h>
SCE_PFX_FORCE_INLINE PfxBool pfxGetActive(
    const PfxConstraintPair &pair
);
```

### Arguments

---

*pair*    Constraint pair structure

### Return Values

---

Returns the active flag.

### Description

---

This function gets the active flag.

SCE CONFIDENTIAL

---

## pfxSetActive

---

Set the active flag

### Definition

---

```
#include <physics_effects/base_level/solver/pfx_constraint_pair.h>
SCE_PFX_FORCE_INLINE void pfxSetActive(
    const PfxConstraintPair &pair,
    PfxBool b
);
```

### Arguments

---

*pair*    Constraint pair structure  
*b*        true if active, false if inactive

### Return Values

---

None

### Description

---

This function sets the active flag. If the active flag is false, the constraint solver operation is canceled.



SCE CONFIDENTIAL

---

## pfxGetConstraintId

---

Get index to constraint

### Definition

---

```
#include <physics_effects/base_level/solver/pfx_constraint_pair.h>
SCE_PFX_FORCE_INLINE PfxUInt32 pfxGetConstraintId(
    const PfxConstraintPair &pair
);
```

### Arguments

---

*pair* Constraint pair structure

### Return Values

---

Returns the index to the constraint.

### Description

---

This function gets the index to the constraint.

SCE CONFIDENTIAL

---

## pfxSetConstraintId

---

Set index to constraint

### Definition

---

```
#include <physics_effects/base_level/solver/pfx_constraint_pair.h>
SCE_PFX_FORCE_INLINE void pfxSetConstraintId(
    const PfxConstraintPair &pair,
    PfxUInt32 i
);
```

### Arguments

---

<i>pair</i>	Constraint pair structure
<i>i</i>	Index to constraint

### Return Values

---

None

### Description

---

This function sets the index to the constraint.

## **Rigid Body State**

000004892117

# Classes

## PfxRigidState

State of rigid body

### Definition

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {};
```

### Description

This class represents the current state of the rigid body. It stores data such as position, velocity, and contact filter.

128-byte alignment is required.

### Method List

Method	Description
reset	Resets the parameters to their initial values
getRigidBodyId	Gets the rigid body index
setRigidBodyId	Sets the rigid body index
getContactFilterSelf	Gets the self contact filter
setContactFilterSelf	Sets the self contact filter
getContactFilterTarget	Gets the target contact filter
setContactFilterTarget	Sets the target contact filter
getMotionType	Gets the motion type
setMotionType	Sets the motion type
getLinearDamping	Gets the damping value of linear motion
setLinearDamping	Sets the damping value of linear motion
getAngularDamping	Gets the damping value of angular motion
setAngularDamping	Sets the damping value of angular motion
getPosition	Gets the position
setPosition	Sets the position
getOrientation	Gets the orientation
setOrientation	Sets the orientation
getLinearVelocity	Gets the linear velocity
setLinearVelocity	Sets the linear velocity
getAngularVelocity	Gets the angular velocity.
setAngularVelocity	Sets the angular velocity.
movePosition	Sets the linear velocity for moving to the specified position after the specified time
moveOrientation	Sets the angular velocity for rotating to the specified orientation after the specified time
isAsleep	Returns whether the rigid body is in the sleep mode
isAwake	Returns whether the rigid body is in the active mode
wakeup	Wakes up the rigid body
sleep	Puts the rigid body to sleep
getUseSleep	Gets the sleep flag
setUseSleep	Sets the sleep flag
incrementSleepCount	Increments the sleep count by 1

SCE CONFIDENTIAL

Method	Description
resetSleepCount	Resets the sleep count to 0
getSleepCount	Gets the sleep count
getMaxLinearVelocity	Gets the maximum linear velocity
setMaxLinearVelocity	Sets the maximum linear velocity
getMaxAngularVelocity	Gets the maximum angular velocity
setMaxAngularVelocity	Sets the maximum angular velocity
getUserData	Gets the user data
setUserData	Sets the user data

000004892117

# Public Methods

## reset

Set parameters to their initial values

### Definition

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    inline void reset();
};
```

### Arguments

None

### Return Values

None

### Description

This public method initializes the rigid body parameters.

SCE CONFIDENTIAL

---

# getRigidBodyId

---

Get rigid body index

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidBodyState {
    PfxUInt16 getRigidBodyId() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the index of the rigid body.

## Description

---

This public method gets the index of the rigid body.

SCE CONFIDENTIAL

---

# setRigidBodyId

---

Set rigid body index

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setRigidBodyId(PfxUInt16 i);
};
```

## Arguments

---

*i* Index of rigid body

## Return Values

---

None

## Description

---

This public method sets the index of the rigid body.



SCE CONFIDENTIAL

---

## getContactFilterSelf

---

Get self contract filter

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    PfxUInt32 getContactFilterSelf() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the self contact filter.

### Description

---

This public method gets the self contact filter.

SCE CONFIDENTIAL

---

## setContactFilterSelf

---

Set self contact filter

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setContactFilterSelf(PfxUInt32 filter);
};
```

### Arguments

---

*filter* Self contact filter

### Return Values

---

None

### Description

---

This public method sets the self contact filter.

SCE CONFIDENTIAL

---

## getContactFilterTarget

---

Get target contact filter

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    PfxUInt32 getContactFilterTarget() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the target contact filter.

### Description

---

This public method gets the target contact filter.

SCE CONFIDENTIAL

---

## setContactFilterTarget

---

Set target contact filter

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setContactFilterTarget(PfxUInt32 filter);
};
```

### Arguments

---

*filter* Target contact filter

### Return Values

---

None

### Description

---

This public method sets the target contact filter.

SCE CONFIDENTIAL

---

# getMotionType

---

Get motion type

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    ePfxMotionType getMotionType() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the motion type.

## Description

---

This public method gets the motion type.

SCE CONFIDENTIAL

---

# setMotionType

---

Set motion type

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setMotionType(ePfxMotionType t);
};
```

## Arguments

---

*t* Motion type

## Return Values

---

None

## Description

---

This public method sets the motion type.

If the range of the argument value is invalid, an assert is called.

SCE CONFIDENTIAL

---

## getLinearDamping

---

Get damping value of linear motion

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidBodyState {
    PfxFloat getLinearDamping() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the damping value of the linear motion.

### Description

---

This public method gets the damping value of the linear motion.

SCE CONFIDENTIAL

---

## setLinearDamping

---

Set damping value of linear motion

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setLinearDamping(PfxFloat damping);
};
```

### Arguments

---

*damping* Damping value of linear motion

### Return Values

---

None

### Description

---

This public method sets the damping value of the linear motion.



SCE CONFIDENTIAL

---

## getAngularDamping

---

Get damping value of angular motion

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidBodyState {
    PfxFloat getAngularDamping() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the damping value of the angular motion.

### Description

---

This public method gets the damping value of the angular motion.

SCE CONFIDENTIAL

---

## setAngularDamping

---

Set damping value of angular motion

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setAngularDamping(PfxFloat damping);
};
```

### Arguments

---

*damping* Damping value of angular motion

### Return Values

---

None

### Description

---

This public method sets the damping value of the angular motion.

SCE CONFIDENTIAL

---

# getPosition

---

Get position

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    PfxVector3 getPosition() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the position.

## Description

---

This public method gets the position.

SCE CONFIDENTIAL

---

## setPosition

---

Set position

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setPosition(const PfxVector3 &pos);
};
```

### Arguments

---

*pos* Position

### Return Values

---

None

### Description

---

This public method sets the position.

SCE CONFIDENTIAL

---

# getOrientation

---

Get orientation

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidBodyState {
    PfxQuat getOrientation() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the orientation.

## Description

---

This public method gets the orientation.

SCE CONFIDENTIAL

---

# setOrientation

---

## Set orientation

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setOrientation(const PfxQuat &rot);
};
```

### Arguments

---

*rot* Orientation

### Return Values

---

None

### Description

---

This public method sets the orientation.

SCE CONFIDENTIAL

---

# getLinearVelocity

---

Get linear velocity

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    PfxVector3 getLinearVelocity() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the linear velocity.

## Description

---

This public method gets the linear velocity.

SCE CONFIDENTIAL

---

## setLinearVelocity

---

Set linear velocity

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setLinearVelocity(const PfxVector3 &vel);
};
```

### Arguments

---

*vel* Linear velocity

### Return Values

---

None

### Description

---

This public method sets the linear velocity.



SCE CONFIDENTIAL

---

# getAngularVelocity

---

Get angular velocity

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    PfxVector3 getAngularVelocity() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the angular velocity.

## Description

---

This public method gets the angular velocity.

SCE CONFIDENTIAL

---

# setAngularVelocity

---

Set angular velocity

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setAngularVelocity(const PfxVector3 &vel);
};
```

## Arguments

---

*vel* Angular velocity

## Return Values

---

None

## Description

---

This public method sets the angular velocity.

---

## movePosition

---

Set liner velocity for moving to specified position after specified time

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    inline void movePosition(const PfxVector3 &pos, PfxFloat timeStep);
};
```

### Arguments

---

<i>pos</i>	Position after move
<i>timeStep</i>	Time step (second)

### Return Values

---

None

### Description

---

This public method sets the linear velocity for moving to the specified position after the specified time.

SCE CONFIDENTIAL

---

## moveOrientation

---

Set angular velocity for rotating to specified orientation after specified time

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidBodyState {
    inline void moveOrientation(const PfxQuat &rot, PfxFloat timeStep);
};
```

### Arguments

---

<i>rot</i>	Orientation after rotation
<i>timeStep</i>	Time step (second)

### Return Values

---

None

### Description

---

This public method sets the angular velocity for rotating to the specified orientation after the specified time.

SCE CONFIDENTIAL

---

# isAsleep

---

Returns whether the rigid body is in the sleep mode

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidBodyState {
    PfxBool isAsleep() const;
};
```

## Arguments

---

None

## Return Values

---

Returns true when the rigid body state is sleep.

## Description

---

This public method returns whether the rigid body state is sleep.

SCE CONFIDENTIAL

---

# isAwake

---

Return whether rigid body is in active mode

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    PfxBool isAwake() const;
};
```

## Arguments

---

None

## Return Values

---

Returns true when the rigid body is active.

## Description

---

This public method returns whether the rigid body is in the active mode.

SCE CONFIDENTIAL

---

# wakeup

---

---

## Wake up rigid body

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void wakeup();
};
```

### Arguments

---

None

### Return Values

---

None

### Description

---

This public method releases the rigid body from the sleep mode and sets it to the active mode.

SCE CONFIDENTIAL

---

# sleep

---

---

Put rigid body to sleep

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void sleep();
};
```

## Arguments

---

None

## Return Values

---

None

## Description

---

This public method forcibly transitions the rigid body state to sleep.

Rigid bodies whose motion type is either `kPfxMotionTypeFixed` or `kPfxMotionTypeTrigger` cannot be set in the sleep state.



SCE CONFIDENTIAL

---

## getUseSleep

---

Get sleep flag

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    PfxUInt8 getUseSleep() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the sleep flag.

### Description

---

Returns 1 when sleep is enabled, and 0 when sleep is disabled.

SCE CONFIDENTIAL

---

## setUseSleep

---

Set sleep flag

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setUseSleep(PfxUInt8 b);
};
```

### Arguments

---

*b* Sleep enable (1) / disable (0)

### Return Values

---

None

### Description

---

This public method specifies whether to sleep for each rigid body state. To enable sleep, set 1, and to disable sleep, set 0.

SCE CONFIDENTIAL

---

# incrementSleepCount

---

Increment sleep count by 1

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void incrementSleepCount();
};
```

## Arguments

---

None

## Return Values

---

None

## Description

---

This public method increments the sleep count by 1.

SCE CONFIDENTIAL

---

# resetSleepCount

---

Reset sleep count

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void resetSleepCount();
};
```

## Arguments

---

None

## Return Values

---

None

## Description

---

This public method sets the sleep count to 0.

SCE CONFIDENTIAL

---

# getSleepCount

---

Get sleep count

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    PfxUInt16 getSleepCount() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the sleep count.

## Description

---

This public method gets the sleep count.

SCE CONFIDENTIAL

---

# getMaxLinearVelocity

---

Get maximum linear velocity

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    PfxFloat getMaxLinearVelocity() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the maximum linear velocity.

## Description

---

This public method gets the maximum linear velocity.

---

# setMaxLinearVelocity

---

Set maximum linear velocity

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setMaxLinearVelocity(PfxFloat maxVelocity);
};
```

## Arguments

---

*maxVelocity* Maximum linear velocity

## Return Values

---

Sets the maximum linear velocity.

## Description

---

When the velocity of a rigid body is updated with `pfxApplyExternalForce()`, if the linear velocity of the rigid body exceeds the maximum linear velocity, it will be reset to the maximum value.

SCE CONFIDENTIAL

---

## getMaxAngularVelocity

---

Get the maximum angular velocity

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidBodyState {
    PfxFloat getMaxAngularVelocity() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the maximum angular velocity.

### Description

---

This public method gets the maximum angular velocity.



---

## setMaxAngularVelocity

---

Set maximum angular velocity

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setMaxAngularVelocity(PfxFloat maxVelocity);
};
```

### Arguments

---

*maxVelocity* Maximum angular velocity

### Return Values

---

Sets the maximum angular velocity.

### Description

---

When the velocity of a rigid body is updated with `pfxApplyExternalForce()`, if the angular velocity of the rigid body exceeds the maximum angular velocity, it will be reset to the maximum value.

SCE CONFIDENTIAL

---

# getUserData

---

Get user data

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void *getUserData() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the user data.

## Description

---

This public method gets the user data.

SCE CONFIDENTIAL

---

## setUserData

---

Set user data

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setUserData(void *d);
};
```

### Arguments

---

*d* User data

### Return Values

---

Sets the user data.

### Description

---

This public method sets the user data as a void type pointer.

SCE CONFIDENTIAL

---

# getUserParam

---

Get user parameters

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    PfxUInt32 getUserParam(int i) const;
};
```

## Arguments

---

*i* Slot index

## Return Values

---

Returns user parameters.

## Description

---

This public method obtains user parameters. Four 32-bit integer values can be stored as user parameters. Specify 0, 1, 2, and/or 3 to the slot index and obtain the corresponding parameters.

SCE CONFIDENTIAL

---

## setUserParam

---

Set user parameters

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_state.h>
class SCE_PFX_ALIGNED(128) PfxRigidState {
    void setUserParam(int i, PfxUInt32 param);
};
```

### Arguments

---

<i>i</i>	Slot index
<i>param</i>	User parameter

### Return Values

---

Sets user parameters.

### Description

---

This public method sets the *param* parameters corresponding to the 0, 1, 2, and/or 3 slots specified to the slot index.

# Rigid Body Attributes

000004892117

# Classes

## PfxRigidBody

### Rigid body attributes

#### Definition

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_body.h>
class SCE_PFX_ALIGNED(128) PfxRigidBody {};
```

#### Description

This is a class that expresses the physical attributes of a rigid body, such as mass and friction. The values of the parameters cannot be changed during simulation.

128-byte alignment is required.

#### Method List

Method	Description
reset	Resets the parameters to their initial values
getMass	Gets the mass
setMass	Sets the mass
getInertia	Gets the inertia tensor
setInertia	Sets the inertia tensor
getRestitution	Gets the restitution coefficient
setRestitution	Sets the restitution coefficient
getFriction	Gets the friction coefficient
setFriction	Sets the friction coefficient

# Public Methods

## reset

Reset parameters to their initial values

### Definition

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_body.h>
class SCE_PFX_ALIGNED(128) PfxRigidBody {
    inline void reset();
};
```

### Arguments

None

### Return Values

None

### Description

This public method initializes the parameters of the rigid body attributes.



SCE CONFIDENTIAL

---

## getMass

---

Get mass

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_body.h>
class SCE_PFX_ALIGNED(128) PfxRigidBody {
    PfxFloat getMass() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the mass.

### Description

---

This public method gets the mass.

SCE CONFIDENTIAL

---

## setMass

---

Set mass

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_body.h>
class SCE_PFX_ALIGNED(128) PfxRigidBody {
    void setMass(PfxFloat mass);
};
```

### Arguments

---

*mass* Mass

### Return Values

---

None

### Description

---

This public method sets the mass.

SCE CONFIDENTIAL

---

## getInertia

---

Get inertia tensor

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_body.h>
class SCE_PFX_ALIGNED(128) PfxRigidBody {
    const PfxMatrix3& getInertia() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the inertia tensor.

### Description

---

This public method gets the inertia tensor.

SCE CONFIDENTIAL

---

## setInertia

---

### Set inertia tensor

#### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_body.h>
class SCE_PFX_ALIGNED(128) PfxRigidBody {
    void setInertia(
        const PfxMatrix3 SCE_VECTORMATH_AOS_MATRIX_ARG inertia
    );
};
```

#### Arguments

---

*inertia* Inertia tensor

#### Return Values

---

None

#### Description

---

This public method sets the inertia tensor.

SCE CONFIDENTIAL

---

# getRestitution

---

Get restitution coefficient

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_body.h>
class SCE_PFX_ALIGNED(128) PfxRigidBody {
    PfxFloat getRestitution() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the restitution coefficient.

## Description

---

This public method gets the restitution coefficient.

SCE CONFIDENTIAL

---

## setRestitution

---

Set restitution coefficient

### Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_body.h>
class SCE_PFX_ALIGNED(128) PfxRigidBody {
    void setRestitution(PfxFloat restitution);
};
```

### Arguments

---

*restitution*    Restitution coefficient

### Return Values

---

None

### Description

---

This public method sets the restitution coefficient.

SCE CONFIDENTIAL

---

# getFriction

---

Get friction

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_body.h>
class SCE_PFX_ALIGNED(128) PfxRigidBody {
    PfxFloat getFriction() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the friction.

## Description

---

This public method gets the friction.

SCE CONFIDENTIAL

---

# setFriction

---

Set friction

## Definition

---

```
#include <physics_effects/base_level/rigidbody/pfx_rigid_body.h>
class SCE_PFX_ALIGNED(128) PfxRigidBody {
    void setFriction(PfxFloat friction);
};
```

## Arguments

---

*friction* Friction

## Return Values

---

None

## Description

---

This public method sets the friction. No distinction is made between dynamic friction and static friction.



# Rigid Body Shape

000004892117

# Classes

## PfxCollidable

Rigid body shape

### Definition

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {};
```

### Description

This is a class that expresses the shape of a rigid body. PfxCollidable functions as a container that stores several PfxShape expressing a single shape.

128-byte alignment is required.

### Method List

Method	Description
reset	Resets the parameters to their initial values
finish	Completes shape registration
addShape	Adds a shape
getNumShapes	Gets the number of shapes
getMaxNumShapes	Gets the maximum number of shapes that can be registered
getShape	Gets the shape
getShapeId	Gets the index of the shape stored in the array
getHalf	Gets the size of the bounding box
getCenter	Gets the center of the bounding box

# Public Methods

## reset

Reset parameters to their initial values

### Definition

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {
    inline void reset();
};
```

### Arguments

None

### Return Values

None

### Description

This public method initializes the rigid body shape parameters.

---

# reset

---

## Reset parameters to their initial values

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {
    inline void reset(
        PfxShape *base,
        PfxUInt16 *ids,
        int n=1
    );
};
```

### Arguments

---

<i>base</i>	Address of shape array
<i>ids</i>	Address of index array
<i>n</i>	Number of shapes

### Return Values

---

None

### Description

---

When two or more shapes are included, prepare an external array for storing the shapes and call `reset()`.

SCE CONFIDENTIAL

---

# finish

---

---

## Complete shape registration

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {
    void finish();
};
```

### Arguments

---

None

### Return Values

---

None

### Description

---

After adding a shape, be sure to call `finish()` to complete the registration.

SCE CONFIDENTIAL

---

## addShape

---

Add a shape

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {
    void addShape(const PfxShape &shape);
};
```

### Arguments

---

*shape* Shape

### Return Values

---

None

### Description

---

This public method adds a shape. The contents of the shape are copied.

SCE CONFIDENTIAL

---

## getNumShapes

---

Get number of shapes

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {
    inline PfxUInt32 getNumShapes() const;
};
```

### Arguments

---

None

### Return Values

---

None

### Description

---

This public method gets the number of shapes.

SCE CONFIDENTIAL

---

## getMaxNumShapes

---

Get maximum number of shapes that can be registered

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {
    inline PfxUInt32 getMaxNumShapes() const;
};
```

### Arguments

---

None

### Return Values

---

None

### Description

---

This public method gets the maximum number of shapes that can be registered.



SCE CONFIDENTIAL

---

# getShape

---

Get shape

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {
    inline const PfxShape& getShape(int i) const;
    inline PfxShape& getShape(int i);
};
```

## Arguments

---

*i* Index of shape

## Return Values

---

Returns the shape.

## Description

---

This public method gets the shape. If the index exceeds the range, assert is called.

SCE CONFIDENTIAL

---

## getShapeId

---

Get index of shape stored in array

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {
    inline PfxUInt16 getShapeId(int i) const;
};
```

### Arguments

---

*i* Index of shape

### Return Values

---

Returns the index of the shape stored in the array.

### Description

---

In the case of complex shapes, shape No. 0 and subsequent shapes are stored in an external shape array. This method is used for getting the index for the external shape array of the specified shape. If the argument index exceeds the range, assert is called.

SCE CONFIDENTIAL

---

## getHalf

---

Get size of bounding box

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {
    inline PfxVector3 getHalf() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the size of the bounding box.

### Description

---

This public method gets the size of the bounding box.

SCE CONFIDENTIAL

---

## getCenter

---

Get center of bounding box

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_collidable.h>
class SCE_PFX_ALIGNED(128) PfxCollidable {
    inline PfxVector3 getCenter() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the center of the bounding box.

### Description

---

This public method gets the center of the bounding box.

SCE CONFIDENTIAL

---

**Shape**

000004892117

Document serial number: 000004892117

# Classes

## PfxShape

### Shape class

#### Definition

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {};
```

#### Description

This class represents a single shape. Register it to `PfxCollidable` after setting the actual shape. 16-byte alignment is required.

#### Method List

Method	Description
<code>reset</code>	Resets the parameters to their initial values
<code>getType</code>	Gets the type of shape
<code>getAabb</code>	Gets the bounding box
<code>getSphere</code>	Gets a sphere shape
<code>setSphere</code>	Sets a sphere shape
<code>getBox</code>	Gets a box shape
<code>setBox</code>	Sets a box shape
<code>getCapsule</code>	Gets a capsule shape
<code>setCapsule</code>	Sets a capsule shape
<code>getCylinder</code>	Gets a cylinder shape
<code>setCylinder</code>	Sets a cylinder shape
<code>getConvexMesh</code>	Gets a convex mesh
<code>setConvexMesh</code>	Sets a convex mesh
<code>getLargeTriMesh</code>	Gets a large mesh
<code>setLargeTriMesh</code>	Sets a large mesh
<code>getOffsetTransform</code>	Gets an offset transform
<code>setOffsetTransform</code>	Sets an offset transform
<code>getOffsetPosition</code>	Gets the offset position
<code>setOffsetPosition</code>	Sets the offset position
<code>getOffsetOrientation</code>	Gets the offset orientation
<code>setOffsetOrientation</code>	Sets the offset orientation
<code>getContactFilterSelf</code>	Gets the self contact filter
<code>setContactFilterSelf</code>	Sets the self contact filter
<code>getContactFilterTarget</code>	Gets the target contact filter
<code>setContactFilterTarget</code>	Sets the target contact filter

# Public Methods

## reset

Reset parameters to their initial values

### Definition

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline void reset();
};
```

### Arguments

None

### Return Values

None

### Description

This public method initializes the shape parameters.

SCE CONFIDENTIAL

---

# getType

---

Get type of shape

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline PfxUInt8 getType() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the following shape types.

Value	Shape Type
kPfxShapeSphere	Sphere
kPfxShapeBox	Box
kPfxShapeCapsule	Capsule
kPfxShapeCylinder	Cylinder
kPfxShapeConvexMesh	Convex mesh
kPfxShapeLargeTriMesh	Large mesh

## Description

---

This public method gets the shape type.



SCE CONFIDENTIAL

---

## getAabb

---

Get size of bounding box

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    void getAabb(PfxVector3 &aabbMin, PfxVector3 &aabbMax) const;
};
```

### Arguments

---

*aabbMin* Minimum coordinate value of bounding box  
*aabbMax* Maximum coordinate value of bounding box

### Return Values

---

None

### Description

---

This public method stores the size of the bounding box in *aabbMin*, *aabbMax* given as arguments.

SCE CONFIDENTIAL

---

# getSphere

---

Get sphere

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline PfxSphere getSphere() const;
};
```

## Arguments

---

None

## Return Values

---

Returns a sphere.

## Description

---

This public method gets a sphere.

SCE CONFIDENTIAL

---

# setSphere

---

## Set sphere

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline void setSphere(PfxSphere sphere);
};
```

### Arguments

---

*sphere* Sphere

### Return Values

---

None

### Description

---

This public method sets a sphere.

SCE CONFIDENTIAL

---

## getBox

---

Get box

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline PfxBox getBox() const;
};
```

### Arguments

---

None

### Return Values

---

Returns a box.

### Description

---

This public method gets a box.

SCE CONFIDENTIAL

---

## setBox

---

Set box

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline void setBox(PfxBox SCE_VECTORMATH_AOS_VECTOR_ARG box);
};
```

### Arguments

---

*box* Box

### Return Values

---

None

### Description

---

This public method sets a box.

SCE CONFIDENTIAL

---

# getCapsule

---

## Get capsule

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline PfxCapsule getCapsule() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the capsule.

### Description

---

This public method gets a capsule.

SCE CONFIDENTIAL

---

# setCapsule

---

## Set capsule

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline void setCapsule(PfxCapsule capsule);
};
```

### Arguments

---

*capsule* Capsule

### Return Values

---

None

### Description

---

This public method sets a capsule.

SCE CONFIDENTIAL

---

# getCylinder

---

Get cylinder

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline PfxCylinder getCylinder() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the cylinder.

## Description

---

This public method gets a cylinder.



SCE CONFIDENTIAL

---

# setCylinder

---

Set cylinder

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline void setCylinder(PfxCylinder cylinder);
};
```

## Arguments

---

*cylinder* Cylinder

## Return Values

---

None

## Description

---

This public method sets a cylinder.

Document serial number: 000004892117

SCE CONFIDENTIAL

---

# getConvexMesh

---

Get convex mesh

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline const PfxConvexMesh* getConvexMesh() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the pointer to the convex mesh.

## Description

---

This public method gets the pointer to the convex mesh.

SCE CONFIDENTIAL

---

## setConvexMesh

---

Set convex mesh

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline void setConvexMesh(const PfxConvexMesh *convexMesh);
};
```

### Arguments

---

*convexMesh* Pointer to convex mesh

### Return Values

---

None

### Description

---

This public method sets a convex mesh.

SCE CONFIDENTIAL

---

# getLargeTriMesh

---

Get large mesh

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline const PfxLargeTriMesh* getLargeTriMesh() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the pointer to the large mesh.

## Description

---

This public method gets the pointer to the large mesh.

SCE CONFIDENTIAL

---

# setLargeTriMesh

---

Set large mesh

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline void setLargeTriMesh(const PfxLargeTriMesh *largeMesh);
};
```

## Arguments

---

*largeMesh* Pointer to large mesh

## Return Values

---

None

## Description

---

This public method sets a large mesh.

---

# getOffsetTransform

---

Get offset transform

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline PfxTransform3 getOffsetTransform() const;
};
```

## Arguments

---

None

## Return Values

---

Returns an offset transform.

## Description

---

This public method gets an offset transform. The offset is expressed in relation to the rigid body origin.

SCE CONFIDENTIAL

---

# setOffsetTransform

---

Set offset transform

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline void setOffsetTransform(const PfxTransform3 &xfrm);
};
```

## Arguments

---

*xfrm* Offset transform

## Return Values

---

None

## Description

---

This public method sets an offset transform. The offset is expressed in relation to the rigid body origin.

SCE CONFIDENTIAL

---

# getOffsetPosition

---

Get offset position

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline PfxVector3 getOffsetPosition() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the offset position.

## Description

---

This public method gets the offset position. The offset is expressed in relation to the rigid body origin.



SCE CONFIDENTIAL

---

## setOffsetPosition

---

Set offset position

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline void setOffsetPosition(
        const PfxVector3 SCE_VECTORMATH_AOS_VECTOR_ARG pos
    );
};
```

### Arguments

---

*pos* Offset position

### Return Values

---

None

### Description

---

This public method sets the offset position. The offset is expressed in relation to the rigid body origin.

SCE CONFIDENTIAL

---

# getOffsetOrientation

---

Get offset orientation

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline PfxQuat getOffsetOrientation() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the offset orientation.

## Description

---

This public method gets the offset orientation. The offset is expressed in relation to the rigid body origin.

SCE CONFIDENTIAL

---

# setOffsetOrientation

---

## Set offset orientation

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    inline void setOffsetOrientation(
        const PfxQuat SCE_VECTORMATH_AOS_VECTOR_ARG rot
    );
};
```

### Arguments

---

*rot* Offset orientation

### Return Values

---

None

### Description

---

This public method sets the offset orientation. The offset is expressed in relation to the rigid body origin.

SCE CONFIDENTIAL

---

## getContactFilterSelf

---

Get self contact filter

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    PfxUInt32 getContactFilterSelf() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the self contact filter.

### Description

---

This public method gets the self contact filter.

SCE CONFIDENTIAL

---

## setContactFilterSelf

---

Set self contact filter

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    void setContactFilterSelf(PfxUInt32 filter);
};
```

### Arguments

---

*filter* Contact filter value

### Return Values

---

None

### Description

---

This public method sets the self contact filter.

SCE CONFIDENTIAL

---

## getContactFilterTarget

---

Get target contact filter

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    PfxUInt32 getContactFilterTarget() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the target contact filter.

### Description

---

This public method gets the target contact filter.

SCE CONFIDENTIAL

---

## setContactFilterTarget

---

Set target contact filter

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_shape.h>
class SCE_PFX_ALIGNED(16) PfxShape {
    void setContactFilterTarget(PfxUInt32 filter);
};
```

### Arguments

---

*filter* Contact filter value

### Return Values

---

None

### Description

---

This public method sets the target contact filter.

**Sphere**

000004892117



# Classes

## PfxSphere

### Sphere

#### Definition

```
#include <physics_effects/base_level/collision/pfx_sphere.h>
class PfxSphere {
    PfxFloat m_radius;
};
```

#### Members

*m\_radius* Radius of sphere

#### Description

This class expresses spheres.

#### Method List

Method	Description
PfxSphere	Creates a sphere with the specified radius

# Constructors and Destructors

## PfxSphere

Create sphere of specified radius

### Definition

```
#include <physics_effects/base_level/collision/pfx_sphere.h>
class PfxSphere {
    PfxSphere(PfxFloat radius);
};
```

### Arguments

*radius*      Radius of sphere

### Return Values

None

### Description

Creates a sphere of the specified radius.

SCE CONFIDENTIAL

---

**Box**

000004892117

Document serial number: 000004892117

# Classes

## PfxBox

Box

### Definition

```
#include <physics_effects/base_level/collision/pfx_box.h>
class PfxBox {
    PfxVector3 m_half;
};
```

### Members

*m\_half* Half size of box

### Description

This class expresses boxes.

### Method List

Method	Description
PfxBox	Creates a box of the specified size

# Constructors and Destructors

## PfxBox

Create box of specified size

### Definition

```
#include <physics_effects/base_level/collision/pfx_box.h>
class PfxBox {
    PfxBox(const PfxVector3 SCE_VECTORMATH_AOS_VECTOR_ARG half);
    PfxBox(PfxFloat hx, PfxFloat hy, PfxFloat hz);
};
```

### Arguments

<i>half</i>	Half size of box
<i>hx, hy, hz</i>	Half size of box

### Return Values

None

### Description

Creates a box of the specified size.

SCE CONFIDENTIAL

---

**Capsule**

000004892117

Document serial number: 000004892117

# Classes

## PfxCapsule

### Capsule

#### Definition

```
#include <physics_effects/base_level/collision/pfx_capsule.h>
struct PfxCapsule {
    PfxFloat m_halfLen;
    PfxFloat m_radius;
};
```

#### Members

*m\_halfLen* Half length of capsule  
*m\_radius* Radius of capsule

#### Description

This class expresses capsules. The axis of a capsule always follows the X axis. To change the direction, adjust the offset orientation given to *PfxShape*.

#### Method List

Method	Description
<i>PfxCapsule</i>	Creates a capsule of the specified radius and length

# Constructors and Destructors

## PfxCapsule

Create capsule of specified radius and length

### Definition

```
#include <physics_effects/base_level/collision/pfx_capsule.h>
class PfxCapsule {
    PfxCapsule(PfxFloat halfLength, PfxFloat radius);
};
```

### Arguments

<i>halfLength</i>	Half length of capsule
<i>radius</i>	Radius of capsule

### Return Values

None

### Description

Creates a capsule of the specified radius and length.



SCE CONFIDENTIAL

---

**Cylinder**

000004892117

Document serial number: 000004892117

# Classes

## PfxCylinder

### Cylinder

#### Definition

```
#include <physics_effects/base_level/collision/pfx_cylinder.h>
struct PfxCylinder {
    PfxFloat m_halfLen;
    PfxFloat m_radius;
};
```

#### Members

*m\_halfLen* Half length of cylinder  
*m\_radius* Radius of cylinder

#### Description

This class expresses cylinders. The axis of a cylinder always follows the X axis. To change the direction, adjust the offset orientation given to `PfxShape`.

#### Method List

Method	Description
<code>PfxCylinder</code>	Creates a cylinder of the specified radius and length

# Constructors and Destructors

## PfxCylinder

Create cylinder of the specified radius and length

### Definition

```
#include <physics_effects/base_level/collision/pfx_cylinder.h>
class PfxCylinder {
    PfxCylinder(PfxFloat halfLength, PfxFloat radius);
};
```

### Arguments

<i>halfLength</i>	Half length of cylinder
<i>radius</i>	Radius of cylinder

### Return Values

None

### Description

Creates a cylinder of the specified radius and length.

# Convex Mesh

000004892117

# Structures

## PfxConvexMesh

### Convex mesh structure

#### Definition

```
#include <physics_effects/base_level/collision/pfx_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxConvexMesh {
    PfxUInt8 m_numVerts;
    PfxUInt8 m_numIndices;
    PfxUInt16 *m_indices;
    PfxVector3 *m_verts;
    PfxVector3 m_half;
};
```

#### Members

<i>m_numVerts</i>	Number of vertices
<i>m_numIndices</i>	Number of triangle indexes
<i>m_verts</i>	Vertex array
<i>m_indices</i>	Index array
<i>m_half</i>	Size of bounding box

#### Description

This structure expresses convex meshes. To create it, use the `pfxCreateConvexMesh()` utility function.

16-byte alignment is required.

#### Method List

Method	Description
<code>PfxConvexMesh</code>	Initializes the convex mesh parameters
<code>updateAABB</code>	Calculates the size of the bounding box

# Constructors and Destructors

## PfxConvexMesh

Initialize convex mesh parameters

### Definition

```
#include <physics_effects/base_level/collision/pfx_tri_mesh.h>
struct PfxConvexMesh {
    PfxConvexMesh() ;
};
```

### Arguments

None

### Return Values

None

### Description

Initializes the convex mesh parameters.

# Public Methods

## updateAABB

Calculate size of bounding box

### Definition

```
#include <physics_effects/base_level/collision/pfx_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxConvexMesh {
    inline void updateAABB();
};
```

### Arguments

None

### Return Values

None

### Description

This public method calculates the size of the bounding box and saves it to the *m\_half* internal parameter.

**Large Mesh**

000004892117



# Structures

## PfxQuantize, PfxQuantize2, PfxQuantize3

### Quantization data structure

#### Definition

```
#include <physics_effects/base_level/collision/pfx_tri_mesh.h>
struct PfxQuantize {
    PfxInt16 elem;
};
struct PfxQuantize2 {
    PfxInt16 elem[2];
};
struct PfxQuantize3 {
    PfxInt16 elem[3];
};
```

#### Members

*elem* Quantization data

#### Description

This structure stores values that have been compressed through quantization.

#### Method List

Method	Description
PfxQuantize	Initializes the quantization data
PfxQuantize2	Initializes the quantization data
PfxQuantize3	Initializes the quantization data

# Constructors and Destructors

## PfxQuantize, PfxQuantize2, PfxQuantize3

Initialize quantization data

### Definition

```
#include <physics_effects/base_level/collision/pfx_tri_mesh.h>
struct PfxQuantize {
    PfxQuantize(PfxInt16 value);
};
struct PfxQuantize2 {
    PfxQuantize2(PfxInt16 value1, PfxInt16 value2);
};
struct PfxQuantize3 {
    PfxQuantize3(PfxInt16 value1, PfxInt16 value2, PfxInt16 value3);
};
```

### Arguments

*value* Quantization data  
*value1* Quantization data  
*value2* Quantization data  
*value3* Quantization data

### Return Values

None

### Description

This structure initializes the quantization data with the values assigned to the arguments.

# Structures

## PfxEdge

Edge structure included in island mesh

### Definition

```
#include <physics_effects/base_level/collision/pfx_tri_mesh.h>
struct PfxEdge {
    PfxUInt8 m_vertId[2];
    PfxUInt8 m_angleType;
    PfxUInt8 m_tilt;
};
```

### Members

*m\_vertId*      Vertex index of end point  
*m\_angleType*   Edge type  
*m\_tilt*        Edge angle

### Description

An edge represents the boundary of facets.

The types of edge are classified as follows according to the angle formed by two facets.

Value	Description
SCE_PFX_EDGE_FLAT	Flat edge
SCE_PFX_EDGE_CONVEX	Convex edge
SCE_PFX_EDGE_CONCAVE	Concave edge

# Structures

## PfxExpandedFacet, PfxQuantizedFacet

Facet structure that makes up island mesh of array type

### Definition

```
#include <physics_effects/base_level/collision/pfx_tri_mesh.h>
struct PfxExpandedFacet {
    PfxFloat3 m_normal;
    PfxFloat3 m_half;
    PfxFloat3 m_center;
    PfxFloat m_thickness;
    PfxUInt8 m_vertIds[3];
    PfxUInt8 m_edgeIds[3];
    PfxUInt32 m_userData;
};
struct PfxQuantizedFacet {
    PfxQuantize2 m_normal;
    PfxQuantize3 m_half;
    PfxQuantize3 m_center;
    PfxQuantize m_thickness;
    PfxUInt8 m_vertIds[3];
    PfxUInt8 m_edgeIds[3];
    PfxUInt32 m_userData;
};
```

### Members

<i>m_normal</i>	Normal
<i>m_half</i>	Size
<i>m_center</i>	Center
<i>m_thickness</i>	Thickness of facet
<i>m_vertIds</i>	Vertex index
<i>m_edgeIds</i>	Edge index
<i>m_userData</i>	User data

### Description

This is a facet structure that is created when the array type is specified during large mesh creation.

# Structures

## PfxExpandedFacetBvh, PfxQuantizedFacetBvh

Facet structure that makes up island mesh of BVH type

### Definition

```
#include <physics_effects/base_level/collision/pfx_tri_mesh.h>
struct PfxExpandedFacetBvh {
    PfxFloat3 m_normal;
    PfxFloat m_thickness;
    PfxUInt8 m_vertIds[3];
    PfxUInt8 m_edgeIds[3];
    PfxUInt32 m_userData;
};
struct PfxQuantizedFacetBvh {
    PfxQuantize2 m_normal;
    PfxQuantize m_thickness;
    PfxUInt8 m_vertIds[3];
    PfxUInt8 m_edgeIds[3];
    PfxUInt32 m_userData;
};
```

### Members

<i>m_normal</i>	Normal
<i>m_thickness</i>	Thickness of facet
<i>m_vertIds</i>	Vertex index
<i>m_edgeIds</i>	Edge index
<i>m_userData</i>	User data

### Description

This is a facet structure that is created when the BVH type is specified during large mesh creation.

# Structures

## PfxExpandedTriMesh, PfxQuantizedTriMesh

Island mesh structure of array type

### Definition

```
#include <physics_effects/base_level/collision/pfx_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxExpandedTriMesh {
    PfxUInt8 m_numVerts;
    PfxUInt8 m_numEdges;
    PfxUInt8 m_numFacets;
    PfxEdge *m_edges;
    PfxExpandedFacet *m_facets;
    PfxFloat3 *m_verts;
};
struct SCE_PFX_ALIGNED(16) PfxQuantizedTriMesh {
    PfxUInt8 m_numVerts;
    PfxUInt8 m_numEdges;
    PfxUInt8 m_numFacets;
    PfxEdge *m_edges;
    PfxQuantizedFacet *m_facets;
    PfxQuantize3 *m_verts;
};
```

### Members

<i>m_numVerts</i>	Number of vertices
<i>m_numEdges</i>	Number of edges
<i>m_numFacets</i>	Number of triangles
<i>m_edges</i>	Pointer to edge buffer
<i>m_facets</i>	Pointer to facet buffer
<i>m_verts</i>	Pointer to vertex buffer

### Description

This is an island mesh structure that is created when the array type is specified during large mesh creation. It expresses the partial meshes that make up large meshes and stores groups of divided triangles.

Island meshes being automatically created with the `pfxCreateLargeTriMesh()` function, they need not be explicitly created.

16-byte alignment is required.

# Structures

## PfxExpandedTriMeshBvh, PfxQuantizedTriMeshBvh

Island mesh structure of BVH type

### Definition

```
#include <physics_effects/base_level/collision/pfx_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxExpandedTriMeshBvh {
    PfxUInt8 m_numVerts;
    PfxUInt8 m_numEdges;
    PfxUInt8 m_numFacets;
    PfxEdge *m_edges;
    PfxExpandedFacetBvh *m_facets;
    PfxFloat3 *m_verts;
    PfxAabb16 *m_bvhNodes;
    PfxUInt32 m_bvhRootId;
};

struct SCE_PFX_ALIGNED(16) PfxQuantizedTriMeshBvh {
    PfxUInt8 m_numVerts;
    PfxUInt8 m_numEdges;
    PfxUInt8 m_numFacets;
    PfxEdge *m_edges;
    PfxQuantizedFacetBvh *m_facets;
    PfxQuantize3 *m_verts;
    PfxAabb16 *m_bvhNodes;
    PfxUInt32 m_bvhRootId;
};
```

### Members

<i>m_numVerts</i>	Number of vertices
<i>m_numEdges</i>	Number of edges
<i>m_numFacets</i>	Number of triangles
<i>m_edges</i>	Pointer to edge buffer
<i>m_facets</i>	Pointer to facet buffer
<i>m_verts</i>	Pointer to vertex buffer
<i>m_bvhNodes</i>	Pointer to node buffer of BVH
<i>m_bvhRootId</i>	Root node of BVH

### Description

This is an island mesh structure that is created when the BVH type is specified during large mesh creation.

16-byte alignment is required.

# Structures

## PfxLargeTriMesh

Large mesh structure

### Definition

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    PfxUInt32 m_type;
    PfxVector3 m_offset;
    PfxVector3 m_half;
    PfxUInt16 m_numIslands;
    PfxAabb16 *m_aabbList;
    PfxUInt32 m_numBvhNodes;
    PfxAabb16 *m_bvhNodes;
    PfxUInt32 m_bvhRootId;
    void *m_islands;
};
```

### Members

<i>m_type</i>	Type
<i>m_offset</i>	Center of large mesh
<i>m_half</i>	Size of large mesh
<i>m_numIslands</i>	Number of islands
<i>m_aabbList</i>	AABB array of island mesh
<i>m_numBvhNodes</i>	Number of BVH nodes
<i>m_bvhNodes</i>	BVH node buffer
<i>m_bvhRootId</i>	Root node of BVH
<i>m_islands</i>	Array of island mesh

### Description

This class expresses large mesh shapes. It is used to express complex shapes such as landscapes. One large mesh is made up of several island meshes. To create a large mesh, use the `pfxCreateLargeTriMesh()` utility function.

The following four patterns can be selected as types of large mesh during large mesh creation.

Type	Description
<code>SCE_PFX_LARGE_MESH_TYPE_EXPANDED_ARRAY</code>	The data is expanded and the island is stored in an array.
<code>SCE_PFX_LARGE_MESH_TYPE_QUANTIZED_ARRAY</code>	The data is compressed and the island is stored in an array.
<code>SCE_PFX_LARGE_MESH_TYPE_EXPANDED_BVH</code>	The data is expanded and the island is stored in a BVH.
<code>SCE_PFX_LARGE_MESH_TYPE_QUANTIZED_BVH</code>	The data is compressed and the island is stored in a BVH.

16-byte alignment is required.



**Method List**

Method	Description
PfxLargeTriMesh	Initializes the large mesh parameters
getLocalPosition	Gets the coordinate values of the local coordinates of the large mesh
getWorldPosition	Converts the local coordinates value of the large mesh to the original coordinates
quantizePosition	Compresses the coordinate values
quantizeVector	Compresses the vector
quantizeNormal	Compresses the normal vector
quantizeFloat	Compresses the floating-point value
decodePosition	Expands the compressed coordinate values
decodeVector	Expands the compressed vector
decodeNormal	Expands the compressed normal vector
decodeFloat	Expands the compressed floating-point value
isUsingBvh	Judges whether BVH is used for storing island
isQuantized	Judges whether mesh data is compressed

# Constructors and Destructors

## PfxLargeTriMesh

Initialize large mesh parameters

### Definition

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct PfxLargeTriMesh {
    PfxLargeTriMesh();
};
```

### Arguments

None

### Return Values

None

### Description

Initializes the large mesh parameters.

# Public Methods

## getLocalPosition

Get coordinate values for local coordinates of large mesh

### Definition

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxVecInt3 getLocalPosition(
        const PfxVector3 &worldPos
    ) const;
    inline PfxVecInt3 getLocalPosition(
        const PfxVector3 &worldMinPosition,
        const PfxVector3 &worldMaxPosition,
        PfxVecInt3 &localMinPosition,
        PfxVecInt3 &localMaxPosition
    ) const;
};
```

### Arguments

*worldPos*    Coordinate value

### Return Values

Returns the position in the local coordinate system of the large mesh as the `PfxVecInt3` type.

### Description

This public method converts the coordinate values to the local coordinates of the large mesh. Locally, the coordinates are managed with integers.

SCE CONFIDENTIAL

---

## getWorldPosition

---

Convert local coordinate values of large mesh to original coordinates

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxVector3 getWorldPosition(
        const PfxVecInt3 &localPos
    ) const;
};
```

### Arguments

---

*localPos* Local coordinates

### Return Values

---

Returns the converted coordinate value

### Description

---

The local coordinates are converted to integers and saved. Conversion to floating point numbers is done.

SCE CONFIDENTIAL

---

# quantizePosition

---

Compress coordinate value

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxQuantize3 quantizePosition(
        const PfxVector3 &p
    ) const;
};
```

## Arguments

---

*p* Coordinate value

## Return Values

---

Returns the compressed coordinate value.

## Description

---

The coordinate value is quantized and converted into three 16-bit integer values.

SCE CONFIDENTIAL

---

# quantizeVector

---

## Compress vector

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxQuantize3 quantizeVector(
        const PfxVector3 &v
    ) const;
};
```

### Arguments

---

v Vector

### Return Values

---

Returns the compressed vector.

### Description

---

The vector is quantized and converted into three 16-bit integer values.

SCE CONFIDENTIAL

---

# quantizeNormal

---

Compress normal vector

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxQuantize2 quantizeNormal(
        const PfxVector3 &n
    ) const;
};
```

## Arguments

---

$n$  Normal vector

## Return Values

---

Returns the compressed normal vector.

## Description

---

The normal vector is quantized and converted into two 16-bit integer values.

SCE CONFIDENTIAL

---

# quantizeFloat

---

Compress floating point value

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxQuantize quantizeFloat(
        const PfxVector3 &value
    ) const;
};
```

## Arguments

---

*value* Floating point value

## Return Values

---

Returns the compressed floating point value.

## Description

---

The floating point value is quantized and converted into a 16-bit integer value.



SCE CONFIDENTIAL

---

# decodePosition

---

Expand compressed coordinate value

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxVector3 decodePosition(
        const PfxQuantize3 &q
    ) const;
};
```

## Arguments

---

$q$  Compressed coordinate value

## Return Values

---

Returns the expanded coordinate value.

## Description

---

Converts the compressed coordinate value to the `PfxVector3` type.

SCE CONFIDENTIAL

---

# decodeVector

---

Expand compressed vector

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxVector3 decodeVector(
        const PfxQuantize3 &q
    ) const;
};
```

## Arguments

---

$q$  Compressed vector

## Return Values

---

Returns the expanded vector.

## Description

---

Converts the compressed vector to the PfxVector3 type.

SCE CONFIDENTIAL

---

# decodeNormal

---

Expand compressed normal vector

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxVector3 decodeNormal(
        const PfxQuantize2 &q
    ) const;
};
```

## Arguments

---

$q$  Compressed normal vector

## Return Values

---

Returns the expanded normal vector.

## Description

---

Converts the compressed normal vector to the PfxVector3 type.

SCE CONFIDENTIAL

---

# decodeFloat

---

Expand compressed floating point value

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxFloat decodeFloat(
        PfxQuantize  $q$ 
    ) const;
};
```

## Arguments

---

$q$  Compressed floating point value

## Return Values

---

Returns the expanded floating point value.

## Description

---

Converts the compressed floating point value to the PfxFloat type.

SCE CONFIDENTIAL

---

# isUsingBvh

---

Judge if BVH is used to store island

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxBool isUsingBvh() const
};
```

## Arguments

---

None

## Return Values

---

Returns true when an island is stored as BVH.

SCE CONFIDENTIAL

---

# isQuantized

---

Judge if mesh data is compressed

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_large_tri_mesh.h>
struct SCE_PFX_ALIGNED(16) PfxLargeTriMesh {
    inline PfxBool isQuantized() const
};
```

## Arguments

---

None

## Return Values

---

Returns true when mesh data is compressed.

## Solver Body

000004892117

# Structures

## PfxSolverBody

### Solver body structure

#### Definition

```
#include <physics_effects/base_level/solver/pfx_solver_body.h>
struct SCE_PFX_ALIGNED(128) PfxSolverBody {
    PfxVector3 m_deltaLinearVelocity;
    PfxVector3 m_deltaAngularVelocity;
    PfxQuat m_orientation;
    PfxMatrix3 m_inertiaInv;
    PfxFloat m_massInv;
};
```

#### Members

<i>m_deltaLinearVelocity</i>	Linear velocity difference
<i>m_deltaAngularVelocity</i>	Angular velocity difference
<i>m_orientation</i>	Orientation
<i>m_inertiaInv</i>	Inverse matrix of inertia tensor
<i>m_massInv</i>	Inverse number of mass

#### Description

This is the solver body structure used for solver calculations. It sets the parameters required for solver body structures from the rigid body data with the `pfxSetupSolverBodies()` function.

128-byte alignment is required.



SCE CONFIDENTIAL

---

**Joint**

000004892117

Document serial number: 000004892117

# Structures

## PfxJointConstraint

### Joint constraint structure

#### Definition

```
#include <physics_effects/base_level/solver/pfx_joint_constraint.h>
struct PfxJointConstraint {
    PfxInt8 m_lock;
    PfxInt8 m_warmStarting;
    PfxFloat m_movableLowerLimit;
    PfxFloat m_movableUpperLimit;
    PfxFloat m_bias;
    PfxFloat m_weight;
    PfxFloat m_damping;
    PfxFloat m_maxImpulse;
    PfxConstraintRow m_constraintRow;
};
```

#### Members

<i>m_lock</i>	Type of movement limit on constraint axis
<i>m_warmStarting</i>	Use result of previous frame as initial value
<i>m_movableLowerLimit</i>	Lower limit of movement range on constraint axis
<i>m_movableUpperLimit</i>	Upper limit of movement range on constraint axis
<i>m_bias</i>	Adjustment of constraint force in return direction if movement range is exceeded
<i>m_weight</i>	Weight value for adjusting effect of calculated constraint force
<i>m_damping</i>	Damping value expressing friction on constraint axis
<i>m_maxImpulse</i>	Maximum impulse value
<i>m_constraintRow</i>	Internal parameter used for constraint calculation

#### Description

This structure expresses the joint constraint.

SCE CONFIDENTIAL

# PfxJoint

## Joint structure

### Definition

```
#include <physics_effects/base_level/solver/pfx_joint.h>
struct SCE_PFX_ALIGNED(128) PfxJoint {
    PfxUInt8 m_active;
    PfxUInt8 m_numConstraints;
    PfxUInt8 m_type;
    PfxUInt16 m_rigidBodyIdA;
    PfxUInt16 m_rigidBodyIdB;
    PfxJointConstraint m_constraints[6];
    void *m_userData;
    PfxVector3 m_param[4];
    PfxVector3 m_anchorA;
    PfxVector3 m_anchorB;
    PfxMatrix3 m_frameA;
    PfxMatrix3 m_frameB;
};
```

### Members

<i>m_active</i>	Joint active
<i>m_numConstraints</i>	Number of constraints to be used
<i>m_type</i>	Type of joint
<i>m_rigidBodyIdA</i>	Index of parent rigid body
<i>m_rigidBodyIdB</i>	Index of child rigid body
<i>m_constraints</i>	Constraint
<i>m_userData</i>	User data
<i>m_param</i>	Internally used parameter
<i>m_anchorA</i>	Connection point in parent rigid body coordinates
<i>m_anchorB</i>	Connection point in child rigid body coordinates
<i>m_frameA</i>	Joint frame in parent rigid body coordinates
<i>m_frameB</i>	Joint frame in child rigid body coordinates

### Description

This is a structure that expresses a joint. It has a data structure that forms the basis of all joints. 128-byte alignment is required.

## Sub Data of Collision

000004892117

# Structures

## PfxSubData

Structure storing sub data of large mesh

### Definition

```
#include <physics_effects/base_level/collision/pfx_sub_data.h>
struct PfxSubData {
    PfxUInt8 m_type;
    struct {
        PfxUInt32 userData;
        PfxUInt16 islandId;
        PfxUInt8 facetId;
        PfxUInt16 s;
        PfxUInt16 t;
    } m_facetLocal;
};
```

### Members

<i>m_type</i>	Type
<i>m_facetLocal.userData</i>	User data
<i>m_facetLocal.islandId</i>	Island index
<i>m_facetLocal.facetId</i>	Triangle index
<i>m_facetLocal.s</i>	Coordinates on triangle in barycentric coordinate system
<i>m_facetLocal.t</i>	Coordinates on triangle in barycentric coordinate system

### Description

This structure is used to get the accurate large mesh part, during collision judgment or raycast.

By using the barycentric coordinate system, it is possible to calculate the contact point on a triangle with the following equation.

When the vertices that make up the triangle are P0, P1, and P2, the coordinates can be calculated from the values of *s* and *t* with the following equation.

$$\text{Coordinate} = s * (P1 - P0) + t * (P2 - P0)$$

The values set for type are as follows.

Value	Description
PfxSubData::NONE	No value is set to the sub data
PfxSubData::MESH_INFO	The large mesh data is saved to the sub data

SCE CONFIDENTIAL

**Method List**

Method	Description
PfxSubData	Sets the parameters to their initial values
getIslandId	Gets the island index
setIslandId	Sets the island index
getFacetId	Gets the triangle index
setFacetId	Sets the triangle index
getFacetLocalS, getFacetLocalT	Gets the coordinates on the triangle in the barycentric coordinate system
setFacetLocalS, setFacetLocalT	Sets the coordinates on the triangle in the barycentric coordinate system
getUserData	Gets the user data
setUserData	Sets the user data

# Constructors and Destructors

## PfxSubData

Set parameters to their initial values

### Definition

```
#include <physics_effects/base_level/collision/pfx_sub_data.h>
struct PfxSubData {
    PfxSubData ();
};
```

### Arguments

None

### Return Values

None

### Description

Initializes the parameters of the sub data.

# Public Methods

## getIslandId

Get island index

### Definition

```
#include <physics_effects/base_level/collision/pfx_sub_data.h>
struct PfxSubData {
    PfxUInt16 getIslandId();
};
```

### Arguments

None

### Return Values

Returns the island index.

### Description

This public method gets the island index of the large mesh.



SCE CONFIDENTIAL

---

# setIslandId

---

## Set island index

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_sub_data.h>
struct PfxSubData {
    void setIslandId(PfxUInt16 i);
};
```

### Arguments

---

*i* Island index

### Return Values

---

None

### Description

---

This public method sets the island index of the large mesh.

SCEI CONFIDENTIAL

---

# getFacetId

---

Get triangle index

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_sub_data.h>
struct PfxSubData {
    PfxUInt8 getFacetId();
};
```

## Arguments

---

None

## Return Values

---

Returns the triangle index.

## Description

---

This public method gets the triangle index of the island mesh.

SCEI CONFIDENTIAL

---

## setFacetId

---

### Set triangle index

#### Definition

---

```
#include <physics_effects/base_level/collision/pfx_sub_data.h>
struct PfxSubData {
    void setFacetId(PfxUInt8 i);
};
```

#### Arguments

---

*i* Triangle index

#### Return Values

---

None

#### Description

---

This public method sets the triangle index of the island mesh.

---

## getFacetLocalS, getFacetLocalT

---

Get coordinate values on triangle in barycentric coordinate system

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_sub_data.h>
struct PfxSubData {
    PfxFloat getFacetLocalS();
    PfxFloat getFacetLocalT();
};
```

### Arguments

---

None

### Return Values

---

Returns the coordinate values on the triangle in the barycentric coordinate system.

### Description

---

This public method gets the coordinate values on the triangle in the barycentric coordinate system. Values  $s$  and  $t$  are parameters for calculating the coordinates on the triangle.

SCE CONFIDENTIAL

---

## setFacetLocalS, setFacetLocalT

---

Set coordinate values on triangle in barycentric coordinate system

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_sub_data.h>
struct PfxSubData {
    void setFacetLocalS(PfxFloat s);
    void setFacetLocalT(PfxFloat t);
};
```

### Arguments

---

- s* Value *s* on triangle in barycentric coordinate system
- t* Value *t* on triangle in barycentric coordinate system

### Return Values

---

None

### Description

---

This public method sets the coordinate values on the triangle in the barycentric coordinate system.

SCE CONFIDENTIAL

---

# getUserData

---

Get user data

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_sub_data.h>
struct PfxSubData {
    PfxUInt32 getUserData() ;
};
```

## Arguments

---

None

## Return Values

---

Returns the user data.

## Description

---

This public method gets the user data.

SCEI CONFIDENTIAL

---

## setUserData

---

Set user data

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_sub_data.h>
struct PfxSubData {
    void setUserData(PfxUInt32 data);
};
```

### Arguments

---

*data* User data

### Return Values

---

None

### Description

---

This public method sets the user data.

## Collision Data

000004892117



# Structures

## PfxContactPoint

Structure that stores contact point

### Definition

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
struct PfxContactPoint {
    PfxUInt8 m_duration;
    PfxUInt8 m_shapeIdA;
    PfxUInt8 m_shapeIdB;
    PfxSubData m_subData;
    PfxFloat m_distance;
    PfxFloat m_localPointA[3];
    PfxFloat m_localPointB[3];
    PfxConstraintRow m_constraintRow[3];
};
```

### Members

<i>m_duration</i>	Continuous count
<i>m_shapeIdA</i>	Index of shape A
<i>m_shapeIdB</i>	Index of shape B
<i>m_subData</i>	Sub data of collision
<i>m_distance</i>	Penetration depth
<i>m_localPointA</i>	Collision coordinates in coordinate system of shape A
<i>m_localPointB</i>	Collision coordinates in coordinate system of shape B
<i>m_constraintRow</i>	Structure storing constraint data for solver operation

### Description

This is a structure that stores the parameters related to one contact point. The continuous count is incremented as long as the collision is maintained.

In case of collision with a large mesh, the information indicating the part where the collision occurred is stored in *m\_subData*.

# Classes

## PfxContactManifold

Class that stores collision data

### Definition

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
class SCE_PFX_ALIGNED(128) PfxContactManifold {};
```

### Description

This is the class that manages the collision data. The contact point coordinates change moment by moment as the result of the movement of rigid bodies, but the validity of contact points can be updated by calling `refresh()` at every frame. Contact points whose collision coordinates are at a certain distance or greater are automatically discarded. In addition, the continuous count is incremented while the collision is maintained.

128-byte alignment is required.

### Method List

Method	Description
<code>reset</code>	Resets the parameters to their initial values
<code>addContactPoint</code>	Adds a contact point
<code>removeContactPoint</code>	Deletes a contact point
<code>getNumContacts</code>	Gets the number of contact points
<code>getContactPoint</code>	Gets a contact point
<code>refresh</code>	Updates all the contact points
<code>merge</code>	Merges separate collision data
<code>getDuration</code>	Gets the continuous count
<code>getRigidBodyIdA</code>	Gets the index of rigid body A
<code>getRigidBodyIdB</code>	Gets the index of rigid body B

# Public Methods

## reset

Reset parameters to their initial values

### Definition

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
class SCE_PFX_ALIGNED(128) PfxContactManifold {
    void reset(
        PfxUInt16 rigidBodyIdA,
        PfxUInt16 rigidBodyIdB
    );
};
```

### Arguments

*rigidBodyIdA*   Index A of rigid body  
*rigidBodyIdB*   Index B of rigid body

### Return Values

None

### Description

This public method initializes the collision data parameters.

# addContactPoint

## Add contact point

### Definition

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
class SCE_PFX_ALIGNED(128) PfxContactManifold {
    void addContactPoint(
        PfxFloat newDistance,
        const PfxVector3 &newNormal,
        const PfxPoint3 &newPointA,
        const PfxPoint3 &newPointB,
        PfxSubData subData
    );
    void addContactPoint(
        const PfxContactPoint &cp
    );
};
```

### Arguments

<i>newDistance</i>	Penetration depth
<i>newNormal</i>	Collision normal in world coordinate system
<i>newPointA</i>	Collision coordinates in rigid body A local coordinate system
<i>newPointB</i>	Collision coordinates in rigid body B local coordinate system
<i>subData</i>	Sub data
<i>cp</i>	Structure that stores contact points

### Return Values

None

### Description

This public method adds contact points. Up to four contact points can be held. When a fifth contact point is added, the four points defining the largest area and including the contact point with the deepest depth are selected.

SCE CONFIDENTIAL

---

# removeContactPoint

---

Remove contact point

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
class SCE_PFX_ALIGNED(128) PfxContactManifold {
    void removeContactPoint(int i);
};
```

## Arguments

---

*i* Index of contact point

## Return Values

---

None

## Description

---

This public method removes contact points.

SCE CONFIDENTIAL

---

## getNumContacts

---

Get number of contact points

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
class SCE_PFX_ALIGNED(128) PfxContactManifold {
    int getNumContacts() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the number of contact points.

### Description

---

This public method gets the number of contact points.

SCE CONFIDENTIAL

---

# getContactPoint

---

Get contact point

## Definition

---

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
class SCE_PFX_ALIGNED(128) PfxContactManifold {
    PfxContactPoint &getContactPoint(int i);
    const PfxContactPoint &getContactPoint(int i) const;
};
```

## Arguments

---

*i* Index of contact point

## Return Values

---

Returns a contact point.

## Description

---

This public method gets the contact point of the specified index.

# refresh

Update all contact points

## Definition

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
class SCE_PFX_ALIGNED(128) PfxContactManifold {
    void refresh(
        const PfxVector3 &pA,
        const PfxQuat &qA,
        const PfxVector3 &pB,
        const PfxQuat &qB
    );
};
```

## Arguments

$pA$  Position of rigid body A  
 $qA$  Orientation of rigid body A  
 $pB$  Position of rigid body B  
 $qB$  Orientation of rigid body B

## Return Values

None

## Description

This public method updates all the contact points from the rigid body's new position and orientation. Contact points at a certain distance or greater are discarded.



SCE CONFIDENTIAL

---

## merge

---

---

Merge separate collision data

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
class SCE_PFX_ALIGNED(128) PfxContactManifold {
    void merge(const PfxContactManifold &contact)
};
```

### Arguments

---

*contact* Collision data

### Return Values

---

None

### Description

---

This public method merges separate collision data.

SCE CONFIDENTIAL

---

## getDuration

---

Get continuous count

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
class SCE_PFX_ALIGNED(128) PfxContactManifold {
    PfxUInt16 getDuration() const
};
```

### Arguments

---

None

### Return Values

---

Returns the continuous count.

### Description

---

This public method gets the continuous count.

SCE CONFIDENTIAL

---

## getRigidBodyIdA, getRigidBodyIdB

---

Get indices of rigid bodies A and B

### Definition

---

```
#include <physics_effects/base_level/collision/pfx_contact_manifold.h>
class SCE_PFX_ALIGNED(128) PfxContactManifold {
    PfxUInt16 getRigidBodyIdA() const;
    PfxUInt16 getRigidBodyIdB() const;
};
```

### Arguments

---

None

### Return Values

---

Returns the number of contact points.

### Description

---

This public method gets the number of contact points.

SCE CONFIDENTIAL

---

**Ray**

000004892117

Document serial number: 000004892117

# Structures

## PfxRayInput

### Ray input structure

#### Definition

```
#include <physics_effects/low_level/collision/pfx_ray.h>
struct SCE_PFX_ALIGNED(16) PfxRayInput {
    PfxVector3 m_startPosition;
    PfxVector3 m_direction;
    PfxUInt32 m_contactFilterSelf;
    PfxUInt32 m_contactFilterTarget;
    PfxUInt8 m_facetMode;
};
```

#### Members

<i>m_startPosition</i>	Start point of ray
<i>m_direction</i>	Direction vector of ray
<i>m_contactFilterSelf</i>	Self contact filter (Default value: 0xffffffff)
<i>m_contactFilterTarget</i>	Target contact filter (Default value: 0xffffffff)
<i>m_facetMode</i>	Intersect mode (Default value: SCE_PFX_RAY_FACET_MODE_FRONT_ONLY)

#### Description

This ray structure is expressed with a start point and a direction. It is specified so that the magnitude of the *m\_direction* direction vector is the same as the length of the ray.

16-byte alignment is required.

The contact filter is a filter that allows individual specification of whether to perform judgment of intersection with rigid bodies and shapes.

*m\_facetMode* is a flag that specifies whether to take into consideration the front and back of the triangle when judging intersection with a large mesh.

For *m\_facetMode*, set one of the following values. If a value other than the following values is specified, intersection judgment is not performed.

Value	Description
SCE_PFX_RAY_FACET_MODE_FRONT_ONLY	Judgment only when ray intersects from front to back
SCE_PFX_RAY_FACET_MODE_BACK_ONLY	Judgment only when ray intersects from back to front
SCE_PFX_RAY_FACET_MODE_FRONT_AND_BACK	Both front and back used for judgment

SCE CONFIDENTIAL

# PfxRayOutput

## Ray output structure

### Definition

```
#include <physics_effects/low_level/collision/pfx_ray.h>
struct SCE_PFX_ALIGNED(16) PfxRayOutput {
    PfxVector3 m_contactPoint;
    PfxVector3 m_contactNormal;
    PfxFloat m_variable;
    PfxUInt16 m_objectId;
    PfxUInt8 m_shapeId;
    PfxBool m_contactFlag : 1;
    PfxSubData m_subData;
};
```

### Members

<i>m_contactPoint</i>	Intersection coordinates in world coordinate system
<i>m_contactNormal</i>	Normal vector in world coordinate system
<i>m_variable</i>	Variable indicating intersection position on ray
<i>m_objectId</i>	Object index
<i>m_shapeId</i>	Shape index
<i>m_contactFlag</i>	Intersection flag
<i>m_subData</i>	Sub data

### Description

This structure receives the output from the raycast. The result of the intersection nearest the start point of the ray is stored. Upon detection of the intersection of a ray and object, *m\_contactFlag* is set to true, the rigid body index is returned to *m\_objectId*, and the index indicating which number the shape is among the rigid body shapes is returned to *m\_shapeId*. Moreover, in the case of intersection with a large mesh, the data indicating which part the intersection occurred at is stored in *m\_subData*. 16-byte alignment is required.

# Simulation Island

000004892117

# Structures

## PfxIslandUnit

Simulation island unit structure

### Definition

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
struct PfxIslandUnit {
    // Member not disclosed
};
```

### Members

Members are not disclosed

### Description

This unit expresses a single object (rigid body) included in a simulation island.



SCE CONFIDENTIAL

---

# PfxIsland

---

## Simulation island structure

### Definition

---

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
struct PfxIsland {
    // Member not disclosed
};
```

### Members

---

Members are not disclosed

### Description

---

This is a structure that controls simulation islands.

Document serial number: 000004892117

# Task Manager

000004892117

# Classes

## PfxPsp2TaskManager

PlayStation®Vita task manager

### Definition

```
#include <physics_effects/low_level/task/pfx_task_manager.psp2.h>
class PfxPsp2TaskManager {};
```

### Description

This is a task management class for executing simulation processing in parallel. It is specified for the argument of an API that supports this class, and is executed in parallel on multiple threads by dividing the processing into multiple tasks. Threads that are started up from the task manager immediately enter the event wait status, and the processing waits until an event is issued from the API.

### Method List

Method	Description
PfxPsp2TaskManager	Constructor of task manager
~PfxPsp2TaskManager	Destructor of task manager
getWorkBytes	Gets the size of the work area
getNumTasks	Gets the number of tasks to be used
setNumTasks	Sets the number of tasks to be used
initialize	Initializes the task manager
finalize	Terminates the task manager

# Constructors and Destructors

## PfxPsp2TaskManager

Constructor of task manager

### Definition

```
#include <physics_effects/low_level/task/pfx_task_manager.psp2.h>
class PfxPsp2TaskManager {
    PfxPsp2TaskManager (
        PfxUInt32 numTasks,
        PfxUInt32 maxTasks,
        void *workBuff,
        PfxUInt32 workBytes
    );
};
```

### Arguments

<i>numTasks</i>	Number of execution tasks
<i>maxTasks</i>	Maximum number of tasks
<i>workBuff</i>	Pointer to work area
<i>workBytes</i>	Size of work area

### Return Values

None

### Description

Allocate the value returned from `getWorkBytes()` as the size of the work area buffer to be used by the task manager, and specify it to the constructor.

SCE CONFIDENTIAL

---

## ~PfxPsp2TaskManager

---

Destructor of task manager

### Definition

---

```
#include <physics_effects/low_level/task/pfx_task_manager.psp2.h>
class PfxPsp2TaskManager {
    ~PfxPsp2TaskManager();
};
```

### Arguments

---

None

### Return Values

---

None

### Description

---

Clears the internal buffer.

# Public Methods

## getWorkBytes

Get size of work area to be used by task manager

### Definition

```
#include <physics_effects/low_level/task/pfx_task_manager.psp2.h>
class PfxPsp2TaskManager {
    static PfxUInt32 getWorkBytes(PfxUInt32 maxTasks);
};
```

### Arguments

*maxTasks* Maximum number of tasks

### Return Values

Returns the size of the work area to be used by the task manager.

### Description

This public method gets the size of the work area to be used by the task manager. Allocate a work buffer of the size corresponding to the returned value, and specify it as the constructor argument of the task manager.

SCE CONFIDENTIAL

---

# getNumTasks

---

Get number of execution tasks

## Definition

---

```
#include <physics_effects/low_level/task/pfx_task_manager.psp2.h>
class PfxPsp2TaskManager {
    PfxUInt32 getNumTasks() const;
};
```

## Arguments

---

None

## Return Values

---

Returns the number of execution tasks.

## Description

---

This public method gets the number of execution tasks.

---

# setNumTasks

---

Set number of execution tasks

## Definition

---

```
#include <physics_effects/low_level/task/pfx_task_manager.psp2.h>
class PfxPsp2TaskManager {
    void setNumTasks(PfxUInt32 tasks);
};
```

## Arguments

---

*tasks*    Number of execution tasks

## Return Values

---

None

## Description

---

This public method sets the number of execution tasks. If the maximum number of tasks is exceeded, the maximum number of tasks is set.



SCE CONFIDENTIAL

---

# initialize

---

## Initialize task manager

### Definition

---

```
#include <physics_effects/low_level/task/pfx_task_manager.psp2.h>
class PfxPsp2TaskManager {
    void initialize();
};
```

### Arguments

---

None

### Return Values

---

None

### Description

---

This public method initializes the task manager. The number of threads corresponding to the maximum number of tasks is started up.

SCE CONFIDENTIAL

---

# finalize

---

Terminate task manager

## Definition

---

```
#include <physics_effects/low_level/task/pfx_task_manager.psp2.h>
class PfxPsp2TaskManager {
    void finalize();
};
```

## Arguments

---

None

## Return Values

---

None

## Description

---

This public method terminates the task manager. It closes all the threads and releases their resources.

# Heap Manager

000004892117

# Classes

## PfxHeapManager

Heap manager

### Definition

```
#include <physics_effects/base_level/base/pfx_heap_manager.h>
class PfxHeapManager {};
```

### Description

Heap Manager is a simple memory manager that uses stacks. The memory allocated by an application beforehand is specified to the constructor of the heap manager. The heap manager pools this memory and uses it by carving out some memory from this pool when needed. Memory allocation and release being implemented by using stacks, there is the limitation of having to release memory resources in the opposite sequence to the allocation sequence, but this operation is extremely fast and memory fragmentation is not an issue.

### Method List

Method	Description
PfxHeapManager	Constructor of heap manager
~PfxHeapManager	Destructor of heap manager
allocate	Allocates buffers
deallocate	Releases buffer allocations
clear	Releases all buffers
getAllocated	Gets the number of bytes of allocated buffers
getRest	Gets the number of remaining bytes that can be allocated

# Constructors and Destructors

## PfxHeapManager

Constructor of heap manager

### Definition

```
#include <physics_effects/base_level/base/pfx_heap_manager.h>
class PfxHeapManager {
    PfxHeapManager (
        PfxUInt8 *buf,
        PfxInt32 bytes
    );
};
```

### Arguments

*buf*      Address of buffer  
*bytes*    Size of buffer

### Return Values

None

### Description

The buffers assigned to the constructor argument are initialized through internal pooling.

SCE CONFIDENTIAL

---

## ~PfxHeapManager

---

Destructor of heap manager

### Definition

---

```
#include <physics_effects/base_level/base/pfx_heap_manager.h>
class PfxHeapManager {
    ~PfxHeapManager();
};
```

### Arguments

---

None

### Return Values

---

None

### Description

---

Nothing is done.

# Public Methods

## allocate

Allocate memory of specified size

### Definition

```
#include <physics_effects/base_level/base/pfx_heap_manager.h>
class PfxHeapManager {
    void *allocate(
        size_t bytes,
        PfxInt32 alignment
    )
};
```

### Arguments

*bytes*            Number of bytes of memory to be allocated  
*alignment*       Alignment specification

### Return Values

Returns the address of the allocated memory.

### Description

The minimum allocation size is 16 bytes. The alignments that can be specified are only 16-byte and 128-byte alignment. If nothing is specified, 16-byte alignment is automatically selected. Assert is called if allocation fails.

SCEI CONFIDENTIAL

---

# deallocate

---

Release allocated memory

## Definition

---

```
#include <physics_effects/base_level/base/pfx_heap_manager.h>
class PfxHeapManager {
    void deallocate(void *p);
};
```

## Arguments

---

*p* Address of allocated memory

## Return Values

---

None

## Description

---

This public method releases allocated memory. Be sure to call this public method in the reverse sequence to the call sequence.



SCE CONFIDENTIAL

---

# clear

---

---

Initialize memory

## Definition

---

```
#include <physics_effects/base_level/base/pfx_heap_manager.h>
class PfxHeapManager {
    void clear();
};
```

## Arguments

---

None

## Return Values

---

None

## Description

---

This public method releases all the allocated memories.

SCE CONFIDENTIAL

---

## getAllocated

---

Get number of bytes of allocated memory

### Definition

---

```
#include <physics_effects/base_level/base/pfx_heap_manager.h>
class PfxHeapManager {
    PfxInt32 getAllocated();
};
```

### Arguments

---

None

### Return Values

---

Returns the number of bytes of the allocated memory.

### Description

---

This public method gets the number of bytes of the allocated memory.

SCE CONFIDENTIAL

---

## getRest

---

Get number of bytes of allocatable memory

### Definition

---

```
#include <physics_effects/base_level/base/pfx_heap_manager.h>
class PfxHeapManager {
    PfxInt32 getRest() ;
};
```

### Arguments

---

None

### Return Values

---

Returns the number of bytes of the allocatable memory.

### Description

---

This public method gets the number of bytes of the allocatable memory.

## Joint APIs

000004892117

---

# pfxUpdateJointPairs

---

## Update joint pairs

### Definition

---

```
#include <physics_effects/base_level/solver/pfx_joint.h>
void pfxUpdateJointPairs (
    PfxConstraintPair &pair,
    PfxUInt32 jointId,
    const PfxJoint &joint,
    const PfxRigidState &stateA,
    const PfxRigidState &stateB
)
```

### Arguments

---

<i>pair</i>	Joint pair
<i>jointId</i>	Joint index
<i>joint</i>	Joint structure
<i>stateA</i>	Parent rigid body state
<i>stateB</i>	Child rigid body state

### Return Values

---

None

### Description

---

Sets joint-related parameters to one `PfxConstraintPair` structure. One pair has a data structure that allows efficient access to related data and is used during solver operations.

# PfxBallJointInitParam

Ball joint initialization parameter

## Definition

```
#include <physics_effects/base_level/solver/pfx_joint_ball.h>
struct PfxBallJointInitParam {
    PfxVector3 anchorPoint;
    PfxMatrix3 jointFrame;
    PfxBool enableJointFrame;
    PfxFloat damping;
};
```

## Members

<i>anchorPoint</i>	Connection coordinate value of joint (Default value: (0.0f, 0.0f, 0.0f))
<i>jointFrame</i>	Joint frame
<i>enableJointFrame</i>	Enable joint frame (default: false)
<i>damping</i>	Damping

## Description

This structure is used to specify parameters when initializing ball joints with `pfxInitializeBallJoint()`. It is used to reproduce a joint connected at one point only that can turn freely.

SCE CONFIDENTIAL

---

# pfxInitializeBallJoint

---

## Initialize ball joint

### Definition

---

```
#include <physics_effects/base_level/solver/pfx_joint_ball.h>
PfxInt32 pfxInitializeBallJoint(
    PfxJoint &joint,
    const PfxRigidState &stateA,
    const PfxRigidState &stateB,
    const PfxBallJointInitParam &param
)
```

### Arguments

---

*joint* Joint structure  
*stateA* Parent rigid body state  
*stateB* Child rigid body state  
*param* Joint initialization parameters

### Return Values

---

Returns SCE\_PFX\_OK(0) upon normal termination.  
Returns the error SCE\_PFX\_ERR\_OUT\_OF\_RANGE if the parameter range is incorrect.

### Description

---

This is a function that initializes ball joints.

# PfxSwingTwistJointInitParam

## Swing twist joint initialization parameters

### Definition

```
#include <physics_effects/base_level/solver/pfx_joint_swing_twist.h>
struct PfxSwingTwistJointInitParam {
    PfxVector3 anchorPoint;
    PfxVector3 twistAxis;
    PfxFloat twistLowerAngle;
    PfxFloat twistUpperAngle;
    PfxFloat swingLowerAngle;
    PfxFloat swingUpperAngle;
    PfxMatrix3 jointFrame;
    PfxBool enableJointFrame;
    PfxFloat damping;
    PfxFloat bias;
};
```

### Members

<i>anchorPoint</i>	Connection coordinate value of joint (default value: (0.0f, 0.0f, 0.0f))
<i>twistAxis</i>	Twist axis (default value: (1.0f, 0.0f, 0.0f))
<i>twistLowerAngle</i>	Radian value of lower limit of twist angle (default value: -0.26f)
<i>twistUpperAngle</i>	Radian value of upper limit of twist angle (default value: 0.26f)
<i>swingLowerAngle</i>	Radian value of lower limit of swing angle (default value: 0.0f)
<i>swingUpperAngle</i>	Radian value of upper limit of swing angle (default value: 0.7f)
<i>jointFrame</i>	Joint frame
<i>enableJointFrame</i>	Enable joint frame (default value: false)
<i>damping</i>	Damping
<i>bias</i>	Adjustment value for the joint's rigidity

### Description

This structure is used to specify parameters when initializing swing twist joints with `pfxInitializeSwingTwistJoint()`. It is used when reproducing joints that have the movement range of cylinders like shoulders. Specify that the twist angle is between -180 degrees and 180 degrees, and the swing angle is between 0 degrees and 180 degrees.



SCE CONFIDENTIAL

---

# pfxInitializeSwingTwistJoint

---

Initialize swing twist joint

## Definition

---

```
#include <physics_effects/base_level/solver/pfx_joint_swing_twist.h>
PfxInt32 pfxInitializeSwingTwistJoint(
    PfxJoint &joint,
    const PfxRigidState &stateA,
    const PfxRigidState &stateB,
    const PfxSwingTwistJointInitParam &param
)
```

## Arguments

---

*joint* Joint structure  
*stateA* Parent rigid body state  
*stateB* Child rigid body state  
*param* Joint initialization parameter

## Return Values

---

Returns SCE\_PFX\_OK (0) upon normal termination.  
Returns the error SCE\_PFX\_ERR\_OUT\_OF\_RANGE if the parameter range is incorrect.

## Description

---

This function initializes swing twist joints.

# PfxHingeJointInitParam

## Hinge joint initialization parameters

### Definition

```
#include <physics_effects/base_level/solver/pfx_joint_hinge.h>
struct PfxHingeJointInitParam {
    PfxVector3 anchorPoint;
    PfxVector3 axis;
    PfxFloat lowerAngle;
    PfxFloat upperAngle;
    PfxMatrix3 jointFrame;
    PfxBool enableJointFrame;
    PfxFloat damping;
    PfxFloat bias;
};
```

### Members

<i>anchorPoint</i>	Connection coordinate value of joint (default value: (0.0f, 0.0f, 0.0f))
<i>axis</i>	Movable axis of hinge (default value: (1.0f, 0.0f, 0.0f))
<i>lowerAngle</i>	Radian value of lower limit of hinge angle (default value: 0.0f)
<i>upperAngle</i>	Radian value of upper limit of hinge angle (default value: 0.0f)
<i>jointFrame</i>	Joint frame
<i>enableJointFrame</i>	Enable joint frame (default value: false)
<i>damping</i>	Damping
<i>bias</i>	Adjustment value for the joint's rigidity

### Description

This structure is used to specify parameters when initializing hinge joints with `pfxInitializeHingeJoint()`. It is used when reproducing joints that have a hinge-like structure. Specify that the hinge angle is between -180 degrees and 180 degrees.

SCE CONFIDENTIAL

---

# pfxInitializeHingeJoint

---

Initialize hinge joint

## Definition

---

```
#include <physics_effects/base_level/solver/pfx_joint_hinge.h>
PfxInt32 pfxInitializeHingeJoint(
    PfxJoint &joint,
    const PfxRigidState &stateA,
    const PfxRigidState &stateB,
    const PfxHingeJointInitParam &param
)
```

## Arguments

---

*joint* Joint structure  
*stateA* Parent rigid body state  
*stateB* Child rigid body state  
*param* Joint initialization parameter

## Return Values

---

Returns SCE\_PFX\_OK (0) upon normal termination.  
Returns the error SCE\_PFX\_ERR\_OUT\_OF\_RANGE if the parameter range is incorrect.

## Description

---

This function initializes hinge joints.

# PfxSliderJointInitParam

Slider joint initialization parameter

## Definition

```
#include <physics_effects/base_level/solver/pfx_joint_slider.h>
struct PfxSliderJointInitParam {
    PfxVector3 anchorPoint;
    PfxVector3 direction;
    PfxFloat lowerDistance;
    PfxFloat upperDistance;
    PfxMatrix3 jointFrame;
    PfxBool enableJointFrame;
    PfxFloat damping;
    PfxFloat bias;
};
```

## Members

<i>anchorPoint</i>	Connection coordinate value of joint (default value: (0.0f, 0.0f, 0.0f))
<i>direction</i>	Movable axis of slider (default value: (1.0f, 0.0f, 0.0f))
<i>lowerDistance</i>	Lower limit of movable distance (default value: 0.0f)
<i>upperDistance</i>	Upper limit of movable distance (default value: 0.0f)
<i>jointFrame</i>	Joint frame
<i>enableJointFrame</i>	Enable joint frame (default value: false)
<i>damping</i>	Damping
<i>bias</i>	Adjustment value for the joint's rigidity

## Description

This structure is used to specify parameters when initializing slider joints with `pfxInitializeSliderJoint()`. It is used to reproduce joints that can move only in a specific direction.

SCE CONFIDENTIAL

# pfxInitializeSliderJoint

Initialize slider joint

## Definition

```
#include <physics_effects/base_level/solver/pfx_joint_slider.h>
PfxInt32 pfxInitializeSliderJoint(
    PfxJoint &joint,
    const PfxRigidState &stateA,
    const PfxRigidState &stateB,
    const PfxSliderJointInitParam &param
)
```

## Arguments

*joint* Joint structure  
*stateA* Parent rigid body state  
*stateB* Child rigid body state  
*param* Joint initialization parameter

## Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.  
 Returns the error SCE\_PFX\_ERR\_OUT\_OF\_RANGE if the parameter range is incorrect.

## Description

This function initializes slider joints.

---

# PfxFixJointInitParam

---

Fixed joint initialization parameter

## Definition

---

```
#include <physics_effects/base_level/solver/pfx_joint_fix.h>
struct PfxFixJointInitParam {
    PfxVector3 anchorPoint;
};
```

## Members

---

*anchorPoint* Connection coordinate value of joint (default value: (0.0f, 0.0f, 0.0f))

## Description

---

This structure is used to specify parameters when initializing fixed joints with `pfxInitializeFixJoint()`. It is used to fix two rigid bodies at a single point.

SCE CONFIDENTIAL

---

# pfxInitializeFixJoint

---

Initialize fixed joint

## Definition

---

```
#include <physics_effects/base_level/solver/pfx_joint_fix.h>
PfxInt32 pfxInitializeFixJoint(
    PfxJoint &joint,
    const PfxRigidState &stateA,
    const PfxRigidState &stateB,
    const PfxFixJointInitParam &param
)
```

## Arguments

---

*joint* Joint structure  
*stateA* Parent rigid body state  
*stateB* Child rigid body state  
*param* Joint initialization parameter

## Return Values

---

Returns SCE\_PFX\_OK (0) upon normal termination.  
Returns the error SCE\_PFX\_ERR\_OUT\_OF\_RANGE if the parameter range is incorrect.

## Description

---

This function initializes fixed joints.

# PfxUniversalJointInitParam

Universal joint initialization parameter

## Definition

```
#include <physics_effects/base_level/solver/pfx_joint_universal.h>
struct PfxUniversalJointInitParam {
    PfxVector3 anchorPoint;
    PfxVector3 axis;
    PfxVector3 upVec;
    PfxFloat swing1LowerAngle;
    PfxFloat swing1UpperAngle;
    PfxFloat swing2LowerAngle;
    PfxFloat swing2UpperAngle;
    PfxMatrix3 jointFrame;
    PfxBool enableJointFrame;
    PfxFloat damping;
    PfxFloat bias;
};
```

## Members

<i>anchorPoint</i>	Connection coordinate value of joint (default value: (0.0f, 0.0f, 0.0f))
<i>axis</i>	Movable axis (default value: (1.0f, 0.0f, 0.0f))
<i>upVec</i>	Up vector (default value: (0.0f, 1.0f, 0.0f))
<i>swing1LowerAngle</i>	Lower limit of swing 1 angle (default value: -0.7f)
<i>swing1UpperAngle</i>	Upper limit of swing 1 angle (default value: 0.7f)
<i>swing2LowerAngle</i>	Lower limit of swing 2 angle (default value: -0.7f)
<i>swing2UpperAngle</i>	Upper limit of swing 2 angle (default value: 0.7f)
<i>jointFrame</i>	Joint frame
<i>enableJointFrame</i>	Enable joint frame (default value: false)
<i>damping</i>	Damping
<i>bias</i>	Adjustment value of the joint's rigidity

## Description

This structure is used to specify parameters when initializing universal joints with `pfxInitializeUniversalJoint()`. It is used to reproduce a joint that has two swing axes. Specify that the swing angle is between 0 degrees and 180 degrees.

When the movable scopes of both axes exceed 90 degrees and the two axes become closer to being perpendicular, behavior will become unstable. When the movable scope of one axis exceeds 90 degrees, make sure to specify a value that does not exceed 90 for the other axis.



---

# pfxInitializeUniversalJoint

---

## Initialize universal joint

### Definition

---

```
#include <physics_effects/base_level/solver/pfx_joint_universal.h>
PfxInt32 pfxInitializeUniversalJoint(
    PfxJoint &joint,
    const PfxRigidState &stateA,
    const PfxRigidState &stateB,
    const PfxUniversalJointInitParam &param
)
```

### Arguments

---

*joint* Joint structure  
*stateA* Parent rigid body state  
*stateB* Child rigid body state  
*param* Joint initialization parameter

### Return Values

---

Returns SCE\_PFX\_OK(0) upon normal termination.  
Returns the error SCE\_PFX\_ERR\_OUT\_OF\_RANGE if the parameter range is incorrect.

### Description

---

This function initializes universal joints.

## Broad Phase APIs

000004892117

SCE CONFIDENTIAL

# pfxUpdateBroadphaseProxy

Create broadphase proxy

## Definition

```
#include
<physics_effects/base_level/broadphase/pfx_update_broadphase_proxy.h>
PfxInt32 pfxUpdateBroadphaseProxy(
    PfxBroadphaseProxy &proxy,
    const PfxRigidState &state,
    const PfxCollidable &coll,
    const PfxVector3 &worldCenter,
    const PfxVector3 &worldExtent,
    PfxUInt32 axis
)
```

## Arguments

<i>proxy</i>	Broadphase proxy
<i>state</i>	Rigid body state
<i>coll</i>	Rigid body shape
<i>worldCenter</i>	Center of world space
<i>worldExtent</i>	Size of world space
<i>axis</i>	Detection axis

## Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.

Returns the error SCE\_PFX\_ERR\_OUT\_OF\_WORLD when the position of the rigid body is outside the world space.

## Description

Copies the parameters from the rigid body data to the broadphase proxy. The broadphase proxy is used to detect intersecting pairs. The minimum value on the detection axis of the bounding box of the rigid body is stored as the sort key.

SCE CONFIDENTIAL

# pfxUpdateBroadphaseProxy

## Creation of broadphase proxy

### Definition

```
#include
<physics_effects/base_level/broadphase/pfx_update_broadphase_proxy.h>
PfxInt32 pfxUpdateBroadphaseProxy(
    PfxBroadphaseProxy &proxyX,
    PfxBroadphaseProxy &proxyY,
    PfxBroadphaseProxy &proxyZ,
    PfxBroadphaseProxy &proxyXb,
    PfxBroadphaseProxy &proxyYb,
    PfxBroadphaseProxy &proxyZb,
    const PfxRigidState &state,
    const PfxCollidable &coll,
    const PfxVector3 &worldCenter,
    const PfxVector3 &worldExtent
)
```

### Arguments

<i>proxyX</i>	Broadphase proxy (sort in +X axis direction)
<i>proxyY</i>	Broadphase proxy (sort in +Y axis direction)
<i>proxyZ</i>	Broadphase proxy (sort in +Z axis direction)
<i>proxyXb</i>	Broadphase proxy (sort in -X axis direction)
<i>proxyYb</i>	Broadphase proxy (sort in -Y axis direction)
<i>proxyZb</i>	Broadphase proxy (sort in -Z axis direction)
<i>state</i>	Rigid body state
<i>coll</i>	Rigid body shape
<i>worldCenter</i>	Center of world space
<i>worldExtent</i>	Size of world space

### Return Values

Returns SCE\_PFX\_OK (0) upon normal termination.

Returns the error SCE\_PFX\_ERR\_OUT\_OF\_WORLD when the position of the rigid body is outside the world space.

### Description

Simultaneously creates broadphase proxies corresponding to each of the axes from the rigid body data. The minimum (or maximum) value of the bounding box of the rigid body for each of the axes is stored as the sort key.

# PfxUpdateBroadphaseProxiesParam

Parameters used to update broadphase proxy arrays

## Definition

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
struct PfxUpdateBroadphaseProxiesParam {
    void *workBuff;
    PfxUInt32 workBytes;
    PfxBroadphaseProxy *proxiesX;
    PfxBroadphaseProxy *proxiesY;
    PfxBroadphaseProxy *proxiesZ;
    PfxBroadphaseProxy *proxiesXb;
    PfxBroadphaseProxy *proxiesYb;
    PfxBroadphaseProxy *proxiesZb;
    PfxRigidState *offsetRigidStates;
    PfxCollidable *offsetCollidables;
    PfxUInt32 numRigidBodies;
    PfxUInt32 outOfWorldBehavior;
    PfxVector3 worldCenter;
    PfxVector3 worldExtent;
};
```

## Members

<i>workBuff</i>	Pointer to work area
<i>workBytes</i>	Size of work area
<i>proxiesX</i>	Broadphase proxy array sorted in +X axis direction (16-byte alignment)
<i>proxiesY</i>	Broadphase proxy array sorted in +Y axis direction (16-byte alignment)
<i>proxiesZ</i>	Broadphase proxy array sorted in +Z axis direction (16-byte alignment)
<i>proxiesXb</i>	Broadphase proxy array sorted in -X axis direction (16-byte alignment)
<i>proxiesYb</i>	Broadphase proxy array sorted in -Y axis direction (16-byte alignment)
<i>proxiesZb</i>	Broadphase proxy array sorted in -Z axis direction (16-byte alignment)
<i>offsetRigidStates</i>	Offset address of rigid body state array (128-byte alignment)
<i>offsetCollidables</i>	Offset address of rigid body shape array (128-byte alignment)
<i>numRigidBodies</i>	Number of broadphase proxies
<i>outOfWorldBehavior</i>	Handling of rigid body placed out of world (default value: 0)
<i>worldCenter</i>	Center of world space
<i>worldExtent</i>	Size of world space

## Description

This structure is used to specify the parameters passed to the `pfxUpdateBroadphaseProxies()` function for updating broadphase proxy arrays. Six broadphase proxy arrays, corresponding to the number of rigid bodies, must be allocated in advance.

The handling of rigid bodies placed out of world can be specified with the following flag combinations.

Value	Description
<code>SCE_PFX_OUT_OF_WORLD_BEHAVIOR_FIX_MOTION</code>	Changes the motion type to fixed
<code>SCE_PFX_OUT_OF_WORLD_BEHAVIOR_REMOVE_PROXY</code>	Removes proxy array member from proxy array

---

# PfxUpdateBroadphaseProxiesResult

---

Structure that receives broadphase proxy array update result

## Definition

---

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
struct PfxUpdateBroadphaseProxiesResult {
    PfxInt32 numOutOfWorldProxies;
};
```

## Members

---

*numOutOfWorldProxies*    Number of rigid bodies placed out of world

## Description

---

This structure is used to receive the result of the `pfxUpdateBroadphaseProxies()` function for updating broadphase proxy arrays.

# **pfxGetWorkBytesOfUpdateBroadphaseProxies**

Get size of work area used for updating broadphase proxy array

## **Definition**

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
PfxUInt32 pfxGetWorkBytesOfUpdateBroadphaseProxies(
    PfxUInt32 numRigidBodies
)
PfxUInt32 pfxGetWorkBytesOfUpdateBroadphaseProxies(
    PfxUInt32 numRigidBodies,
    PfxUInt32 maxTasks
)
```

## **Arguments**

<i>numRigidBodies</i>	Number of rigid bodies
<i>maxTasks</i>	Number of tasks

## **Return Values**

Returns the size of the work area used for broadphase proxy creation.

## **Description**

Allocate a work buffer of the returned size and specify it for the `PfxUpdateBroadphaseProxiesParam` broadphase proxy array update parameter.

# pfxUpdateBroadphaseProxies

## Update broadphase proxy array

### Definition

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
PfxInt32 pfxUpdateBroadphaseProxies (
    PfxUpdateBroadphaseProxiesParam &param,
    PfxUpdateBroadphaseProxiesResult &result
)
// Parallel version
PfxInt32 pfxUpdateBroadphaseProxies (
    PfxUpdateBroadphaseProxiesParam &param,
    PfxUpdateBroadphaseProxiesResult &result,
    PfxTaskManager *taskManager
)
```

### Arguments

*param* Input parameter  
*result* Structure that receives result  
*taskManager* Task manager (only when multithread is used)

### Return Values

Returns SCE\_PFX\_OK (0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid
SCE_PFX_ERR_OUT_OF_BUFFER	Specified buffer capacity is insufficient

### Description

This structure is used to update all the broadphase proxy arrays corresponding to all the axis directions, and sort them by axis. Updated broadphase proxy arrays can be used for intersecting pair detection and raycasts.

If a rigid body has been placed outside the specified world area, its handling is decided according to the specification of the *outOfWorldBehavior* flag of *PfxUpdateBroadphaseProxiesParam*. If removal from the proxy array is specified, the final number of valid arrays is *param.numRigidBodies* - *result.numOutOfWorldProxies*.



# PfxFindPairsParam

Parameters used for intersecting pair detection

## Definition

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
struct PfxFindPairsParam {
    void *workBuff;
    PfxUInt32 workBytes;
    void *pairBuff;
    PfxUInt32 pairBytes;
    PfxBroadphaseProxy *proxies;
    PfxUInt32 numProxies;
    PfxUInt32 maxPairs;
    int axis;
};
```

## Members

<i>workBuff</i>	Pointer to work area
<i>workBytes</i>	Size of work area
<i>pairBuff</i>	Pointer to pair buffer (16-byte alignment)
<i>pairBytes</i>	Size of pair buffer
<i>proxies</i>	Pointer to broadphase proxy array (16-byte alignment)
<i>numProxies</i>	Number of broadphase proxies
<i>maxPairs</i>	Maximum number of pairs that can be acquired
<i>axis</i>	Detection axis

## Description

This structure is used to specify the parameters to be passed to the `pfxFindPairs()` intersecting pair detection function. Align the pair buffer at the 16-byte boundary. The broadphase proxy array must be sorted in advance along the detection axis.

---

# PfxFindPairsResult

---

Structure that receives intersecting pair detection result

## Definition

---

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
struct PfxFindPairsResult {
    PfxBroadphasePair *pairs;
    PfxUInt32 numPairs;
};
```

## Members

---

*pairs*      Pair array  
*numPairs*   Number of detected pairs

## Description

---

This structure is used to receive the results of the `pfxFindPairs()` intersecting pair detection function. Detected intersecting pairs are sorted according to a unique value created from two rigid body indices.

SCE CONFIDENTIAL

---

## pfxGetWorkBytesOfFindPairs

---

Get size of work area used for intersecting pair detection

### Definition

---

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
PfxUInt32 pfxGetWorkBytesOfFindPairs(
    PfxUInt32 maxPairs,
    PfxUInt32 maxTasks
)
```

### Arguments

---

*maxPairs* Maximum number of pairs that can be acquired  
*maxTasks* Number of tasks (default value: 1)

### Return Values

---

Returns the size of the work area used for intersecting pair detection.

### Description

---

Allocate a work buffer of the returned size and specify it for the `PfxFindPairsParam` intersecting pair detection parameter.

SCE CONFIDENTIAL

---

## pfxGetPairBytesOfFindPairs

---

Get size of pair buffer returned upon intersecting pair detection

### Definition

---

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
PfxUInt32 pfxGetPairBytesOfFindPairs(
    PfxUInt32 maxPairs
)
```

### Arguments

---

*maxPairs* Maximum number of pairs that can be acquired

### Return Values

---

Returns the size of the pair buffer returned upon intersecting pair detection.

### Description

---

Allocate a pair buffer of the returned size and specify it for the `PfxFindPairsParam` intersecting pair detection parameter.

SCE CONFIDENTIAL

# pfxFindPairs

Detect intersection of broadphase proxies

## Definition

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
PfxInt32 pfxFindPairs (
    PfxFindPairsParam &param,
    PfxFindPairsResult &result
)
// Parallel version
PfxInt32 pfxFindPairs (
    PfxFindPairsParam &param,
    PfxFindPairsResult &result,
    PfxTaskManager *taskManager
)
```

## Arguments

*param*            Input parameter  
*result*            Structure that receives result  
*taskManager*    Task manager (only when multithread is used)

## Return Values

Returns SCE\_PFX\_OK (0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid
SCE_PFX_ERR_OUT_OF_BUFFER	Specified buffer capacity is insufficient
SCE_PFX_ERR_OUT_OF_MAX_PAIRS	Number of detected pairs exceeds specified value

## Description

Detects pairs of broadphase proxies whose bounding boxes (AABB) intersect, and returns the result to `PfxFindPairsResult`. The area of the pair array returned as a result is acquired from the pair buffer specified to `PfxFindPairsParam`. Do not discard the pair buffer until after it has finished being used. Since it is not possible to know in advance the maximum number of detected pairs, specify the maximum number of pairs with some extra. If the number of detected pairs exceeds the maximum number of pairs, the `SCE_PFX_ERR_OUT_OF_MAX_PAIRS` error is returned. In this case, allocate a larger capacity buffer and execute `pfxFindPairs()` again.

\* To create a broadphase proxy, use `pfxUpdateBroadphaseProxy()`.

# PfxDecomposePairsParam

Parameters used for comparing intersecting pairs

## Definition

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
struct PfxDecomposePairsParam {
    void *workBuff;
    PfxUInt32 workBytes;
    void *pairBuff;
    PfxUInt32 pairBytes;
    PfxBroadphasePair *previousPairs;
    PfxUInt32 numPreviousPairs;
    PfxBroadphasePair *currentPairs;
    PfxUInt32 numCurrentPairs;
};
```

## Members

<i>workBuff</i>	Pointer to work area
<i>workBytes</i>	Size of work area
<i>pairBuff</i>	Pointer to pair buffer(16-byte alignment)
<i>pairBytes</i>	Size of pair buffer
<i>previousPairs</i>	Sorted previous pair array (16-byte alignment)
<i>numPreviousPairs</i>	Number of previous pairs
<i>currentPairs</i>	Sorted newly detected pair array (16-byte alignment)
<i>numCurrentPairs</i>	Number of newly detected pairs

## Description

This structure is used to specify the parameters to be passed to the `pfxDecomposePairs()` function for comparing two pair arrays. Sort in advance the pair arrays specified for *previousPairs* and *currentPairs*. The key value for sorting is automatically appended by the `pfxFindPairs()` function. Align the pair buffer and pair arrays at the 16-byte boundary.

# PfxDecomposePairsResult

Structure that receives result of intersecting pair comparison

## Definition

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
struct PfxDecomposePairsResult {
    PfxBroadphasePair *outNewPairs;
    PfxUInt32 numOutNewPairs;
    PfxBroadphasePair *outKeepPairs;
    PfxUInt32 numOutKeepPairs;
    PfxBroadphasePair *outRemovePairs;
    PfxUInt32 numOutRemovePairs;
};
```

## Members

<i>outNewPairs</i>	New pair array
<i>numOutNewPairs</i>	Number of new pairs
<i>outKeepPairs</i>	Kept pair array
<i>numOutKeepPairs</i>	Number of kept pairs
<i>outRemovePairs</i>	Discarded pair array
<i>numOutRemovePairs</i>	Number of discarded pairs

## Description

This structure is used to receive the result of the `pfxDecomposePairs()` intersecting pair comparison function.

---

## pfxGetWorkBytesOfDecomposePairs

---

Get size of work area used for intersecting pair comparison

### Definition

---

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
PfxUInt32 pfxGetWorkBytesOfDecomposePairs (
    PfxUInt32 numPreviousPairs,
    PfxUInt32 numCurrentPairs,
    int maxTasks
)
```

### Arguments

---

<i>numPreviousPairs</i>	Number of previous detected pairs
<i>numCurrentPairs</i>	Number of current detected pairs
<i>maxTasks</i>	Number of tasks (default value: 1)

### Return Values

---

Returns the size of the work area used for intersecting pair comparison.

### Description

---

Allocate a work buffer of the returned size and specify it for the `PfxDecomposePairsParam` intersecting pair comparison parameter.



SCE CONFIDENTIAL

---

## pfxGetPairBytesOfDecomposePairs

---

Get size of pair buffer returned during intersecting pair comparison

### Definition

---

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
PfxUInt32 pfxGetPairBytesOfDecomposePairs (
    PfxUInt32 numPreviousPairs,
    PfxUInt32 numCurrentPairs
)
```

### Arguments

---

<i>numPreviousPairs</i>	Number of previous detected pairs
<i>numCurrentPairs</i>	Number of current detected pairs

### Return Values

---

Returns the size of the pair buffer returned during intersecting pair comparison.

### Description

---

Allocate a pair buffer of the returned size and specify it to the `PfxDecomposePairsParam` intersecting pair comparison parameter.

# pfxDecomposePairs

Compare two intersecting pairs

## Definition

```
#include <physics_effects/low_level/broadphase/pfx_broadphase.h>
PfxInt32 pfxDecomposePairs (
    PfxDecomposePairsParam &param,
    PfxDecomposePairsResult &result
)
// Parallel version
PfxInt32 pfxDecomposePairs (
    PfxDecomposePairsParam &param,
    PfxDecomposePairsResult &result,
    PfxTaskManager *taskManager
)
```

## Arguments

*param*            Input parameter  
*result*            Structure that receives result  
*taskManager*    Task manager (only when multithread is used)

## Return Values

Returns SCE\_PFX\_OK (0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid
SCE_PFX_ERR_OUT_OF_BUFFER	Specified buffer capacity is insufficient

## Description

Compares new and old pair arrays and returns the result to PfxDecomposePairsResult. Returns the result as new pairs in the case of pairs that only exist in the new pair arrays, as kept pairs in the case of pairs that exist in both new and old pair arrays, and as discard pairs in the case of pairs that only exist in the old pair arrays.

The area of the pair array returned as the result is acquired from the pair buffer specified to PfxDecomposePairsParam. Do not discard the pair buffer until after it has finished being used.

# Collision Detection APIs

# PfxDetectCollisionParam

## Parameters used for collision detection

### Definition

```
#include <physics_effects/low_level/collision/pfx_collision_detection.h>
struct PfxDetectCollisionParam {
    PfxConstraintPair *contactPairs;
    PfxUInt32 numContactPairs;
    PfxContactManifold *offsetContactManifolds;
    PfxRigidState *offsetRigidStates;
    PfxCollidable *offsetCollidables;
    PfxUInt32 numRigidBodies;
};
```

### Members

<i>contactPairs</i>	Collision detection pair array (16-byte alignment)
<i>numContactPairs</i>	Number of collision detection pairs
<i>offsetContactManifolds</i>	Offset address of contact data array (128-byte alignment)
<i>offsetRigidStates</i>	Offset address of rigid body state array (128-byte alignment)
<i>offsetCollidables</i>	Offset address of rigid body shape array (128-byte alignment)
<i>numRigidBodies</i>	Total number of rigid bodies

### Description

This structure is used to specify the parameters required for collision detection. The index of the pair contact data output in advance from the broad phase is set and specified as the collision detection pair.

# pfxDetectCollision

## Detect collision of rigid bodies

### Definition

```
#include <physics_effects/low_level/collision/pfx_collision_detection.h>
PfxInt32 pfxDetectCollision(
    PfxDetectCollisionParam &param
)
// Parallel version
PfxInt32 pfxDetectCollision(
    PfxDetectCollisionParam &param,
    PfxTaskManager *taskManager
)
```

### Arguments

*param*                      Input parameter  
*taskManager*              Task manager (only when multithread is used)

### Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid

### Description

Gets the index to the rigid bodies and collision data from the collision detection pair array, and perform access to the offset address + index as the actual data. If the data is not valid, assert is executed.

Gets the position in the world and judgment state from the two rigid body states included in the pair and the rigid body shapes, and calls a different judgment function according to each shape combination. If a collision is detected, the collision coordinates, the repelling direction and the penetration depth are calculated, and up to four contact points is stored to the contact data.

# Constraint Solver APIs

000004892117

# PfxSetupSolverBodiesParam

Parameters used for solver body setup

## Definition

```
#include <physics_effects/low_level/solver/pfx_constraint_solver.h>
struct PfxSetupSolverBodiesParam {
    PfxRigidState *states;
    PfxRigidBody *bodies;
    PfxSolverBody *solverBodies;
    PfxUInt32 numRigidBodies;
};
```

## Members

<i>states</i>	Rigid body state array (128-byte alignment)
<i>bodies</i>	Rigid body attribute array (128-byte alignment)
<i>solverBodies</i>	Solver body array (128-byte alignment)
<i>numRigidBodies</i>	Total number of rigid bodies

## Description

Updates the solver bodies based on the rigid body data. The same number of solver body arrays as the number of rigid bodies must be prepared and allocated in advance.

# pfxSetupSolverBodies

## Solver body setup

### Definition

```
#include <physics_effects/low_level/solver/pfx_constraint_solver.h>
PfxInt32 pfxSetupSolverBodies(
    PfxSetupSolverBodiesParam &param
)
// Parallel version
PfxInt32 pfxSetupSolverBodies(
    PfxSetupSolverBodiesParam &param,
    PfxTaskManager *taskManager
)
```

### Arguments

*param*                      Input parameter  
*taskManager*              Task manager (only when multithread is used)

### Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid

### Description

Executes the setup of the solver body structure to be used for solver operations. The parameters required for the operations are copied from the body data, and the solver body is used instead of rigid body states or rigid body attributes in the operation loop.



# PfxSetupContactConstraintsParam

Parameters used for collision constraint setup

## Definition

```
#include <physics_effects/low_level/solver/pfx_constraint_solver.h>
struct PfxSetupContactConstraintsParam {
    PfxConstraintPair *contactPairs;
    PfxUInt32 numContactPairs;
    PfxContactManifold *offsetContactManifolds;
    PfxRigidState *offsetRigidStates;
    PfxRigidBody *offsetRigidBody;
    PfxSolverBody *offsetSolverBodies;
    PfxUInt32 numRigidBodies;
    PfxFloat timeStep;
    PfxFloat separateBias;
};
```

## Members

<i>contactPairs</i>	Collision pair array (16-byte alignment)
<i>numContactPairs</i>	Number of collision pairs
<i>offsetContactManifolds</i>	Offset address of contact data array (128-byte alignment)
<i>offsetRigidStates</i>	Offset address of rigid body state array (128-byte alignment)
<i>offsetRigidBody</i>	Offset address of rigid body attribute array (128-byte alignment)
<i>offsetSolverBodies</i>	Offset address of solver body array (128-byte alignment)
<i>numRigidBodies</i>	Total number of rigid bodies
<i>timeStep</i>	Timestep (default value: 0.016f)
<i>separateBias</i>	Bias value (default value: 0.2f)

## Description

This structure is used to specify the parameters required for collision constraint setup. The pair array output from the collision judgment is specified as the collision pair. The index to the `PfxContactManifold` collision data must be allocated for all the pairs.

The time is specified in units of 1 second for the timestep. The bias value is the adjustment value of the constraint force pulling apart rigid bodies that have collided. Specify it in the range of 0.0 to 1.0.

# pfxSetupContactConstraints

## Collision constraint setup

### Definition

```
#include <physics_effects/low_level/solver/pfx_constraint_solver.h>
PfxInt32 pfxSetupContactConstraints (
    PfxSetupContactConstraintsParam &param
)
// Parallel version
PfxInt32 pfxSetupContactConstraints (
    PfxSetupContactConstraintsParam &param,
    PfxTaskManager *taskManager
)
```

### Arguments

*param*                      Input parameter  
*taskManager*              Task manager (only when multithread is used)

### Return Values

Returns SCE\_PFX\_OK (0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid

### Description

Sets up the data to be used for solver operations, based on the rigid body and collision data.

# PfxSetupJointConstraintsParam

## Parameters used for joint constraint setup

### Definition

```
#include <physics_effects/low_level/solver/pfx_constraint_solver.h>
struct PfxSetupJointConstraintsParam {
    PfxConstraintPair *jointPairs;
    PfxUInt32 numJointPairs;
    PfxJoint *offsetJoints;
    PfxRigidState *offsetRigidStates;
    PfxRigidBody *offsetRigidBodies;
    PfxSolverBody *offsetSolverBodies;
    PfxUInt32 numRigidBodies;
    PfxFloat timeStep;
};
```

### Members

<i>jointPairs</i>	Joint pair array (16-byte alignment)
<i>numJointPairs</i>	Number of joint pairs
<i>offsetJoints</i>	Offset address of joint array (128-byte alignment)
<i>offsetRigidStates</i>	Offset address of rigid body state array (128-byte alignment)
<i>offsetRigidBodies</i>	Offset address of rigid body attribute array (128-byte alignment)
<i>offsetSolverBodies</i>	Offset address of solver body array
<i>numRigidBodies</i>	Total number of rigid bodies
<i>timeStep</i>	Timestep (default value: 0.016f)

### Description

This structure is used to specify the parameters required for joint constraint setup. The joint pairs must be prepared in advance from the joint structure using the `pfxUpdateJointPairs()` function. The time is specified in units of 1 second for the timestep.

# pfxSetupJointConstraints

## Joint constraint setup

### Definition

```
#include <physics_effects/low_level/solver/pfx_constraint_solver.h>
PfxInt32 pfxSetupJointConstraints(
    PfxSetupJointConstraintsParam &param
)
// Parallel version
PfxInt32 pfxSetupJointConstraints(
    PfxSetupJointConstraintsParam &param,
    PfxTaskManager *taskManager
)
```

### Arguments

*param*                      Input parameter  
*taskManager*              Task manager (only when multithread is used)

### Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid

### Description

Sets up the data to be used for solver operations, based on the rigid body and joint data.

# PfxSolveConstraintsParam

## Parameters used for constraint solver

### Definition

```
#include <physics_effects/low_level/solver/pfx_constraint_solver.h>
struct PfxSolveConstraintsParam {
    void *workBuff;
    PfxUInt32 workBytes;
    PfxConstraintPair *contactPairs;
    PfxUInt32 numContactPairs;
    PfxContactManifold *offsetContactManifolds;
    PfxConstraintPair *jointPairs;
    PfxUInt32 numJointPairs;
    PfxJoint *offsetJoints;
    PfxRigidState *offsetRigidStates;
    PfxSolverBody *offsetSolverBodies;
    PfxUInt32 numRigidBodies;
    PfxUInt32 iteration;
};
```

### Members

<i>workBuff</i>	Pointer to work area
<i>workBytes</i>	Size of work area
<i>contactPairs</i>	Collision pair array (16-byte alignment)
<i>numContactPairs</i>	Number of collision pairs
<i>offsetContactManifolds</i>	Offset address of contact data array (128-byte alignment)
<i>jointPairs</i>	Joint pair array (16-byte alignment)
<i>numJointPairs</i>	Number of joint pairs
<i>offsetJoints</i>	Offset address of joint array (128-byte alignment)
<i>offsetRigidStates</i>	Offset address of rigid body state array (128-byte alignment)
<i>offsetSolverBodies</i>	Offset address of solver body array (128-byte alignment)
<i>numRigidBodies</i>	Total number of rigid bodies
<i>iteration</i>	Number of operation iterations (default value: 5)

### Description

This structure is used to specify the parameters to be passed to the `pfxSolveConstraints()` constraint solver function. In order to simultaneously solve the collision and joint constraints, operations are repeated for all the constraints for the specified number of iterations. The larger the number of iterations, the higher the accuracy is, but at the price of lower performance.

# pfxGetWorkBytesOfSolveConstraints

Get size of work area used for constraint solver

## Definition

```
#include <physics_effects/low_level/solver/pfx_constraint_solver.h>
PfxUInt32 pfxGetWorkBytesOfSolveConstraints(
    PfxUInt32 numRigidBody,
    PfxUInt32 numContactPairs,
    PfxUInt32 numJointPairs
)
```

## Arguments

<i>numRigidBody</i>	Total number of rigid bodies
<i>numContactPairs</i>	Number of collision pairs
<i>numJointPairs</i>	Number of joint pairs

## Return Values

Returns the size of the work area to be used for the constraint solver.

## Description

Allocate the work buffer of the returned size and specify it for the `PfxSolveConstraintsParam` constraint solver parameter.

# pfxSolveConstraints

## Constraint solver

### Definition

```
#include <physics_effects/low_level/solver/pfx_constraint_solver.h>
PfxInt32 pfxSolveConstraints(
    PfxSolveConstraintsParam &param
)
// Parallel version
PfxInt32 pfxSolveConstraints(
    PfxSolveConstraintsParam &param,
    PfxTaskManager *taskManager
)
```

### Arguments

*param*                      Input parameter  
*taskManager*              Task manager (only when multithread is used)

### Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid

### Description

This is a solver function that simultaneously solves multiple constraints caused by collisions and joints between rigid bodies, using a reiterative operation solving process. The constraint force output from the solver is converted to velocity and is finally reflected to the rigid body state.

# External Force and Position Calculation APIs



# **pfxApplyExternalForce**

Apply external force to rigid body

## **Definition**

```
#include <physics_effects/base_level/solver/pfx_integrate.h>
static SCE_PFX_FORCE_INLINE void pfxApplyExternalForce(
    PfxRigidState &state,
    const PfxRigidBody &body,
    const PfxVector3 &extForce,
    const PfxVector3 &extTorque,
    PfxFloat timeStep
)
```

## **Arguments**

<i>state</i>	Rigid body state
<i>body</i>	Rigid body attribute
<i>extForce</i>	External force
<i>extTorque</i>	External torque
<i>timeStep</i>	Timestep

## **Return Values**

None

## **Description**

The given external force is converted to the velocity and reflected to the rigid body state. The time is specified in units of 1 second for the timestep.

---

# pfxIntegrate

---

## Update position of rigid body

### Definition

---

```
#include <physics_effects/base_level/solver/pfx_integrate.h>
static SCE_PFX_FORCE_INLINE void pfxIntegrate(
    PfxRigidState &state,
    const PfxRigidBody &body,
    PfxFloat timeStep
)
```

### Arguments

---

<i>state</i>	Rigid body state
<i>body</i>	Rigid body attribute
<i>timeStep</i>	Timestep

### Return Values

---

None

### Description

---

Calculates the position after the timestep from the velocity of the rigid body and reflects it to the rigid body state. The velocity is maintained as is.

To perform batch processing to arrays of rigid bodies, use `pfxUpdateRigidStates()`.

# PfxUpdateRigidStatesParam

Parameters used for rigid body position update

## Definition

```
#include <physics_effects/low_level/solver/pfx_update_rigid_states.h>
struct PfxUpdateRigidStatesParam {
    PfxRigidBodyState *states;
    PfxRigidBody *bodies;
    PfxUInt32 numRigidBodies;
    PfxFloat timeStep;
};
```

## Members

<i>states</i>	Rigid body state array (128-byte alignment)
<i>bodies</i>	Rigid body attribute array (128-byte alignment)
<i>numRigidBodies</i>	Total number of rigid bodies
<i>timeStep</i>	Timestep

## Description

This structure is used to specify the parameters to be passed to the `pfxUpdateRigidStates()` function for executing position update for an array of rigid bodies. The time is specified in units of 1 second for the timestep.

SCE CONFIDENTIAL

# pfxUpdateRigidStates

Update rigid body position

## Definition

```
#include <physics_effects/low_level/solver/pfx_update_rigid_states.h>
PfxInt32 pfxUpdateRigidStates(
    PfxUpdateRigidStatesParam &param
)
// Parallel version
PfxInt32 pfxUpdateRigidStates(
    PfxUpdateRigidStatesParam &param,
    PfxTaskManager *taskManager
)
```

## Arguments

*param*                      Input parameter  
*taskManager*              Task manager (only when multithread is used)

## Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid

## Description

Updates in batch the positions of rigid bodies.

# Simulation Island APIs

000004892117

---

# PfxGenerateIslandParam

---

Parameters used for simulation island creation

## Definition

---

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
struct PfxGenerateIslandParam {
    void *islandBuff;
    PfxUInt32 islandBytes;
    PfxConstraintPair *pairs;
    PfxUInt32 numPairs;
    PfxUInt32 numObjects;
};
```

## Members

---

<i>islandBuff</i>	Pointer to island buffer
<i>islandBytes</i>	Size of island buffer
<i>pairs</i>	Pair array (16-byte alignment)
<i>numPairs</i>	Number of pairs
<i>numObjects</i>	Number of objects (rigid bodies)

## Description

---

This structure is used to specify the parameters to be passed to the `pfxGenerateIsland()` function for creating simulation islands. Get the buffer size for the simulation island output with `pfxGetIslandBytesOfGenerateIsland()` beforehand, and set the allocated buffer. Align the pair array to the 16-byte boundary.

SCE CONFIDENTIAL

---

# PfxGenerateIslandResult

---

Structure that receives simulation island result

## Definition

---

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
struct PfxGenerateIslandResult {
    PfxIsland *island;
};
```

## Members

---

*island* Simulation island structure

## Description

---

This structure is used to store the result returned from the `pfxGenerateIsland()` function for creating simulation island.

Document serial number: 000004892117

SCE CONFIDENTIAL

---

## **pfxGetIslandBytesOfGenerateIsland**

---

Get island buffer size to be used for simulation island creation

### **Definition**

---

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
PfxUInt32 pfxGetIslandBytesOfGenerateIsland(
    PfxUInt32 numObjects
)
```

### **Arguments**

---

*numObjects* Total number of objects

### **Return Values**

---

Returns the island buffer size to be used for simulation island creation.

### **Description**

---

Allocate a buffer of the returned size and specify it as the `PfxGenerateIslandParam` input parameter for the simulation island creation function.



# pfxGeneratelsland

## Create simulation island

### Definition

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
PfxInt32 pfxGenerateIsland(
    PfxGenerateIslandParam &param,
    PfxGenerateIslandResult &result
)
```

### Arguments

```
param    Input parameter
result   Structure that receives result
```

### Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.  
Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid
SCE_PFX_ERR_OUT_OF_BUFFER	Specified buffer capacity is insufficient

### Description

Builds a simulation island from a pair array. Do not discard the simulation island buffer specified in the input parameter until after simulation island use has finished.

# pfxAppendPairs

Add pairs to simulation island

## Definition

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
PfxUInt32 pfxAppendPairs (
    PfxIsland *island,
    PfxConstraintPair *pairs,
    PfxUInt32 numPairs
)
```

## Arguments

*island*      Simulation island structure (16-byte alignment)  
*pairs*        Pair array (16-byte alignment)  
*numPairs*    Number of pairs

## Return Values

Returns SCE\_PFX\_OK (0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	Input parameter is invalid
SCE_PFX_ERR_INVALID_ALIGN	Input parameter alignment is invalid

## Description

Updates an already created simulation island by adding a pair array. The size of the buffer that is used for the simulation island does not change through this operation.

If the argument value is invalid, an assert is called.

SCE CONFIDENTIAL

---

## pfxGetNumIslands

---

Get total number of simulation islands

### Definition

---

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
PfxUInt32 pfxGetNumIslands (
    const PfxIsland *islands
)
```

### Arguments

---

*islands* Simulation island structure

### Return Values

---

Returns the total number of simulation islands.

### Description

---

Gets the total number of simulation islands.

If the argument value is invalid, an assert is called.

---

# pfxGetFirstUnitInIsland

---

Get first unit of specified simulation island

## Definition

---

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
PfxIslandUnit *pfxGetFirstUnitInIsland(
    const PfxIsland *islands,
    PfxUInt32 islandId
)
```

## Arguments

---

*islands*     Simulation island structure  
*islandId*   Index of simulation island

## Return Values

---

Returns the first unit belonging to the specified simulation island.  
If an out-of-range value is set, assert is called.

## Description

---

Gets the first unit of the specified simulation island.  
If the argument value is invalid, an assert is called.

SCE CONFIDENTIAL

---

## pfxGetNextUnitInIsland

---

Get next unit

### Definition

---

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
PfxIslandUnit *pfxGetNextUnitInIsland(
    const PfxIslandUnit *islandUnit
)
```

### Arguments

---

*islandUnit* Simulation island unit structure

### Return Values

---

Returns the next unit. Returns NULL if there is no next unit.

### Description

---

Gets the next unit.

If the argument value is invalid, an assert is called.

SCE CONFIDENTIAL

---

## pfxGetUnitId

---

Gets unit index

### Definition

---

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
PfxUInt32 pfxGetUnitId(
    const PfxIslandUnit *islandUnit
)
```

### Arguments

---

*islandUnit* Simulation island unit structure

### Return Values

---

Returns the index of the specified unit. Assert is called if the unit does not exist.

### Description

---

Gets the unit index. This index can be used as the index of the rigid body.  
If the argument value is invalid, an assert is called.

SCE CONFIDENTIAL

---

## pfxGetIslandId

---

Get index of island that stores unit

### Definition

---

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
PfxUInt32 pfxGetIslandId(
    const PfxIsland *islands,
    PfxUInt32 unitId
)
```

### Arguments

---

*islands*    Simulation island structure  
*unitId*    Index of simulation island unit

### Return Values

---

Returns index of island to which unit belongs. If the unit is not found, assert is called.

### Description

---

Gets the index of the island that stores the unit.  
If the argument value is invalid, an assert is called.

SCEI CONFIDENTIAL

---

# pfxResetIsland

---

## Reset island

### Definition

---

```
#include <physics_effects/low_level/collision/pfx_island_generation.h>
void pfxResetIsland(
    PfxIsland *islands
)
```

### Arguments

---

*islands* Simulation island structure

### Return Values

---

None

### Description

---

Clears the contents of the simulation island.  
If the argument value is invalid, an assert is called.



# Raycast APIs

000004892117

# PfxRayCastParam

## Parameters used for raycast

### Definition

```
#include <physics_effects/low_level/collision/pfx_ray_cast.h>
struct PfxRayCastParam {
    PfxRigidBodyState *offsetRigidBodyStates;
    PfxCollidable *offsetCollidables;
    PfxBroadphaseProxy *proxiesX;
    PfxBroadphaseProxy *proxiesY;
    PfxBroadphaseProxy *proxiesZ;
    PfxBroadphaseProxy *proxiesXb;
    PfxBroadphaseProxy *proxiesYb;
    PfxBroadphaseProxy *proxiesZb;
    PfxUInt32 numProxies;
    PfxVector3 rangeCenter;
    PfxVector3 rangeExtent;
};
```

### Members

<i>offsetRigidBodyStates</i>	Offset address of rigid body state array (128-byte alignment)
<i>offsetCollidables</i>	Offset address of rigid body shape array (128-byte alignment)
<i>proxiesX</i>	Broadphase proxy array sorted in +X axis direction (16-byte alignment)
<i>proxiesY</i>	Broadphase proxy array sorted in +Y axis direction (16-byte alignment)
<i>proxiesZ</i>	Broadphase proxy array sorted in +Z axis direction (16-byte alignment)
<i>proxiesXb</i>	Broadphase proxy array sorted in -X axis direction (16-byte alignment)
<i>proxiesYb</i>	Broadphase proxy array sorted in -Y axis direction (16-byte alignment)
<i>proxiesZb</i>	Broadphase proxy array sorted in -Z axis direction (16-byte alignment)
<i>numProxies</i>	Number of broadphase proxies (= Total number of rigid bodies)
<i>rangeCenter</i>	Center of area to be raycast
<i>rangeExtent</i>	Size of area to be raycast

### Description

Creates broadphase proxy of all rigid bodies to be judged with the `pfxUpdateBroadphaseProxy()` function and allocates it to parameters. The optimum broadphase proxy for the ray direction is selected by providing broadphase proxies for all the axes.

Allocate as is the world size set during broadphase proxy creation as the raycast area.

---

# pfxCastSingleRay

---

## Single raycast

### Definition

---

```
#include <physics_effects/low_level/collision/pfx_ray_cast.h>
void pfxCastSingleRay(
    const PfxRayInput &rayInput,
    PfxRayOutput &rayOutput,
    const PfxRayCastParam &param
)
```

### Arguments

---

<i>rayInput</i>	Ray input structure
<i>rayOutput</i>	Ray output structure
<i>param</i>	Input parameter

### Return Values

---

There are no return values. If an invalid input parameter is detected, assert is called.

### Description

---

One ray is cast onto the world. The intersection data that is the closest to the start point is stored to the *PfxRayOutput* structure.

When the `pfxCastSingleRay()` function is called from multiple threads for the same world space, do not update the input parameter contents until all the raycasts have been completed.

# pfxCastRays

## Batch raycast

### Definition

```
#include <physics_effects/low_level/solver/pfx_batched_ray_cast.h>
void pfxCastRays (
    PfxRayInput *rayInputs,
    PfxRayOutput *rayOutputs,
    int numRays,
    PfxRayCastParam &param
)
// Parallel version
void pfxCastRays (
    PfxRayInput *rayInputs,
    PfxRayOutput *rayOutputs,
    int numRays,
    PfxRayCastParam &param,
    PfxTaskManager *taskManager
)
```

### Arguments

<i>rayInputs</i>	Array of ray input structures (16-byte alignment)
<i>rayOutputs</i>	Array of ray output structures (16-byte alignment)
<i>numRays</i>	Total number of rays
<i>param</i>	Input parameter
<i>taskManager</i>	Task manager (only when multithread is used)

### Return Values

There are no return values. If *param* is an invalid value, an assert is called.

### Description

Casts multiple rays onto the world space. Ray input array processing is done sequentially, and upon detection of an intersection, the intersection information closest to the start point is stored to the corresponding `PfxRayOutput` structure.

## Sort APIs

000004892117

SCE CONFIDENTIAL

# pfxParallelSort

## Sort

### Definition

```
#include <physics_effects/low_level/sort/pfx_parallel_sort.h>
PfxInt32 pfxParallelSort(
    PfxSortData16 *data,
    PfxUInt32 numData,
    void *workBuff,
    PfxUInt32 workBytes
)
PfxInt32 pfxParallelSort(
    PfxSortData32 *data,
    PfxUInt32 numData,
    void *workBuff,
    PfxUInt32 workBytes
)
// Parallel version
PfxInt32 pfxParallelSort(
    PfxSortData16 *data,
    PfxUInt32 numData,
    void *workBuff,
    PfxUInt32 workBytes,
    PfxTaskManager *taskManager
)
PfxInt32 pfxParallelSort(
    PfxSortData32 *data,
    PfxUInt32 numData,
    void *workBuff,
    PfxUInt32 workBytes,
    PfxTaskManager *taskManager
)
```

### Arguments

<i>data</i>	Array of data to be sorted (16-byte alignment)
<i>numData</i>	Number of data to be sorted
<i>workBuff</i>	Pointer to work area (16-byte alignment)
<i>workBytes</i>	Size of work area
<i>taskManager</i>	Task manager (only when multithread is used)

### Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_OUT_OF_BUFFER	The size of the work area is insufficient
SCE_PFX_ERR_INVALID_ALIGN	The alignment of the pointer to the work area is invalid

### Description

Sorts an array of sort data that is 16-byte or 32-byte aligned. Used for pair or broadphase proxy array sorting.

## Utility APIs

000004892117

SCE CONFIDENTIAL

---

## pfxCalcMassBox

---

Calculate box mass

### Definition

---

```
#include <physics_effects/util/pfx_mass.h>
PfxFloat pfxCalcMassBox(
    PfxFloat density,
    const PfxVector3 &halfExtent
)
```

### Arguments

---

<i>density</i>	Density
<i>halfExtent</i>	Size of box

### Return Values

---

Returns the mass.

### Description

---

Calculates the mass from the size and density of the box.



SCE CONFIDENTIAL

---

# pfxCalcInertiaBox

---

Calculate inertia tensor of box

## Definition

---

```
#include <physics_effects/util/pfx_mass.h>
PfxMatrix3 pfxCalcInertiaBox(
    const PfxVector3 &halfExtent,
    PfxFloat mass
)
```

## Arguments

---

<i>halfExtent</i>	Size of box
<i>mass</i>	Mass

## Return Values

---

Returns the inertia tensor.

## Description

---

Calculates the inertia tensor from the size and mass of the box.

SCE CONFIDENTIAL

---

# pfxCalcMassSphere

---

Calculate mass of sphere

## Definition

---

```
#include <physics_effects/util/pfx_mass.h>
PfxFloat pfxCalcMassSphere(
    PfxFloat density,
    PfxFloat radius
)
```

## Arguments

---

*density* Density  
*radius* Radius of sphere

## Return Values

---

Returns the mass.

## Description

---

Calculates the mass from the radius and density of the sphere.

SCE CONFIDENTIAL

---

# pfxCalcInertiaSphere

---

Calculate inertia tensor of sphere

## Definition

---

```
#include <physics_effects/util/pfx_mass.h>
PfxMatrix3 pfxCalcInertiaSphere(
    PfxFloat radius,
    PfxFloat mass
)
```

## Arguments

---

*radius*   Radius of sphere  
*mass*     Mass

## Return Values

---

Returns the inertia tensor.

## Description

---

Calculates the inertia tensor from the radius and mass of the sphere.

SCE CONFIDENTIAL

---

# pfxCalcMassCylinder

---

Calculate mass of cylinder

## Definition

---

```
#include <physics_effects/util/pfx_mass.h>
PfxFloat pfxCalcMassCylinder(
    PfxFloat density,
    PfxFloat halfLength,
    PfxFloat radius
)
```

## Arguments

---

<i>density</i>	Density
<i>halfLength</i>	Length of cylinder
<i>radius</i>	Radius of cylinder

## Return Values

---

Returns the mass.

## Description

---

Calculates the mass from the length, radius and density of the cylinder.

# pfxCalcInertiaCylinderX, pfxCalcInertiaCylinderY, pfxCalcInertiaCylinderZ

Calculate inertia tensor of cylinder

## Definition

```
#include <physics_effects/util/pfx_mass.h>
PfxMatrix3 pfxCalcInertiaCylinderX(
    PfxFloat halfLength,
    PfxFloat radius,
    PfxFloat mass
)
PfxMatrix3 pfxCalcInertiaCylinderY(
    PfxFloat halfLength,
    PfxFloat radius,
    PfxFloat mass
)
PfxMatrix3 pfxCalcInertiaCylinderZ(
    PfxFloat halfLength,
    PfxFloat radius,
    PfxFloat mass
)
```

## Arguments

<i>halfLength</i>	Length of cylinder
<i>radius</i>	Radius of cylinder
<i>mass</i>	Mass

## Return Values

Returns the inertia tensor.

## Description

Calculates the inertia tensor from the length, radius and mass of the cylinder.

Use one of the functions depending on the followings.

- When cylinder axis runs parallel to X axis, pfxCalcInertiaCylinderX()
- When cylinder axis runs parallel to Y axis, pfxCalcInertiaCylinderY()
- When cylinder axis runs parallel to Z axis, pfxCalcInertiaCylinderZ()

---

# pfxMassTranslate

---

## Translate inertia tensor

### Definition

---

```
#include <physics_effects/util/pfx_mass.h>
PfxMatrix3 pfxMassTranslate (
    PfxFloat mass,
    const PfxMatrix3 &inertia,
    const PfxVector3 &translation
)
```

### Arguments

---

<i>mass</i>	Mass
<i>inertia</i>	Inertia tensor
<i>translation</i>	Translation

### Return Values

---

Returns the inertia tensor after translation.

### Description

---

The position of the center of gravity can be changed by translating the inertia tensor.

SCE CONFIDENTIAL

---

# pfxMassRotate

---

Rotate inertia tensor

## Definition

---

```
#include <physics_effects/util/pfx_mass.h>
PfxMatrix3 pfxMassRotate (
    const PfxMatrix3 &inertia,
    const PfxMatrix3 &rotate
)
```

## Arguments

---

*inertia* Inertia tensor  
*rotate* Rotation matrix

## Return Values

---

Returns the inertia tensor following rotation.

## Description

---

Rotates the inertia tensor.

# PfxCreateConvexMeshParam

Parameters used for convex mesh creation function

## Definition

```
#include <physics_effects/util/pfx_mesh_creator.h>
struct PfxCreateConvexMeshParam {
    PfxUInt32 flag;
    PfxFloat *verts;
    PfxUInt32 numVerts;
    void *triangles;
    PfxUInt32 numTriangles;
    PfxUInt32 vertexStrideBytes;
    PfxUInt32 triangleStrideBytes;
};
```

## Members

<i>flag</i>	Flag (default value: SCE_PFX_MESH_FLAG_16BIT_INDEX   SCE_PFX_MESH_FLAG_AUTO_ELIMINATION)
<i>verts</i>	Pointer to vertex buffer
<i>numVerts</i>	Number of vertices
<i>triangles</i>	Pointer to triangle buffer
<i>numTriangles</i>	Number of triangles
<i>vertexStrideBytes</i>	Number of bytes between vertex data (default value: 12)
<i>triangleStrideBytes</i>	Number of bytes between triangle data (default value: 6)

## Description

This structure is used to specify parameters when creating a convex mesh with the `pfxCreateConvexMesh()` function.

The following combinations of values are input to *flag*.

Value	Description
SCE_PFX_MESH_FLAG_NORMAL_FLIP	Inverts triangle index sequence
SCE_PFX_MESH_FLAG_16BIT_INDEX	Makes triangle index a 16-bit integer (unsigned)
SCE_PFX_MESH_FLAG_32BIT_INDEX	Makes triangle index a 32-bit integer (unsigned)
SCE_PFX_MESH_FLAG_AUTO_ELIMINATION	Deletes triangles with same vertex and surface area of 0



# pfxCreateConvexMesh

## Create convex mesh

### Definition

```
#include <physics_effects/util/pfx_mesh_creator.h>
PfxInt32 pfxCreateConvexMesh(
    PfxConvexMesh &convex,
    const PfxCreateConvexMeshParam &param
)
```

### Arguments

*convex*    Convex mesh  
*param*    Input parameter

### Return Values

Returns SCE\_PFX\_OK (0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	The number of vertices or triangles is 0 or NULL has been specified for the pointer
SCE_PFX_ERR_OUT_OF_RANGE	The number of vertices or triangles exceeds the designated number
SCE_PFX_ERR_INVALID_FLAG	The flag setting is incorrect

### Description

Creates a convex mesh from the vertices and triangle buffers.

Whether the input shape is a convex shape is not judged within the function.

The buffer for storing the vertices and triangles when creating convex meshes is allocated dynamically.

After use, always release with `pfxReleaseConvexMesh()`.

Up to 128 vertices or 64 triangles can be held by a convex mesh. If the designated value is exceeded, the SCE\_PFX\_ERR\_OUT\_OF\_RANGE error is returned.

SCEI CONFIDENTIAL

---

# pfxReleaseConvexMesh

---

Release convex mesh

## Definition

---

```
#include <physics_effects/util/pfx_mesh_creator.h>
void pfxReleaseConvexMesh (
    PfxConvexMesh &cmesh
)
```

## Arguments

---

*cmesh* Convex mesh

## Return Values

---

None

## Description

---

Releases the buffer allocated with `pfxCreateConvexMesh()`.

# PfxCreateLargeTriMeshParam

Parameters used for large mesh creation

## Definition

```
#include <physics_effects/util/pfx_mesh_creator.h>
struct PfxCreateLargeTriMeshParam {
    PfxUInt32 flag;
    PfxFloat *verts;
    PfxUInt32 numVerts;
    void *triangles;
    PfxUInt32 *userData;
    PfxUInt32 numTriangles;
    PfxUInt32 vertexStrideBytes;
    PfxUInt32 triangleStrideBytes;
    PfxUInt32 numFacetsLimit;
    PfxFloat islandsRatio;
    PfxFloat defaultThickness;
};
```

## Members

<i>flag</i>	Flag (default value: SCE_PFX_MESH_FLAG_16BIT_INDEX   SCE_PFX_MESH_FLAG_AUTO_ELIMINATION)
<i>verts</i>	Pointer to vertex buffer
<i>numVerts</i>	Number of vertices
<i>triangles</i>	Pointer to triangle buffer
<i>userData</i>	Pointer to user data buffer (array of 32-bit integer values)
<i>numTriangles</i>	Number of triangles
<i>vertexStrideBytes</i>	Number of bytes between vertex data (default value: 12)
<i>triangleStrideBytes</i>	Number of bytes between triangle data (default value: 6)
<i>numFacetsLimit</i>	Threshold of number of triangles registered to island (default value: 15)
<i>islandsRatio</i>	Size ratio of islands for entire mesh (default value: 0.2f)
<i>defaultThickness</i>	Default value of triangle thickness (default value: 0.025f)

## Description

This structure is used to specify the parameters for creating a large mesh with the `pfxCreateLargeTriMesh()` function.

The following combinations of values are input to *flag*.

Value	Description
SCE_PFX_MESH_FLAG_NORMAL_FLIP	Inverts triangle index sequence
SCE_PFX_MESH_FLAG_16BIT_INDEX	Makes triangle index a 16-bit integer (unsigned)
SCE_PFX_MESH_FLAG_32BIT_INDEX	Makes triangle index a 32-bit integer (unsigned)
SCE_PFX_MESH_FLAG_AUTO_ELIMINATION	Deletes triangles with same vertex and surface area of 0
SCE_PFX_MESH_FLAG_AUTO_THICKNESS	Adds thickness to triangle
SCE_PFX_MESH_FLAG_USE_BVH	Uses BVH structure for storing a mesh
SCE_PFX_MESH_FLAG_USE_QUANTIZED	Quantizes mesh data for compression purposes
SCE_PFX_MESH_FLAG_OUTPUT_INFO	Outputs messages when creating a mesh
SCE_PFX_MESH_FLAG_HIGH_QUALITY	Optimizes the mesh structure to output

# pfxCreateLargeTriMesh

## Create large mesh

### Definition

```
#include <physics_effects/util/pfx_mesh_creator.h>
PfxInt32 pfxCreateLargeTriMesh(
    PfxLargeTriMesh &lmesh,
    const PfxCreateLargeTriMeshParam &param
)
```

### Arguments

*lmesh* Large mesh  
*param* Input parameter

### Return Values

Returns SCE\_PFX\_OK (0) upon normal termination.

Returns one of the following error codes (negative value) for errors.

Value	Description
SCE_PFX_ERR_INVALID_VALUE	The number of vertices or triangles is 0 or NULL has been specified for the pointer.
SCE_PFX_ERR_OUT_OF_RANGE	The number of input parameter vertices or triangles exceeds the designated number.
SCE_PFX_ERR_OUT_OF_BUFFER	Buffer could not be allocated due to insufficient memory.
SCE_PFX_ERR_INVALID_FLAG	The flag setting is invalid.
SCE_PFX_ERR_OUT_OF_RANGE_VERTEX	The number of vertices exceeds the maximum number that can be included in one island.
SCE_PFX_ERR_OUT_OF_RANGE_EDGE	The number of edges exceeds the maximum number that can be included in one island.
SCE_PFX_ERR_OUT_OF_RANGE_FACET	The number of triangles exceeds the maximum number that can be included in one island.
SCE_PFX_ERR_OUT_OF_RANGE_ISLAND	The number of islands exceeds the maximum number that can be included in a large mesh.
SCE_PFX_ERR_ZERO_AREA_FACET	Detects a triangle whose surface area after compression will be 0

### Description

Creates a large mesh from the vertices and triangle buffers.

The mesh structure can be efficiently searched hierarchically by dividing the input triangle into multiple groups (islands). The maximum number of islands that can be held by a large mesh is 512. Up to 128 vertices and 64 triangles can be held by an island. If the designated value is exceeded, the SCE\_PFX\_ERR\_OUT\_OF\_RANGE error is returned. Arbitrary user data (32-bit integer values) can be assigned to individual triangles. The buffer for storing the islands or additional data during large mesh creation is allocated dynamically.

Following use, be sure to release the allocated buffer with the `pfxReleaseLargeTriMesh()` function.

Although the edge shared by three or more triangles does not result in an error, a warning message will be output, and the third or later triangles will be excluded from the judgment.

SCE CONFIDENTIAL

---

# pfxReleaseLargeTriMesh

---

Release large mesh

## Definition

---

```
#include <physics_effects/util/pfx_mesh_creator.h>
void pfxReleaseLargeTriMesh(
    PfxLargeTriMesh &lmesh
)
```

## Arguments

---

*lmesh* Large mesh

## Return Values

---

None

## Description

---

Releases the allocated buffer with the `pfxCreateLargeTriMesh()` function.

SCE CONFIDENTIAL

# pfxSetUtilityAllocator

Specify memory allocator used by utility function group

## Definition

```
#include <physics_effects/util/pfx_util_common.h>
void pfxSetUtilityAllocator(
    SCE_PFX_FUNC_ALLOC func_alloc,
    SCE_PFX_FUNC_REALLOC func_realloc,
    SCE_PFX_FUNC_FREE func_free
)
```

## Arguments

<i>func_alloc</i>	Pointer to the memory allocator function
<i>func_realloc</i>	Pointer to the memory reallocator function
<i>func_free</i>	Pointer to the memory release function

## Return Values

None

## Description

Sets the memory allocator called by a utility function to the one designated by the user.

If the allocator is not specified with this function, the standard functions `memalign()`, `reallocalign()` and `free()` are used for the utility.

The types of the function pointer are as follows.

```
typedef void* (*SCE_PFX_FUNC_ALLOC)(size_t align, size_t size);
typedef void* (*SCE_PFX_FUNC_REALLOC)(void* ptr, size_t align, size_t size);
typedef void (*SCE_PFX_FUNC_FREE)(void* ptr);
```

# Serialization APIs

000004892117

# Structures

## PfxSerializeCapacity

Structure storing size of physics instance subject to serialization processing

### Definition

```
#include <physics_effects/util/pfx_serialize_ex.h>
struct PfxSerializeCapacity
{
    PfxUInt32 maxRigidBodies;
    PfxUInt32 maxShapes;
    PfxUInt32 maxJoints;
    PfxUInt32 maxLargeMeshes;
    PfxUInt32 maxConvexMeshes;
    PfxUInt32 maxContacts;
    PfxUInt32 maxNonContactPairs;
    PfxUInt32 numRigidBodies;
    PfxUInt32 numShapes;
    PfxUInt32 numJoints;
    PfxUInt32 numLargeMeshes;
    PfxUInt32 numConvexMeshes;
    PfxUInt32 numContacts;
    PfxUInt32 numNonContactPairs;
};
```

### Members

<i>maxRigidBodies</i>	Maximum number of rigid bodies
<i>maxShapes</i>	Maximum number of shapes
<i>maxJoints</i>	Maximum number of joints
<i>maxLargeMeshes</i>	Maximum number of large meshes
<i>maxConvexMeshes</i>	Maximum number of convex meshes
<i>maxContacts</i>	Maximum number of contacts
<i>maxNonContactPairs</i>	Maximum number of non-contact pairs
<i>numRigidBodies</i>	Number of rigid bodies
<i>numShapes</i>	Number of shapes
<i>numJoints</i>	Number of joints
<i>numLargeMeshes</i>	Number of large meshes
<i>numConvexMeshes</i>	Number of convex meshes
<i>numContacts</i>	Number of contacts
<i>numNonContactPairs</i>	Number of non-contact pairs

### Description

For the serialization processing, this structure is used to notify to the serialization processing the maximum size and current size of the physics instance storage area being allocated at the application level.

In particular, when performing the serialization input processing, if the read data exceeds the maximum number set for this instance, the application must implement a callback function to reallocate the area.



# PfxSerializeBuffer

Structure collecting the pointers to serialization target area

## Definition

```
#include <physics_effects/util/pfx_serialize_ex.h>
struct PfxSerializeBuffer
{
    PfxVector3* worldCenter;
    PfxVector3* worldExtent;
    PfxVector3* gravity;
    PfxRigidState* states;
    PfxRigidBody* bodies;
    PfxCollidable* collidables;
    PfxShape* shapes;
    PfxJoint* joints;
    PfxUInt32* nonContactPairs;
    PfxFloat* timeStep;
    PfxFloat* separateBias;
    PfxUInt32* iteration;
    PfxLargeTriMesh** largeMeshes;
    PfxConvexMesh** convexMeshes;
};
```

## Members

<i>worldCenter</i>	Pointer to the world's center coordinates
<i>worldExtent</i>	Pointer to the world's extent
<i>gravity</i>	Pointer to the gravity
<i>states</i>	Pointer to the rigid body state buffer
<i>bodies</i>	Pointer to the rigid body attribute buffer
<i>collidables</i>	Pointer to the rigid body shape buffer
<i>shapes</i>	Pointer to the shape buffer
<i>joints</i>	Pointer to the joint buffer
<i>nonContactPairs</i>	Pointer to the non-contact pair buffer
<i>timeStep</i>	Pointer to the time step
<i>separateBias</i>	Pointer to the bias value
<i>iteration</i>	Pointer to the number of iterations
<i>largeMeshes</i>	Pointer to the large mesh buffer
<i>convexMeshes</i>	Pointer to the convex mesh buffer

## Description

For the serialization processing, this structure stores the pointers to the physics instance storage area being allocated at the user application level.

The pointer destination buffer is used as the data storage destination during input, and as the output data reference source during output.

Note that the large mesh buffer and the convex mesh buffer constitute the pointer array for each mesh, respectively. During input, allocate the memory for meshes internally, and store the pointer to the array. This pointer is set to the rigid body shape that refers to the mesh. Implement release of the mesh data at the application level. If using a user-specified memory allocator for the memory allocation for mesh data, make this setting using `pfxSetUtilityAllocator()`.

# Functions

## pfxSerializeRead

Serialization processing for inputting data from a file

### Definition

```
#include <physics_effects/util/pfx_serialize_ex.h>
PfxInt32 pfxSerializeRead (
    void* fh,
    PfxSerializeInitFunc funcInit,
    PfxSerializeTermFunc funcTerm,
    PfxSerializeUpdateFunc funcUpdate,
    PfxSerializeResizeFunc funcResize,
    PfxSerializeErrorFunc funcError = 0,
    eFileFormat format = kSnapshot
)
```

### Arguments

<i>fh</i>	FILE type pointer of the C standard library
<i>funcInit</i>	Pointer to the initialization callback function for serialization
<i>funcTerm</i>	Pointer to the termination callback function for serialization
<i>funcUpdate</i>	Pointer to the update callback function for serialization
<i>funcResize</i>	Pointer to the buffer resizing callback function at serialization
<i>funcError</i>	Pointer to the error handling callback function that is called when an error arises
<i>format</i>	Input format (currently only kSnapshot is valid)

### Return Values

Returns SCE\_PFX\_OK(0) for normal termination.

Returns the error SCE\_PFX\_ERR\_INVALID\_VALUE if the parameter is invalid.

### Description

This function is used to read a file that has been serialized beforehand. The read data is stored in the buffer specified in initialization callback function. The user must open an input file through the C standard library (text mode) and prepare *fh*, a pointer to the FILE type instance beforehand. The file will not be closed within the serialization processing. Thus, the application must close the file after the serialization has ended.

Each callback function specified to the arguments is called at the appropriate timing during the serialization processing. The initialization callback function is called prior to serialization, and the destination buffer and size information are set to structures PfxSerializeCapacity and PfxSerializeBuffer and are passed to serialization processing.

The amount of data stored in the file and the specified buffer capacity are compared, and if the buffer size is insufficient, the buffer resizing callback function is called. Perform buffer reallocation in the buffer resizing callback function and return true. If false is returned, or if the buffer resizing callback function has not been specified, capacity allocation is considered to have failed, the serialization processing is aborted, and the error handling callback function is called.

Upon completion of loading, after the data has been stored to the buffer, the termination callback function is called. Describe additional setups and other processing to this callback function.

SCE CONFIDENTIAL

---

During file reading, the update callback function can be called periodically to check the progress status.

In case of an error, the error handling callback function will be called.

000004892117

# pfxSerializeWrite

Serialization processing for outputting data into a file

## Definition

```
#include <physics_effects/util/pfx_serialize_ex.h>
PfxInt32 pfxSerializeWrite (
    void* fh,
    PfxSerializeInitFunc funcInit,
    PfxSerializeTermFunc funcTerm,
    PfxSerializeErrorFunc funcError = 0,
    eFileFormat format = kSnapshot
)
```

## Arguments

<i>fh</i>	FILE type pointer of the C standard library
<i>funcInit</i>	Pointer to the initialization callback function for serialization
<i>funcTerm</i>	Pointer to the termination callback function for serialization
<i>funcError</i>	Pointer to the error handling callback function that is called when an error arises
<i>format</i>	Input format (currently only kSnapshot is valid)

## Return Values

Returns SCE\_PFX\_OK (0) for normal termination of serialization processing  
Returns the error SCE\_PFX\_ERR\_INVALID\_VALUE if the parameter is invalid.

## Description

This function is used to write the Physics Effects instance into a file.

The user must open an input file through the C standard library and prepare a pointer to the FILE type instance beforehand. Be sure to open the file in writable binary mode. The file will not be closed within the serialization processing. Thus, the user must close the file after the serialization has ended.

Each callback function specified to the arguments is called at the appropriate timing during the serialization processing. The initialization callback function is called prior to serialization, and the write out reference source buffer and size information are set to structures PfxSerializeCapacity and PfxSerializeBuffer and are passed to serialization processing.

Upon completion of the write processing, the termination callback function is called. If necessary, execute the postprocessing within this function.

In case of an error, the error handling callback function will be called.

# Callback Functions

## PfxSerializeInitFunc

Initialization callback

### Definition

```
#include <physics_effects/util/pfx_serialize_ex.h>
typedef void(*PfxSerializeInitFunc)(
    PfxSerializeCapacity *capacity,
    PfxSerializeBuffer *buffer
);
```

### Arguments

<i>capacity</i>	Structure storing sizes of physics instances
<i>buffer</i>	Structure storing the pointers to the buffers

### Return Values

None

### Description

This callback function is called during serialization initialization.

If it is called from `pfxSerializeRead()`, the size of each physics instance is set to *capacity*, and the information of the pointer to the storage destination buffer is set to *buffer*. In the case of insufficient capacity, the resizing callback function is called.

If this function is called from `pfxSerializeWrite()`, the size of each physics instance is set to *capacity*, and the information of the pointer to the reference source buffer is set to *buffer*.

---

# PfxSerializeTermFunc

---

## Termination callback

### Definition

---

```
#include <physics_effects/util/pfx_serialize_ex.h>
typedef void(*PfxSerializeTermFunc) (
    PfxSerializeCapacity *capacity,
    PfxSerializeBuffer *buffer
);
```

### Arguments

---

*capacity*    Structure storing sizes of physics instances  
*buffer*       Structure storing the pointers to the buffers

### Return Values

---

None

### Description

---

This callback function is called upon completion of the serialization processing.

If it is called from `pfxSerializeRead()`, the size of the physics instance that is actually loaded is stored in *capacity*, and the data is stored in the buffers indicated by the pointers in *buffer*.

---

# PfxSerializeResizeFunc

---

## Buffer resizing callback

### Definition

---

```
#include <physics_effects/util/pfx_serialize_ex.h>
typedef PfxBool(*PfxSerializeResizeFunc) (
    PfxSerializeCapacity *capacity,
    PfxSerializeBuffer *buffer,
    const PfxSerializeCapacity *capacityLoaded
);
```

### Arguments

---

<i>capacity</i>	Structure storing sizes of physics instances
<i>buffer</i>	Structure storing the pointers to the buffers
<i>capacityLoaded</i>	Structure storing the sizes of physics instances to be loaded

### Return Values

---

Returns `true` when the buffer reallocation was successful, and `false` when it failed.

### Description

---

This function is called when the capacity of the buffer specified with the initialization callback function during file loading is insufficient. Because the capacity that is actually required is set to *capacityLoaded*, compare that value with the size specified to *capacity*, and reallocate the buffer for size of insufficiency.

SCE CONFIDENTIAL

---

# PfxSerializeUpdateFunc

---

## Update callback

### Definition

---

```
#include <physics_effects/util/pfx_serialize_ex.h>
typedef void(*PfxSerializeUpdateFunc) (
    PfxUInt32 progress,
    PfxUInt32 maxProgress
);
```

### Arguments

---

<i>progress</i>	Position during progress
<i>maxProgress</i>	Position at completion

### Return Values

---

None

### Description

---

This function, which is called periodically during serialization input, reports the current progress status to the application.



SCE CONFIDENTIAL

---

# PfxSerializeErrorFunc

---

## Error handling callback

### Definition

---

```
#include <physics_effects/util/pfx_serialize_ex.h>
typedef void(*PfxSerializeErrorFunc) (
    PfxInt32 errorCode,
    const char **tags,
    int numTags
);
```

### Arguments

---

*errorCode*    Error code  
*tags*        Array of tag character strings  
*numTags*     Number of tags stored to array

### Return Values

---

None

### Description

---

This function is called when an error occurs during serialization input/output. When an error occurs during file analysis, the tag information for determining the occurrence location is set along with the error code. For the tag information, the hierarchy from the root in the file is returned as an array of tag character strings.

One of the following is set for the error code.

Value	Description
SCE_PFX_ERR_SERIALIZE_INVALID_FILE	File loading failed
SCE_PFX_ERR_SERIALIZE_INVALID_VERSION	The format version is different
SCE_PFX_ERR_SERIALIZE_INVALID_TAG	An unidentifiable tag was found
SCE_PFX_ERR_SERIALIZE_INVALID_FORM	The data file format contains an error
SCE_PFX_ERR_SERIALIZE_INVALID_COUNT	Data inconsistency occurred

# Debug Rendering APIs

000004892117

# Structures

## PfxLargeMeshFlagTable

Structure managing the table of debug rendering type flag of large mesh

### Definition

```
#include <physics_effects/base_level/sort/pfx_sort_data.h>
Struct PfxLargeMeshFlagTable {
    PfxUInt32 rigidbodyId;
    PfxUInt8 * largeMeshFlagTable;
};
```

### Members

<i>rigidbodyId</i>	Index of rigid body
<i>largeMeshFlagTable</i>	Pointer to the flag table that manages the type of large mesh debug rendering

### Description

This structure manages both the rigid body index and the table storing the debug rendering type flag of each triangle to which a large mesh is set.

# Classes

## PfxDebugRender

Debug rendering class

### Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {};
```

### Description

This class provides functions to visualize the information in the physics engine for the debugging purpose. At the application level, functions to execute basic rendering processing to render points, lines, boxes, etc., are provided so as to prevent dependence on specific rendering APIs, and they are called through the user callback functions when debug rendering is executed. Before calling the debug rendering functions, it is necessary to set the required basic rendering processing function for each debug rendering function.

### Method List

Method	Description
setDebugRenderPointFunc	Sets the point rendering function
setDebugRenderLineFunc	Sets the line rendering function
setDebugRenderArcFunc	Sets the arc rendering function
setDebugRenderAabbFunc	Sets the bounding box rendering function
setDebugRenderBoxFunc	Sets the box rendering function
resetVisible	Resets the debug rendering visibility flag of a rigid body
getVisible	Gets the debug rendering visibility flag of each rigid body
setVisible	Sets the debug rendering visibility flag of each rigid body
renderWorld	Renders the bounding box in the world area
renderAabb	Renders the bounding box of the rigid body
renderLocalAxis	Renders the local coordinate axes
renderIsland	Renders the simulation island
renderContact	Renders the collision information
renderLargeMesh	Renders the debug information of a large mesh
renderLargeMeshInFrustum	Renders the debug information of the large meshes in the view frustum
renderLargeMeshByFlag	Renders the debug information of a large mesh according to the flag table
renderJoint	Renders the debug information of a joint
resetLargeMeshFlagTables	Resets the rendering type flag table of a large mesh
getLargeMeshFlag	Gets the rendering type flag of a large mesh
setLargeMeshFlag	Sets the rendering type flag of a large mesh
getScale	Gets the rendering scale of debug information
setScale	Sets the rendering scale of debug information

# Constructors and Destructors

## PfxDebugRender

Constructor of debug rendering class

### Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender{
    PfxDebugRender ();
};
```

### Arguments

None

### Return Values

None

### Description

This constructor is used to initialize the debug rendering class.

SCEI CONFIDENTIAL

---

## ~PfxDebugRender

---

Destructor of debug rendering class

### Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    ~PfxDebugRender ();
};
```

### Arguments

---

None

### Return Values

---

None

### Description

---

This destructor is used to clear the internal buffer.

# Public Methods

## setDebugRenderPointFunc

Set point rendering function

### Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void setDebugRenderPointFunc(PfxDebugRenderPointFunc func);
};
```

### Arguments

*func* Function pointer to the point rendering function

### Return Values

None

### Description

This public method sets the point rendering function prepared at the application level. The point rendering function must be set through this method before `renderContact()` and `renderJoint()` are used. Assert is called if the function is not set.

SCEI CONFIDENTIAL

---

# setDebugRenderLineFunc

---

Set line rendering function

## Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void setDebugRenderLineFunc (PfxDebugRenderLineFunc func);
};
```

## Arguments

*func* Function pointer to the line rendering function

## Return Values

None

## Description

This public method sets the line rendering function prepared at the application level.

The line rendering function must be set through this method before `renderContact()`, `renderLocalAxis()`, `renderLargeMeshByFlag()`, `renderLargeMesh()` and `renderJoint()` are used. Assert is called if the function is not set.



---

# setDebugRenderArcFunc

---

Set arc rendering function

## Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void setDebugRenderArcFunc (PfxDebugRenderArcFunc func);
};
```

## Arguments

---

*func* Function pointer to the arc rendering function

## Return Values

---

None

## Description

---

This public method sets the arc rendering function prepared at the application level.

The arc rendering function must be set through this method before `renderJoint()` is used. Assert is called if the function is not set.

---

# setDebugRenderAabbFunc

---

Set bounding box rendering function

## Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void setDebugRenderAabbFunc (PfxDebugRenderAabbFunc func);
};
```

## Arguments

---

*func* Function pointer to the bounding box rendering function

## Return Values

---

None

## Description

---

This public method sets the bounding box rendering function prepared at the application level. The bounding box rendering function must be set through this method before `renderWorld()`, `renderAabb()` and `renderIsland()` are used. Assert is called if the function is not set.

---

# setDebugRenderBoxFunc

---

Set box rendering function

## Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void setDebugRenderBoxFunc (PfxDebugRenderBoxFunc func);
};
```

## Arguments

---

*func* Function pointer to the box rendering function

## Return Values

---

None

## Description

---

This public method sets the box rendering function prepared at the application level.

The box rendering function must be set through this method before `renderContact()`, `renderLocalAxis()`, `renderLargeMeshByFlag()`, `renderLargeMesh()` and `renderJoint()` are used. Assert is called if the function is not set.

---

# resetVisible

---

Reset debug rendering visibility flag of rigid body

## Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void resetVisible (
        const PfxUInt32 numRigidbody
    );
};
```

## Arguments

---

*numRigidbody*    Number of rigid bodies

## Return Values

---

None

## Description

---

This public method discards the debug rendering visibility flag of the rigid bodies being held and rebuilds the visibility flag from the number of rigid bodies given as an argument. Flags in the rebuilt table are set with "Show".

# getVisible

Get debug rendering visibility flag of each rigid body

## Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    PfxInt32 getVisible (
        const PfxUInt32 rigidbodyId,
        PfxUInt8 &flag
    );
};
```

## Arguments

*rigidbodyId* Index of rigid body to be obtained  
*flag* Debug rendering visibility flag of rigid body to be obtained

## Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.

Returns the error SCE\_PFX\_ERR\_OUT\_OF\_RANGE if the parameter range is invalid and error SCE\_PFX\_ERR\_INVALID\_FLAG if the flag value is invalid.

## Description

This public method gets the rendering type flag set through the `setVisible()` method.

The following values are set to *flag*.

Value	Description
SCE_PFX_DRENDER_INVISIBLE	Hide
SCE_PFX_DRENDER_VISIBLE	Show

SCE CONFIDENTIAL

# setVisible

Set debug rendering visibility flag of each rigid body

## Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    PfxInt32 setVisible (
        const PfxUInt32 rigidbodyId,
        const PfxUInt8 flag
    );
};
```

## Arguments

*rigidbodyId*      Index of rigid body to be set  
*flag*              Debug rendering visibility flag of rigid body to be set

## Return Values

Returns SCE\_PFX\_OK(0) upon normal termination.

Returns the error SCE\_PFX\_ERR\_OUT\_OF\_RANGE if the parameter range is invalid and error SCE\_PFX\_ERR\_INVALID\_FLAG if the flag value is invalid.

## Description

This public method sets the debug rendering visibility flag to the rigid body specified with *rigidbodyId*.

The following values are set to *flag*.

Value	Description
SCE_PFX_DRENDER_INVISIBLE	Hide
SCE_PFX_DRENDER_VISIBLE	Show

---

# renderWorld

---

## Render bounding box in world area

### Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void renderWorld(
        const PfxVector3 &center,
        const PfxVector3 &halfExtent
    );
};
```

### Arguments

---

<i>center</i>	Center coordinates value of bounding box in the world area
<i>halfExtent</i>	Size of bounding box in the world area

### Return Values

---

None

### Description

---

This public method renders the bounding box in the world area.

The bounding box rendering function must be set through `setDebugRenderAabbFunc()` beforehand.

Assert is called if the function is not set.

# renderAabb

## Render bounding box of rigid body

### Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void renderAabb(
        const PfxRigidBodyState *states,
        const PfxCollidable *collidables,
        const PfxUInt32 numRigidbodies
    );
};
```

### Arguments

<i>states</i>	Rigid body state
<i>collidables</i>	Rigid body shape
<i>numRigidbodies</i>	Number of rigid bodies

### Return Values

None

### Description

This public method renders the bounding box of each rigid body.

The bounding box rendering function must be set through `setDebugRenderAabbFunc()` beforehand.

Assert is called if the function is not set.



---

# renderLocalAxis

---

## Render local coordinate axes

### Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void renderLocalAxis(
        const PfxRigidState *states,
        const PfxUInt32 numRigidbody
    );
};
```

### Arguments

---

<i>states</i>	Rigid body state
<i>numRigidbody</i>	Number of rigid bodies

### Return Values

---

None

### Description

---

This public method renders the local coordinate axes of each rigid body.  
The line rendering function must be set through `setDebugRenderLineFunc()` beforehand.  
Assert is called if the function is not set.

---

# renderIsland

---

## Render simulation island

### Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void renderIsland(
        const PfxIsland *island,
        const PfxRigidBodyState *states,
        const PfxCollidable *collidables
    );
};
```

### Arguments

---

<i>island</i>	Simulation Island
<i>states</i>	Rigid body state
<i>collidables</i>	Rigid body shape

### Return Values

---

None

### Description

---

This public method renders the simulation island.

The bounding box rendering function must be set through `setDebugRenderAabbFunc()` beforehand.

Assert is called if the function is not set.

# renderContact

## Render collision information

### Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void renderContact (
        const PfxContactManifold *contacts,
        const PfxBroadphasePair *pairsBuff,
        const PfxRigidState *states,
        const PfxUInt32 numContacts
    );
};
```

### Arguments

<i>contacts</i>	Contact information
<i>pairsBuff</i>	Pair buffer
<i>states</i>	Rigid body state
<i>numContacts</i>	Number of contacts

### Return Values

None

### Description

This public method renders each collision point and normal vector.

The point rendering function and line rendering function must be set through

`setDebugRenderPointFunc()` and `setDebugRenderLineFunc()` respectively in advance.

Assert is called if the function is not set.

# renderLargeMesh

## Render debug information of large mesh

### Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void renderLargeMesh(
        const PfxRigidBodyState *states,
        const PfxCollidable *collidables,
        const PfxUInt32 numRigidbodies,
        const PfxUInt32 flag
    );
};
```

### Arguments

<i>states</i>	Rigid body state
<i>collidables</i>	Rigid body shape
<i>numRigidbodies</i>	Number of rigid bodies
<i>flag</i>	Mesh rendering type flag

### Return Values

None

### Description

This public method performs rendering processing for all the flags to which the island mesh, edge of the triangle and AABB of the triangle, which are collectively referred to as the debug information of each large mesh, are specified.

The line rendering function and box rendering function must be set through `setDebugRenderLineFunc()` and `setDebugRenderBoxFunc()` respectively in advance. Assert is called if the function is not set.

# renderLargeMeshInFrustum

Render debug information of large mesh in view frustum

## Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void renderLargeMeshInFrustum (
        const PfxRigidState *states,
        const PfxCollidable *collidables,
        const PfxUInt32 numRigidbody,
        const PfxUInt32 flag,
        const PfxVector4* planes,
        int numPlanes
    );
};
```

## Arguments

<i>states</i>	Rigid body state
<i>collidables</i>	Rigid body shape
<i>numRigidbody</i>	Number of rigid bodies
<i>flag</i>	Mesh rendering type flag
<i>planes</i>	Array of planes making up view frustum
<i>numPlanes</i>	Number of planes making up view frustum

## Return Values

None

## Description

This public method renders all the debug information on the islands included in the specified view frustum for the rendering flags to which the island mesh, edge of the triangle and AABB of the triangle, which are collectively referred to as the debug information of each large mesh, are specified.

The line rendering function and box rendering function must be set through `setDebugRenderLineFunc()` and `setDebugRenderBoxFunc()`, respectively, in advance.

Assert is called if the functions are not set.

The range that is displayed depends on the value of *planes*.

numPlanes value	Description
0	Renders everything (same as <code>renderLargeMesh()</code> )
1	Renders the triangles included in the island whose center coordinate and radius consist of the first three elements and the fourth element, respectively, of <i>planes</i> [0].
2 or higher	With the plane whose normal vector consists of the first three elements and whose distance from the origin consists of the fourth element, respectively, of each <i>planes</i> , as the boundary, renders the triangles included in the island whose normal vector points in the opposite direction.

# renderLargeMeshByFlag

Render debug information of large mesh according to the flag table

## Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void renderLargeMeshByFlag(
        const PfxRigidBodyState *states,
        const PfxCollidable *collidables,
        const PfxUInt32 flag
    );
};
```

## Arguments

<i>states</i>	Rigid body state
<i>collidables</i>	Rigid body shape
<i>flag</i>	Mesh rendering type flag

## Return Values

None

## Description

Among the mesh rendering type flag table set through `setLargeMeshFlag()` in advance, this public method only renders the debug information of the large mesh specified with *flag*.

The line rendering function and box rendering function must be set through `setDebugRenderLineFunc()` and `setDebugRenderBoxFunc()` respectively in advance.

Assert is called if the function is not set.

# renderJoint

## Render debug information of joint

### Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void renderJoint(
        const PfxJoint *joints,
        const PfxRigidState *states,
        const PfxUInt32 numJoints
    );
};
```

### Arguments

<i>joints</i>	Joint structure
<i>states</i>	Rigid body state
<i>numJoints</i>	Number of joints

### Return Values

None

### Description

This public method renders the debug information of each joint.

The point, line and arc rendering functions must be set through `setDebugRenderPointFunc()`, `setDebugRenderLineFunc()` and `setDebugRenderArcFunc()` respectively in advance.

Assert is called if the function is not set.

---

# resetLargeMeshFlagTables

---

Reset rendering type flag table of large mesh

## Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void resetLargeMeshFlagTables (
        const PfxCollidable *collidables,
        const PfxUInt32 numRigidbody
    );
};
```

## Arguments

---

<i>collidables</i>	Rigid body shape
<i>numRigidbody</i>	Number of rigid bodies

## Return Values

---

None

## Description

---

This public method discards the rendering type flag table of the mesh being held and rebuilds the new rendering type flag table from the rigid body shape given as an argument. Flags in the rebuilt table are cleared with 0.

Assert is called if the rebuilding of the flag table fails.



SCE CONFIDENTIAL

# getLargeMeshFlag

Get rendering type flag of large mesh

## Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    PfxInt32 getLargeMeshFlag(
        const PfxUInt32 rigidbodyId,
        const PfxUInt32 islandId,
        const PfxUInt32 facetId,
        PfxUInt8 &flag
    );
};
```

## Arguments

*rigidbodyId* Index of the rigid body to which the mesh is set  
*islandId* Index of the island mesh  
*facetId* Index of the triangle  
*flag* Rendering type flag to be acquired

## Return Values

Returns SCE\_PFX\_OK(0) for normal termination.

Returns an error of SCE\_PFX\_ERR\_OUT\_OF\_RANGE if the range of parameter is invalid.

## Description

This public method gets the rendering type flag set through the `setLargeMeshFlag()` method.  
 Combination of the following values is set to *flag*.

Value	Description
SCE_PFX_DRENDER_MESH_FLG_NONE	No flag is set
SCE_PFX_DRENDER_MESH_FLG_ISLAND	Renders the specified island mesh
SCE_PFX_DRENDER_MESH_FLG_EDGE	Renders the specified edge of triangle
SCE_PFX_DRENDER_MESH_FLG_FACET_AABB	Renders the specified bounding box (AABB) of triangle
SCE_PFX_DRENDER_MESH_FLG_NORMAL	Renders the normal of triangle
SCE_PFX_DRENDER_MESH_FLG_THICKNESS	Renders the thickness of triangle
SCE_PFX_DRENDER_MESH_FLG_ALL	Specifies all the flags

SCE CONFIDENTIAL

# setLargeMeshFlag

Set rendering type flag of large mesh

## Definition

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    PfxInt32 setLargeMeshFlag(
        const PfxUInt32 rigidbodyId,
        const PfxUInt32 islandId,
        const PfxUInt32 facetId,
        const PfxUInt8 flag
    );
};
```

## Arguments

<i>rigidbodyId</i>	Index of the rigid body to which the mesh is set
<i>islandId</i>	Index of the island mesh
<i>facetId</i>	Index of the triangle
<i>flag</i>	Rendering type flag

## Return Values

Returns SCE\_PFX\_OK(0) for normal termination.

Returns an error of SCE\_PFX\_ERR\_OUT\_OF\_RANGE if the range of parameter is invalid.

## Description

This public method sets a flag to the rendering type flag table of the large mesh specified with *rigidbodyId*.

to *flag* specify combination of the following values.

Value	Description
SCE_PFX_DRENDER_MESH_FLG_NONE	Clears the flag
SCE_PFX_DRENDER_MESH_FLG_ISLAND	Renders the island mesh
SCE_PFX_DRENDER_MESH_FLG_EDGE	Renders the edge of triangle
SCE_PFX_DRENDER_MESH_FLG_FACET_AABB	Renders the bounding box (AABB) of triangle
SCE_PFX_DRENDER_MESH_FLG_NORMAL	Renders the normal of triangle
SCE_PFX_DRENDER_MESH_FLG_THICKNESS	Renders the thickness of triangle
SCE_PFX_DRENDER_MESH_FLG_ALL	Specifies all the flags

SCE CONFIDENTIAL

---

## getScale

---

Get rendering scale of debug information

### Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    PfxFloat getScale();
};
```

### Arguments

---

None

### Return Values

---

Returns the value of the scale

### Description

---

This public method returns the rendering scale value of the debug information.

SCEI CONFIDENTIAL

---

## setScale

---

Set rendering scale of debug information

### Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
class PfxDebugRender {
    void setScale(PfxFloat scale);
};
```

### Arguments

---

*scale* Scale

### Return Values

---

None

### Description

---

This public method sets the rendering scale value of the debug information.

# Callback Functions

## PfxDebugRenderPointFunc

Callback function that is called during point rendering

### Definition

```
#include <physics_effects/util/pfx_debug_render.h>
typedef void (*PfxDebugRenderPointFunc) (
    const PfxVector3 &position,
    const PfxVector3 &color
);
```

### Arguments

<i>position</i>	Position of point
<i>color</i>	Color of point

### Return Values

None

### Description

Implement the codes for rendering points at the specified positions.

---

# PfxDebugRenderLineFunc

---

Callback function that is called during line rendering

## Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
typedef void (*PfxDebugRenderLineFunc) (
    const PfxVector3 &position1,
    const PfxVector3 &position2,
    const PfxVector3 &color
);
```

## Arguments

---

<i>position1</i>	Start position of the line
<i>position2</i>	End position of the line
<i>color</i>	Color of the line

## Return Values

---

None

## Description

---

Implement the codes for rendering lines at the specified positions.

SCE CONFIDENTIAL

# PfxDebugRenderArcFunc

Callback function that is called during arc rendering

## Definition

```
#include <physics_effects/util/pfx_debug_render.h>
typedef void (*PfxDebugRenderArcFunc) (
    const PfxVector3 &pos,
    const PfxVector3 &axis,
    const PfxVector3 &dir,
    const float radius,
    const float startRad,
    const float endRad,
    const PfxVector3 &color
);
```

## Arguments


<i>pos</i>	Center of the arc
<i>axis</i>	Axis of rotation of the arc
<i>dir</i>	Vector from the center to the arc
<i>radius</i>	Radius of the arc
<i>startRad</i>	Rendering start angle of the arc
<i>endRad</i>	Rendering end angle of the arc
<i>color</i>	Color of the arc

## Return Values

None

## Description

Implement the codes for rendering arcs.



---

# PfxDebugRenderAabbFunc

---

Callback function that is called during bounding box rendering

## Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
typedef void (*PfxDebugRenderAabbFunc) (
    const PfxVector3 &center,
    const PfxVector3 &halfExtent,
    const PfxVector3 &color
);
```

## Arguments

---

<i>center</i>	Center of the bounding box
<i>halfExtent</i>	Extent of the bounding box
<i>color</i>	Color of the bounding box

## Return Values

---

None

## Description

---

Implement the codes for rendering boxes parallel to the XYZ axes.



---

# PfxDebugRenderBoxFunc

---

Callback function that is called during box rendering

## Definition

---

```
#include <physics_effects/util/pfx_debug_render.h>
typedef void (*PfxDebugRenderBoxFunc) (
    const PfxTransform3 &transform,
    const PfxVector3 &halfExtent,
    const PfxVector3 &color
);
```

## Arguments

---

<i>transform</i>	Transform of the box
<i>halfExtent</i>	Extent of the box
<i>color</i>	Color of the box

## Return Values

---

None

## Description

---

Implement the codes for rendering boxes.