

# **libsfmt132049 Reference**

© 2011 Sony Computer Entertainment Inc.  
All Rights Reserved.  
SCE Confidential

## Table of Contents

---

<b>Constants .....</b>	<b>3</b>
SCE_SFMT132049_ARRAY_SIZE .....	4
<b>Datatypes .....</b>	<b>5</b>
SceSfmt132049Context .....	6
<b>Functions .....</b>	<b>7</b>
sceSfmt132049InitGenRand .....	8
sceSfmt132049InitByArray .....	9
sceSfmt132049GenRand32 .....	10
sceSfmt132049GenRand64 .....	11
sceSfmt132049FillArray32 .....	12
sceSfmt132049FillArray64 .....	13

# Constants

000004892117

SCE CONFIDENTIAL

---

## **SCE\_SFMT132049\_ARRAY\_SIZE**

---

Array size for SFMT132049 pseudo random number calculation

### **Definition**

---

```
#include <libsfmt132049.h>
#define SCE_SFMT132049_ARRAY_SIZE 1032 /* (132049 / 128) + 1 */
```

### **Description**

---

This constant defines the array size for pseudo random numbers in conformance with SFMT132049. In addition to indicating the array size that is maintained as state in the `SceSfmt132049Context` structure, this constant is also used by the `sceSfmt132049FillArray32()` and `sceSfmt132049FillArray64()` functions to indicate the minimum size for generating random numbers.

### **See Also**

---

`SceSfmt132049Context`, `sceSfmt132049FillArray32()`, `sceSfmt132049FillArray64()`

# Datatypes

000004892117

# SceSfmt132049Context

---

Context information for SFMT132049 pseudo random number calculation

## Definition

---

```
#include <libsfmt132049.h>
typedef struct SceSfmt132049Context {
    unsigned int idx;
    unsigned int sfmt[SCE_SFMT132049_ARRAY_SIZE][4];
} SceSfmt132049Context;
```

## Description

---

This structure is a work area for calculating pseudo random numbers in conformance with SFMT132049.

One instance of this work area must be prepared for each random number sequence.

## See Also

---

SCE\_SFMT132049\_ARRAY\_SIZE, sceSfmt132049InitGenRand(),  
sceSfmt132049InitByArray()

# Functions

000004892117

# sceSfmt132049InitGenRand

Initialize SFMT132049 pseudo random number work area

## Definition

```
#include <libsfmt132049.h>
SceInt32 sceSfmt132049InitGenRand (
    SceSfmt132049Context *pCtx,
    SceUInt32 seed
);
```

## Calling Conditions

Multithread safe

## Arguments

*pCtx* Pointer to an `SceSfmt132049Context` structure, which represents a random number sequence as a context.  
*seed* Specifies a random number sequence.

## Return Values

If an error occurs, a negative value is returned.

Value	Result
SCE_OK	Normal completion

## Description

This function uses a 32-bit seed to initialize an SFMT132049 random number sequence, which is represented by the `SceSfmt132049Context` structure. This function must be executed before the `sceSfmt132049GenRand32()`, `sceSfmt132049GenRand64()`, `sceSfmt132049FillArray32()`, and `sceSfmt132049FillArray64()` functions.

Since only the `SceSfmt132049Context` structure indicated by *pCtx* is initialized, multiple random number sequences can be handled simultaneously by having multiple `SceSfmt132049Context` structures.

## See Also

`SceSfmt132049Context`, `sceSfmt132049InitByArray()`



# sceSfmt132049InitByArray

Initialize SFMT132049 pseudo random number work area

## Definition

```
#include <libsfmt132049.h>
SceInt32 sceSfmt132049InitByArray (
    SceSfmt132049Context *pCtx,
    const SceUInt32 initkey[],
    SceUInt32 keylength
);
```

## Calling Conditions

Multithread safe

## Arguments

<i>pCtx</i>	Pointer to an <code>SceSfmt132049Context</code> structure, which represents a random number sequence as a context.
<i>initkey</i>	Specifies the array to be used for initializing.
<i>keylength</i>	Number of elements in <i>initkey</i> .

## Return Values

If an error occurs, a negative value is returned.

Value	Result
SCE_OK	Normal completion

## Description

This function uses an array of 32-bit seeds to initialize an SFMT132049 random number sequence, which is represented by the `SceSfmt132049Context` structure. This function must be executed before the `sceSfmt132049GenRand32()`, `sceSfmt132049GenRand64()`, `sceSfmt132049FillArray32()`, and `sceSfmt132049FillArray64()` functions.

Since only the `SceSfmt132049Context` structure indicated by *pCtx* is initialized, multiple random number sequences can be handled simultaneously by having multiple `SceSfmt132049Context` structures.

## See Also

`SceSfmt132049Context`, `sceSfmt132049InitGenRand()`

## sceSfmt132049GenRand32

---

Generate an SFMT132049 32-bit pseudo random number

### Definition

---

```
#include <libmt132049.h>
SceUInt32 sceSfmt132049GenRand32 (
    SceSfmt132049Context *pCtx
);
```

### Calling Conditions

---

Multithread safe

### Arguments

---

*pCtx* Pointer to an `SceSfmt132049Context` structure, which represents a random number sequence as a context.

### Return Values

---

32-bit pseudo random number

### Description

---

This function generates a 32-bit pseudo random number that conforms to SFMT132049.

Before using this function, the `SceSfmt132049Context` structure must be initialized by calling the `sceSfmt132049InitGenRand()` or `sceSfmt132049InitByArray()` functions.

### See Also

---

`SceSfmt132049Context`, `sceSfmt132049InitGenRand()`, `sceSfmt132049InitByArray()`

---

## sceSfmt132049GenRand64

---

Generate an SFMT132049 64-bit pseudo random number

### Definition

---

```
#include <libmt132049.h>
SceUInt64 sceSfmt132049GenRand64 (
    SceSfmt132049Context *pCtx
);
```

### Calling Conditions

---

Multithread safe

### Arguments

---

*pCtx* Pointer to an `SceSfmt132049Context` structure, which represents a random number sequence as a context.

### Return Values

---

64-bit pseudo random number

### Description

---

This function generates a 64-bit pseudo random number that conforms to SFMT132049.

Before using this function, the `SceSfmt132049Context` structure must be initialized by calling the `sceSfmt132049InitGenRand()` or `sceSfmt132049InitByArray()` functions.

Note that if the `sceSfmt132049GenRand32()` and `sceSfmt132049GenRand64()` functions are used together and the `sceSfmt132049GenRand64()` function is called after the `sceSfmt132049GenRand32()` function has been called an odd number of times, a full 64-bit random number will not be obtained. Instead, this function will return a 64-bit value in which the upper 32 bits are zero.

### See Also

---

`SceSfmt132049Context`, `sceSfmt132049InitGenRand()`, `sceSfmt132049InitByArray()`

## sceSfmt132049FillArray32

Generate an array of SFMT132049 32-bit pseudo random numbers

### Definition

```
#include <libmt132049.h>
SceInt32 sceSfmt132049FillArray32 (
    SceSfmt132049Context *pCtx,
    SceUInt32 array[],
    SceUInt32 size
);
```

### Calling Conditions

Multithread safe

### Arguments

*pCtx* Pointer to an `SceSfmt132049Context` structure, which represents a random number sequence as a context.

*array* Buffer for receiving the generated random numbers

*size* Number of elements in *array* (multiple of 4 that is larger than `SCE_SFMT132049_ARRAY_SIZE*4`)

### Return Values

If an error occurs, a negative value is returned.

Value	Result
<code>SCE_OK</code>	Normal completion

### Description

This function generates an arbitrary number of 32-bit pseudo random numbers that conform to SFMT132049. *size* specifies the number of elements in *array* and must be a multiple of 4 that is larger than `(SCE_SFMT132049_ARRAY_SIZE * 4)`.

Before using this function, the `SceSfmt132049Context` structure must be initialized by calling the `sceSfmt132049InitGenRand()` or `sceSfmt132049InitByArray()` functions.

When the `sceSfmt132049FillArray32()` function is used together with the `sceSfmt132049GenRand32()` function, the `sceSfmt132049FillArray32()` function can be called only after the `sceSfmt132049GenRand32()` function has been called `(SCE_SFMT132049_ARRAY_SIZE * 4)` times.

When the `sceSfmt132049FillArray32()` function is used together with the `sceSfmt132049GenRand64()` function, the `sceSfmt132049FillArray32()` function can be called only after the `sceSfmt132049GenRand64()` function has been called `(SCE_SFMT132049_ARRAY_SIZE * 2)` times.

### See Also

`SceSfmt132049Context`, `sceSfmt132049InitGenRand()`, `sceSfmt132049InitByArray()`

## sceSfmt132049FillArray64

Generate an array of SFMT132049 64-bit pseudo random numbers

### Definition

```
#include <libmt132049.h>
SceInt32 sceSfmt132049FillArray64 (
    SceSfmt132049Context *pCtx,
    SceUInt64 array[],
    SceUInt32 size
);
```

### Calling Conditions

Multithread safe

### Arguments

*pCtx* Pointer to an `SceSfmt132049Context` structure, which represents a random number sequence as a context.

*array* Buffer for receiving the generated random numbers

*size* Number of elements in *array* (multiple of 2 that is larger than `SCE_SFMT132049_ARRAY_SIZE*2`)

### Return Values

If an error occurs, a negative value is returned.

Value	Result
<code>SCE_OK</code>	Normal completion

### Description

This function generates an arbitrary number of 64-bit pseudo random numbers that conform to SFMT132049. *size* specifies the number of elements in *array* and must be a multiple of 2 that is larger than `(SCE_SFMT132049_ARRAY_SIZE * 2)`.

Before using this function, the `SceSfmt132049Context` structure must be initialized by calling the `sceSfmt132049InitGenRand()` or `sceSfmt132049InitByArray()` functions.

When the `sceSfmt132049FillArray64()` function is used together with the `sceSfmt132049GenRand32()` function, the `sceSfmt132049FillArray64()` function can be called only after the `sceSfmt132049GenRand32()` function has been called `(SCE_SFMT132049_ARRAY_SIZE * 4)` times.

When the `sceSfmt132049FillArray64()` function is used together with the `sceSfmt132049GenRand64()` function, the `sceSfmt132049FillArray64()` function can be called only after the `sceSfmt132049GenRand64()` function has been called `(SCE_SFMT132049_ARRAY_SIZE * 2)` times.

### See Also

`SceSfmt132049Context`, `sceSfmt132049InitGenRand()`, `sceSfmt132049InitByArray()`