

generates and manages this transport profile as a part of the transport domain configuration. Do not adjust the transport profile using a text editor at operating system level.

The diagram illustrates the configuration of the Transport Control Program (tp) parameters. It shows a 'Transport Directory' box connected via an 'RFC' to a 'Transport Tool' window. The 'Transport Tool' window displays a list of parameters with their categories and values. The 'RECCLIENT' parameter is highlighted with a red oval and set to 'ALL *'. A legend window titled 'S4D(1)/000 Legend: Transport tool configuration' provides details about the parameter types.

Global	Parameters	Cat	Value
<input checked="" type="checkbox"/>	TRANSDIR		/usr/sap/trans
<input type="checkbox"/>	ABAPNTFMODE		b
<input type="checkbox"/>	CTC		1
<input type="checkbox"/>	IMPORT_SINGLE_ONLY		0
<input type="checkbox"/>	IMPORT_SINGLE_STRATEGY		0
<input type="checkbox"/>	NBUFORM		1
<input type="checkbox"/>	NO_IMPORT_ALL		0
<input type="checkbox"/>	RECCLIENT		ALL *
<input type="checkbox"/>	REPEATONERROR		9
<input type="checkbox"/>	STOPONERROR		9
<input type="checkbox"/>	TP_VERSION		380
<input type="checkbox"/>	WORKFLOW		

*** This example shows the activation of the table change logging during import for all clients**

Figure 45: Configuring the Transport Control Program tp

To display the *tp* parameters of an SAP system, call transaction *STMS*. Choose *Overview* → *Systems*. Mark one SAP system and choose *SAP System* → *Display*. Choose the tab *Transport Tool*. From the menu, choose *Goto* → *tp Parameters*. This displays the parameters in *TP_<domain name>.PFL*, as well as the default value of other parameters used by the programs *tp* and *R3trans*. If a parameter is not specified in the *TP_<domain name>.PFL* file, a default value will be used. Global parameters override defaults. Local parameters override global parameters. For example, you can specify a global parameter value for all but one SAP system, if a local parameter applies to that SAP system.

You can switch between the *Display All Parameters* and *Display Substituted Parameters Only* views (content of *TP_<domain name>.PFL*), by using the *Display Less* and *Display More* buttons.



Note:

The example in the above figure shows the setting of the *tp* parameter *RECCLIENT* to *ALL* (all clients). This can be used to record changes to data caused by the import of transport requests. This may be necessary for audit purposes. To record data changes done from within the SAP system, you can use profile parameter *rec/client*, as mentioned in a previous lesson.