

RenderWare Graphics

Tool

2dconvert

Contact Us

Criterion Software Ltd.

For general information about RenderWare Graphics e-mail info@csl.com.

Contributors

RenderWare Graphics development and documentation teams.

The information in this document is subject to change without notice and does not represent a commitment on the part of Criterion Software Ltd. The software described in this document is furnished under a license agreement or a non-disclosure agreement. The software may be used or copied only in accordance with the terms of the agreement. It is against the law to copy the software on any medium except as specifically allowed in the license or non-disclosure agreement. No part of this manual may be reproduced or transmitted in any form or by any means for any purpose without the express written permission of Criterion Software Ltd.

Copyright © 1993 - 2003 Criterion Software Ltd. All rights reserved.

Canon and RenderWare are registered trademarks of Canon Inc. Nintendo is a registered trademark and NINTENDO GAMECUBE a trademark of Nintendo Co., Ltd. Microsoft is a registered trademark and Xbox is a trademark of Microsoft Corporation. PlayStation is a registered trademark of Sony Computer Entertainment Inc. Macromedia is a registered trademark and Flash is a trademark of Macromedia, Inc. All other trademark mentioned herein are the property of their respective companies.

Table of Contents

1.1	Introduction	4
1.1.1	File types.....	4
1.1.2	Other Documentation	4
1.2	Operation	5
1.2.1	File Locations	5
1.2.2	Basic Operation	5
1.2.3	Help Message	5
1.2.4	Export Options	8
1.2.5	Output Files Options.....	8
1.2.6	fontalias.txt	8
1.2.7	Testing the Output.....	9
1.3	Summary.....	10

1.1 Introduction

2dconvrt is primarily an importer of Flash **.swf** files into the RenderWare Graphics **.anm** format. These files may then be played back with the **2dviewer** viewer, which uses the **Rt2dAnim** library.

It can also separate out the different component files that make up the 2D content in a **.swf** file.

1.1.1 File types

It should be noted that the output files from **2dconvrt**, e.g. **.dff**, **.anm**, are considered to have legacy file types as of RenderWare Graphics 3.5. This does *not* mean that the data that these files contain is obsolete. RenderWare Graphics 3.5, and its respective viewers in the SDK, will continue to read the files as before, and there is no need to reconvert existing data.

1.1.2 Other Documentation

- API Reference
 - **Rt2d** toolkit
 - **Rt2dAnim** toolkit (Maestro)
- 2d Graphics Toolkit Chapter in the User Guide

1.2 Operation

1.2.1 File Locations

The `2dconvrt` program is located in the RenderWare Graphics `tools/2dconvrt` directory. This directory contains the `2dconvrt` executable, a data directory including some sample `.swfs`, a sample font directory and a `fontalias.txt` configuration file.

1.2.2 Basic Operation

The `2dconvrt` program may be run from the command line, or a windows shortcut could be set up to launch it in the correct directory.

It can be run on one or more `.swf` files. Wildcards may be used in the specification of which files are to be converted.

Examples:

```
2dconvrt dilbert1.swf
```

The result of this command will be a `dilbert1.anm` file in the same directory as the source `.swf` file.

```
2dconvrt *.swf
```

The result of this command will be a `.anm` file for every `.swf` in the directory.

1.2.3 Help Message

If the converter is run with no parameters, or the `-h` parameter, the following help message is displayed.

2dconvrt : RenderWare 2D Animation File Importer

(c) 2001 Criterion Software Ltd.

2dconvrt usage :

2dconvrt <misc options> <export options> <output files options>
<filename>.swf

<misc options>

- h : Display this help message
- q : Quiet mode : no message is output
- fa <filename> : Use this file for font aliasing
the default file is fontalias.txt

<export options> - if none are specified, default options are xm
and xb

- xo : Export static objects
- xs : Export scenes
- xm : Export maestro (default)
- xa : Export animations
- xb : Export bitmaps out of given files (default)
- r <instance> : Do not export objects called <instance>

<output files options>

The conversion process may generate .anm (maestro or animations),
.dff (2d object, eg shape, scene, or text strings) and .png
(bitmap) files.

Output files are named using the following scheme:

<output filename><_type><_globalNum><_localNum>.<ext>

- p <prefix> : Replace <filename> with <prefix>.
- t : Fill <_type> and use it in the <output
filename>.
- g : Fill <_globalNum> and use it.
<_globalNum> is the file index if a
list of file is submitted or 0.
- l : Don't use <_localNum>.
<_localNum> is the object index in
the current swf file.
- i : use the object TagId for <_localNum>.
In a flash file every object have its own tagId
a tagId is a unique number that identify this
object

2dconvrt supports wildcards in input filenames.

Examples:

2dconvrt *.swf

convert all .swf files in the current directory to .anm files

```
2dconvrt -xo test.swf
    extract all 2d objects as .dff files from test.swf
```

For more information on 2dconvrt please refer to the user guide.

1.2.4 Export Options

The default export option of **2dconvrt** is to convert the Flash **.swf** file to a RenderWare Graphics **.anm** file.

This may be changed through the export options. The **-xo** and **-xs** options save **.dff** files containing individual shapes and entire scenes from the animation respectively.

The **-xb** option is used to extract bitmaps in **.png** format from the **.swf** file.

The **-xa** option extracts lone animations (one for each movie clip including the main clip) that can be used in conjunction with the corresponding scene obtained with **-xs**.

The **-r <instance>** option stops objects with instance names of **<instance>** from being exported. This is a handy method of preventing the "virtual controller" used during development from being exported with production files. See the "Maestro" user guide chapter in *UserGuideVol3.pdf* and **maestro1** example for more details of virtual controllers.

If any export option is chosen, the default (**-xm**) is not used.

1.2.5 Output Files Options

These options may be used to control the naming and numbering of the output files.

-p specifies the prefix to be used in filename generation; the default is the same name as the input file.

-t specifies that a file type be included in the filename of each file generated.

By default, the files are numbered in the order they appear in the **.swf** file. **-l** can be used to disable this numbering.

Inside the source file, objects have unique IDs. Sometimes it is convenient to name output files by the ID of the object that sourced it. The **-i** flag allows this to be done.

1.2.6 fontalias.txt

This configuration file specifies the location of fonts relative to where **2dconvrt** is run, and also mappings between fonts in Flash and fonts in RenderWare Graphics.

Care should be taken that if **2dconvrt** is run from a different directory than that where its executable is located, that directory should contain a valid **fontalias.txt** file.

1.2.7 Testing the Output

The output from the converter may be tested in the **2dviewer** viewer included with the RenderWare Graphics SDK. Files to be tested may be dragged into the **2dviewer** window.

Note that the viewer looks for all fonts in a single "font" directory below that of the **2dviewer** executable. It searches for images (**.pngs**) in the same directory as the **.anm** being played.

The viewer may also be used to display scenes or shapes contained in **.dffs**.

1.3 Summary

This chapter has covered:

- purpose of the **2dconvrt** program
- location of files involved in using the **2dconvrt** program
- command line parameters
- testing the results of **2dconvrt**