

# Notes on using the X16 Edit ROM version

December 26, 2020

## 1 Introduction

This document describes the steps required to install and use the X16 Edit ROM version:

- Prepare a custom ROM image
- Enter startup code in RAM

The methods described herein are tested on emulator version R38.

## 2 Prepare a custom ROM image

The first task is to prepare a custom ROM image that may be mounted in the emulator.

You got the standard ROM image when you downloaded the emulator. It's the file rom.bin, normally in the same folder as the emulator.

The standard ROM image uses banks 0–6 as follows:

0. KERNAL
1. Keyboard layout tables
2. CBM-DOS
3. GEOS KERNAL
4. BASIC interpreter
5. Machine language monitor
6. Charset data
7. Unused

The most user-friendly option would be to distribute a complete custom ROM image with banks 0–6 from the standard rom.bin, and with X16 Edit ROM code in bank 7.

The X16 Kernal is, however, not free software, and I am probably not allowed to distribute it in its original form or in an amended form. Consequently, the X16 Edit ROM version contains only the X16 Edit code (one bank, 16 kB). To get a usable ROM image, you need to append the X16 Edit ROM code to the standard rom.bin file.

In Linux and MacOS this may be done with the cat utility as follows:

```
cat rom.bin x16edit-rom-x.x.x.bin > customrom.bin
```

If you're using Windows, and cat is not available, you may try using the type command instead (not tested):

```
type rom.bin x16edit-rom-x.x.x.bin > customrom.bin
```

Select the custom rom on starting the emulator:

```
xemu -rom customrom.bin
```

### 3 Startup code

Starting the X16 Editor ROM version requires a small startup program stored in RAM.

The startup program should do the following:

- Switch to the ROM bank where X16 Edit is stored, which will be bank 7 if you follow the ROM image preparation instructions above.
- Set the part of banked RAM available to the editor—load the start bank in the X register and the last bank in the Y register. Bank 0 is used by the Kernal, so you should not specify a start bank number lower than 1.
- Call the editor ROM entry point, \$C000.
- On returning from the editor, restore the ROM bank select to its original value.

An example of such a startup code typed in the built-in monitor could look like this (don't type in the comments after semicolons):

```
.A 9E00 LDA $9F60      ;Get current ROM bank...
.A 9E03 PHA           ;... and store it on the stack
.A 9E04 LDA #$07      ;Store bank 7...
```

```

.A 9E06 STA $9F60      ;...in the ROM select
.A 9E09 LDX #$01       ;Set first RAM bank used to 1
.A 9E0B LDY #$FF       ;Set last RAM bank used to 255
.A 9E0D JSR $C000       ;Call editor entry point
.A 9E10 PLA            ;Retrieve original ROM bank...
.A 9E11 STA $9F60       ;...and write it to ROM select
.A 9E14 RTS

```

Run this startup code with SYS \$9E00.

## 4 Final comments

The X16 Edit ROM version is currently a proof of concept, showing that the code is ready to be installed and run in ROM.

The installation and startup process is not very convenient for the end-user at this stage. The editor version is of most interest if you like to install your own custom ROM image or if the X16 project would like to officially include the editor in the standard ROM. In the latter case, there could be a BASIC command to start the editor in a similar way that the built-in monitor is started.