

A quick start guide for minimal working setup of NWH Vehicle Physics 2.

Requirements

- A vehicle model with proper Unity rotation and pivots. Make sure your model uses the following axes: Z - Forward, Y - Up and X - Right. If your model has incorrect rotation and/or pivots check this [guide](#).



An example of a vehicle model with Unity-correct rotation.

- Separate wheel objects for each wheel, ideally with `wheel` in the name (script uses the name to detect the wheels automatically, case is ignored).



Example vehicle model hierarchy.

Physics Settings

Adjusting physics settings is optional but can solve some issue and improve the behavior of the asset.

- Under Project Settings ⇒ Physics it is recommended to:
 - Turn off Queries Hit Backfaces
 - Turn off Queries Hit Triggers
- Under Project Settings ⇒ Time it is recommended to change the Fixed Timestep from default 0.02 (50Hz) to 0.01667 (60Hz) or lower, depending on target platform. This will result in smoother physics behavior.

VehicleSetupWizard

To set up a vehicle automatically and skip the steps below, `VehicleSetupWizard` can be used. Make sure you vehicle has correct pivots and rotation first. Then, attach `VehicleSetupWizard` to the root object of the vehicle - where the `Rigidbody` would normally be placed. Follow the steps from the wizard inspector and the vehicle will be up and running shortly. `VehicleSetupWizard` logs all of its actions in the console along with any errors and/or warnings. Make sure to check for those and correct them manually if needed.

Rigidbody

- Add a Rigidbody component to the vehicle root, Car in the image above. Set the mass to a reasonable value, e.g. 1400.

Colliders

- Add a Collider (BoxCollider, MeshCollider, etc.) to the vehicle.
- Create and assign a new layer (e.g. WheelControllerIgnore) to all vehicle colliders. This will prevent wheels detecting the vehicle as ground. Do not use Default layer or any of the ground layers or they will not be detected by the wheel!

WheelController


For a vehicle to function first of all it needs wheels. NWH Vehicle Physics uses included asset WheelController for this instead of default WheelCollider. For more info check out [WheelController Setup](#) page.

- WheelController needs to be attached to a separate object from the wheel. That object will act as a suspension anchor and will represent the beginning of spring travel. Therefore, it needs to be positioned above the wheel center. Easiest way to create those objects is to duplicate the existing wheel objects, remove all components except Transform from them and move the duplicated objects slightly above the wheel center.



Vehicle hierarchy with WheelControllers and positioning of front left WheelController on the example vehicle.

- Add WheelController component to the objects created in the previous step. WheelController will initialize itself with default values and will try to set the necessary fields automatically. Check if the following fields are set:
 - Parent - root object of the vehicle. Must have Rigidbody attached. Car for this example.
 - Visual - wheel model. Wheel_FL, Wheel_FR, etc. for this example.
- Turn on Gizmos and select the wheels. The wheel gizmo and suspension gizmo will appear. Adjust Width and Radius of WheelController until they fit the wheel model.



Wheel gizmo. The vertical 'I' represents the suspension travel while the cylinder represents the wheel.


- Press play. Vehicle suspension is now functional. If you experience vehicle flying into the air check that you have a Rigidbody set up with correct mass and at least one Collider attached to the vehicle. For more info check *Troubleshooting* section of [WheelController Setup](#) page.

Input

- Check [Input Setup](#).

Cameras

- Add a Camera as a child of vehicle object (right click ⇒ Camera) and attach CameraFollow component to it.
- Assign the vehicle as Target.



Example single camera setup.

VehicleController

- Add VehicleController component to the vehicle root - where Rigidbody is.
- VehicleController will automatically set up default values and automatically set up Differentials, Wheels and WheelGroups. Check console for output.
- Go to Settings tab and click on Validate Setup button to for automatic validity check.
- Press play. Vehicle will now function but will not respond to any user input.

From:

<http://nwhvehiclephysics.com/> - **Documentation**

Permanent link:

<http://nwhvehiclephysics.com/doku.php/Setup/QuickStart>

Last update: **2020/05/13 09:10**

