

Advanced settings

Adjusting autoencoder architecture/training

to use a different autoencoder, a different architecture can be chosen. Change the encoder model in client.py to your desired encoder model:

```
class Encode(nn.Module):
    def __init__(self):
        super(Encode, self).__init__()
        self.conva = nn.Conv2d(32, 16, 3, padding=1)
        self.convb = nn.Conv2d(16, 8, 3, padding=1)
        self.convc = nn.Conv2d(8, 4, 3, padding=1)

    def forward(self, x):
        x = self.conva(x)
        x = self.convb(x)
        x = self.convc(x)
        return x
```

and the decoder model in server.py to your desired decoder model:

```
class Decode(nn.Module):
    def __init__(self):
        super(Decode, self).__init__()
        self.t_convx = nn.ConvTranspose2d(4, 8, 1, stride=1)
        self.t_conva = nn.ConvTranspose2d(8, 16, 1, stride=1)
        self.t_convb = nn.ConvTranspose2d(16, 32, 1, stride=1)

    def forward(self, x):
        x = self.t_convx(x)
        x = self.t_conva(x)
        x = self.t_convb(x)
        return x
```

To pretrain the models, use the pretrainer.py. you can use any dataset/hyperparameter to pretrain the autoencoder in the pretrainer.py.

Attention: client model, encoder model and decoder model in the pretrainer.py have to be the same as in the client.py and server.py. Also, the data-shape at the cut layer has to correspond to the input/output shape of the autoencoder.

The pretrainer will create files named: convencoder.pth and convdecoder.pth. these files contain the weights for the encoder model/ decoder model for the actual training process. By copying these files into the client.py / server.py directory, they will be load autonomously by these scripts in their main function before starting the actual training process:

client.py:

```
global encode
encode = Encode()
encode.load_state_dict(torch.load("./convencoder.pth"))
encode.eval()
encode.to(device)
```

server.py

```
global decode
decode = Decode()
decode.load_state_dict(torch.load("./convdecoder.pth"))
decode.eval()
decode.to(device)
```

Adjusting model architecture:

in order to use a different model architecture, simply adjust the model architecture at the client into the client.py:

```
class Client(nn.Module):
    def __init__(self):
        super(Client, self).__init__()
        self.conv1 = nn.Conv2d(3, 32, kernel_size=(3, 3), stride=(1, 1), padding=(1, 1))
        self.relu1 = nn.ReLU()
        self.pool1 = nn.MaxPool2d(kernel_size=2, stride=2, padding=0, dilation=1, ceil_mode=False)
        self.norm1 = nn.BatchNorm2d(32)
        self.conv2 = nn.Conv2d(32, 32, kernel_size=(3, 3), stride=(1, 1), padding=(1, 1))
        self.relu2 = nn.ReLU()
        self.norm2 = nn.BatchNorm2d(32)
        self.drop1 = nn.Dropout2d(0.2)

    def forward(self, x):
        x = self.conv1(x)
        x = self.relu1(x)
        x = self.pool1(x)
        x = self.norm1(x)
        x = self.conv2(x)
        x = self.relu2(x)
        x = self.norm2(x)
        x = self.drop1(x)
        return x
```

or at the server in the server.py:

```
class Server(nn.Module):
    def __init__(self):
        super(Server, self).__init__()
        self.conv3 = nn.Conv2d(32, 64, kernel_size=(3, 3), stride=(1, 1))
        self.relu3 = nn.ReLU()
        self.norm3 = nn.BatchNorm2d(64)
        self.conv4 = nn.Conv2d(64, 64, kernel_size=(3, 3), stride=(1, 1))
        self.relu4 = nn.ReLU()
        self.norm4 = nn.BatchNorm2d(64)
        self.pool2 = nn.MaxPool2d(kernel_size=2, stride=2, padding=0, dilation=1, ceil_mode=False)
        self.drop2 = nn.Dropout2d(0.3)
        self.conv5 = nn.Conv2d(64, 128, kernel_size=(3, 3), stride=(1, 1))
        self.relu5 = nn.ReLU()
        self.norm5 = nn.BatchNorm2d(128)
        self.conv6 = nn.Conv2d(128, 128, kernel_size=(3, 3), stride=(1, 1))
        self.relu6 = nn.ReLU()
        self.norm6 = nn.BatchNorm2d(128)
        self.pool3 = nn.MaxPool2d(kernel_size=2, stride=2, padding=0, dilation=1, ceil_mode=False)
        self.drop3 = nn.Dropout2d(0.4)
        self.linear1 = nn.Linear(in_features=128, out_features=43, bias=True)

    def forward(self, x):
        x = self.conv3(x)
        x = self.relu3(x)
        x = self.norm3(x)
        x = self.conv4(x)
        x = self.relu4(x)
        x = self.norm4(x)
        x = self.pool2(x)
        x = self.drop2(x)
        x = self.conv5(x)
        x = self.relu5(x)
        x = self.norm5(x)
        x = self.conv6(x)
        x = self.relu6(x)
        x = self.norm6(x)
        x = self.pool3(x)
        x = self.drop3(x)
        x = x.view(x.size(0), -1)
        x = nn.functional.log_softmax(self.linear1(x), dim=1)
        return x
```

Attention: The data-shape at the cut layer has to correspond to the input/output shape of the autoencoder.

Changing Optimizer/ Loss/ Training device

Optimizer, loss and the device (as well as the models for encoder, decoder, client and server) are globally defined in the main function of the client.py/ server.py and can be changed.

client.py:

```
global device
device = torch.device('cuda:0' if torch.cuda.is_available() else 'cpu')

global client
client = Client()
client.to(device)

global encode
encode = Encode()
encode.load_state_dict(torch.load("./convencoderlate.pth"))
encode.eval()
encode.to(device)

global optimizer
optimizer = SGD(client.parameters(), lr=lr, momentum=0.9)

global error
error = nn.CrossEntropyLoss()
```

server.py:

```
global device
device = torch.device('cuda:0' if torch.cuda.is_available() else 'cpu')

global server
server = Server()
server.to(device)

global decode
decode = Decode()
decode.load_state_dict(torch.load("./convdecoder.pth"))
decode.eval()
decode.to(device)

global optimizer
optimizer = SGD(server.parameters(), lr=lr, momentum=0.9)

global error
error = nn.CrossEntropyLoss()
```

Customized Pretraining

The pretraining can also be customized. The pretrainer of the autoencoder can be found in the /ae_pretrainer/ae_pretrainer.py directory.

The dataset used for pretraining can be set. By default, the CIFAR10 dataset is used:

```
transform = transforms.Compose([
    transforms.ToTensor(),
    transforms.Normalize((0.4914, 0.4822, 0.4465), (0.2023, 0.1994, 0.2010)),
])

trainset = torchvision.datasets.CIFAR10(root='./data', train=True,
download=True, transform=transform)
testset = torchvision.datasets.CIFAR10(root='./data', train=False,
download=True, transform=transform)

# Load Datasets
train_loader = torch.utils.data.DataLoader(trainset, batch_size=batchsize,
shuffle=True, num_workers=2)
test_loader = torch.utils.data.DataLoader(testset, batch_size=test_batches,
shuffle=False, num_workers=2)
```

To set the training parameter, learningrate, training epochs, batchsize and number of test batches can be changed.

```
batchsize = 64
test_batches = 1500
epoch = 250
lr = 0.0001
```

The lossfunction and device can be configured in the main function of the ae_pretrainer.py file

```
global device
device = torch.device('cuda:0' if torch.cuda.is_available() else 'cpu')
global error
error = nn.MSELoss()
```

Since a customized adaptive learning rate mechanism is used, the optimizer for encoder and decoder have to be set in the start_training() function.

Parameters for the customized adaptive learningrate training can be set as the following parameters:

```
prev_loss = 999
diverge_tresh = 1.1
lr_adapt = 0.5
```

The `diverge_thresh` variable describes, that if the thresh of an training epoch is above this threshold (e.g. 1.1 = the loss has increased by 10% in comparison to the previous training epoch), the weightchanges from this epoch are dropped (due to divergence, state from previous epoch is load). Additionally, the learningrate is modified by the factor `lr_adapt`. `prev_loss` is a helpvariable of the loss of the “imaginary previous epoch” of the first training epoch.

Also, encoder and decoder model can be changed in the `ae_pretrain.py` file.

encoder

```
class Encode(nn.Module):
    def __init__(self):
        super(Encode, self).__init__()
        self.conva = nn.Conv2d(64, 16, 3, padding=1)
        self.convb = nn.Conv2d(16, 8, 3, padding=1)
        self.convc = nn.Conv2d(8, 4, 3, padding=1)##

    def forward(self, x):
        x = self.conva(x)
        x = self.convb(x)
        x = self.convc(x)
        return x
```

decoder

```
class Decode(nn.Module):
    def __init__(self):
        super(Decode, self).__init__()
        self.t_convx = nn.ConvTranspose2d(4, 8, 1, stride=1)
        self.t_conva = nn.ConvTranspose2d(8, 16, 1, stride=1)
        self.t_convb = nn.ConvTranspose2d(16, 64, 1, stride=1)

    def forward(self, x):
        x = self.t_convx(x)
        x = self.t_conva(x)
        x = self.t_convb(x)
        return x
```

Attention: client model, encoder model and decoder model in the `pretrainer.py` have to be the same as in the `client.py` and `server.py`. Also, the data-shape at the cut layer has to correspond to the input/output shape of the autoencoder.

In the `ae_pretrainer.py` file, the `Clientmodel` always has to match the client side model in the `client/client.py`

After the training has finished, two files (`convencoder.pth`, `convdecoder.pth`) are created autonomously in the `/ae_pretrainer` directory. The `convencoder.pth` file has to be copied into the `/client` directory, and the `convdecoder.pth` file into the `/server` directory.

Measuring Message Size and FLOPs

In order to figure out the size of a message in bytes, the following function can be added to the client.py or server.py:

```
import struct
import sys

def get_size_send_msg(msg):
    """
    can be called to figure out the message size of a message in byte
    :param msg: message
    :return: string that includes the meassagesize in bytes
    """

    msg = [0, msg] # add getid
    msg = pickle.dumps(msg)
    # add 4-byte length in network byte order
    msg = struct.pack('>I', len(msg)) + msg
    return ("sendsize: ", sys.getsizeof(msg), " bytes")
```

In order to estimate the FLOPs (Floating Point Operations) of the forward pass of a MODEL, the library thop can be used: <https://github.com/Lyken17/pytorch-OpCounter>.

```
import thop
flops_client, params = thop.profile(MODEL, inputs=(torch.rand(batchsize, 3, 32,
32).to(device),))
```

Recreate Environment

In the repository, an environment.yaml file is provided. The Conda environment can be recreated easily, by running the following command:

```
conda env create -f environment.yaml
```