










linkIsEnabled Usage Example

Follow along with these steps to see how a link to the System workspace was created using the  **linkIsEnabled** symbol. This example tests the value of the Product cell in the selected row to determine whether or not to offer the link on that row.

1. Open the Managed System Status workspace in the Navigator Physical view: Click  **Enterprise** to open the default workspace; right-click  **Enterprise** and click **Workspace > Managed System Status**.
2. Right-click a row in the Managed System Status table and click **Link To >**  **Link Wizard**.
3. Create a new link, name it `System Details`, select a link type of **Relative**, and target the  Windows Systems workspace.
4. Click **Next** to go to the Workspace Link Wizard - Parameters.
5. Click  **theLinkIsEnabled** row. The Expression box reads `true`.
6. Click **Modify Expression**.
7. In the Expression Editor, click **Clear**, and then click **Symbol**.
8. In the **Symbols** list, select  **Product** and click **OK**. The expression is displayed as
`$kfw.INODESTS:ATTRIBUTE.INODESTS.PRODUCT$`.
9. Click **Operator**, select  **Equal** and click **OK** to see the `==` operator.
10. Type "NT" at the end of the expression, which should then read,
`$kfw.INODESTS:ATTRIBUTE.INODESTS.PRODUCT$ == "NT"`.
11. Click **Evaluate**. If the row from where you started the Link Wizard has `NT` in the Product column, the test will be `true`; otherwise, it will be `false`.
12. Click **Finish**.
 Click the  link indicator in one of the NT rows to open the Services workspace for that monitoring agent. Note that you can disable the link indicator for invalid rows by clearing ☐ **Link Indicator Always Enabled**.