

**TECH**  
**VAULT**

# WINDOW FUNCTIONS

## PART 2 (Frames)



AMR ELHELW




**func(<args>) OVER (...)**

→ **PARTITION BY ...**

→ **ORDER BY ...**


**Partitions**



**Table**

**func(<args>) OVER (**  
**PARTITION BY ...**  
**)**

Frame →



func(<args>) OVER (  
PARTITION BY ...  
ORDER BY ...  
)

**Frame  
Specification** { • **ROWS**  
• **RANGE**

# ROWS

- Defines the frame in terms of number of rows before and after the current row
- Syntax:**

ROWS BETWEEN <frame start> AND <frame end>

UNBOUNDED PRECEDING

N PRECEDING

CURRENT ROW

UNBOUNDED FOLLOWING

N FOLLOWING

CURRENT ROW

# ROWS

- **Examples**

ROWS BETWEEN UNBOUNDED PRECEDING AND CURRENT ROW

ROWS BETWEEN 2 PRECEDING AND 2 FOLLOWING

ROWS BETWEEN UNBOUNDED PRECEDING AND UNBOUNDED FOLLOWING

ROWS BETWEEN CURRENT ROW AND 1 FOLLOWING

ROWS BETWEEN CURRENT ROW AND CURRENT ROW

# RANGE

- Defines the frame in terms of values before and after the value in the current row (current value)
- **Syntax:**

RANGE BETWEEN <frame start> AND <frame end>

UNBOUNDED PRECEDING

N PRECEDING

CURRENT ROW

UNBOUNDED FOLLOWING


N FOLLOWING

CURRENT ROW



# RANGE

```
... OVER(  
  PARTITION BY ...  
  ORDER BY quantity  
  RANGE BETWEEN <frame start> AND <frame end>  
)
```



quantity BETWEEN <start\_val> AND <end\_val>

If  $X$  is the value of "quantity" in the current row

- CURRENT ROW  $\rightarrow X$
- $N$  PRECEDING  $\rightarrow X - N$  (not  $N$  rows before)
- $N$  FOLLOWING  $\rightarrow X + N$  (not  $N$  rows after)


|         | Quantity |            |
|---------|----------|------------|
|         | ...      | 385 -> 415 |
| Current | 387      |            |
|         | 415      |            |
|         | 420      |            |
|         | 420      |            |
|         | 502      |            |
|         | ...      |            |

RANGE BETWEEN 30 PRECEDING  
AND CURRENT ROW

quantity BETWEEN  $X - 30$  AND  $X$

# RANGE

```
... OVER(  
  PARTITION BY ...  
  ORDER BY quantity DESC  
  RANGE BETWEEN <frame start> AND <frame end>  
)
```



**quantity BETWEEN <start\_val> AND <end\_val>**

If **X** is the value of “quantity” in the current row

- CURRENT ROW → **X**
- **N** PRECEDING → ~~**X - N** (not N rows before)~~ **X + N**
- **N** FOLLOWING → ~~**X + N** (not N rows after)~~ **X - N**

|  | Quantity |  |
|--|----------|--|
|  | ...      |  |
|  | 502      |  |
|  | 420      |  |
|  | 420      |  |
|  | 415      |  |
|  | 387      |  |
|  | ...      |  |

# RANGE

- **Default Frame** (when ORDER BY is used):

RANGE BETWEEN UNBOUNDED PRECEDING AND CURRENT ROW

- From beginning of partition until row with the same value as current row
- Might include rows after current row if they have the same value