

# FOGUserGuide

## From FOGProject Wiki

**A guide to deployment, management, And concept overview For FOG.**

Based on a document by: Thomas J. Munn CISSP

## Contents

- 1 Introduction
  - 1.1 Preface
    - 1.1.1 What is FOG?
    - 1.1.2 How should FOG be implemented?
    - 1.1.3 What features are included with FOG?
    - 1.1.4 How much does FOG cost?
  - 1.2 Background on FOG
    - 1.2.1 Why FOG?
- 2 Installation on Different Operating Systems
  - 2.1 Debian Lenny
  - 2.2 Fedora
    - 2.2.1 Installation on Fedora 8
    - 2.2.2 Installation on Fedora 13
  - 2.3 Ubuntu
    - 2.3.1 Ubuntu 10.04
    - 2.3.2 Ubuntu 9.04
    - 2.3.3 Ubuntu 7.10
  - 2.4 CentOS 5.3
  - 2.5 VMWare 0.27
- 3 Network Integration
  - 3.1 Wake On Lan (WOL)
    - 3.1.1 Cisco WOL - Layer 3
  - 3.2 Multicast/UDPCast
    - 3.2.1 Cisco Multicast - Layer 3
- 4 Upgrading FOG
- 5 Getting Started
  - 5.1 Basic Tasks
  - 5.2 Tips
- 6 Modifying existing DHCP server to work with FOG
  - 6.1 Windows
  - 6.2 Linux
  - 6.3 Cisco
  - 6.4 DD-WRT & Tomato
  - 6.5 Sonicwall
- 7 Client Setup
- 8 Foundational Concepts
  - 8.1 Unicasting
  - 8.2 Multicasting
  - 8.3 Queuing
  - 8.4 Menu Bar
- 9 FOG Benchmarks
  - 9.1 Internal Benchmarks
- 10 Managing FOG
  - 10.1 Dashboard
    - 10.1.1 Overview

- 10.1.2 System Overview
- 10.1.3 System Activity
- 10.1.4 Disk Information
- 10.1.5 30 Day Imaging History
- 10.2 Hosts
  - 10.2.1 Overview
  - 10.2.2 Adding a new host
    - 10.2.2.1 Method 1: Manually Adding
    - 10.2.2.2 Method 2: Adding a new host via Full Registration
    - 10.2.2.3 Method 3: Adding a new host via Quick Registration
    - 10.2.2.4 Method 4: Uploading Host Information
    - 10.2.2.5 Overview
    - 10.2.2.6 Other notes
    - 10.2.2.7 Uploading the File
  - 10.2.3 Managing Hosts
    - 10.2.3.1 General
    - 10.2.3.2 Multiple MAC Address Support
  - 10.2.4 Host Status
  - 10.2.5 Creating Host Groups
- 10.3 Groups
  - 10.3.1 Overview
  - 10.3.2 Creating Groups
  - 10.3.3 Managing Groups
    - 10.3.3.1 Group Basic Tasks
    - 10.3.3.2 Group Membership Setup
    - 10.3.3.3 Group Image Associations
    - 10.3.3.4 Group Operating System Associations
    - 10.3.3.5 Group Snapins
    - 10.3.3.6 Group Service Settings
    - 10.3.3.7 Group Active Directory Setup
    - 10.3.3.8 Group Printers
    - 10.3.3.9 Group Membership Information
- 10.4 Images
  - 10.4.1 Overview
  - 10.4.2 Creating Images Objects
  - 10.4.3 Modifying Image Objects
  - 10.4.4 Adding Existing Image Objects
- 10.5 Storage Manangement
  - 10.5.1 Overview
  - 10.5.2 Adding a Storage Node
    - 10.5.2.1 Installing the Node
    - 10.5.2.2 Adding the Node to the Management Portal
  - 10.5.3 Monitoring The Master Node
  - 10.5.4 Master Node Status
- 10.6 Users
  - 10.6.1 Overview
  - 10.6.2 Creating Accounts
  - 10.6.3 Modifying Users
- 10.7 Tasks
  - 10.7.1 Overview
  - 10.7.2 General Tasks
  - 10.7.3 Advanced Tasks
    - 10.7.3.1 Debug
    - 10.7.3.2 Upload - Unicast (Debug)
    - 10.7.3.3 Send - Unicast (Debug)
    - 10.7.3.4 Send - Unicast (Without Snapins)
    - 10.7.3.5 Deploy All Snapins
    - 10.7.3.6 Deploy Single Snapin

- 10.7.3.7 Memory Test
  - 10.7.3.8 Wake Up
  - 10.7.3.9 Fast Wipe
  - 10.7.3.10 Normal Wipe
  - 10.7.3.11 Full Wipe
  - 10.7.3.12 Disk Surface Test
  - 10.7.3.13 File Recovery
  - 10.7.3.14 Virus Scan
  - 10.7.3.15 Hardware Inventory
- 10.7.4 Scheduling
  - 10.7.4.1 Single Execution Scheduling
  - 10.7.4.2 Cron Style Task Scheduling
- 10.8 Printers
  - 10.8.1 FOG Version
  - 10.8.2 Known Issues
  - 10.8.3 Overview
  - 10.8.4 Adding New Printers
  - 10.8.5 Linking Printers to Hosts
  - 10.8.6 Creating a Samba Based Printer Store on FOG
- 10.9 The FOG Client Service
  - 10.9.1 Overview
  - 10.9.2 Module specific configuration settings
  - 10.9.3 Installation
    - 10.9.3.1 Quiet Installation
  - 10.9.4 Functions and Operation
    - 10.9.4.1 Auto Log Out
    - 10.9.4.2 Hostname Changer
    - 10.9.4.3 Host Register
    - 10.9.4.4 Task Reboot
    - 10.9.4.5 Directory Cleaner
    - 10.9.4.6 Display Manager
    - 10.9.4.7 Green FOG
    - 10.9.4.8 Snapin Client
    - 10.9.4.9 User Tracker
    - 10.9.4.10 User Cleanup
    - 10.9.4.11 Printer Manager
    - 10.9.4.12 Client Updater
  - 10.9.5 Keeping Clients up to date
    - 10.9.5.1 Overview
    - 10.9.5.2 Posting Updates
  - 10.9.6 FOG Tray
  - 10.9.7 Troubleshooting
- 10.10 Snap-ins
  - 10.10.1 Overview
  - 10.10.2 Creating a Snapin
  - 10.10.3 Preparing the FOG Server
    - 10.10.3.1 Fedora
    - 10.10.3.2 Ubuntu
    - 10.10.3.3 VMWare
  - 10.10.4 Uploading the Snapin
  - 10.10.5 Linking the Snapin to Hosts
- 10.11 Client Side Tasks
  - 10.11.1 FOG Version
  - 10.11.2 Overview
  - 10.11.3 fog.memtest
  - 10.11.4 fog.reg
  - 10.11.5 fog.reginput
    - 10.11.5.1 Operating System ID

- 10.11.5.2 Image ID
- 10.12 Active Directory Integration
  - 10.12.1 Setup
    - 10.12.1.1 Overview
    - 10.12.1.2 Security
    - 10.12.1.3 Preparing the Image
    - 10.12.1.4 FOG Setup
    - 10.12.1.5 Making AD Integration Easier
  - 10.12.2 Securing Active Directory Integration
    - 10.12.2.1 Overview
    - 10.12.2.2 The Development Environment
    - 10.12.2.3 Getting the Source
    - 10.12.2.4 Encrypting Your Password
- 10.13 FOG Reports
  - 10.13.1 FOG Version
  - 10.13.2 Overview
  - 10.13.3 Running Reports
  - 10.13.4 Importing User Created Reports
  - 10.13.5 Creating Custom Report
- 10.14 Other Settings
  - 10.14.1 Boot Image Key Map
  - 10.14.2 FOG Client Kernel
    - 10.14.2.1 Overview
    - 10.14.2.2 Kernel Types
    - 10.14.2.3 Updating the Kernel
- 10.15 Mobile Management Interface
  - 10.15.1 Overview
  - 10.15.2 Using the mobile Interface
- 11 Plugins
  - 11.1 Capone
    - 11.1.1 FOG Version
    - 11.1.2 Overview
    - 11.1.3 Installation/Activation
      - 11.1.3.1 Enabling Plugins
      - 11.1.3.2 Enabling Capone
    - 11.1.4 Using Capone
- 12 Backing up FOG
  - 12.1 Overview
  - 12.2 Original Installation Tar File
  - 12.3 Web Directory
  - 12.4 OPT Directory
  - 12.5 Images Directory
  - 12.6 MySQL Database
- 13 Restoring FOG
  - 13.1 Web Directory
  - 13.2 OPT Directory
  - 13.3 MySQL Databse
- 14 Advanced Installations
  - 14.1 Overview
  - 14.2 Separate TFTP and DHCP Server
  - 14.3 Separate NFS Server
- 15 Other Advanced Topics
- 16 Caveats and Other Tips
- 17 Troubleshooting and Debugging
  - 17.1 Troubleshooting an image push to a client
  - 17.2 Troubleshooting an image upload
  - 17.3 Troubleshooting Driver Issues
    - 17.3.1 Method 1

- 17.3.2 Method 2
- 17.4 Bottleneck
- 18 About the Developers
  - 18.1 Chuck Syperski
  - 18.2 Jian Zhang
- 19 Appendix C: Alternative Resources
- 20 Additional helpful information

## Introduction

### Preface

This document is intended to be modified by FOG users, in fact it is based on a document created by a FOG user. If you feel something could be said better or put more clearly, it is encouraged that you make changes to this document. We just ask that you keep it constructive and in good taste. In order to edit the wiki you are now required to create an account, as spamming of the forum has gotten pretty bad recently.

### What is FOG?

FOG is a Linux-based, free and open source computer imaging solution for Windows XP, Windows Vista, and Linux (limited) that ties together a few open-source tools with a php-based web interface. FOG doesn't use any boot disks, or CDs; everything is done via TFTP and PXE. Also with FOG many network drivers are built into the kernel, so you don't really need to worry about nic drivers (unless there isn't kernel support for it yet). FOG also supports putting an image that came from a computer with a 80GB partition onto a machine with a 40GB hard drive as long as the data is less than 40GB. FOG supports multi-casting, meaning that you can image many PCs from the same stream. So it should be as fast whether you are imaging 1 PC or 20.

### How should FOG be implemented?

FOG is best implemented on a dedicated server, any spare machine you have. We recommend that you have **sufficient** hard drive space as each image you make is usually between 5 and 10 GB and it's best to have a **gigabit NIC** with as much processor and RAM you can throw at it.

### What features are included with FOG?

FOG is more than just an imaging solution, FOG has grown into a imaging/cloning and network management solution. FOG now performs tasks like installing and managing printers, tracking user access to computers, installing applications remotely via snaps, and automatic user log offs. If a computer is badly infected with a virus or malware, you can boot FOG in AV mode and have it remove the viruses. You can wipe your disks, destroying all information that was on them, you can restore deleted files, or scan the disk for bad blocks.

### How much does FOG cost?

FOG is an Open Source project and licensed under the GPL which means that you are free to use FOG on as many computers as you like for free. This also means that if you want to make any changes to the source code you are free to do so.

The creators of FOG make no profits from this project with the exception of donations. FOG comes with absolutely **NO WARRANTY** and the creators of FOG are in **NO WAY RESPONSIBLE FOR ANY DAMAGE OR LOSS CAUSED BY FOG!** Please see the license file included with the FOG release for more information. With that being said we attempt to do a very good job of supporting our users, in fact it is one of the goals of FOG to have better support than most commercial products. All support requests should be placed through the FOG's sourceforge forum which is located at:

[http://sourceforge.net/forum/?group\\_id=201099](http://sourceforge.net/forum/?group_id=201099)

Thanks for supporting open source software and enjoy!

## **Background on FOG**

### **Why FOG?**

Working in an educational environment our organization's techs very often re-imaged computers in their day to day activities. For a long time we used a commercial product that in many ways didn't meet our needs. It wasn't web based, and you needed to create driver disks, floppys or USB drives. Other things were very difficult, such as searching for a host by MAC address and the product was expensive, even with an educational discount. So we started to investigate ways in which we could do things better, and as our organization struggled to make a commercial product work better by trying to pxe boot dos, and testing it in Windows PE, we, the FOG Team started to build linux based solution on our own time. We finally got a working version and decided to release it as open source since we use many other open source products, and figured we should give back to the community.

## **Installation on Different Operating Systems**

### **Debian Lenny**

### **Fedora**

#### **Installation on Fedora 8**

#### **Installation on Fedora 13**

### **Ubuntu**

#### **Ubuntu 10.04**

#### **Ubuntu 9.04**

#### **Ubuntu 7.10**

### **CentOS 5.3**

(CentOS 5.4 & 5.5 also covered)

### **VMWare 0.27**

## **Network Integration**

### **Wake On Lan (WOL)**

#### **Cisco WOL - Layer 3**

### **Multicast/UDPCast**

#### **Cisco Multicast - Layer 3**

## **Upgrading FOG**

**It is highly recommended that you backup your data before you perform the upgrade.**

Upgrading from one version of FOG to a newer version is as easy as running the installer for the new version of FOG. It will update your system while leaving your data in place.

FOG will **NOT** modify:

- Any modified reports
- Image Files
- All database settings

FOG **WILL** modify:

- Any Custom changes to php/init.gz file.
- Any changes to dhcpd.conf.
- Any changes to /etc/xinetd.d/tftp.
- Any changes to /etc/vsftpd/vsftpd.conf.
- Any changes to /etc/exports.
- Any changes to php config files on /var/www/fog and /opt/fog

## Getting Started

### Basic Tasks

So you have a FOG server installed and setup, now what do you do? Below are a few common "Getting Started" items.

1. Uploading your first Image
2. Deploying your Image a single client
3. Deploying your Image a group of clients

### Tips

1. FOG requires that all hosts be entered in the FOG Database for imaging. The most important part is getting the MAC address of the host right. FOG uses the MAC for targeting image installs and acquires. Using the wrong MAC could result in unpredictable results, including the complete erasure of the wrong pc! The IP address isn't that important, and the 'name' field is more for the user. Mac address format is 00:12:3F:C4:57:0C . Using dashes, spaces, or no items at all will result in the GUI not accepting the host.
2. After hosts are entered, it is wise to group them together by function, hardware, or common image. The image will be shared among all members of a particular group. This occurs within the 'hosts' screen, and NOT on the groups screen. This is a little confusing, so it helps to think of the 'groups' screen as a task generator, rather than controlling group memberships.
3. Hosts are then configured to boot via PXE boot by going into the BIOS. Make sure PXE boot is the FIRST option, NOT the hard disk, or things won't work.
4. Configure your 'master' pc for the first image. Probably a good idea to run 'sysprep (<http://support.microsoft.com/kb/302577>) ' prior to imaging, but not necessary. Sysprep will make your imaging life easier, if hardware is different, etc. See Microsoft.com for more details on using sysprep.

## Modifying existing DHCP server to work with FOG

If you already have a DHCP server setup on your network you don't want two. So if you chose to not install DHCP during FOG installation you will need to set some options in your current DHCP server to point PXE services to the FOG server.

### Windows

To set options 066 and 067 on Windows Server:

1. Open DHCP configuration **Start > Administrative Tools > DHCP**.
2. Then expand your server, expand the applicable scope (often only one is there)
3. right click on **Scope Options**
4. click **Configure Options**
5. tick **066** and enter the IP Address of the FOG server

6. tick **067** and enter **pxelinux.0** (thats a zero).
7. Make sure that 060 is unticked.

For a video walk through jump to 6:44, on: <http://www.youtube.com/user/hotfortech#p/a/u/1/Ak6kfvGM0Dk>

## Linux

If you would like to use an existing Linux based DHCPD server you will need to perform the following steps:

1. Edit your dhcpd.conf file (ie: vim /etc/dhcpd.conf)
2. In the global section or in a subnet declaration add **next-server X.X.X.X**; and **filename "pxelinux.0"**; where X.X.X.X is the IP of your FOG server.
3. Restart your dhcpd server (ie: service dhcpd restart)

## Cisco

If you would like to use a DHCP-enabled Cisco router you will need to perform the following steps:

1. Enter priveleged mode (**enable**).
2. If you don't know your DHCP pool name, enter **show running-config** and look for *ip dhcp pool* in the output.
3. Enter global configuration mode (**configure terminal**).
4. Enter DHCP scope configuration mode (**ip dhcp pool <pool name>**).
5. Configure the following options:
  1. **next-server <ip address to fog server>**
  2. **bootfile pxelinux.0**
6. Exit configuration mode by entering **exit** twice.
7. Save your configuration (**copy running-config startup-config**).

## DD-WRT & Tomato

If you would like to use a DD-WRT or Tomato router for DHCP you will need to perform the following steps:

1. Go to the Services tab
2. Enable DNSMasq, and Local DNS
3. Under Additional DNSMasq Options add the following **dhcp-boot=pxelinux.0,,X.X.X.X** where X.X.X.X is the IP of your FOG server
4. Save/Apply settings

Please see our knowledge base article [1] ([http://www.fogproject.org/wiki/index.php?title=FOG\\_with\\_DD-WRT\\_firmware](http://www.fogproject.org/wiki/index.php?title=FOG_with_DD-WRT_firmware)) for more information on this.

## Sonicwall

If your Sonicwall device is acting as the DHCP server, you will need to perform the following steps:

1. Login to your Sonicwall web admin interface
2. Go to **Network > DHCP Server**
3. Edit the DHCP Range where your client(s) reside
4. Click the tab labeled **Advanced**
5. Under "Network Boot Settings," configure the following options:
  1. Next Server: **X.X.X.X** where X.X.X.X is the IP of your FOG server
  2. Boot File: **pxelinux.0**
6. Click **OK** to save

Note that the "Windows" DHCP Options 66 and 67 do not work in Sonicwall DHCP Server. You must use the fields provided by Sonicwall - Next Server and Boot File.



## Client Setup

When using FOG all clients should be setup to have PXE boot as the first boot device. This allows imaging tasks to be deployed without visiting the client computer, while only slowing down the boot process by a few seconds.

## Foundational Concepts

This section provides some basic concepts that the FOG Project uses.

### Unicasting


Unicasting in FOG means sending a single image to a single host. This can mean an upload or a deploy, and is independent of the image type.

### Multicasting

Multicasting in FOG uses UDPcast to send a single image to multiple computers using only slightly more bandwidth then sending the image to a single computer or unicast. Multicasting in FOG may require special switch configuration. A multicast will not begin until all members are ready to begin by default. This can be changed by editing UDPSENDER\_MAXWAIT in /opt/fog/service/etc/config.php which is in seconds.

### Queuing

FOG uses a simple queuing system to prevent its storage servers being overworked. If you have a single FOG storage node in FOG with a queue size of 10, then this means that if you unicast an image to 30 computers, only the first 10 computers will be imaged. The other 20 computers will be waiting "in queue" for an open slot. What will be seen on the client side is the following:



```
* Waiting for an slot, 23 PCs are in front of me. (7 min)
* Waiting for an slot, 23 PCs are in front of me. (7 min)
* Waiting for an slot, 23 PCs are in front of me. (8 min)
* Waiting for an slot, 23 PCs are in front of me. (8 min)
* Waiting for an slot, 23 PCs are in front of me. (8 min)
* Waiting for an slot, 23 PCs are in front of me. (8 min)
* Waiting for an slot, 23 PCs are in front of me. (8 min)
* Waiting for an slot, 23 PCs are in front of me. (8 min)
* Waiting for an slot, 23 PCs are in front of me. (8 min)
* Waiting for an slot, 23 PCs are in front of me. (8 min)
* Waiting for an slot, 12 PCs are in front of me. (8 min)
* Waiting for an slot, 12 PCs are in front of me. (8 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (9 min)
* Waiting for an slot, 12 PCs are in front of me. (10 min)
* Waiting for an slot, 12 PCs are in front of me. (10 min)
* Waiting for an slot, 12 PCs are in front of me. (10 min)
* Waiting for an slot, 12 PCs are in front of me. (10 min)
* Waiting for an slot, 12 PCs are in front of me. (10 min)
```

This queue system allows for the IT staff to start tasks for hundreds or thousands of computers and let FOG manage the clients so the servers don't get overwhelmed with client requests.

### Menu Bar



This menu appears at the top of every page on Fog's web UI. The icons are, from left to right:

**Home/Dashboard** - This is the home screen of the FOG management portal.

**Users** - Individual administrators of the FOG resources.

**Hosts** - This section houses the hosts, which are the pcs to be imaged or to extract images from.

**Groups** - This section houses groups, which are similar PCS' that need tasks done en-masse.

**Images** - This section allows you to manage the image files stored on the FOG server.

**Storage Management** - This section allows you to add/remove storage nodes from the FOG system.

**Snap-ins** - This section provides ways to automate various post-imaging tasks, not covered in this document

**Printers** - This section allows for management of printers, allowing you create printer objects that can later be assigned to hosts or groups.

**FOG Service Configuration** - This section allows you to control how the client service functions.

**Tasks** - This section allow you to perform imaging tasks such as acquiring or deploying images.

**Reports** - Reports let you pull information from the FOG database either as HTML, pdf, or csv.

**Info/Misc** - The section has the rest of the settings that don't fit anywhere else like the kernel updater and the client service updater.

**Logoff** - Click this to log off of the Fog web UI.

Note: "Groups" do not control group memberships. Group memberships are controlled via the 'host' icon.


## FOG Benchmarks

### Internal Benchmarks

## Managing FOG

### Dashboard

#### Overview



The FOG dashboard is the first page you are presented with after login. This page just gives you an overview of what is happening on your FOG server.

### System Overview

The system overview box is the top left hand box on this page. The information presented in this box is the current user, the server IP address or hostnames for your web server, tftp server and storage server (which can all be different). This section also gives you the system uptime or how long the system has been running without restart, the number of users logged into the Linux box, and lastly the system load.

### System Activity

The system activity box is in the top row, the middle box. What this section shows is the unicast queue, or the number of unicast downloads that are currently in progress, which on a default setup, the maximum value is 10. This means that after 10 hosts are receiving images (at once) the 11th will wait for one of the hosts in progress to complete before starting. The reason this was created was so that you could queue up 100 machines with different images (all unicast) and still keep the system functional. We have heard of this queue being used to re-image an entire building of computers ( ~ 1000+ ) overnight. This section only updates on page refresh, and not in real time.

### Disk Information

The disk information box is the top, right hand section of the dashboard page. This is a semi-realtime display of the storage remaining on the storage server. If you get an error in this box, please see Dashboard Error: Permission denied...

### 30 Day Imaging History

This image shows your imaging trends for the past 30 days

## Hosts

### Overview

Video Tutorial (<http://freeghost.sourceforge.net/videotutorials/hostinfo.html>)

A host in FOG is typically a computer, but it can be any network device. Hosts are used to identify a computer on the network and are used to manage the device.

### Adding a new host

#### Method 1: Manually Adding

Video Tutorial (<http://www.fogproject.org/videotutorials/addimghost.html>)

Adding a new host can be done in the hosts section of FOG (the single monitor). Then by clicking on the "Add New Host" button on the left hand menu. At least a hostname and a MAC address must be entered in order to add the host to the FOG database.

A host consists of the required fields:

- **Hostname** - A string used for the Windows Hostname of client, this must be less than 15 characters long.
- **MAC address** - This field is used in for for a unique identifier for the host. The string must be separated by : (colon), in the format of 00:11:22:33:44:55.

Hosts can also include, but are not required:

- **IP address** - Just your typical IP address, in the typical formation of X.X.X.X or 192.168.1.1.
- **Description** - Information for your own reference.
- **Image Association** - This field is a drop down box that will allow you select an image object created in the **Images** section.
- **Operating System** - Drop down box that allow you to select the primary type of operating system running on this host.
- **Kernel** - This is only used if you want to overwrite the default kernel used for FOG.
- **Kernel Arguments** - This allow you to add additional kernel arguments for booting the host (ie: vga=6, or irqpoll).
- **Primary Disk** - This option allows you to force a device to use during imaging if fog fails to detect the correct device node.

This page also allows for configuration of Active Directory integration, but this topic will be covered later. When all settings are added, click on the "Add" button.

#### Method 2: Adding a new host via Full Registration

This is the preferred method (as of version 0.12), and maybe the easiest method for getting a host into the FOG database, but it requires you to visit the host. When at the client computer, during the boot up process when you see the pxe boot menu select **Perform Full Host Registration and Inventory**. If you are using the text based pxe boot menu, type **fog.reginput**. During this phase you will be prompted for general information about the host like hostname, operation system, and even image. If you enter a valid operating system and image id, you will be able to deploy and image to this computer directly from registration. If you would like to push an image down to this computer, select **y** when prompted.

After the requested information is entered, FOG will pull a quick hardware inventory the client.

This method of registration will only register the primary, wired mac address with the FOG server.

For more information on these commands please see:

Client Side Tasks ([http://www.fogproject.org/wiki/index.php?title=FOGUserGuide#Client\\_Side\\_Tasks](http://www.fogproject.org/wiki/index.php?title=FOGUserGuide#Client_Side_Tasks))

**Method 3: Adding a new host via Quick Registration**

Quick registration is very much like the Full host registration, with the exception that it will not prompt you for any input, nor give you the option to image the computer directly from the registration screen. When the host is added to the FOG server, it will be named with the hosts primary mac address. This method is great for adding a lab of 30 computers to FOG quickly and easily.

To enable this feature

1. Go to **Other Information**
2. select **FOG Settings**
3. Find section **FOG Quick Registration**
4. change value **FOG\_QUICKREG\_AUTOPOP** to **1**
5. Set **FOG\_QUICKREG\_IMG\_ID** to the image ID you would like to use for all newly created hosts.
6. Set **FOG\_QUICKREG\_OS\_ID** to the OS ID you would like to use for all newly created hosts.
7. Change **FOG\_QUICKREG\_SYS\_NAME** to what you would like to name you new machines, where \* will be replaced by a number. If you would like to zero pad numbers you can use **LAB300-\*** which would result with **LAB300-03** or **LAB300-09**.
8. Set **FOG\_QUICKREG\_SYS\_NUMBER** to the first number you would like to use.

After each registration the computer will automatically image and the **FOG\_QUICKREG\_SYS\_NUMBER** will incremented by 1.

**Method 4: Uploading Host Information****Overview**

When getting started with FOG, you need to enter the host information for the devices on your network. We understand this can be a long difficult process, so in order to make this process easier we created a page that allows you to upload most of the host information from a CSV file.

The CSV file that is uploaded to FOG must be in the following format, and the file should not have a header row.

**MAC Address, Host name, IP Address, Description, OSID , ImageID**

**Other notes**

- The MAC Address (required) is the NIC's MAC address seperated by : (colon).
- The Host name (required) is the computer's Host name (must be less than 15 characters, should not include underscores, according to [2] (<http://tools.ietf.org/html/rfc952>) ).
- The IP Address is the computer's IP address (format x.x.x.x). This field is currently not used by FOG.
- The Description is any text description you would like associated with the computer.
- The OSID is the number representing the operating system. It can be found in the table "supportedOS" in the field osID.
- The ImageID is the number representing the images file linked to this image. The image definition must already exist and this number can be found in the table "images" in the field imageID.
- The bold fields are required.
- The file must be saved as a CSV without a header row.

**Uploading the File**

1. After the file is prepared and saved, you will need to log into the FOG Management Portal.
2. Then click on the Hosts icon.
3. On the left-hand menu, click on Upload Hosts.
4. Browse for your file, then click Upload CSV.

**Managing Hosts****General**

Once hosts have been added to the FOG database you can modify or delete them. Finding a host which you wish to edit can be done in two ways, the first is by listing all the hosts that exist. This is done by clicking on the "List All Hosts" button. The second way to locate a host is to use the search function. To search for hosts click on the "New Search" button, if you would like to search for all hosts you can enter a "\*" or "%". The search function will search in the host's name, description, IP and MAC address.

Once a host is located, it can be edited by clicking on the edit button. Clicking on the edit button will display all the properties that were shown during host creation with the addition of snapin, printers, active directory, service settings, hardware, virus history, and login information.

The entire host object can be removed from the FOG system by clicking on the delete option at the bottom of the Host Menu.

### Multiple MAC Address Support

(Content not yet complete.)

### Host Status

New in version 0.29 of FOG is the Host Status which will basically display an indicator icon next to the host within the FOG UI showing the status of the machine. This function basically does a ping based on the host's name. So in order for this to work you must have an internal DNS server that is tied in with your DHCP server, so that when a DHCP address is given out, the DNS server is notified with the new IP. If that is setup correctly, you must make sure your FOG server is able to ping a host from the command line using:

```
ping somehostname
```

If the server isn't able to ping the client, then the status of the host in the UI will always show as unreachable. If you can ping the client using the FQDN, like

```
#Replace forproject.org with your domain suffix
ping somehostname.fogproject.org
```

Then you will need to adjust the DNS **Search domains** setting on your sever. After making this change you will need to restart the apache server for it to take affect.

If after this, you still can't ping your clients, the problem may be due to a firewall issue with the clients. In this case, client specific configuration changes might be needed.

### Creating Host Groups

FOG allows you to create groups of hosts which then allows you to take action on a whole grouping of hosts. Hosts can be created either on the "List All Hosts" section or by doing a search for hosts. To create a group select the computer you would like to be member of the group by placing a check in the box next to the hostname, or by clicking the check all button in the title row. After the hosts are selected scroll to the bottom of the screen and then enter a name in the create to group box or select a group to add the hosts to. Then click on the "Process Group Changes" button.

## Groups

### Overview

Groups in FOG are used to organize your hosts into real world logical clusters. This is intended to ease management of the computers. A single host can be a member of infinitely many groups, so if a computer happens to be a member of the group called "Third Floor", it could also be a member of "Math Department", or "Dell PCs." Groups make using FOG possible for organizations with a very large number of PC's.

### Creating Groups

Groups are created in the hosts section of FOG based on searches, for information on how to create groups,

please see Creating Host Groups.

## Managing Groups

After a group has been created, it can be managed from the groups section of FOG. Locating groups is very similar to locating hosts, you can either list all groups or you can search for groups. When searching for groups your search criteria is matched against the group name or the group description. Once a group is located it can be modified by clicking on the "Edit" button on the right hand side of the table.

Under the section "Modify Group [Groupname]" there are options to change the group name, group description or to delete the group. If you wish to update the group name or the group description make your change then click on the "Update" button within that section. If you would like to remove the group then simply click on the "Delete" button within this section.

### Group Basic Tasks

This section will allow you to start a task on this group of hosts without going to the tasks section of fog. From this section you can start a unicast deploy to all hosts within the group.

### Group Membership Setup

This page allows you to view / delete membership of the group. This section will list all of the members of the group and give you the option to remove members from the group.

### Group Image Associations

The groups page also allows you to update the image association for all the members of the group. This can be done in the "Image Association for [groupname]" section. Select the image association from the drop-down box and select "Update Images" and then all your host objects for that group will be modified.

### Group Operating System Associations

You can also change the Operating System association for all hosts in the group via the **OS Assoc** Button in the Group Menu. Clicking the update button will apply the changes to all members of the group.

### Group Snapins

You can add or remove snapins to all hosts in a group, but because the nature of groups, it is not possible to see what snapins are currently associated with a group. This is because the snapins are not directly associated with the group, they are associated with the host and it is possible for all members of the groups to have different snapins linked with each host. What fog does allow you to do is batch add a snapin to all the hosts within a group. At the same time you can batch remove a snapin from all the hosts within a group. These functions can be done via the **Add Snapins** and **Remove Snapins** button in the Group Menu.

### Group Service Settings

The **Service Settings** page allows you to enable or disable certain service modules on all hosts in the group, as well as change some service settings for group such as screen resolution, and auto log off settings.

### Group Active Directory Setup

Active Directory integration settings can also be distributed to all members of a group via this page. The section "Modify AD information for [groupname]" allows you to do so. This section provides the same options as the host screen but allows you to mass update all of your hosts.

### Group Printers

The **Printers** page allows you to add or remove printer associations to all hosts within the group. This page also allows you to set the management level all hosts within the group.

## Group Membership Information

The most important thing to remember about groups in FOG is that they do not contain their own properties. When you make changes to a group, you are really make changes to every host object within the group. For example, if you change the OS association for a group, then go back to the one of the host objects that is a member of that group, it will have the new OS association on that object.

## Images

### Overview

Image objects in FOG are the representation of the physical files that contain the disk or partition images that are saved on the FOG server.

### Creating Images Objects

Image objects in FOG are created in the Images section of the FOG management portal. To create a new image click on the "New Image" button on the left hand menu. An image object requires a name and a image file path.

When creating images you have a few choices in how you want that image to 'act'. The possible partition types include:

- Single Partition
- Multiple Partition - Single Disk
- Multiple Partition - All Disks
- Raw Image

**Single Partition** - Single Partition images support only single NTFS partitions. These partitions are resizable, meaning that an image from a 200GB hard disk can be put on a 10GB hard disk as long as the data is less than 10GB. This image type is destructive, which means that your partitions will be modified, and if the task doesn't finish without error it is possible that your computer may not be bootable.

**Multiple Partition - Single Disk** - Single Disk will back up all the supported partitions on the first disk drive detected by FOG, but the partitions are NOT resizable by FOG. This means that the image must be restored to a disk of the same or larger capacity. It is possible to backup NTFS drives with vendor specific 'restore' partitions with this type of image.

It is possible to backup Linux systems with this type of image given the following criteria:

- There is a Grub boot loader present.
- LVM is not used.
- The partitions include **ext2, ext3, reiserfs, or swap**.
- The swap partition should be moved out of the extended partition (for ubuntu 9.04)

Linux support is still pretty primitive, and has only been tested with a default Ubuntu 8.04 Installation.

**Multiple Partition - All Disks** - All Disks will back up all the supported partitions on all disk drives detected by FOG, but the partitions are NOT resizable by FOG. This means that the image must be restored to a disk of the same or larger capacity.

**Raw Image** - Raw Image will do a raw sector-by-sector copy of your hard disk, which means that if you have a 80GB hard drive, dd will process 80GB of data, and you will end up with a VERY LARGE image that is VERY SLOW to create and restore.

All of these images can be deployed using multicast or unicast to clients.

### Modifying Image Objects

Image object can be located either by a search or by listing all image objects.

### Adding Existing Image Objects



To restore an image to the FOG database:

1. Create a new Image definition through the management browser
2. Specify image name (SampleXPImage)
3. Specify storage group (default)
4. Specify image file path (SampleXPImage)
5. Specify image type
6. Log into the box hosting FOG, and move/rename your image to match browser input
7. Create hierarchy if necessary. FOG, by default, puts images in /images/, so for the above example, you would need to create a folder structure like so: /images/SampleXPImage
8. Drop your image file into the folder (be sure it's named the same as image name above)


## Storage Manangement

### Overview


The Storage Manager section of FOG was added in version 0.24 of FOG and introduces the concept of **Storage Groups**. Basically, a storage group is a group of NFS servers that share images and share the load of computers being imaged. Any member of a storage group is referred to as a **Storage Node**. You may have as many storage groups as you wish and as many storage nodes within those groups as you wish. In each storage group, there is one storage node which is designated as the **Master** of that group. Basically what this means is that is the node where all image uploads go, this node handles multicasting tasks for the group, and is the image replicator for the group. This means that whatever images are stored on this node are what gets distributed to the entire group.

What this new system of storage management gives us is a distributed model for FOG which allows for more unicast transfers at a single time. We also gain data redundancy. We also take stress off of the main FOG server.

Below is a brief overview of Storage Groups



This image shows a single Storage Group and the flow of data within the group. The queue size of the system is the sum of the queue size of all the storage nodes within the system. So if you have 4 nodes each with a queue size of 10, then the queue size of the system is 40, which means 40 clients can be imaged (unicast) at one time.



This image shows that it is possible to have multiple storage groups on your network, which are isolated from each other. This image also demonstrates, that uploads always go to the master node and multicast session always send data from the master node. Images are pushed out from the master node of the group to all other members of the group.

### Key Benefits

- Increased throughput
- Redundant Storage
- Scalability

### Adding a Storage Node

Video Tutorial: <http://www.youtube.com/watch?v=X72WthDGwsW&fmt=18>

To add an additional storage node to the network, the computer should be prepared in the same way the main FOG server would be prepared (disable firewall, SELinux, etc). You can also safely mix operating systems for the nodes of your storage group, some nodes can be running fedora, and some can be running Ubuntu. It is important to update your storage nodes when you upgrade to a new version of FOG. Installation of a storage node is done with the same installer for a normal FOG server. Installation can be started by running the installer script, the steps are detailed below.

### Installing the Node

1. Run the installation script, `./installfog.sh`
2. Select your operating system.
3. When prompted for Server Installation Mode, select **S**, for storage node.
4. Enter the IP address of the storage node.

5. Confirm you interface
6. Then you will need to enter the IP address or host name of the node running the FOG database
7. Then you will be prompted for a username (typically fogstorage)
8. and a password that is located on the FOG server, that will allow the storage node to access the main FOG server's database. This information is located in the FOG management portal for convenience (on the main for server). It can be accessed via **Other Information** -> **FOG settings** -> section **FOG Storage Nodes**.
9. You will then be prompted to confirm your installation settings, if they are correct press **Y** end hit **Enter**.
10. When installation completes, the install will produce a username and password that will be needed to add the storage node to the FOG management portal.

#### Adding the Node to the Management Portal

1. Log into the FOG Management Portal
2. Navigate to the **Storage Management** section.
3. Click on **Add Storage Nodes**.
4. For the **Storage Node Name**, enter any alpha numeric string to represent the storage node.
5. Enter any description you wish
6. Enter the IP address of the storage node you are adding. This must be the IP address of the node, DO NOT use a hostname here or the node will not function correctly.
7. Enter the maximum number of unicast clients you would like this node to handle at one time. The value that we recommend is 10.
8. Is Master Node is a very dangerous settings, but for right now leave it unchecked, for more details please see: #Master Node Status.
9. Next, select the storage group you would like this member to be a part of, in our example we will pick **Default**
10. Next, specify the image location on the storage node, typically **/images/**, your image location should always end with a **/**.
11. Next, you will want to check the box, to enable the node.
12. The last two fields take the username and password that are generated during the installation of the storage node.
13. Then click **Add** to have the node join the storage group.

#### Monitoring The Master Node

On all storage nodes there is a new service (as of version 0.24) called FOGImageReplicator which is a very basic script which, if the node is the master, copies all of its images to all other nodes in the storage group. The coping is done every ten minutes by default, which means your images are NOT instantly duplicated to all nodes.

If you would like to view the status of the image replication, you can do so on the storage node by switching to tty3, by typing **ctl + alt + f3**. Output is also logged to a file in the **/opt/fog/log** directory.

#### Master Node Status

The **Master Node** in a storage group is the node that distributes images files to all other nodes in the storage group. So, if you have all your images distributed across 3 nodes in a storage group, if you add a new storage node that has no images stored on it, making that node master will cause it to take over and push it's image store of nothing to all other nodes, wiping out all of your images. So it is important to be very careful and backup your images when you change a node's master status.

#### Users

##### Overview

FOG has only two levels of users, **regular** users and **mobile** users. Regular users have access to the mobile portal and the full management portal. Mobile users have access to only the mobile management portal.

## Creating Accounts

All accounts are created under the "Users" section of the FOG portal. To create a new account click on the "New User" button on the left hand side of the page. All accounts must have a unique username, and a password. After filling in the required information click on the "Create User" button.

## Modifying Users

FOG accounts can be modified from within the users section. First you must locate the account you wish to modify by clicking on the "List all Users" button on the left hand side of the page. When a user is located, click on the edit button on the right hand side of the table.

## Tasks

### Overview

Tasks are all the actions that you can take on a computer, and in FOG there are numerous tasks that can be done including:

- Upload - Unicast
- Upload - Unicast (Debug)
- Download - Unicast
- Download - Unicast (Debug)
- Download - Unicast (Without Snapins)
- Download - Multicast
- Debug
- Deploy All Snapins
- Deploy Single Snapin
- Memory Test
- Wake Up
- Fast Wipe
- Normal Wipe
- Full Wipe
- Disk Surface Test
- File Recovery
- Virus Scan
- Hardware Inventory

In the tasks section of FOG you can perform tasks on single hosts or groups of hosts. This section also allows you to monitor selective tasks, and stop/cancel tasks.

### General Tasks

The general/common Tasks in FOG include unicast image upload, and unicast image send, as well as a multicast image send. In FOG, sending an image to the server is considered an image upload, and deploying an image to the client is called a send. Both of these tasks can be started directly from the search, list all hosts, and list all groups pages.

To perform a simple image upload, click on the upward facing arrow next to the host. Uploads are only possible on a host, not a group. Uploading an image will also overwrite any image file that may already exist for that host without any notification or confirmation.

Please note that uploading images of Windows Vista and Windows 7 requires special command to be run on the clients prior to image upload. Please see [What do I have to do to an image before uploading?](#) for more details.

For a video demonstration of an image upload, please see: <http://www.youtube.com/watch?v=jPPZr0abVfg&fmt=18>

To perform a simple image send, click on the downward facing arrow next to the host. An image send can be done on a host or a group. When sending an image to multiple computers FOG works in queue mode, which

means that it will only send to 10 (by default) computers at one time. This is done to keep the server from being overworked. As soon as the a machine finishes, another from the queue joins.

To perform a multicast image send you must search for a group of hosts on the "Task Management" page. Multicast tasks can only be performed on a group of hosts. Multicast tasks will send to all the computers in the group at once, and the task will not start sending until all members of the group have connected with the server. After starting a multicast task, status can be view by clicking on [ctl]+[alt]+f2. A log is also kept for multicast transfers which is stored at /opt/fog/log.

## Advanced Tasks

The advanced Tasks in FOG include everything that is not a simple upload, simple send or mutlicast send.

### Debug

Debug mode boots the linux image to a bash prompt and allows the user to issue all commands by hand.

### Upload - Unicast (Debug)

Does the same thing that debug mode does, with the exception that the environment is setup to upload the image. To start the imaging process just type:

```
fog
```

### Send - Unicast (Debug)

Does the same thing that debug mode does, with the exception that the environment is setup to send the image. To start the imaging process just type:

```
fog
```

### Send - Unicast (Without Snapins)

This task does a normal send task with the exception that if any snapins are associated with the host, they are not deployed to the host.

### Deploy All Snapins

This task will send all the snapins associated with a host to the host without imaging it.

### Deploy Single Snapin

This task will send a single snapin that is associated with the host to the host without imaging it. (Note: The snapin must be associated with the host already)

### Memory Test

Boots to Memtest86, a memory testing tool. This a task will not exit with out user intervention at the client side. The task must also be manually stopped via the management front end.

### Wake Up

Wakes up host or group of hosts using Wake-on-Lan.

### Fast Wipe

This task does a quick and dirty wipe of the drive. This task writes zeros to the first ~40MB of the disk. This task should NOT be used if you don't want your data to be recoverable.

### Normal Wipe

This task writes random data to the entire surface area of the disk.

### Full Wipe

This task writes random data, multiple times to the entire surface of the disk.

### Disk Surface Test

This task will look for bad blocks on the hard disk and report them back to the client console.

### File Recovery

This task will load an application that can be used to recover lost files from the hard disk.

### Virus Scan

This task will update and load ClamAV and scan the partition for viruses. It will either scan and report or scan and quarantine files, it will also report back to the management portal with the results of the scan.

### Hardware Inventory

Video Tutorial (<http://freeghost.sourceforge.net/videotutorials/InventoryUpdate.swf.html>)


The hardware inventory task will execute the same task as the fog.reginput client side task. Since the host is already registered, all it will do is update the computers inventory and restart. It is envisioned that this task could be run on a regular interval on a group of all computers in your network, or some sub group of computers in your network. Then on the next reboot of those computers an inventory would be performed.

## Scheduling

As of version 0.27 of FOG, select tasks can be scheduled using a static date/time combination or using a cron style repetitive task scheduling. Task scheduling can be performed on either single hosts, or on groups of computers. One thing to note about task scheduling that isn't intuitive is that it **requires an image to be associated with the host, even for non-image based tasks!** The reason for this is because tasks are only run on the master storage node associated with that host, and the only way to tie a storage node to a host is via an image. We did this to prevent multiple storage nodes to try running the same task for a specific host.

### Single Execution Scheduling

Single task execution will run a task at a single date and time, then the task will be discarded. To schedule a single execution task, you would go to the tasks section of fog, then select the host or group you would like to schedule the task, then select the task you would like to schedule. You will then be presented with the screen show below.



To schedule a single execution task, click on white text box below "Schedule Single Task Execution?" and a pop up calendar will load and allow you to select your date and time for the task. Click on the date to close the calendar, then start you task.

### Cron Style Task Scheduling

Cron style task execution allows you to do complex repetitive task scheduling. After a cron task executes, it is not removed, as single executions tasks are. Cron style tasks, as the name suggests are similar to the Linux cron task scheduler format. Cron style tasks are created as single execution tasks are, except when presented with scheduling options, select the option "Schedule Cron Style Task Execution". Below that check box are a series of text boxes including:

```

%min    -> Minute
%hour   -> Hour
%dom     -> Day of Month
%month  -> Month
%dw     -> Day of Week

```

To give an example of how this works, if you wanted a upload task to run at **10:00pm everyday** you would enter the following:

```
% 22 * * *
```

This basically says run the task a **0** minutes into the hour, on the **22nd hour (10:00pm)**, on **every day of the month**, on **every month of the year**, on **every day of the week**.

To take this example further, lets say you only wanted to upload the image **every other day**, we could do this by adding:

```
% 22 */2 * *
```

The **\*/2** now tells the scheduler to only run on **even days of the month**.

We could even ask the scheduler to only do a backup on **even weekdays** by adding:

```
% 22 */2 * 1-5
```

The 1-5 we just added says only run on days 1 through 5, which relate to Monday - Friday.

Now we will ask the scheduler to only backup in the month of February.

```
% 22 */2 2 1-5
```

Another basic example could be if you wanted to run an inventory update on the first of every month you could use:

```
% 30 1 1 * *
```

This task would then run at **1:30** on the **1st of every month**.

The FOG scheduler doesn't support 100% of the operations that cron supports, below are the operations that are supported:

```

%4      -      Listing a static number
%4,5,6,7 -      Listing a group of numbers
%4-7    -      ranges of numbers
%4-7,10 -      ranges and lists
%*/5    -      * divided by a number
%*      -      Wildcard

```

For more information on cron please see <http://en.wikipedia.org/wiki/Cron>

## Printers

### FOG Version

Relates to FOG Version 0.12 or higher.

### Known Issues

Setting of the default printer will only work if the fog tray icon is running.

### Overview

The printers section of FOG allows you to create printer definitions that you can later associate with hosts. The FOG service looks at these associations and during service it will attempt to install any printers listed. This service has three settings which define how the printers are managed, printer management can be set to:

- No Printer Management
- Add Only
- Add and Remove

All hosts default to **No Printer Management** which means that the FOG service does nothing to the hosts printers. **Add Only** does as the name implies, and will only add printers to the host machine, it will not remove any existing printers that may be installed. **Add and Remove** will take full control of the hosts printing system and only allow for the printers that are specified by the FOG management console to exist on the host.

### Adding New Printers

Video Tutorial (<http://freeghost.sourceforge.net/videotutorials/printer.swf.html>)

In order for the printer to be added to the host computer, the printer drivers must be stored in a public area, or included on the host computer. This public area can be a Novell Network share where public has read-only access, a Windows share that is public read-only to everyone, or a Samba share (possibly residing on the FOG server) that is public read-only to everyone. This share must be accessible via a UNC path as the service may attempt to install the printers before drive mapping occurs. In this share the printer drives and .inf file must exist. FOG supports install IP based (Jet-Direct) printers, public access NDS printers, Local printers, windows share based printers, (and we think, but could use a confirmation as it hasn't been tested) AD based printers.

If you wish to see what printers are included with Windows XP, navigate to c:\windows\inf\ntprint.inf. Open this file with a text editor and you will be able to install all the printers listed using the ntprint.inf file.

To create a new printer definition click on the Printer icon on the system menu bar. Then on the left hand menu, click on **Add New Printer**. The form you are presented with will require you to enter:

- **Printer Model** - This must match the name in the INF file.
- **Printer Alias** - This can be anything you wish and it is what the end user will see.
- **Printer Port** - This is something like **LPT1:**, or **IP\_1.1.1.2**.
- **Printer INF File** - This is the path to the INF file for the printer driver.
- **Printer IP** - (optional) This is ip address of an IP based printers only, this can take the form of **1.2.3.4:9100** or **1.2.4.5**. If the port doesn't exist already, it will create one named **IP\_x.x.x.x**, where x.x.x.x is the ip address. That is what should be entered in the port field.

After all the required information is entered, click on the **Add Printer** button.

### Linking Printers to Hosts

Video Tutorial (<http://freeghost.sourceforge.net/videotutorials/printer.swf.html>)



Linking printers to hosts can be done from either the hosts section or the groups section. In the hosts section find the host you would like to add a printer to, click on the edit button associated with that host. In the host menu, click on the **Printers** button. First select how you would like the host to be managed, either **No Printer Management**, **Add Only**, or **Add and Remove**. Then in the section below, select the printer you would like to install from the drop down list and click on the **Update** button.

### Creating a Samba Based Printer Store on FOG

If you do not have a public sever where you can store your printer drivers for the FOG Printer Manager, then it is very easy to set one up on the FOG server using Samba, so all your Windows Clients will be able to connect.

Creating a Samba Based Printer Store on FOG

## The FOG Client Service

### Overview

The FOG Client Service is a Windows Service that is intended to be installed on the client computers during the image creation process. The FOG service communicates with the FOG server to provide certain service to the client computers including:

- Auto Log Off (0.16)
- Hostname Changes
- Active Directory Integration
- Directory Cleaner (0.16)
- Display Manager (0.16)
- Green FOG (0.16)
- Host registration
- Task Restarting
- Snapin Installation
- User Tracker
- Printer Manager
- User Cleanup (0.16)
- Client Updater
- User Tracker

### Module specific configuration settings

The FOG Client Service is very modular in nature, which means you can install portions of the services provided, and leave off others. This also means that it is very easy to create new sub services if you know a little C#. All configuration data is held in a local INI file. Which is typically stored in

```
c:\program files\fog\etc\config.ini
```

This file holds, in the general section:

- FOG Server IP address
- FOG Service installation root
- FOG Service working directory
- FOG Log file path
- Flag indicating if GUI messages should be displayed
- The max log file size

### Installation


Video Tutorial (<http://freeghost.sourceforge.net/videotutorials/FogServiceInstall.swf.html>)

The FOG service should be installed on the computer to be imaged before uploading the image to the FOG Server.

The FOG service is located in the **FOG Service/bin** directory or if the FOG server is already installed it can be downloaded from:

```
http://[serverip]/fog/client/
```

Double-click on the **setup.exe** to start the installation wizard. At the end of the wizard you will need to enter the IP address or hostname of your FOG server.



Then restart the computer, if you don't restart the computer you will have issues with the service GUI appearing correctly.

### Quiet Installation

As of version 0.29 and higher, the FOG client now supports a quiet installation mode. This can help automate deployments, by allowing the command to be run without user interaction from batch files. To do this the setup.exe file must be run from the command line with the arguments **fog-defaults=true /qb**.

So the full command would be:

```
setup.exe fog-defaults=true /qb
```

## Functions and Operation

### Auto Log Out

Added in Version 0.16

This module of the FOG Service will log a user off of a client pc after X minutes of inactivity. This module will display a screen saver-like GUI after 3/4 of the inactive time is up. So if the time out value is 40 minutes, the GUI will be displayed at 30 minutes of inactivity. When the time is up, the client computer will reboot. This service module can be configured via the management portal via:

```
FOG Service Configuration -> Auto Log Out
```

To enable the module globally, place a check in the box next to **Auto Log Out Enabled?**. The time to auto log off can be changed globally via **Default log out time:**. The minimum recommended value for this setting is 4 minutes.

The background image for the auto log off module can be modified via:

```
Other Information -> FOG Settings
```

The settings can be changed by modifying the value for **FOG\_SERVICE\_AUTOLOGOFF\_BGIMAGE**. This settings will accept a jpg file that is local to the client computer like:

```
c:\images\image.jpg
```

This setting will also accept files located on a web server such as:

```
http://www.somedomain.com/image.jpg
```

Provided with FOG is a simple php script that will display a random images that is located on the FOG server. To use this option set **FOG\_SERVICE\_AUTOLOGOFF\_BGIMAGE** to

```
http://x.x.x.x/fog/public/randomimage.php
```

Then simply put the images you would like to use in the following directory on the fog server:

```
/var/www/html/fog/public/imagepool
```

Images used for the auto log off module must be in jpg format, and must be 300px by 300px.

### Hostname Changer

This module of the FOG Service is used to change the hostname of the client computer and to allow the client to (optionally) join a Active Directory Domain after imaging. This process only runs shortly after service startup, which means typically only when you start your computer. The service communicates with the FOG server over port 80 and determines the hostname that is present in the FOG database for the host. The hosts are matched to the FOG database by their MAC addresses. If the hostnames are found to be different, the client changes the computers hostname and restart the computer.

The config.ini file contains configuration options for this module.

```
netdompath=
```

Allows you to set the path to the netdom.exe file. In some cases the file does not exist on the system. It can be downloaded from: Microsoft Download Center (<http://www.microsoft.com/downloads/details.aspx?FamilyId=49AE8576-9BB9-4126-9761-BA8011FABF38&displaylang=de>)

### Host Register

As of version 0.29, this module will only add additional mac address to a host that is already registered, and add them to the pending mac address table, where they need to be approved in the FOG UI.

### Task Reboot

This module periodically checks in with the FOG server to see if the client has an imaging task assigned to it. If a task is found AND no one is logged into the workstation, then the client will restart and join the task.

The config.ini file contains configuration options for this module. As of version 0.13 of FOG you can change:

```
forcerestart=0
```

to

```
forcerestart=1
```

This will make the computer restart if a task is found, regardless of whether a user is logged into the computer.

You can change how often the service will check in with the server by changing:

```
checkintime=xxx
```

where xxx is the number of seconds the service will wait between check-ins.

### **Directory Cleaner**

Added in version 0.16

This module will clean out (delete) the contents of a directory on user log off. This useful when you don't want any settings cached between users. This module will only delete the contents of a directory and not the root directory itself, so if you specify **c:\trash**, the service will remove all files and folders located within c:\trash but leave the folder c:\trash.

### **Display Manager**

Added in version 0.16

This module is used to restore screen resolution between clients. This will restore a fixed resolution and refresh rate when a user logs into a computer.

### **Green FOG**

Added in version 0.16

This module will simply shutdown/restart the client computer at a fixed schedule if no user is logged in. The schedule can be defined via the management portal.

### **Snapin Client**

This module periodically checks in with the FOG server to see if the client has a snapin set to be deployed to it. If a snapin is found AND no imaging task is associated with the client, then the client will download the snapin and install it in the background.

The configuration file contains settings for this module including:

```
checkintime=xxx
```

where xxx is the number of seconds the service will wait between check-ins.

### **User Tracker**

This module attempts to track user access to the host computer by the Windows user name. It attempts to track logins and logoffs as well as the state of the computer at service startup. The service will even attempt to track users when they are not on the network by writing all entries to a journal file, then replying the journal the next time the client is on the network.

There are no configuration settings for this module.

### **User Cleanup**

This module will remove all users not white listed in management portal on log off. This module is useful when using services like dynamic local user. All entries in the management white list are treated as prefixes

to usernames, which means that they will white list all users that start with whatever was entered in the management front end. For example, if you enter **admin** in the management white list, then users **admin**, and **administrator** will NOT be removed from the computer.

#### Printer Manager

This module checks on service startup to see what printers should be installed/removed from the client PC.

There are no configuration settings for this module.

#### Client Updater

This module waits (randomly) between 60 and 500 seconds after service startup to check the local fog server for client updates, and if any are found the service will download and install them. Updates will NOT take effect until after the service is restarted.

There are no configuration settings for this module.

### Keeping Clients up to date

#### Overview

As of version 0.12 of FOG, we have included a client updater module. This module is no different from any of the other sub service modules. This service waits anywhere between 60 and 500 seconds after the FOG service starts up, and then attempts to check with the server for newer FOG service modules. If new modules are found the client will download them, and they will be active on the NEXT service startup. These modules are controlled from the FOG Management Console.

Only certain modules can be updated, only those that are a sub class of AbstractFOGService. This means you should **NEVER** attempt to update the FOGService executable (FOGService.exe file), or the AbstractFOGService.dll file. It is recommended that you not update the ClientUpdater.dll, because if the ClientUpdater.dll file becomes corrupt or not functional, your clients will not be able to update from that point on. Below are a list of the .dll files that can be updated.

- UserTracker.dll
- TaskReboot.dll
- SnapinClient.dll
- PrinterManager.dll
- HostRegister.dll
- HostnameChange.dll
- GUIWatcher.dll
- ClientUpdater.dll
- config.ini

Care must also be taken when updating the config.ini file, if the IP address is incorrect or the syntax of the file is incorrect, it could leave the FOG service crippled on the client computers.

#### Posting Updates

To add new modules that can be pushed down to clients, first install a client with the new service or new module and confirm that it works as you would like. Log into the FOG management console, then go to the Information/Misc section (the little "i" icon). Click on **Client Updater** on the left-hand menu. Now click on the browse button to select the module (.dll) file you would like to post, then click on the upload button. After uploading the file should appear in the table above. If you are adding a new module, you will probably want to upload a new config.ini file to include new configuration settings required by that new module.

#### FOG Tray

The FOG Tray is a Windows application that runs on user login that docks in the system tray. The FOG Tray, like the FOG service is very modular in nature. New modules can be dropped in the FOG tray directory and on next load they will be loaded. This tray icon has the ability to communicate with the FOG service, this

allows fog more interactivity with the end-user.

What happens is that when the FOG service's printer manager module gets a request to set a default printer, the service attempts to contact the FOG Tray. If communication is established, then the service will ask the tray to set the default printer. On the other hand the end user can right click on the "F" icon in the system tray, then select printers, then update my printers. What this will do is attempt to send a request from the FOG Tray to the FOG Service and have the service check for printer updates (new printers or printers to be removed). If one is found the service will install any new printers assigned in the FOG Management portal.

This application is in its very early stages and currently doesn't have a lot of functionality. It is currently only used to allow end users to update their printers and to allow the setting of default printers (from the FOG service). Our vision for the FOG Tray is to add modules that would allow users to installed printers that published as public (via the management portal) without the printer being directly assigned to their host. We would also like to do the same thing for snapins where some of your snapins could be defined as public where anyone could install them on their computer.

## Troubleshooting

If you have problems with the FOG Service, please refer to the log file that is located at:

```
c:\fog.log
```

## Snap-ins

### Overview

The FOG Service has the ability to install snapins to the clients. Snapins can be anything from whole applications like Microsoft Office to registry keys or desktop icons. Snapins can even be used to uninstall applications or remove unwanted files. For the end use's point of view, they will not even noticed that a snapin is being installed until it is complete. At this point a message will notify them that a new application has been installed on their computer. Snapins can in MSI (0.17) or EXE formats, and can be created with any snapin creation tool like InstallRite or already packaged MSI files (0.17).

### Creating a Snapin

FOG doesn't provide a tool to create snapins, but there are free tools that will do this for you. In this example we will use Epsilon Squared's InstallRite which can be downloaded from <http://www.epsilonquared.com/installrite.htm>. This application will package up your snapin as an exe file which will be uploaded to the FOG server.

1. To run InstallRite navigate to c:\program files\Epsilon Squared\InstallRite\InstallRite.exe
2. Click on "Install new software and create an InstallKit"
3. On the Configure screen, click Next.
4. On the Snapshot screen click next to create a new system snapshot.
5. On the next screen,click the browse button to select the application you wish to install, then click next.
6. When installation is complete InstallRite will come into focus, click the next button. InstallRite will scan your system again.
7. Enter a name for your snapin.
8. Click "Build Install Kit"
9. Select "Quiet Installation Mode", Never reboot, even if needed, and "Never prompt the user and only overwrite older files"
10. Click OK and it will build your snapin.

### Preparing the FOG Server

If your snapin is larger than 2MB you will need to make two changes to the FOG server to allow uploads of larger than 2MB.

**Fedora**

1. On the FOG Server click on Applications -> Accessories -> Text Editor.
2. Select Open and navigate to "/etc/php.ini"
3. Change UPLOAD\_MAX\_FILESIZE to 1900MB (On a 32Bit OS don't set this value above 2GB)
4. Change POST\_MAX\_SIZE to the same value.
5. Save and close the text editor.
6. Click on Applications ->System Tools -> Terminal and type "service httpd restart"

**Ubuntu**

1. sudo gedit /etc/php5/apache2/php.ini
2. Change
  1. memory\_limit = 1900M
  2. post\_max\_size=1900M
  3. upload\_max\_filesize=1900M
3. Save Changes
4. sudo /etc/init.d/apache2 restart

**VMWare**

1. sudo vim /etc/php5/apache2/php.ini
2. Edit the following lines in the document (read below for assistance with working in VIM)
  1. memory\_limit = 1900M
  2. post\_max\_size=1900M
  3. upload\_max\_filesize=1900M

- To edit content in vim you will need to press the "**I**" key on your keyboard to enter input mode.
- Hitting the **Escape** key will bring you out of input mode.
- Once out of input mode type **:w** and then **enter** to save the file
- Restart FOG once the file has been saved

**Uploading the Snapin**

Video Tutorial (<http://freeghost.sourceforge.net/videotutorials/CreateSnapin.swf.html>)

1. In the FOG Management Portal click on the Snapin Icon (Puzzle Pieces).
2. On the left-hand menu click on the New Snapin Button.
3. Enter a Snapin Name and Description.
4. Browse to the snapin file you wish to upload.
5. If you want the computer to restart after the snapin is installed click on the "Reboot after install"
6. Click "Add"

As of version 0.17, fog supports using typical msi files as snapin files.

If the snapin file is a msi file you must perform these additional steps:

1. Set **Snapin Run With:** to the path of msixec.exe (ie: c:\windows\system32\msixec.exe)
2. Set **Snapin Run With Arguments:** to **/i**
3. Set **Snapin Arguments:** to **/qn**

If the snapin file is a .vb script you must perform these additional steps:

1. Set **Snapin Run With:** to the path of cscript.exe (ie: c:\windows\system32\cscript.exe)

### Documentation on list of support snapin's and command line arguments [[3]

([http://www.fogproject.org/wiki/index.php?title=Supported\\_Snapin%27s\\_and\\_Command\\_Line\\_Switches](http://www.fogproject.org/wiki/index.php?title=Supported_Snapin%27s_and_Command_Line_Switches)) ]

There are MANY more supported applications that can be installed via command line arguments. You might have better luck installing them directly via .EXE / .MSI / or scripting them via .VBS . For more info on this consult the forums --Ssx4life 09:04, 8 October 2009 (MST)

### Linking the Snapin to Hosts

In order for a snapin to be deployed it must be linked with a host. To do this perform the following:

1. In the FOG Management Portal, click on the Hosts Icon.
2. Search for and select a host and click on the edit button.
3. Scroll down to the snapin section.
4. Select the snapin you just created from the drop-down box and click the "Add Snapin" button.

The next time you image the computer the FOG Service will attempt to install that snapin. If you have problems, please see the fog log file located at c:\fog.log on the client PC.

## Client Side Tasks

### FOG Version

Applies to version 0.12 or higher.

### Overview

FOG attempts to keep management centralized, but in an attempt to make deploying machines as easy as possible FOG has added a few basic client side tasks. These tasks can be run from the client computer during the PXE boot process. When the client boots and the FOG banner is displayed the pxe client will display a prompt like **boot:** or something similar. At this point you have 3 seconds to start typing one of the following commands.

- fog.memtest
- fog.reg
- fog.reginput

### **fog.memtest**

This command will run the memtest86+ on the client computer.

### **fog.reg**

This command will run the basic host registration and inventory process without any user input. It will register any new/unregistered hosts with the FOG server and pull a basic hardware inventory from them. The hostname of the computer will be the same as the MAC address without the ":".

If a host is already registered, then only an inventory will be performed.

### **fog.reginput**

View Host Registration Video (<http://freeghost.sourceforge.net/videotutorials/RegImage.swf.html>)

This command will run the full host registration process with user input, inventory and give the option to push down an image, all at the same time. During this process the user registering the host will be prompted for the computer host name, ip address, operating system ID, image ID, Primary User of the computer, asset tag 1, and asset tag 2.

If a valid hostname, os id, and image id are given and the option is selected to image the workstation after registration, the host will reboot and an imaging send will began.



If a host is already registered, then only an inventory will be performed, this prevents end-users from re-registering a machine with a different hostname, etc.

This task was designed for institutions that may get shipments of hundreds of computers that need to be deployed very quickly. They can be unboxed, inventoried, imported into FOG and imaged very quickly.

### Operating System ID

As of Version 0.17 of fog, you can now enter ? at the Operating System ID prompt to get a listing of the valid operating system id values.

The following are valid values for operating system IDs:

- **1** - Windows 2000 / Windows XP
- **2** - Windows Vista
- **3** - Windows 98
- **4** - Windows (Other)
- **5** - Windows 7
- **50** - Linux
- **99** - Other

### Image ID

Image IDs can be found in the management console, in the Images section. Search for the image, and click on the edit button associated with the image, the image id will be in the Address/url bar in the format of **&imageid=xx**.

As of version 0.17, you can enter ? at the Image ID prompt to get a listing of all your images and their ID numbers.

## Active Directory Integration

### Setup

#### Overview

FOG has the ability to register a host with Active Directory, in a limited sense. FOG relies on the netdom.exe executable that is provided as part of the support tools on the Windows installation media. In order for Active Directory integration to function, your image will need to have the FOG service installed, along with the Windows Support Tools. It is also very important that before uploading your image that the computer is NOT a member of any domain.

#### Security

#### Important - Please read!

In order to add a computer to a domain, FOG requires a username and password that has rights to the OU where the computer objects are stored in the domain tree. FOG attempts to keep your password secure by encrypting it, but since FOG is open source, it is possible for someone to decrypt your password if you don't change the FOG "Passkey." It is highly recommended that you change this Passkey before implementing the AD integration in a production environment. Changing the Passkey requires you to recompile the FOG Service's Hostname change module, but don't panic this isn't hard and only needs to be done one time. Please see the documentation below.

#### Preparing the Image

Before uploading an image to FOG that you would like to use with Active Directory, please ensure that the image:

- is NOT a member of the domain, change the computer membership to workgroup instead.
- has support tools installed.

- has the FOG service installed.

### FOG Setup

To setup a host to use AD, navigate to the hosts section of the FOG management portal.

1. Search for, and select a host.
2. Click on the Edit button
3. Scroll down to the Active Directory section.
4. Check the box next to Join Domain after image task
5. Enter the domain name.
6. Enter the Organizational Unit where you would like to have the computer stored in AD. Leave if blank for the default. (Must be in LDAP format).
7. Enter the user name that has access to the computer objects.
8. Enter the encrypted password. This password must be encrypted with the FOGCrypt utility. This utility is located in the FOGCrypt folder of the FOG download package. It is a Windows command line application.
9. Click Update.

The next time you image that computer the service will attempt to register the host with the domain information provided. If you have problems please refer to the FOG Service log file located in c:\fog.log

### Making AD Integration Easier

As of version 0.20 of FOG, we have made it a bit easier to manage AD settings in FOG, by allowing for default settings for AD. This will allow the easy population of the domain, OU, username, and password. To set this feature up perform the following:

1. Go to **Other Information -> FOG Settings**
2. Set your default values for the following:
  1. FOG\_AD\_DEFAULT\_DOMAINNAME
  2. FOG\_AD\_DEFAULT\_OU
  3. FOG\_AD\_DEFAULT\_USER
  4. FOG\_AD\_DEFAULT\_PASSWORD (MUST BE ENCRYPTED!)

To test everything out, go to a host that doesn't have anything setup for AD, and click on the edit button for that host. Go to the host menu, and select Active Directory. Click on the **Join Domain after image task:** button and all your default values should be populated.

### Securing Active Directory Integration

#### Overview

In order to add a computer to a domain, FOG requires a username and password that has rights to the OU where the computer objects are stored in the domain tree. FOG attempts to keep your password secure by encrypting it, but since FOG is open source and the methods used to encrypt the password are open for all to see, it is possible for someone to decrypt your password if you don't change the FOG "Passkey." It is highly recommended that you change this Passkey before implementing the AD integration in a production environment. Changing the Passkey requires you to recompile the FOG Service's Hostname change module, but don't panic this isn't hard and it only needs to be done one time.

#### The Development Environment

The hostname change module is written in c#, so in order to recompile it you will need to download Microsoft's Visual Studio Express Edition for C#. This can be downloaded from:

<http://www.microsoft.com/express/vcsharp/>

Install Visual Studio with the standard options.

#### Getting the Source

After Visual Studio Express is installed now we need to get the source code for the hostname change module. This is part of FOG download/installation package. This package can be downloaded from:

[http://sourceforge.net/project/showfiles.php?group\\_id=201099](http://sourceforge.net/project/showfiles.php?group_id=201099)

Extract this package, then navigate to "FOG Service\src\FOG\_HostNameChanger\"

Double-click on HostNameChange.sln to open the project.

If you are asked to convert the project to the latest version, click the Finish button.

If you are using Visual Studio 2010, you need to change the target .NET framework to .NET 2.0. Do this by going to Project > hostnamechanger properties. On the Application tab, change the Target Framework to .NET 2.0

Once the project has opened, on the right-hand panel, in the "Solution Explorer", double-click on MOD\_HostNameChanger.cs.

After do so, you should get the source code to display in the main panel, scroll down to the line:

```
private const String PASSKEY = "FOG-OpenSource-Imaging";
```

Change **FOG-OpenSource-Imaging** to anything you like, just remember what you change it to, as you will need it later.

Then click File -> Save All.

Then click Build -> Build Solution.

This will recompile the hostname change module with your unique key.

Now navigate to "FOG Service\src\FOG\_HostNameChanger\bin\Release"

Copy only the file HostnameChange.dll to some place safe.

Every time you install the FOG service you must replace the file:

c:\Program Files\FOG\HostnameChange.dll with this File

### Encrypting Your Password

Now that we have changed the passkey, we need you update the FOGCrypt ini file to use this new passkey.

Navigate to the FOGCrypt\etc directory from the FOG download package.

Open the config.ini file and change the passkey value to your new passkey, then save the file.

Now open a command window and navigate using the cd command to the FOGCrypt directory.

Type:

```
FOGCrypt [password]
```

Where [password] is the AD user's password that has rights to the Computers section of the AD tree.

The output from this command is what you will enter in the FOG management portal.

## FOG Reports

### FOG Version

Relates to FOG Version 0.12 or higher.

## Overview

FOG Reports allow you to export data from FOG in two major formats including CSV, and PDF.

1. **Snapin Log** - This report will report on snapin installation history.
2. **Imaging Log** - This report will report on images deployed to hosts.
3. **Virus History** - This report lists any viruses that were found on locate computers.
4. **Inventory** - This report will report on the inventory information collect for network clients.
5. **Equipment Loan** - This report can be used for equipment loaned to staff members.
6. **User Login History** - This report contains information about user logins.

## Running Reports

Running a report can be done from the Reports section of FOG, then by picking a report from the left-hand menu.

## Importing User Created Reports

The reporting section of FOG allows for the end user to create and upload custom reports into FOG. A FOG report is a simple php script that is processed by the server. To import a report simply click on the **Upload a Report** button in the reports section, select the report then click on the upload button. The report will then show up on the left-hand menu.

Please be cautious when uploading reports from an unknown source as the writer of the report has full access to the FOG system and database! Make sure your sources are trustworthy before importing a report!

## Creating Custom Report

Custom reports are simple php scripts in FOG. Custom reports can be created based on the following template:

Report Template (<http://freeghost.sf.net/other/ReportTemplate.tar.gz>)

## Other Settings

### Boot Image Key Map

### FOG Client Kernel

#### Overview

In FOG, there aren't really drivers you need to find and download for your clients to work, this is because we ship a Linux kernel that has the majority of hardware device built into it. What this means is if you have a device that doesn't work with FOG you need to either build a new kernel yourself or try a newer kernel that has been released via our kernel updater.

#### Kernel Types

We currently build two "lines" of kernels, one called KS or KitchenSink. This kernel tries to include drivers for as many devices as possible, sometimes at the cost of performance, and this is the kernel that we ship with FOG by default. The other "line" is the PS kernel or the Peter Sykes kernel, which is based on a config submitted by a user. This kernel line tries to be faster, but may not include as many drivers as the KS kernel.

#### Updating the Kernel

It is possible to update your client kernel from within the UI of FOG. To do this perform the following steps:

1. Log into the FOG Management UI.
2. Go to **Other Information**
3. Select **Kernel Updates**
4. Select the Kernel you would like to download, typically the newest kernels are on the top of the list.
5. Click the download icon
6. Select a file name for your kernel, to make it the default kernel leave the name as **bzImage**
7. Click the **Next** Button

## Mobile Management Interface

### Overview

The FOG Mobile web interface is a very basic, stripped down interface for FOG. It is designed to be given to lower level technicians using low powered, mobile devices such as iPod touches, iPhone, PDAs, and internet tablets. The idea behind this interface is to make it easy for techs to re-image a computer while making the rounds at a site.

### Using the mobile Interface

The mobile interface can be access via:

<http://x.x.x.x/fog/mobile>

The portal requires a valid user name in password, which can be created via the FOG portal.



Once logged into the portal, users can search for hosts and image them, and view/cancel active tasks.



They can not change image associations, nor modify any properties of a host.

**Plugins**

**Capone**

**FOG Version**

Applies to version 0.29 or higher.

## Overview

Capone is a plugin for FOG that allows you to image a computer based on DMI/Hardware information without having to register it with the FOG server. This module was originally written for a HP computer warranty service center in the UK. They wanted to be able to restore a computer's image just by plugging it into the network and PXE booting the machine, without any user intervention. This module is great for repair shops and places where you don't need FOG to manage the computer after it is imaged. This is our attempt at pushing FOG into the service/repair sector.

## Installation/Activation

### Enabling Plugins

Plugins are not enabled on the FOG server by default, so this is the first thing we will need to do.

1. Log in to the FOG Web UI.
2. Go to the **Other Information** Section
3. Locate the section **Plugin System** and change **FOG\_PLUGINSYS\_ENABLED** from **0** to **1** and select Save Changes.
4. Click on the Dashboard/Home screen button from the menu bar.

### Enabling Capone

1. You should now have a new icon in the menu bar for plugins near the right hand side that looks like a puzzle piece, click on it.
2. Click on **Activate Plugin**
3. Select **Capone**

### Using Capone

We need to determine what DMI field we want to use for Capone. Currently Capone only supports a single DMI field globally. To do this boot up a client computer and from the PXE boot menu select the option **Client System Information**. When prompted with a menu, select option **7** to show DMI information. Press the enter key to scroll through the fields and pick a field that can uniquely identify the computer type you are working with. Common fields are:

- bios-version
- system-product-name
- system-serial-number

Once you have determined the field you would like to use, perform the following:

1. In the plugins section, select **Installed Plugin**, then select **Capone**
2. In the **Settings** section set your selected DMI field. This settings is global.
3. Now we can create associations for return values from that DMI field and an Image. In **Add Image to DMI Associations** select an image you would like to link to a DMI field response.
4. Select the operating system for the image
5. Then enter the matching value for the DMI field in the text field. This string can be treated as a 'starts with' query. So if you use the field **system-serial-number** and you have a group of computers that all start with **112233** then you can enter that into the text field and it would match a client with the system-serial-number of **1122334455**.

We now have our first association added to Capone. Now what we need to do is to add the Capone menu item to the PXE boot menu.

1. Scroll to the bottom of the capone plugin page and copy all the text in the **PXE Configuration** area.
2. Now go to **Other Information**
3. Select **PXE Boot Menu**
4. Click **Advanced Configuration Options**
5. Paste the text that you copied from the previous page.

Please note that this will not password protect this entry item. If you would like to password protect this item you will need to use the md5pass utility that is in the /opt/fog/Utils directory.

It is possible to have multiple matching entries per DMI result. So for example you could have to associations for response **112233**. In this case, at the console on the client computer you will be prompted for which image you would like to use.

Capone does not use additional storage nodes other than the master within a storage group.

## Backing up FOG

### Overview

Backing up FOG is pretty simple, there are a few directories that need to be backed up, plus the mysql database. The following sections give you an overview of how to backup your FOG system through writing services (<http://essaywritingservices.org/index.php>) . The following should include everything you should backup/save in order to be able to restore FOG. When backing up the directories below it is recommended that you use **cp -a** to ensure that all the rights are maintained.

As of version 0.14 a script is provided with FOG to make backups easier. The script is located at:

```
utils/FOGBackup/FOGBackup.sh
```

To use this script run:

```
./FOGBackup.sh [directory]
```

With this script you must pass an directory that exists to the script as an argument. This directory is where your backups will be stored. This script can be run as a cron job to make daily backups of your FOG data.

### Original Installation Tar File

You should save a copy of the original tar.gz file that was downloaded from FOG/sourceforge.

### Web Directory

The web directory is the directory that contains all the php pages for the FOG management portal. The only reason this directory really should be backed up is because it contains the **reports** directory which may contain custom reports, custom essay writing (<http://custom-essay-writing-service.org/index.php>) . We recommend that you save the entire web directory because in the future we may add new sections that may have custom, or user data.

### OPT Directory

The /opt/fog directory contains the directory that holds snapins, The /opt/fog directory should be backed up along with all its sub directories.

### Images Directory

This is the tough one, the images directory located at **/images**. This holds the partition images and it could be **VERY** large.

### MySQL Database

MySQL holds all the data for FOG, like all your host, image, printer, snapin and inventory information. You can backup your mysql data with the following command:

```
mysqldump --allow-keywords -x -v fog > fogbackup.sql
```



## Restoring FOG

Restoring a FOG installation requires essentially the opposite actions as taken above. This section assumes you backed your installation up manually. This section will assume that your backup is in /opt/fog\_backup. Also, you may need to be root for some of these actions.

First, go to your backup directory:

```
# cd /opt/fog_backup
# ls
fogopt fog.sql web
```

As you can see, I have named my /opt/fog into fogopt, and my /var/www/fog into web. I chose not to backup my /images directory due to some issues copying such large files.

### Web Directory

Restoring your web directory will take two steps. First, remove the current one, if it exists, then copy the backup over to the appropriate location.

```
# rm -rf /var/www/fog
# cp -a /opt/fog_backup/web /var/www/fog
```

### OPT Directory

Restoring the /opt directory is just about the same as the web directory above.

```
# rm -rf /opt/fog
# cp -a /opt/fog_backup/fogopt /opt/fog
```

### MySQL Database

In order to restore the database, you should first drop the current one (if it exists), then create a blank fog database, then import your backup.

```
# mysql -u root -p
Enter password:
mysql> DROP DATABASE fog;
mysql> CREATE DATABASE fog;
mysql> exit
# mysql -D fog -u root -p < fog.sql
```

That should do it!

## Advanced Installations

### Overview

This section gives a rough overview of how to perform advanced installations of FOG.

### Separate TFTP and DHCP Server

In this setup, the TFTP server and the DHCP server are hosted on a separate server. The TFTP server holds the PXE boot files including the Linux Kernel, boot file system image, and pxe config files. The DHCP server is the server that assigns the clients with IP addresses and network connection information.

In this setup we will have two servers:

- **Server A:** This is the 'Master' server which will host Apache, MySql, NFS and HTTP
- **Server B:** This server will host TFTP and DHCP

In our example, both of these servers need to have a fresh install of Fedora. They will both need static IP addresses, in our example we will use:

- **Server A:** 192.168.1.50
- **Server B:** 192.168.1.51

On both nodes, download the FOG installation package from:

[http://sourceforge.net/project/showfiles.php?group\\_id=201099](http://sourceforge.net/project/showfiles.php?group_id=201099)

On Server A install FOG, when you are prompted with:

```
Would you like to use the FOG server for dhcp service? [Y/n]
```

Select "n" to not start DHCP on that server.

After installation is complete navigate to:

```
http://localhost/fog
```

and install the FOG schema.

On server A go to:

```
System -> Administration -> Services
```

Uncheck and Stop the following Services:

- dhcpd (should already be stopped.)
- xinetd
- vsftpd

On Server B install FOG, but this time install the dhcp service.

On server B go to:

```
System -> Administration -> Services
```

Uncheck and Stop the following Services:

- FOGMulticastManager
- httpd
- mysqld

On server B open:

```
/var/www/html/fog/commons/config.php
```

Copy the value from **TFTP\_FTP\_PASSWORD**

Then open

```
/tftpbboot/pxelinux.cfg/default
```

Replace all instances of web=x.x.x.x/fog/ with the the ip address of Server A.

Now on Server A, open:

```
/var/www/html/fog/commons/config.php
```

Replaced the value from **TFTP\_FTP\_PASSWORD** on Server B.

To test your configuration, navigate to

```
http://192.168.1.50/fog
```

login as:

```
Username: fog
Password: password
```

Create a host and then attempt to create a task, if everything works correctly you should see a file created on Server B in the directory /tftpboot/pxeconfig.pxe/ name with the mac address of the host.

## Separate NFS Server

No Content yet.

## Other Advanced Topics

- Building a Custom Kernel
- Creating Custom FOG Service Modules
- Editing the ramdisk/init file

## Caveats and Other Tips

- Defrag the disk prior to imaging
- Run chkdsk prior to imaging
- Have at least 2gb free on the disk, or NTFSresize will fail.
- For importing hosts in a .csv file follow the format below: 1 line per host

```
"00:c0:4f:18:62:63","Hostname","1.1.1.1","Your description","XP/Vista","Image filename to use"
```

## Troubleshooting and Debugging

### Troubleshooting an image push to a client

To make this process easier, we are going to use a Windows XP image. Please also note that this process will wipe out whatever is currently present on the client computer. This tutorial assumes that your disk is /dev/sda1.

1. In the management portal, start a debug task for the client computer in question. Allow the client to boot and at the bash prompt type the following commands.
2. `mkdir /images`
3. `mount -o nolock x.x.x.x:/images /images` (where x.x.x.x is the server ip, you may try also `mount -t nfs -o nolock x.x.x.x:/images /images`)
4. `cd /images`
5. `dd if=/usr/local/fog/mbr/xp.mbr of=/dev/sda1 bs=512 count=1`
6. `fdisk /dev/sda` (No 1 at the end of the device name)
7. Press "d", then "Enter"
8. Press "w", then "Enter"
9. `fdisk /dev/sda`
10. Press "n", then "Enter"

11. Press "p", then "Enter"
12. Press "1", then "Enter"
13. Press "1", then "Enter"
14. Press "Enter"
15. Press "t", then "Enter"
16. Press "7", then "Enter"
17. Press "a", then "Enter"
18. Press "1", then "Enter"
19. Press "w", then "Enter"
20. partprobe
21. /usr/local/sbin/partimage restore /dev/sda1 /images/[imagename] -f3 -b
22. /usr/local/sbin/ntfsresize /dev/sda1 -f -b -P

## Troubleshooting an image upload

To make this process easier, we are going to use an Windows XP image. Please also note that this process will wipe out whatever is currently present on the client computer. This tutorial assumes that your disk is /dev/sda1.

1. In the management portal, start a debug task for the client computer in question. Allow the client to boot and at the bash prompt type the following commands.
2. mkdir /images
3. mount -o nolock x.x.x.x:/images/dev /images (where x.x.x.x is the server ip)
4. cd /images
5. dd if=/dev/sda of=/mbr.backup count=1 bs=512
6. /usr/local/sbin/ntfsresize -f -i -P /dev/sda1  
Look for *You might resize* you will need this number, so write it down. We will call this number *NTFSSize*.
7. Take NTFSSize and divide it by 1000
8. Now add 300000 to that number and write down as **N**
9. Now take NTFSSize again and multiply it by 1.1 and then round that to the nearest whole number and write it down as **F**
10. /usr/local/sbin/ntfsresize -f -n -s **Nk** /dev/sda1  
(where N is the value calculated above with a k after it.)
11. If the test above ends successfully then run:  
/usr/local/sbin/ntfsresize -f -s **Nk** /dev/sda1
12. fdisk /dev/sda
13. Press "d", then Enter
14. Press "w", then Enter
15. fdisk /dev/sda
16. Press "n", then Enter
17. Press "p", then Enter
18. Press "1", then Enter
19. Press "1", then Enter
20. Press "+**FK**", then Enter (where F is the value calculated above; K must be capital)
21. Press "t", then Enter
22. Press "7", then Enter
23. Press "a", then Enter
24. Press "1", then Enter
25. Press "w", then Enter
26. partprobe
27. /usr/local/sbin/partimage save /dev/sda1 /images/[somefile] --volume=9900000000 -z1 -o -d -f3 -b
28. dd if=/mbr.backup of=/dev/sda
29. Press "w", then Enter
30. partprobe
31. /usr/local/sbin/ntfsresize /dev/sda1 -f -b -P

## Troubleshooting Driver Issues

## Method 1

The first step to troubleshooting driver related issues with FOG clients is to download a live CD such as Fedora, or Ubuntu. Boot up the CD and see if the device that wasn't functional under FOG is working with the live CD.

If it is we just need to know the kernel driver name. This can be listed by issuing the following command:

```
lspci -k
```

The output will look something like this:

```
...
03:00.0 Ethernet controller: Broadcom Corporation NetXtreme BCM5754 Gigabit Ethernet PCI Express (rev 02)
    Kernel driver in use: tg3
    Kernel modules: tg3
...
```

In this case we know the driver required in the **tg3** driver for network. You can either submit a request to the forum/feature requests section of sourceforge for this driver to be included, or see the section on building a kernel.

## Method 2

Video Tutorial (<http://freeghost.sourceforge.net/videotutorials/kernel.swf.html>)

The first step to troubleshooting driver related issues with FOG clients is to download a live CD such as Fedora, or Ubuntu. Boot up the CD and see if the device that wasn't functional under FOG is working with the live CD. If it is then:

1. Go to <http://cateee.net/sources/lkddb/>
2. Download the latest version of `lkddb.list.bz2`
3. Go to <http://cateee.net/sources/autokernconf/>
4. Download the latest version of `autokernconf`
5. Copy both files to a directory and extract them
6. Copy `lkddb.list`, `kdetect.sh`, and `autokernconf.sh` to a common directory
7. `cd` to the common directory where the three files listed above are located.
8. run `./kdetect.sh`
9. run `./autokernconf.sh`
10. Then post the contents of the `auto.config` to the FOG Forum ([http://sourceforge.net/forum/?group\\_id=201099](http://sourceforge.net/forum/?group_id=201099)) , along with the model of computer or the device you are having issues with. It would also be helpful to post a link to the manufactures spec page for that device.
11. If a driver exists for this device we will attempt to post an updated kernel to the **kernel updates** section of the FOG Management portal.

## Bottleneck

To determine why a server is not performing as well as expected a program called `atop` is very useful. On Ubuntu `apt-get install atop`, this program will give you CPU, net card and disk information. Generally FOG does not require much CPU but requires great amount of disk and net card resources whilst imaging machines.

## About the Developers

### Chuck Syperski

Chuck Syperski is the lead software developer for FOG computer imaging solution. He is a software developer and network integration specialist for a public school district outside of Chicago, IL. Chuck Syperski has a Bachelor of Science in Computer Science from the University of Illinois. He specializes in Java, jsp, jsf, objective C, C, C++, C#, perl and php. You can contact Chuck Syperski directly via sourceforge as the following link:

<http://sourceforge.net/users/microleaks/>

## **Jian Zhang**

No content

## **Appendix C: Alternative Resources**

For Microsoft sysprep information, see this page: <http://vernalex.com/guides/sysprep/video.shtml>

FOG install HOWTO: <http://www.howtoforge.com/installing-fog-computer-imaging-solution-on-fedora8>

FOG sourceforge page: <http://freeghost.sf.net/>

## **Additional helpful information**

Helpful Mac How (<http://www.mac-how.net/>) articles. Everything about Mac OS.

Retrieved from "<http://www.fogproject.org/wiki/index.php?title=FOGUserGuide>"

---

- This page was last modified on 21 August 2010, at 03:35.
- Content is available under Public Domain.