



Blueprints

Setting up Windows XP guest using virt-manager







Blueprints

Setting up Windows XP guest using virt-manager

**Note**

Before using this information and the product it supports, read the information in “Notices” on page 31.

**Second Edition (March 2010)**

**© Copyright IBM Corporation 2009.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

## Contents

---

**Part 1. Setting up Windows XP guest  
using Virtual Machine manager  
(virt-manager) . . . . . 1**

---

**Part 2. Appendixes. . . . . 29**

**Notices . . . . . 31**  
Trademarks . . . . . 32



---

## Part 1. Setting up Windows XP guest using Virtual Machine manager (virt-manager)

These steps are intended to help a Linux developer who is unfamiliar with the Windows XP operating system and how to install it on a KVM module.

### About this task

These instructions assume that you have already set up a KVM module. If you have not, go to Quick Start Guide for installing and running KVM.


Follow these steps to set up a Windows XP guest in KVM using **virt-manager**.

### Procedure

1. Start **virt-manager** by running the following command:

```
# virt-manager
```

The Virtual Machine Manager window opens:



2. Click **New** to start a new guest installation. This opens the Virtual Machine Creation window as shown below:




3. Click Forward to start the assistant.
4. On the Virtual Machine Name dialog, enter a name for your virtual machine. In this example, the virtual machine is called **WinXP**. Click **Forward**.






5. On the Virtualization method dialog, select Fully Virtualized. The default CPU architecture is x86\_64 and Hypervisor is kvm. Click **Forward**.



6. On the Installation Method dialog, select your installation method. Choose from the following:
- **Local install media (ISO image or CDROM)** - The ISO can be downloaded from the site <http://msdn.microsoft.com/default.aspx>
  - **Network install tree (HTTP, FTP, NFS)** - A network repository like HTTP, FTP or NFS is used for starting the installation.
  - **Network boot (PXE)** - Installation is started by using a PXE boot. You also need to select your OS type and OS variant. In this example, the installation method chosen was Local install media, the OS type was Windows, and the OS variant is Microsoft Windows XP (x86).
- Click **Forward**.



7. Click **Browse** to specify the path to the ISO location. Then click **Forward**.



8. Assign storage for the guest. You can assign a Block device or a File (disk image). In this example, File storage was used. The default location of the disk image is `/var/lib/libvirt/images/` and the default size allocated is 15000 MB. You can specify any other customized location or a different size allocation. Click **Forward**.



9. On the Network dialog, you can choose Virtual network or Shared physical device. The Virtual network option uses Network Address Translation (NAT) to share the default network device with the virtualized guest. Use the virtual network option for wireless networks. The Shared physical device option uses a network bond to give the virtualized guest full access to a network device. In this example, Shared physical device was used. Specifically, br0 (Bridge to eth0). Click **Forward**.


Create a new virtual machine

## Network

Please indicate how you'd like to connect your new virtual machine to the host network.


☐ Virtual network

Network: default

 **Tip:** Choose this option if your host is disconnected, connected via wireless, or dynamically configured with NetworkManager.




☒ Shared physical device

Device: eth0 (Bridge br0)

 **Tip:** Choose this option if your host is statically connected to wired ethernet, to gain the ability to migrate the virtual system. (To share a physical device, configure it as a bridge.)

☐ Set fixed MAC address for your virtual machine?

MAC address:

10. Assign Memory and CPUs to the guest.

The default memory for the guest is 512 MB, and the default CPUs is 1. You can edit the resources as per your requirements.

Click **Forward**.

Create a new virtual machine

## Memory and CPU Allocation

**Memory:**

Please enter the memory configuration for this virtual machine. You can specify the maximum amount of memory the virtual machine should be able to use, and optionally a lower amount to grab on startup. Warning: setting virtual machine memory too high will cause out-of-memory errors in your host domain!

Total memory on host machine: 3.86 GB

Max memory (MB): 2000

Startup memory (MB): 1200

**CPUs:**

Please enter the number of virtual CPUs this virtual machine should start up with.

Logical host CPUs: 4

Maximum virtual CPUs: 16


Virtual CPUs: 2

**Tip:** For best performance, the number of virtual CPUs should be less than (or equal to) the number of physical CPUs on the host system.

Cancel Back Forward


11. On the final summary page, verify that you have all your setting correct for creating the guest. When you are satisfied, click **Finish**.






12. After you click **Finish**, the Windows XP installation dialog opens. Press **Enter** to begin the installation.







13. Accept the Windows XP Licensing Agreement by pressing F8.




14. On the partitioning screen, press **Enter** to install Windows on the unpartitioned space.




15. After the partition has been created, you can also customize the file system for the guest. Press Enter.




After pressing Enter, the formatting of the disk space starts.




After the disk formatting is completed, the system starts copying files.



After copying the files, the guest will reboot.




16. After rebooting, the guest will not be running. Click **Run** to restart it.




17. After the guest is running, the Windows XP installation begins.







18. On the Regional and Language options dialog, verify that information displayed is correct. You can change these settings by selecting **Customize** for Region and **Details** for Language. When you are satisfied, click **Next**.




19. Enter your name and your organization. Click **Next**.




20. Enter the Product Key and click **Next**. Generally the Product Key is shipped with the ISO.




21. Enter the password for the Administrator and click **Next**




22. Select the Date and Time Zone and press **Next**.



23. Set the Network Settings for the guest. You can choose Typical or Custom. Press **Next**.




24. After selecting your Networking settings, the installation proceeds until it is complete. The guest reboots. You can see the Windows guest in a Running state in the virt-manager.



The guest is running and ready to use.







---

## Part 2. Appendixes



---

## Notices

This information was developed for products and services offered in the U.S.A.

IBM® may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10504-1785  
U.S.A.

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:** INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation  
Dept. LRAS/Bldg. 903  
11501 Burnet Road  
Austin, TX 78758-3400  
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106-0032, Japan

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

---

## Trademarks

IBM, the IBM logo, and `ibm.com`<sup>®</sup> are trademarks or registered trademarks of International Business Machines Corporation in the United States, other countries, or both. If these and other IBM trademarked terms are marked on their first occurrence in this information with a trademark symbol (<sup>®</sup> and <sup>™</sup>), these symbols indicate U.S. registered or common law trademarks owned by IBM at the time this information was published. Such trademarks may also be registered or common law trademarks in other countries. A current list of IBM trademarks is available on the Web at Copyright and trademark information at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml)

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Java and all Java-based trademarks and logos are registered trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, or service names may be trademarks or service marks of others.





Printed in USA