

TELUS Component Library

ThemeProvider

Multi-Platform Component

```
<ThemeProvider>{/* themed UDS Base components*/}</ThemeProvider>
```

Introduction

```
import { ThemeProvider } from '@telus-uds/components-base'
```

[Follow the appropriate instructions](#) to add this component in to your app.

Guidance

! INFO

ThemeProvider is automatically included in BaseProvider. **You don't need to include ThemeProvider separately in your app if you are already using BaseProvider.**

ThemeProvider makes a UDS theme available in React context for UDS Base components to consume.

Theme switching

! INFO

coming soon!

Spacing scale

ThemeProvider exposes the (12 stop) spacing scale corresponding to the UDS theme passed via the `useSizingScale` hook

0 / 0px
1 / 4px
2 / 8px
3 / 16px
4 / 24px
5 / 32px
6 / 40px
7 / 48px
8 / 64px
9 / 72px
10 / 96px
11 / 120px

```
function SizingScale() {  
  const Scale = ({ index }) => {  
    const value = useSpacingScale(index)  
    return (  
      <div>  
        {index} / {value}px  
      </div>  
    )  
  }  
  
  return (  
    <div>  
      {Array.apply(null, Array(12)).map((_, i) => (  
        <Scale index={i} key={i} />  
      ))}  
    </div>  
  )  
}
```

Props

Name	Type	Platform	Default	Description
themeOptions	shape	standard	{}	An object containing options allowing to customize the theming

Name	Type	Platform	Default	Description
				<p>experience: -</p> <p><code>`forceAbsoluteFontSize`</code>: available on web only; when set to true, allows using absolute font sizing (in pixels, doesn't scale) instead of the relative sizing (in <code>`rem`</code>, scales dependent on the browser settings)</p> <p><code>`contentMaxWidth`</code>: all configuration of the container max width to be used in components such as Footnote and Notification avoid content to stretch width more than the page width - <code>`forceZIndex`</code>: available on web only, when set to false, sets <code>zIndex</code> of <code>`View`</code> to be <code>`auto`</code> and when true, sets <code>zIndex</code> to <code>`0`</code> (the default from <code>`react-native-web`</code>) -</p> <p><code>`enableHelmetSSR`</code>: on Web SSR, allows React Helmet to run during server-side rendering. This should be disabled unless web app has been specifically configured to stop React Helmet accumulating instances (which may cause a memory leak). See React Helmet's docs: https://github.com/nfl/react-helmet</p>

Name	Type	Platform	Default	Description
children*.	node	standard		
defaultTheme*.	shape	standard		