

NAME

startx – initialize an X session

SYNOPSIS

startx [[*client*] *options* ...] [**--** [*server*] [*display*] *options* ...]

DESCRIPTION

The **startx** script is a front end to **xinit**(1) that provides a somewhat nicer user interface for running a single session of the X Window System. It is often run with no arguments.

Arguments immediately following the *startx* command are used to start a client in the same manner as **xinit**(1). The special argument **--** marks the end of client arguments and the beginning of server options. It may be convenient to specify server options with *startx* to change them on a per-session basis. Some examples of specifying server arguments follow; consult the manual page for your X server to determine which arguments are legal.

startx **--** **--depth** 16

startx **--** **--dpi** 100

startx **--** **--layout** Multihead

Note that in the Debian system, what many people traditionally put in the *.xinitrc* file should go in *.xsession* instead; this permits the same X environment to be presented whether *startx*, *xDM*, or *xinit* is used to start the X session. All discussion of the *.xinitrc* file in the *xinit*(1) manual page applies equally well to *.xsession*. Keep in mind that *.xinitrc* is used only by *xinit*(1) and completely ignored by *xDM*(1).

To determine the client to run, **startx** looks for the following files, in order:

\$(HOME)/.startxrc

/usr/lib/x86_64-linux-gnu/sys.startxrc

\$(HOME)/.xinitrc

/etc/X11/xinit/xinitrc

If command line client options are given, they override this behavior and revert to the **xinit**(1) behavior. To determine the server to run, **startx** first looks for a file called *.xserverrc* in the user's home directory. If that is not found, it uses the file *xserverrc* in the *xinit* library directory. If command line server options are given, they override this behavior and revert to the **xinit**(1) behavior. Users rarely need to provide a *.xserverrc* file. See the **xinit**(1) manual page for more details on the arguments.

The system-wide *xinitrc* and *xserverrc* files are found in the */etc/X11/xinit* directory.

ENVIRONMENT VARIABLES

DISPLAY	This variable gets set to the name of the display to which clients should connect. Note that this gets <i>set</i> , not <i>read</i> .
XAUTHORITY	This variable, if not already defined, gets set to <i>\$(HOME)/.Xauthority</i> . This is to prevent the X server, if not given the <i>--auth</i> argument, from automatically setting up insecure host-based authentication for the local host. See the Xserver (1) and <i>Xsecurity</i> (7) manual pages for more information on X client/server authentication.

FILES

<i>\$(HOME)/.xinitrc</i>	Client to run. Typically a shell script which runs many programs in the background.
<i>\$(HOME)/.xserverrc</i>	Server to run. The default is <i>X</i> .
<i>/etc/X11/xinit/xinitrc</i>	Client to run if the user has no <i>.xinitrc</i> file.
<i>/etc/X11/xinit/xserverrc</i>	Server to run if the user has no <i>.xserverrc</i> file.

SEE ALSO

xinit(1), **X(7)**, **Xserver(1)**, **Xorg(1)**, **xorg.conf(5)**