

NAME

mokutil – utility to manipulate machine owner keys

SYNOPSIS

```

mokutil [--list-enrolled | -l]
    ([--mokx | -X])
mokutil [--list-new | -N]
    ([--mokx | -X])
mokutil [--list-delete | -D]
    ([--mokx | -X])
mokutil [--import keylist | -i keylist]
    ([--hash-file hashfile | -f hashfile] | [--root-pw | -P] |
    [--simple-hash | -s] | [--mokx | -X])
mokutil [--delete keylist | -d keylist]
    ([--hash-file hashfile | -f hashfile] | [--root-pw | -P] |
    [--simple-hash | -s] | [--mokx | -X])
mokutil [--revoke-import]
    ([--mokx | -X])
mokutil [--revoke-delete]
    ([--mokx | -X])
mokutil [--export | -x]
mokutil [--password | -p]
    ([--hash-file hashfile | -f hashfile] | [--root-pw | -P] |
    [--simple-hash | -s])
mokutil [--clear-password | -c]
    ([--simple-hash | -s])
mokutil [--disable-validation]
mokutil [--enable-validation]
mokutil [--sb-state]
mokutil [--test-key keyfile | -t keyfile]
    ([--mokx | -X])
mokutil [--reset]
    ([--hash-file hashfile | -f hashfile] | [--root-pw | -P] |
    [--simple-hash | -s] | [--mok | -X])
mokutil [--generate-hash=password | -gpassword]
mokutil [--ignore-db]
mokutil [--use-db]
mokutil [--import-hash hash]
    ([--hash-file hashfile | -f hashfile] | [--root-pw | -P] |
    [--simple-hash | -s] | [--mokx | -X])
mokutil [--delete-hash hash]
    ([--hash-file hashfile | -f hashfile] | [--root-pw | -P] |
    [--simple-hash | -s] | [--mokx | -X])
mokutil [--set-verbosity (true | false)]
mokutil [--pk]
mokutil [--kek]
mokutil [--db]
mokutil [--dbx]

```

DESCRIPTION

mokutil is a tool to import or delete the machines owner keys (MOK) stored in the database of shim.

OPTIONS

- l, --list-enrolled**
List the keys the already stored in the database
- N, --list-new**
List the keys to be enrolled
- D, --list-delete**
List the keys to be deleted
- i, --import**
Collect the followed files and form a enrolling request to shim. The files must be in DER format.
- d, --delete**
Collect the followed files and form a deleting request to shim. The files must be in DER format.
- revoke-import**
Revoke the current import request (MokNew)
- revoke-delete**
Revoke the current delete request (MokDel)
- x, --export**
Export the keys stored in MokListRT
- p, --password**
Setup the password for MokManager (MokPW)
- c, --clear-password**
Clear the password for MokManager (MokPW)
- disable-validation**
Disable the validation process in shim
- enrolled-validation**
Enable the validation process in shim
- sb-state**
Show SecureBoot State
- t, --test-key**
Test if the key is enrolled or not
- reset** Reset MOK list
- generate-hash**
Generate the password hash
- hash-file**
Use the password hash from a specific file
- P, --root-pw**
Use the root password hash from /etc/shadow
- s, --simple-hash**
Use the old SHA256 password hash method to hash the password
Note: --root-pw invalidates --simple-hash
- ignore-db**
Tell shim to not use the keys in db to verify EFI images
- use-db**
Tell shim to use the keys in db to verify EFI images (default)
- X, --mokx**
Manipulate the MOK blacklist (MOKX) instead of the MOK list

-i, --import-hash

Create an enrolling request for the hash of a key in DER format. Note that this is not the password hash.

-d, --delete-hash

Create an deleting request for the hash of a key in DER format. Note that this is not the password hash.

--set-verbosity

Set the SHIM_VERBOSE to make shim more or less verbose

--pk List the keys in the public Platform Key (PK)

--kek List the keys in the Key Exchange Key Signature database (KEK)

--db List the keys in the secure boot signature store (db)

--dbx List the keys in the secure boot blacklist signature store (dbx)