

NAME

gslp – Format and print text using ghostscript
gsbj – Format and print text for BubbleJet printer using ghostscript
gsdj – Format and print text for DeskJet printer using ghostscript
gsdj500 – Format and print text for DeskJet 500 BubbleJet using ghostscript
gslj – Format and print text for LaserJet printer using ghostscript

SYNOPSIS

gslp **-12BclqRr** **-b**<header> **-f** **-F**<hfont> **-L**<lines> **-p**<outfile> **-T**<n>
--add-to-space <units> **--add-to-width** <units> **--columns** <n> **--detect** **--first-page** <n>
--kern <file.afm> **--last-page** <n> **--(heading|footing)–(left|center|right)** <string> **--margin–(top|bottom|left|right)** <inches> **--no-eject–(file|formfeed)** **--spacing** <n> [gs options] [files]
gsbj [options] [files]
gsdj [options] [files]
gsdj500 [options] [files]
gslj [options] [files]

DESCRIPTION

This utility provides functionality approximately equivalent to the Unix **enscript**(1) program. It prints plain text files using a single font. It currently handles tabs and formfeeds, but not backspaces. It will line-wrap when using fixed-pitch fonts. It will also do kerning and width adjustment.

The default device (**-sDEVICE=**) and resolution (**-r**) are as follows:

gslp	epson	180
gsbj	bj10e	180
gsdj	deskjet	300
gsdj500	djet500	300
gslj	laserjet	300

By default the current date is formatted as the center header.

OPTIONS

Standard switches implemented:

-12BclqRr **-b**<header> **-f** **-F**<hfont> **-L**<lines> **-p**<outfile>

Sun switches implemented:

-T<n> set tab width

Switches ignored:

-GghKkmow **-#** **-C** **-d** **-J** **-n** **-P** **-S** **-s** **-t** **-v**

Switches added:

--add-to-space <units>
 add the given number of 1/72" units to the width of each space (may be negative)
--add-to-width <units>
 add the given number of 1/72" units to the width of each character (may be negative)
--columns <n>
 print in <n> columns
--detect treat the file as PostScript if it starts with %!
--first-page <n>
 start printing at page <n>
--kern <file.afm>
 kern using information from the given .AFM file
--last-page <n>
 stop printing after page <n>

--(heading|footing)-(left|center|right) <string>
set the heading/footing fields; use -B first to clear

--margin-(top|bottom|left|right) <inches>
set a margin

--no-eject-(file|formfeed)
end-of-file/FF only starts a new column, not a new sheet

--spacing <n>
use double (n=2), triple (n=3), etc. spacing

Also, the string %% in a heading or footing is replaced with the page #.

SEE ALSO

gs(1)

VERSION

This document was last revised for Ghostscript version 9.55.0.

AUTHOR

Artifex Software, Inc. are the primary maintainers of Ghostscript. This manpage by George Ferguson.