



In this chapter, I will explain how you can easily define and use ISPF panels. To control applications panels are suited much better than using the simple queries SAY and PULL. Therefore, if you want to create elegant applications in ISPF you should already dominate the creation and use of ISPF panels. The ISPF provides very simple methods and tools to create screens and to use these masks in programs. In ISPF, screens are referred consistently to as panels. There are two ways to create panels:

- ## 10.1 THE DYNAMIC TAG LANGUAGE (DTL)

Why the Dialog Tag Language (DTL)?

Markup tags are easy to use. Because tag names are short and relate directly to the structure of the dialog elements, they are also easy to remember.

DTL lends flexibility to application development. Panels can be quickly changed without your having to tediously line up text and fields. This gives you greater control over application development and updates.

DTL provides consistency when many programmers are working on the same application, or when programmers who are new to your company must update existing applications. Since each programmer is using the same tags, only minor adjustments may be needed to achieve complete uniformity.

DTL techniques improve the way in which interactive programs, like ISPF applications, are developed. The language concentrates on the role of the various elements and their interrelationships, and ISPF takes care of their form and appearance at run time.

DTL also enforces some formatting rules defined by the Systems Application Architecture Common User Access (CUA), so you do not have to be familiar with all of the CUA formatting rules. Therefore, the CUA skills required by programmers who are developing CUA-conforming applications are significantly reduced.*

DTL enables National Language Support (NLS) and the conversion utility provides NLS translations for certain key words.

In other words, if you are looking for an application development and maintenance system that is sophisticated, flexible, and easy to use, that's DTL.

If you come to the conclusion that the DTL is the right tool for you to develop

1/11

10.2 PANEL TYPES IN ISPF

The following table shows which panel types in ISPF exist:

Type	Description
Standard panels	Standard panels in ISPF normally have a width of 80 characters and consist of up to 43 lines on a screen. When they are displayed, the currently displayed panel is completely replaced.
HELP panels	Help panels will be formed using certain instructions in the panel definition. They can contain any number of rows and they have their own scrolling mechanism.
POPUP panels	The dimensions of the pop-up panels are determined in the panel definition. When you call them, they will be embedded in the currently displayed panel. The rest of the underlying panel remains visible. POP Up panels can be moved while the display on the screen using the cursor. HELP panels are very often defined as POP UP panels.

10.3 DEFINITION OF PANELS

In the following chapters, I will explain the key elements of the panel definition using the **Panel Definition Statements**. I will discuss only those definition items that I constantly use when I develop panels. The panel definition statements are described in the brochure **ISPF Dialog Developer's Guide and Reference**.

10.3.1 The structure of a panel

A panel definition generally consists of three elements:

- The attribute characters
- The text fields
- The data fields

The attribute characters

Attribute characters always occupy only **ones** character (byte). They determine the characteristics of the field behind them up to the next attribute character. The attribute character can consist of any characters. In practice, only special characters are used as an attribute character.



Attention:

A sign that is defined as an attribute character can be used throughout the panel definition text only as an attribute character. In other words, when a character below the)ATTR statement in the)BODY section of the panel definition exists, it will be used always as an attribute character, irrespective of whether this is intended or not. Therefore, if you for example want to use a colon (:) in the panel text, you cannot this define as an attribute character.

How to specify the attribute characters; see [section 10.3.3.1](#) The Attribute section starting on page 193.

The text fields

They contain solid, non-rewritable texts. Text fields can be colored using attribute characters. How to specify the text fields; see [section 10.3.3.2](#) The)BODY section on page 195.

Data fields

There are two types of data fields:

- Input fields. These are defined for entering data. Input fields can also be used for output.
- Output Fields. These fields are only defined for output of data. Output fields cannot be used for input.

How to specify the data fields; see [section 10.3.3.2](#) The)BODY section on page 195.

The attribute character in front of the field defines the type of a data field.

Find answers on the fly, or master something new. Subscribe today. [See pricing options.](#)

ISPF panels are typically created using the ISPF editor. In the edit sessions to create ISPF panels it is essential to ensure that **NUMBER OFF** is set. If panel definition lines include line numbers on the right, the display of this panel ends with an error. Panels will be executed as they were created. A compiler or other conversion process is not necessary. (Except DTL panels. However, we do not want to discuss this here).

ISPF panels must be stored in a PDS/PDSE, which must be assigned during the execution of the panels under the DD name **ISPLIB**. Panels can be displayed using the ISPF SELECT, DISPLAY or TBDISPL service. When called by the **TBDISPL** service, the panel must contain a **)MODEL** section.

ISPF panels should have the following basic structure:

- Line 1: Panel ID, Title, Short message area
- Line 2: A command / option field and the scroll definition

Panel ID	Title	Short Message
Command/Option		Scroll

The remaining lines can be designed as desired. ISPF short messages are always displayed at the end of the first line from right to left in their current length. If necessary, parts of the title line are truncated on the right. Long messages will, if this is defined in the **ISPF Settings menu**, always be displayed at the bottom of the panel in a frame. The **)BODY** section defines the panel structure.

10.3.3 The panel definition sections

A panel definition consists of several departments, the **sections**. Each section is intended for a very specific purpose. In the table below, I listed those sections that we want to deal with in this book. Each section starts at column one with a **)** (right parentheses) character that is followed by a keyword identifying the type of section.

Table 10.1: Description of panel sections

Section	Description
)ATTR	The attr section defines the attribute characters for the fields of the panel.
)BODY	The body section defines the panel layout.
)MODEL	The model section defines a structure for the representation of variables of an ISPF table.
)INIT	The init section will go through before the panel is displayed. Here, initial values can be set.
)REINIT	The reinit section will go through when the panel is repeatedly displayed.
)PROC	The proc section will go through when the panel display is exited by a command. Here, the processing of the input values is performed. Typically, the plausibility checks of the input values are performed here.
)END	The end statement ends the panel definition. All lines behind this statement will be ignored.

10.3.3.1 The Attribute section

The **)ATTR** line is usually the first line of a panel definition. However, it is not always necessary. This is the case when the standard character attribute for this panel are sufficient.

The default attribute characters are as follows:

% TYPE (TEXT) INTENS (HIGH)
+ TYPE (TEXT) INTENS (LOW)
_ TYPE (INPUT) INTENS (HIGH)

These default attribute characters can be replaced by other characters using the

Find answers on the fly, or master something new. Subscribe today. [See pricing options.](#)

By defining this ATTR options, the following standard attribute characters are active in this panel:

The attribute characters can be defined in any number and any character in the `)ATTR` section. The following panel definition shows this:

Program 10.1: Panel definition of panel SLEP1

Panel ID	Title	Short Message
Command/Option		Scroll

i **Note:**

If the)ATTR statement is needed in a panel, this must always be the first line. Comment lines can begin first after the)ATTR line.

The table below comes from the brochure **ISPF Dialog Developer's Guide and Reference**. It contains all possible definitions for the attribute characters. The most important type definitions for everyday use are greyed. I will refrain from giving a complete description of all options. This is explained in the before mentioned booklet and occupies circa 30 pages. I recommend you read this when needed. Moreover, the options used in the above type commands are self-explanatory.

Table 10.2:)ATTR definitions list

```

ATTACH
[ AREA (dynamic) [ EXTEND (on/off) ] [ SCROLL (on/off) ]
RETURN (on/off) ]
[ DATA (data-addr=code) ]
[ AREA (static) [ EXTEND (on/off) ] ]
[ AREA (static) [ EXTEND (on/off) ] ]
[ ATTR (on/off) ]
[ CANCEL (on/off) ]
[ CEXACT (on/off) ]
[ COLOR (value) ]
[ COMBOK (on/off) ]
[ COMBOK (on/off) name ]
[ CUCUR (value) ]
[ DCLSTR (on/off) name ]
[ DEPTH (1) ]
[ FORMAT (EXACT) [ EXACT KEY ] ]
[ RESIZE (value) ]
[ ROL (on/off) ]
[ EXTENTS (LOW|LOW|HIGH) ]
[ EXTENT (LEFT|RIGHT|BOTH) ]
[ LISTEN (on/off) ]
[ DONTIME (on/off) ]
[ DONTIME (on/off) name ]
[ OUTLINE (on/off) ]
[ OUTLINE (1) [ 2] [ 3] [ 7] [ BOX|NONE ] ]
[ PAD (char|BELL|SPACE) ]
[ PAD (char|BELL|SPACE) ]
[ PAIR (on/off) ]
[ PASCAL (on/off) ]
[ REP (char) ]
[ REP (on/off) ]
[ REP (value) ]
[ UNPAIR (on/off) ]
[ UNPAIR (on/off) ]

```

10.3.3.2 The)BODY section

The appearance of the panel is determined in the `!BODY` section. The panel appears later as it was designed in this section. The following coding contains all possible options:

Coding 10.1:)BODY section definitions

```

)BODY
(FANA)
(WINDOW (width,depth) )
(CMD (field name))
(SMS (field name))
(LMS (field name))
(ASIS)
(WIDTH (width))
(EXPAND (xy))
(DEFAULT (def1def2def3))
(FORMAT (BASIC|DSC|MX))
(OUTLINE (L|R|O) (UT|BOX|NONE))

```

All information must be on the)BODY line. The greyed options are frequently used. I will explain these here.

)BODY WINDOW (50.20)

This statement defines a pop up panel which is 50 columns **wide** and 20 rows **depth**. It is important to ensure that the in the)BODY section defined rows and columns fit the available framework.

) BODY EXPAND (\$\$)

With this statement, the expansion characters are determined. With these characters, you can fill text lines dynamically with padding characters. See the following example:

Example:

The panel definition of panel SLEP1 contains the following code:

```
>BODY expand ($$)
(ZYSTID *$-# Table display of recently edited data sets $-$
%COMMAND ----> CMD $% $ SCROLL ----> ZSCR:
+dynpan=?#
+sort=?#Date+orthName=?#Max DSNs=?#
+sysdate (sysdate)
+Insert control for edited data sets ---->All+orChange=?#
+Current DSN in edit Allwsp with PPI for all fields FDate Time
```

Find answers on the fly, or master something new. Subscribe today. [See pricing options.](#)

```
ISPF 3 ----- Table display of recently edited data sets Row 1 of 88
COMMAND ---->
Dynparm YES-VIO          Compile state of SLE
Ext. Data set M-Data D Max DMB: 09      NOT COMPILED
Insert control for edited data sets ----- All or Change: All
C Recent DMB in edit  Help with PPI for all fields      Date      Time
-----
```

The first and the last line are shown expanded with the expand character – (hyphen).

i Remark:

The expansion characters must be unique (just like the attribute characters) within the panel definition. Therefore, this character can only be use for the definition of dynamic expanding.

10.3.3.3 The)INIT section

In the)INIT section all measures can be taken that are necessary prior to the display of the panel. Such measures may include:

- Fill variables with initial values.
- Definition of the Z variables using the .ZVARS statement.
- Define the cursor position for the initial display of the panel.
- Specifying the general help panel. This panel appears when the PF1 key is pressed.

Coding 10.2:)INIT section example

```
)INIT
  .ascmd  = ' '
  .ZVARS  = '{(colbars recfm dirblk lrecl blksize #
             prim sec units dsntp)'}
  .cursor = newdsn
  .CHPGOS = 2
  .help   = SSCPT00
  if {units = TRACE}
    units = TRACE$
  if {units = CYLINDER}
    units = CYLINDER$
)REINIT
```

i Note:

In the above .ZVARS definition can be seen how continuation lines are formed in panel definitions by the plus sign.

10.3.3.4 The)PROC section

The)PROC section is run through when the input is terminated by pressing the ENTER or a PF key. In the)PROC section normally plausibility checks and some processing of the entered values are performed. For these purposes, a number of commands are available that are used for the following tasks.

- | | |
|-------------------------|--|
| variable = value | → Assignments |
| IF and ELSE | → Logical operations |
| VER | → Verify |
| VOET / VPUT | → Write and read of ISPF profile variables |

When assignments are performed, the following functions are often used for the determination of the result:

- | | |
|--------------|--------------------------|
| TRUNC | → Cut and build the rest |
| TRANS | → Translate |
| PFK | → PF keys |

If and ELSE:

Because no THEN is available, another rule must exist how commands are defined when an IF statement as **true** ends. This rule is very simple:

i Rule:

If an IF query is recognized as true, then all the instructions in the following lines are executed that are indented at least one column **to the right**.

Again, it is beyond the scope of this book to discuss the above listed statements and functions in detail. To explain the design of an ISPF screen, I will use the screen SSCPP01. The SSCPP01 screen is one screen of the SMART ISPF utilities. The SSC program calls it. The panel has a complex format and is therefore a good example to explain the functionality of an ISPF screen structure:

Coding 10.3: SSCPP01 – Panel definition example

Explanations for some lines in this panel definition:

Lines	Explanation
57+58:	If the variable LRC was set greater than zero in the calling procedure SSC, then the special variable .RESP will be filled with the text END. This means that the PANRC variable is set to 1 at the end in row 11. When after returning from the panel the variable PANRC is 1, the procedure SSC will be exited.
59:	If the special variable .RESP contains the text

Find answers on the fly, or master something new. Subscribe today. [See pricing options.](#)

60–68:	When the function code is EX, then only the expiration date of the data set is changed. In these lines, the date variables that the function DSNINFO has delivered will be checked and if necessary updated. Due to the statement go to out: in line 068 the execution of the panel continues at line 109.
69:	The variable NEWDSN will be verified. NB means NEWDSN must not be blank. DSNNAME means that the variable must contain a valid DSN. If one of these conditions is not met, then the message CR011A is displayed on the screen.
70:	The variable FCHARS will be verified. FCHARS represents function characters. NB means FCHARS must not be blank. LIST means that the variable must contain only one of the values contained in the LIST option within the comma-separated text string. If one of these conditions is not met, then the message CR010A will be displayed.
71+72:	The variable FCHARS contains always two characters. The first character of FCHARS is extracted into the variable FCHAR1 using the TRUNC function and the second character is extracted in the variable FCHAR2 using the .TRAIL function.
73	If the variable FCHAR1 does not contain C, then no copying operation will be performed. In this case, the statements until the line 108 is reached will be executed.
79–81:	Here the functions TRANS and TRUNC are combined. This has the following meaning: With TRUNC the first character of the variable UNITS will be extracted. Then the word following the comma is placed in the UNITS variable with TRANS. This means the full names are set by the TRANS function. The advantage of this method is that you always have to enter only the first letter of CYLINDERS, TRACKS or BLOCK at the input. When the content of the variable UNITS does not begin with one of the letters given in the list, the message CR018A will be displayed and the program will be exited

The commands after line 81 contain further examinations and assignments. I think that the explanations of statements, which I made up to line 081 are sufficient as a guide to understand the other instructions.

10.3.4 Variables in panel definitions

Behind every attribute character for an input or output field a variable must be named. The variable name can consist of up to eight alphanumeric characters. Everywhere in the panel definition, where only a variable name can stand, no ampersand must precede the variable name. For example, in the .ZVARS statement.

Rule:
All variables in the panel definition and in the REXX program, which the panel displays, are known mutually in both elements. If variables are defined in a REXX procedure which are also used in screen definitions, it must be ensured that they are not longer than 8 characters.

The Z variables

Why are Z variables needed?

If a data field in a panel is shorter than the corresponding variable name, then the variable name cannot be written into the data field in the panel. In order to overcome this handicap, the so-called Z-variables were introduced. This works like this: Whenever behind an attribute character for an input or output field only a Z stands, the variable used in this field will be extracted from the corresponding variable name in the allocation of Z variables in the .ZVARS statement and

Find answers on the fly, or master something new. Subscribe today. See pricing options.

1 **Definition:**
The .ZVARS control variable can be set in the initialization section to a list of variable names that correspond to Z place-holders in the body and/or model lines.

Example:

The following excerpt from the panel [Coding 10.3: SSCPP01 – Panel definition](#) example on page 198 shows the allocation of the Z variables in the .ZVARS statement to the panel locations.

```
+ Dynpan -#E +SysFlex -#sysplex+Sysid -#sysid +Bch -#sysnode
+ Model -#oldsm +Compile state of SSC
+ New -#newsm +Sysdate +Sysatime
+ PRCY -#E <- NO TO YES BA BO BE CO CB EX + (see Help with PF1)
+ RECFM -#E + Reference Date -#sdrdate + Creation Date -#sdcdate
+ DIR -#E + Alloc. Dir. Blks -#adirlbk + Creator -#rcrator
+ LRECL -#E + allocated Trk/Cyl -#lrecl + Number of Mem -#memors
+ BLKSIZE -#E + Blocks / Track -#blksttr +Used Dir. Blks -#udirlbk
+ PRIM -#E +Data -#rdued +Space Used -#sued
+ SEC -#E +DSORG -#dsorg + Unit Type -#unit
+ UNITS -#E + Ext. all/used -#extenta +Compressed -#dsesq
+ DSNTYPE -#E + Trks for Dir -#dirltr+Tracks used for directory
+ VOLSER -#vol $role
+STORCLAS -#storclas+ DATACLAS -#dataclas+ MNTCLAS -#mntcl
+ CMC -#cmr $ TDS+ use CMC.DDS+ do not use CMC
+Exp.Date -#exdate $prmo=FFFF/MM/DD+ Blank means ***NONE***
+
% MSG1-#msgivl1
% MSG2-#msgivl2
% REASON-#rcr +rcrtext
% ENQS-#enqs
+\\-\\*Yellow fields are input fields.+\\-\\
)INIT
ssend - ' '
.zvars - ' (dynpan fchars recfm dirblk lrecl blksize +
prim sec units dsntp) '
```

As you can see, 10 variable names are defined in the .ZVARS statement and 10 Z fields are defined in the panel. By the way, you can also address such variables as Z variables which name would not be too long for a direct placement (e.g. PRIM, SEC, UNITS).

4 **Attention:**
When you insert or remove Z variables during the development of a panel, it is essential to adapt the .ZVARS statement accordingly.

10.3.5 Panel processing

ISPF provides multiple services to call up panels:

- The DISPLAY service
- The SELECT service
- The TBDISPL service

10.3.5.1 The DISPLAY Service

The DISPLAY service calls up a panel. It may be indeed some options given. However, these are largely theoretical.

Example 1: Call up a standard panel

The following coding shows a part of the program SSC of the SMART ISPF utilities. The SSC processing starts with the display of the main panel SSCPP01.

```
290 /*****
291 /* Do loop to perform main procedure. */
292 /* Display panel and read it in with data. */
293 /* Perform processing. */
294 *****/
295 do ipanel = 1
296 panrc = 0 /* panel return code for exit control */
297 lrc = 0 /* exit only with PF3 in panel SSCPP01, please check on */
298 *DISPLAY PANEL(SSCPP01)
299 if rc > 9 then do
300 zdlmsg = left('Error at call to panel SSCPP01-3, RC='rc,80)
301 if testin <> 'TERMIN' then zdlmsg = zdlmsg ztrim
302 *SETMSG MSG(ISRZ001)
303 exit
304 end
305 if panrc = 1 then leave ipanel
```

You can also see how the processing of the program is ended. When in panel SSCPP01 the PF3 key is pressed, then the variable PANRC is set to 1. At return from the panel display the IPANEL loop is left and the program exits (statement line 305).

Example 2: Display of a POP UP panel

When the program SSC copies a data set and records would be truncated, then a POP UP panel is issued which displays a warning and the operator can confirm the truncation and continue or exit the processing.

```
if fchar2 = '0' then do
if lrecl < syslrecl then do
oldrecl = syslrecl /* these are used in panel */
newrecl = lrecl /* SSCPP02 */
*ADDEPOP*
*DISPLAY PANEL(SSCPP02)*
*EMMPOP*
if conkt <> 'Y' then do
zdlmsg = 'You do not approve shortening of data',
'records. Copy is not performed!'
*SETMSG MSG(ISRZ001)*
iterate ipanel
end
end
end
```

Find answers on the fly, or master something new. Subscribe today. [See pricing options.](#)

i **Tip:**

You can use the cursor to move a pop-up panel within the totally available display to another position. Proceed as follows: Place the cursor to a point on the frame of the pop up panel and then press ENTER. Then the text **Window move pending** appears in the upper right corner of the screen. If you now move the cursor to any position in the screen and press ENTER, the entire pop up panel will be moved to the new position. Using this method, you can make invisible parts of the surrounding panel visible again.

The SELECT service can also be used to call up panels. These panels must have a special structure. They are normally used to start an application. One of the typical panels of this type is the panel to display the ISPF **Primary Option Menu**. Its name is normally `ISR@PRIM`. This panel has been created with the ISPF Dynamic TAG language. Therefore, I will not discuss the panel here.

The TBDISPL service not only calls the panel in question; but also the content of the underlying ISPF table will be displayed. See [section 10.3.5.1](#) The DISPLAY Service on page 202 and the [section 10.3.5.3](#) The TBDISPL service on page 204.

There are four types of help panels:

- The general help panel for a screen.
- Help panels, which are assigned to a field in the screen
- Full screen help panels.
- POP UP help panels.

Each screen definition may contain an entry for the display of a so called general help screen. The general help panel must be defined in the)INIT section. The general help screen is called when the PF1 key is pressed and the cursor is at a location of the screen for which no specific help panel is defined.

For each data field in a panel a specific help panel can be defined. Such a panel is called, when the cursor is at any position within the data field in JHELP and PF1 is pressed. Field assigned help panels must be defined in the JHELP section. See lines 114 to 138 of the [Coding 10.3](#): SSCPP01 – Panel definition example on page 198.

As the name suggests, these panels replace the entire screen when they are displayed. This type is used the most for general help panels.

This type of panels is mostly used for field assigned help panels. See [section 10.2](#)
Panel types in ISPF on page 190.

The basic structure of a help panel looks like this:

Program 10.2: HELPMASK – Help panel template

[illegible]

To define help panels the grayed lines are needed. I always use this template when I need to create a new help panel. The general help panel is entered in the **JINIT** section of the panel definition. Please note that help panels specified in the **JINIT** section act as general help panels. They appear when PF1 is pressed and the cursor stands at any position in the panel and not in a field for which an own help panel exists.

```
help = name
```

Table display panels are used to display and edit ISPF tables. ISPF tables are two-dimensional tables that are created by using ISPF table services. These services are also used for the data maintenance of the tables. A table display panel contains a **JMODEL** statement in which those variables from the ISPF table are defined which want to be displayed with this panel.

The panel SLEP1 is a typical table display panel. The SMART ISPF utility program SLE uses it:

[illegible]

Excerpt from macro #IMACRO2:

Excerpt from macro #IMACRO2 where the table \$SLETAB is updated respectively created and updated.

```

.....
/* Insert the name of the edited data set into table $SETTAB */
insert into $SETTAB
if $memco >> "" then dm = $memn * ($memco) * /* A member was edited */
else dm = $memn /* A sequential data set was edited */
address $ISPEXEC
%VGET ($SETSID) $MEMK=
%tabname = '$SETTAB'
%TROVEF %tabname= LIBRARY ($ISPTAB) WRITE SHARE
openco = 10
FUNCTION = "", DATE = date("0"), TIME = time();
select
when openco < 0 then do /* Table $SETTAB exists, update it */
%TROVEF %tabname= $MEMK
%TROVEF %tabname= FIELDS (DATE,C,D,TIME,C,D)
%TCLOSE %tabname= LIBRARY ($ISPTAB) REPLYLOOP PAD(100)
end
when openco = 0 then do /* Table $SETTAB does not exist. Create it */
%TCREATE %tabname= KEY (DM) NAMES (FUNCTION,DATE,TIME)
%TRAO %tabname= $MEMK
%TCLOSE %tabname= LIBRARY ($ISPTAB) REPLYLOOP PAD(100)
end
when openco > 0 then do
$editmg = $memns * %terla
$SETMSG MSG ($SETID) *
end
otherwise nop
end /* select */
address $ISDDI1
$DSPINE END BRST*
$BUILTIN END

```

Excerpt from program SLE:

The following excerpt from program SLE shows the command, that displays the panel SLEP1 together with the contents of the table \$\$LETAB.

```

/*-----*/
/* Display table */
/*-----*/
*BTOP      *tabname
*TDISPL    *tabname* PANEL(SLEP1) AUTOSL(NO)*
/* Start error handling */
if rc > 8 then call left error rc /*|||
*TDISPL    *tabname* PANEL(SLEP1) AUTOSL(NO)/*|||
*TDISPL    *tabname* PANEL(SLEP1) AUTOSL(NO)
/* End error handling */
*PF1 (ALLCHN PROFILE) /* save insert indicator ALL or CHANGED
/* PF1 - i then leave k /* PF2 was pressed, go to program and

```

Finally yet importantly, here is a display of panel SLEP1 with the data in table `$$LETAB`.

Screen 10.1: Panel SLEP1 displayed by program SLE

```

HELP 1 ***** Table display of recently updated data sets Row 1 of 20
COMMAND *****                                SCHEDULE ***** USE
***** FILE *****                                *****
Insert control for column data sets ***** NOT COMPILED
Insert control for column data sets ***** NOT COMPILED
***** Row 1 of 1 ***** Help with PPI for all fields ***** Time
*****
DEB001.D001.D001.EXAMPLE1(0000000000) 15/04/08 15:04:00
DEB001.D001.D001.EXAMPLE1(0000000001) 15/04/08 15:04:07
DEB001.D001.D001.EXAMPLE1(0000000002) 15/04/08 15:04:17
DEB001.D001.D001.EXAMPLE1(0000000003) 15/04/08 15:04:24
DEB001.D001.D001.EXAMPLE1(0000000004) 15/04/08 15:04:31
DEB001.D001.D001.EXAMPLE1(0000000005) 15/04/08 15:04:38
DEB001.D001.D001.EXAMPLE1(0000000006) 15/04/08 15:04:45
DEB001.D001.D001.EXAMPLE1(0000000007) 15/04/08 15:04:52
DEB001.D001.D001.EXAMPLE1(0000000008) 15/04/08 15:05:00
DEB001.D001.D001.EXAMPLE1(0000000009) 15/04/08 15:05:07
DEB001.D001.D001.EXAMPLE1(0000000010) 15/04/08 15:05:14
DEB001.D001.D001.EXAMPLE1(0000000011) 15/04/08 15:05:21
DEB001.D001.D001.EXAMPLE1(0000000012) 15/04/08 15:05:28
DEB001.D001.D001.EXAMPLE1(0000000013) 15/04/08 15:05:35
DEB001.D001.D001.EXAMPLE1(0000000014) 15/04/08 15:05:42
DEB001.D001.D001.EXAMPLE1(0000000015) 15/04/08 15:05:49
DEB001.D001.D001.EXAMPLE1(0000000016) 15/04/08 15:05:56
DEB001.D001.D001.EXAMPLE1(0000000017) 15/04/08 15:06:03
DEB001.D001.D001.EXAMPLE1(0000000018) 15/04/08 15:06:10
DEB001.D001.D001.EXAMPLE1(0000000019) 15/04/08 15:06:17
DEB001.D001.D001.EXAMPLE1(0000000020) 15/04/08 15:06:24
DEB001.D001.D001.EXAMPLE1(0000000021) 15/04/08 15:06:31
DEB001.D001.D001.EXAMPLE1(0000000022) 15/04/08 15:06:38
DEB001.D001.D001.EXAMPLE1(0000000023) 15/04/08 15:06:45
DEB001.D001.D001.EXAMPLE1(0000000024) 15/04/08 15:06:52
DEB001.D001.D001.EXAMPLE1(0000000025) 15/04/08 15:06:59
DEB001.D001.D001.EXAMPLE1(0000000026) 15/04/08 15:07:06
DEB001.D001.D001.EXAMPLE1(0000000027) 15/04/08 15:07:13
DEB001.D001.D001.EXAMPLE1(0000000028) 15/04/08 15:07:20
DEB001.D001.D001.EXAMPLE1(0000000029) 15/04/08 15:07:27
DEB001.D001.D001.EXAMPLE1(0000000030) 15/04/08 15:07:34
DEB001.D001.D001.EXAMPLE1(0000000031) 15/04/08 15:07:41
DEB001.D001.D001.EXAMPLE1(0000000032) 15/04/08 15:07:48
DEB001.D001.D001.EXAMPLE1(0000000033) 15/04/08 15:07:55
DEB001.D001.D001.EXAMPLE1(0000000034) 15/04/08 15:08:02
DEB001.D001.D001.EXAMPLE1(0000000035) 15/04/08 15:08:09
DEB001.D001.D001.EXAMPLE1(0000000036) 15/04/08 15:08:16
DEB001.D001.D001.EXAMPLE1(0000000037) 15/04/08 15:08:23
DEB001.D001.D001.EXAMPLE1(0000000038) 15/04/08 15:08:30
DEB001.D001.D001.EXAMPLE1(0000000039) 15/04/08 15:08:37
DEB001.D001.D001.EXAMPLE1(0000000040) 15/04/08 15:08:44
DEB001.D001.D001.EXAMPLE1(0000000041) 15/04/08 15:08:51
DEB001.D001.D001.EXAMPLE1(0000000042) 15/04/08 15:08:58
DEB001.D001.D001.EXAMPLE1(0000000043) 15/04/08 15:09:05
DEB001.D001.D001.EXAMPLE1(0000000044) 15/04/08 15:09:12
DEB001.D001.D001.EXAMPLE1(0000000045) 15/04/08 15:09:19
DEB001.D001.D001.EXAMPLE1(0000000046) 15/04/08 15:09:26
DEB001.D001.D001.EXAMPLE1(0000000047) 15/04/08 15:09:33
DEB001.D001.D001.EXAMPLE1(0000000048) 15/04/08 15:09:40
DEB001.D001.D001.EXAMPLE1(0000000049) 15/04/08 15:09:47
DEB001.D001.D001.EXAMPLE1(0000000050) 15/04/08 15:09:54
DEB001.D001.D001.EXAMPLE1(0000000051) 15/04/08 15:10:01
DEB001.D001.D001.EXAMPLE1(0000000052) 15/04/08 15:10:08
DEB001.D001.D001.EXAMPLE1(0000000053) 15/04/08 15:10:15
DEB001.D001.D001.EXAMPLE1(0000000054) 15/04/08 15:10:22
DEB001.D001.D001.EXAMPLE1(0000000055) 15/04/08 15:10:29
DEB001.D001.D001.EXAMPLE1(0000000056) 15/04/08 15:10:36
DEB001.D001.D001.EXAMPLE1(0000000057) 15/04/08 15:10:43
DEB001.D001.D001.EXAMPLE1(0000000058) 15/04/08 15:10:50
DEB001.D001.D001.EXAMPLE1(0000000059) 15/04/08 15:10:57
DEB001.D001.D001.EXAMPLE1(0000000060) 15/04/08 15:11:04
DEB001.D001.D001.EXAMPLE1(0000000061) 15/04/08 15:11:11
DEB001.D001.D001.EXAMPLE1(0000000062) 15/04/08 15:11:18
DEB001.D001.D001.EXAMPLE1(0000000063) 15/04/08 15:11:25
DEB001.D001.D001.EXAMPLE1(0000000064) 15/04/08 15:11:32
DEB001.D001.D001.EXAMPLE1(0000000065) 15/04/08 15:11:39
DEB001.D001.D001.EXAMPLE1(0000000066) 15/04/08 15:11:46
DEB001.D001.D001.EXAMPLE1(0000000067) 15/04/08 15:11:53
DEB001.D001.D001.EXAMPLE1(0000000068) 15/04/08 15:12:00
DEB001.D001.D001.EXAMPLE1(0000000069) 15/04/08 15:12:07
DEB001.D001.D001.EXAMPLE1(0000000070) 15/04/08 15:12:14
DEB001.D001.D001.EXAMPLE1(0000000071) 15/04/08 15:12:21
DEB001.D001.D001.EXAMPLE1(0000000072) 15/04/08 15:12:28
DEB001.D001.D001.EXAMPLE1(0000000073) 15/04/08 15:12:35
DEB001.D001.D001.EXAMPLE1(0000000074) 15/04/08 15:12:42
DEB001.D001.D001.EXAMPLE1(0000000075) 15/04/08 15:12:49
DEB001.D001.D001.EXAMPLE1(0000000076) 15/04/08 15:12:56
DEB001.D001.D001.EXAMPLE1(0000000077) 15/04/08 15:13:03
DEB001.D001.D001.EXAMPLE1(0000000078) 15/04/08 15:13:10
DEB001.D001.D001.EXAMPLE1(0000000079) 15/04/08 15:13:17
DEB001.D001.D001.EXAMPLE1(0000000080) 15/04/08 15:13:24
DEB001.D001.D001.EXAMPLE1(0000000081) 15/04/08 15:13:31
DEB001.D001.D001.EXAMPLE1(0000000082) 15/04/08 15:13:38
DEB001.D001.D001.EXAMPLE1(0000000083) 15/04/08 15:13:45
DEB001.D001.D001.EXAMPLE1(0000000084) 15/04/08 15:13:52
DEB001.D001.D001.EXAMPLE1(0000
```

For each of the shaded boxes a dedicated help panel is defined

Mnemonics to table display panels

Behind the **MODEL** statement up to **eight** model lines may be defined.

- The table display panels are automatically SCROLLABLE. Therefore, you can handle ISPF tables of any length.
- Scrolling is done with keys PF7 and PF8. PF7 ~ backward, PF8 ~ forward.
- The display can only be performed in 80 columns.
- If you want to also edit the contents of the tables, you should define the first column as an input field for the operation code. See the above panel SLEP1.
- In the row behind the)MODEL line there is no need to be list all names of an ISPF table.