



## Сброс root-пароля Almalinux 9.4

- 1) Заходим в меню загрузки, выбираем нижний пункт и нажимаем кнопку «e» (edit)



- 2) Добавляем в конец строки, перед строкой "initrd (\$root)/initramfs-5.14.0.27.37.1.el9\_4.v86\_64.img \$tuned\_initrd": **rd.break enforcing=0** и нажимаем **F10**



### 3) В консоли Dracut Emergency Shell набираем:

```
mount -o rw,remount /sysroot
chroot /sysroot
passwd root
exit
exit
```

```
Starting dracut pre-pivot and cleanup hook...
[ 3.076102] dracut-pre-pivot[591]: Warning: Break before switch_root
Starting Dracut Emergency Shell...

Generating "/run/initramfs/rdsosreport.txt"

Entering emergency mode. Exit the shell to continue.
Type "journalctl" to view system logs.
You might want to save "/run/initramfs/rdsosreport.txt" to a USB stick or /boot
after mounting them and attach it to a bug report.

switch_root:/# mount -o rw,remount /sysroot
[ 37.298447] EXT4-fs (dm-0): re-mounted 4c29e828-2d44-4559-9bdf-b3eb66061b7a r
/w. Quota mode: none.
switch_root:/# chroot /sysroot
sh-5.1# passwd root
Changing password for user root.
New password:
Retype new password:
passwd: all authentication tokens updated successfully.
sh-5.1# exit
exit
switch_root:/# exit_
```

### 4) Заходим в систему, используя новый пароль