

# Create Ubuntu System & Image for EFI32 BIOS via QEMU

*Lu, Ken(bluewish.ken.lu@gmail.com)*

## [1. Thoughts](#)

## [2. Prerequisite](#)

## [3. Steps](#)

### [3.1 Create RAW GPT image and partitions](#)

### [3.2 Install ubuntu server i386 via Qemu on Default Legacy BIOS](#)

### [3.3 Build UEFI 32bit BIOS for QEMU](#)

### [3.4 Convert ubuntu boot from legacy BIOS to UEFI 32bit BIOS](#)

### [3.5 Create bootable USB device](#)

### [3.6 Full Debug Output from BIOS to Ubuntu](#)

## 1, Thoughts

In sometimes, we need boot ubuntu system on a native UEFI 32-bit BIOS machine, **but all existing OS including window/linux only provides EFI64-bit ISO image**, the only exception is apple Mac OS. So it almost impossible to install any OS on a pure native UEFI 32-bit BIOS based system.

This document introduces how to make that image based on Qemu environment. The core idea is:

- Create a raw qemu image and use GPT as its partition

- Install ubuntu 12.04 server i386 in qemu legacy BIOS mode.
- Install grub-efi32 in installed ubuntu system.
- Build OVMF 32bit UEFI BIOS image
- Boot qemu via OVMF 32bit BIOS image

## 2, Prerequisite

- Ubuntu 12.04 server iso in i386 arch downloaded from <http://releases.ubuntu.com/precise/ubuntu-12.04.3-server-i386.iso>
- Ubuntu develop machine
  - Install GCC4.6 as default compiler
  - Install qemu by “sudo apt-get install qemu”
  - Install iasl by “sudo apt-get install iasl”
  - Install build tools by “sudo apt-get install build-essential bison flex uuid-dev”

## 3, Steps

### 3.1 Create RAW GPT image and partitions

- Create a 2G RAW image file  
`“qemu-img create -f raw gpt.raw 2G”`
- Create GPT partition table in disk:  
`“sudo parted gpt.raw mklabel gpt”`
- Create BiosGrub partition in disk, **since legacy boot need this partition in a GPT disk (MBR no need).**  
`“sudo parted gpt.raw mkpart primary fat32 0% 100M”`
- Create ESP(EFI System Partition), since UEFI boot need this partition for bootia32.efi file  
`“sudo parted gpt.raw mkpart primary fat32 100M 200M”`  
`“sudo parted gpt.raw mkfs 2 fat32”`
- Create rootfs  
`“sudo parted gpt.raw mkpart primary ext2 200M 75%”`  
`“sudo parted gpt.raw mkfs 3 ext2”`
- Create swap partition  
`“sudo parted gpt.raw mkpart primary linux-swaps 75% 100%”`  
`“sudo parted gpt.raw mkfs 4 linux-swaps”`

### 3.2 Install ubuntu server i386 via Qemu on Default Legacy BIOS

After above image created, now install ubuntu server i386 on GPT disk by following command:


```
“qemu-system-i386 -hda gpt.raw -m 1024 -cdrom
ubuntu-12.04.3-server-i386.iso -serial file:log_ia32.txt -boot d”
```

Note:

- By default, the BIOS used by qemu is legacy BIOS. Because the

ubuntu-12.04.3-server-i386 only support legacy boot.


- “-boot d” means boot from cdrom.
- When installing,
  - Set the partition 1 as “biosgrub” type.
  - Mount the partition 2 to /boot/efi.



After installation, booting into ubuntu i386 server still via legacy boot:

- Remove “-boot d” from qemu startup script. So system would boot via hard disk instead of CDROM.
- Press “e” in grub menu
- Add boot parameters “console=ttyS0,115200n2 earlyprintk nomodeset loglevel=7”
- Press F10 to continue boot

Note, you can see the whole boot log by “tail -f log\_ia32.txt”, which is specified by above qemu start up command.



After first boot into ubuntu via legacy BIOS, then:

- Add above additional boot parameter into grub:
  - vim /etc/default/grub
  - add “console=ttyS0,115200n8 earlyprintk nomodeset loglevel=7” in GRUB\_CMDLINE\_LINUX\_DEFAULT macro.
  - sudo update-grub

-

### 3.3 Build UEFI 32bit BIOS for QEMU

- Get the Source code from <https://github.com/tianocore/edk2> by following GIT command:
  - “git clone <https://github.com/tianocore/edk2.git>”
- Build edk2 Linux Tool:
  - cd <edk2>
  - source edksetup.sh
  - cd <edk2>/BaseTools
  - make

- Build IA32 BIOS:
  - `cd <edk2>`
  - `source edksetup.sh`
  - `build -p OvmfPkg/OvmfPkgIa32.dsc -D DEBUG_ON_SERIAL_PORT -b DEBUG -a IA32 -t GCC46`

Note:

- DEBUG\_ON\_SERIAL\_PORT macro is used to output the BIOS debug info to serial file, so you can get log file on qemu via “-serial file:log.txt”
- Get OVMF.fd file at <edk2>/Build/OvmfIa32/DEBUG\_GCC46/FV/OVMF.fd
- Test the new EFI IA32 BIOS image in qemu:
 

“qemu-system-i386 -bios <edk2>/Build/OvmfIa32/DEBUG\_GCC46/FV/OVMF.fd” -serial file:uefi\_log.txt”

see the UEFI BIOS output by “tail -f uefi\_log.txt”

```

ken@ken-desktop-ubuntu: /work/develop/edk2/Build/OvmfIa32/DEBUG_GCC46/FV
03  000002B8  0000022D  000002B8
04  000016F9  00001263  000016F9
Booting EFI Floppy 1
PlatformBdsBootFail
Boot Failed. EFI Floppy 1
PixelBlueGreenRedReserved8BitPerColor
PixelBlueGreenRedReserved8BitPerColor
Memory  Previous  Current  Next
Type    Pages    Pages    Pages
=====
0A      00000004  00000001  00000004
09      00000008  00000006  00000008
00      00000004  00000003  00000004
06      00000039  0000002E  00000039
05      00000030  0000002D  00000030
03      000002B8  0000022D  000002B8
04      000016F9  00001263  000016F9
Booting EFI DVD/CDROM
BlockSize : 2048
LastBlock : 0
PlatformBdsBootFail
Boot Failed. EFI DVD/CDROM
PixelBlueGreenRedReserved8BitPerColor
PixelBlueGreenRedReserved8BitPerColor

```

### 3.4 Convert ubuntu boot from legacy BIOS to UEFI 32bit BIOS

- Refer 3.2, Boot ubuntu via Legacy BIOS first
- In ubuntu terminal, install “grub-efi-ia32” package by
 

“`sudo apt-get install grub-efi-ia32`”

- Then, install grub-efi to /dev/sda disk by:

*“sudo grub-install /dev/sda”*

*Note:*

*- the grub.efi and grub.cfg will be installed into the second partition ESP(EFI System Partition) which has been mounted into /boot/efi node.  
- By default, ubuntu will \*not\* create efi/boot/bootia32.efi file, but only create efi/ubuntu/ folder for grubia32.efi and boot.efi. Then use set variable to save them as default boot loader. But now the action of saving variable will be failed, because current OS is not EFI system.*

- Turn off qemu and restart qemu in UEFI mode via following command line:

*“qemu-system-i386 -bios <edk2>/Build/OvmfIa32/DEBUG\_GCC46/FV/OVMF.fd  
-serial file:uefi\_log.txt -hda gpt.raw”*

*Note:*

*- Use OVMF binaries built from above 3.3  
- Use gpt.raw system image from above 3.2*

- After reboot, you may find system can not boot ubuntu, but jump into EFI shell like below

```
QEMU

Shell>
Shell> fs0:
FS0:\> ls
Directory of: FS0:\
11/23/2013  14:20 <DIR>          1,024  EFI
                0 File(s)          0 bytes
                1 Dir(s)
FS0:\> cd EFI
FS0:\EFI> ls
Directory of: FS0:\EFI\
11/23/2013  14:20 <DIR>          1,024  .
11/23/2013  14:20 <DIR>           0     ..
11/23/2013  14:20 <DIR>          1,024  ubuntu
                0 File(s)          0 bytes
                3 Dir(s)
FS0:\EFI> cd ubuntu
FS0:\EFI\ubuntu> ls
Directory of: FS0:\EFI\ubuntu\
11/23/2013  14:20 <DIR>          1,024  .
11/23/2013  14:20 <DIR>          1,024  ..
11/23/2013  15:23             88,064  grubia32.efi
11/23/2013  15:23             88,064  boot.efi
                2 File(s)       176,128 bytes
                2 Dir(s)
FS0:\EFI\ubuntu> _
```


The reason is:

- In above step of “grub-install /dev/sda”, ubuntu will not create default EFI boot file like “efi/boot/bootia32.efi”, but only create efi/ubuntu/grubia32.efi” file. So EFI BIOS can not find the default boot file for continuing boot.
- Also in previous steps, ubuntu can not save EFI boot option via runtime variable service, because original boot environment is legacy boot but not EFI boot.

The solution is:

- In EFI shell, for fs0: disk:
  - Create EFI/boot folder
  - type “cp fs0:\efi\ubuntu\grubia32.efi fs0:\efi\boot\bootia32.efi

- After reboot, system can boot into original ubuntu server via EFI 32 OVMF bios now~~~~
- After boot, you can run “grub-install /dev/sda” again to save boot variable “ubuntu” into UEFI BIOS variable for future default boot as follows:



```
QEMU
Ubuntu 12.04.3 LTS easyconnect tty1
easyconnect login: root
Password:
Welcome to Ubuntu 12.04.3 LTS (GNU/Linux 3.8.0-29-generic i686)

 * Documentation:  https://help.ubuntu.com/

System information disabled due to load higher than 1.0

The programs included with the Ubuntu system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.

Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.

root@easyconnect:~# grub-install /dev/sda
BootCurrent: 0004
BootOrder: 0005,0000,0001,0002,0003,0004
Boot0000* EFI Floppy
Boot0001* EFI Floppy 1
Boot0002* EFI DVD/CDROM
Boot0003* EFI Hard Drive
Boot0004* EFI Internal Shell
Boot0005* ubuntu
Installation finished. No error reported.
root@easyconnect:~# _
```

### 3.5 Create bootable USB device

Now we can create bootable USB device from the gpt.img with ubuntu system now.

- Plug the USB disk in your work machine

`"sudo dd if=gpt.raw of=/dev/sdb"`

- Verify the USB disk by qemu:

`"qemu-system-i386 -bios <edk2>/Build/OvmfIa32/DEBUG_GCC46/FV/OVMF.fd  
-serial file:uefi_log.txt -hda /dev/sdb"`

### 3.6 Full Debug Output from BIOS to Ubuntu

Because the built-out EFI 32 BIOS and Linux all redirect debug output to serial, and qemu launcher command will redirect the serial to uefi\_log.txt, so you can get full debug log from BIOS



to OS as below:

```
SecCoreStartupWithStack(0xFFFFC000, 0x80000)
File->Type: 0xB
Section->Type: 0x2
Section->Type: 0x19
Section->Type (0x19) != SectionType (0x17)
Section->Type: 0x17
File->Type: 0x2
File->Type (0x2) != FileType (0x4)
File->Type: 0xF0
File->Type (0xF0) != FileType (0x4)
File->Type: 0x4
Section->Type: 0x19
Section->Type (0x19) != SectionType (0x10)
Section->Type: 0x10
Register PPI Notify: DCD0BE23-9586-40F4-B643-06522CED4EDE
Install PPI: 8C8CE578-8A3D-4F1C-9935-896185C32DD3
Install PPI: 5473C07A-3DCB-4DCA-BD6F-1E9689E7349A
The 0th FV start address is 0x00000800000, size is 0x00800000, handle is 0x0
Register PPI Notify: 49EDB1C1-BF21-4761-BB12-EB0031AABB39
Register PPI Notify: EA7CA24B-DED5-4DAD-A389-BF827E8F9B38
Install PPI: B9E0ABFE-5979-4914-977F-6DEE78C278A6
Install PPI: DBE23AA9-A345-4B97-85B6-B226F1617389
Loading PEIM at 0x0000080CC80 EntryPoint=0x0000080CEC0 PcdPeim.efi
Install PPI: 06E81C58-4AD7-44BC-8390-F10265F72480
Install PPI: 01F34D25-4DE2-23AD-3FF3-36353FF323F1
Loading PEIM at 0x00000811D20 EntryPoint=0x00000811F60 StatusCodePei.efi
Install PPI: 229832D3-7A30-4B36-B827-F40CB7D45436
Loading PEIM at 0x00000815320 EntryPoint=0x00000815560 PlatformPei.efi
Platform PEIM Loaded
CMOS:
00: 01 00 08 00 08 00 07 23 11 13 26 02 00 80 00 00
10: 40 00 F0 00 07 80 02 FF FF 2F 00 41 10 10 FF FF
20: C8 41 10 3F 00 00 00 00 00 00 00 00 00 00 00 00
30: FF FF 20 00 00 3F 00 20 30 02 00 00 00 12 00 00
40: 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
50: 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
60: 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
70: 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
MemDetect called
PeiInstallPeiMemory MemoryBegin 0x3C000000, MemoryLength 0x4000000
Reserved variable store memory: 0x3FFD0000; size: 128kb
Platform PEI Firmware Volume Initialization
Firmware Volume HOB: 0x800000 0x800000
Install PPI: 7408D748-FC8C-4EE6-9288-C4BEC092A410
Temp Stack : BaseAddress=0x78000 Length=0x8000
Temp Heap : BaseAddress=0x70000 Length=0x7B8
Total temporary memory: 65536 bytes.
    temporary memory stack ever used: 32768 bytes.
    temporary memory heap used: 1976 bytes.
Old Stack size 32768, New stack size 131072
Heap Offset = 0x0 Stack Offset = 0x3BFA0000
Stack Hob: BaseAddress=0x3C000000 Length=0x20000
TemporaryRamMigration(0x70000, 0x3C018000, 0x10000)
Loading PEIM at 0x0003FFC2000 EntryPoint=0x0003FFC2240 PeiCore.efi
Reinstall PPI: 8C8CE578-8A3D-4F1C-9935-896185C32DD3
Reinstall PPI: 5473C07A-3DCB-4DCA-BD6F-1E9689E7349A
Reinstall PPI: B9E0ABFE-5979-4914-977F-6DEE78C278A6
Install PPI: F894643D-C449-42D1-8EA8-85BDD8C65BDE
Loading PEIM at 0x0003FFB8000 EntryPoint=0x0003FFB8240 DxeIpl.efi
Install PPI: 0AE8CE5D-E448-4437-A8D7-EBF5F194F731
Install PPI: 1A36E4E7-FAB6-476A-8E75-695A0576FDD7
Install PPI: EA7CA24B-DED5-4DAD-A389-BF827E8F9B38
Notify: PPI Guid: EA7CA24B-DED5-4DAD-A389-BF827E8F9B38, Peim notify entry point: 8033A2
The 1th FV start address is 0x0003FC8A000, size is 0x00330000, handle is 0x3FC8A000
```

DXE IPL Entry  
Loading PEIM at 0x0003FC6A000 EntryPoint=0x0003FC6A240 DxeCore.efi  
Loading DXE CORE at 0x0003FC6A000 EntryPoint=0x0003FC6A240  
Install PPI: 605EA650-C65C-42E1-BA80-91A52AB618C6  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3FC81920  
HOBList address in DXE = 0x3FA62010  
Memory Allocation 0x00000006 0x3FFD0000 - 0x3FFFFFFF  
Memory Allocation 0x00000004 0x800000 - 0xFFFFF  
Memory Allocation 0x00000004 0x3FC4A000 - 0x3FC69FFF  
Memory Allocation 0x00000004 0x3FFCF000 - 0x3FFCFFFF  
Memory Allocation 0x00000004 0x3FFC2000 - 0x3FFCEFFF  
Memory Allocation 0x00000004 0x3FFBB000 - 0x3FFC1FFF  
Memory Allocation 0x00000004 0x3FC89000 - 0x3FFBAFFF  
Memory Allocation 0x00000004 0x3FC6A000 - 0x3FC88FFF  
Memory Allocation 0x00000003 0x3FC6A000 - 0x3FC88FFF  
Memory Allocation 0x00000004 0x3FC4A000 - 0x3FC69FFF  
Memory Allocation 0x00000004 0x3C000000 - 0x3C01FFFF  
FV Hob 0x800000 - 0xFFFFF  
FV Hob 0x3FC8A000 - 0x3FFB9FFF  
FV2 Hob 0x3FC8A000 - 0x3FFB9FFF  
InstallProtocolInterface: D8117CFE-94A6-11D4-9A3A-0090273FC14D 3FC810F0  
InstallProtocolInterface: 8F644FA9-E850-4DB1-9CE2-0B44698E8DA4 3FA5E49C  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3FA5E410  
InstallProtocolInterface: 8F644FA9-E850-4DB1-9CE2-0B44698E8DA4 3FA5E11C  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3FA5E090  
InstallProtocolInterface: 220E73B6-6BDB-4413-8405-B974B108619A 3FA5BC9C  
InstallProtocolInterface: 220E73B6-6BDB-4413-8405-B974B108619A 3FA5B51C  
InstallProtocolInterface: EE4E5898-3914-4259-9D6E-DC7BD79403CF 3FC81540  
Loading driver 9B680FCE-AD6B-4F3A-B60B-F59899003443  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3FA63C28  
Loading driver at 0x0003FBD000 EntryPoint=0x0003FBD0273 DevicePathDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9FBB10  
InstallProtocolInterface: 0379BE4E-D706-437D-B037-EDB82FB772A4 3FBE1620  
InstallProtocolInterface: 8B843E20-8132-4852-90CC-551A4E4A7F1C 3FBE1618  
InstallProtocolInterface: 05C99A21-C70F-4AD2-8A5F-35DF3343F51E 3FBE1610  
Loading driver 80CF7257-87AB-47F9-A3FE-D50B76D89541  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3FA63AA8  
Loading driver at 0x0003FBD4000 EntryPoint=0x0003FBD4273 PcdDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9FB310  
InstallProtocolInterface: 11B34006-D85B-4D0A-A290-D5A571310EF7 3FBD87B8  
InstallProtocolInterface: 13A3F0F6-264A-3EF0-F2E0-DEC512342F34 3FBD8770  
Loading driver 733CBAC2-B23F-4B92-BC8E-FB01CE5907B7  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3FA63928  
Loading driver at 0x0003FC0F000 EntryPoint=0x0003FC0F273 FvbServicesRuntimeDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9FAB90  
QEMU Flash: Attempting flash detection at FFE00010  
QemuFlashDetected => FD behaves as FLASH  
QemuFlashDetected => Yes  
Installing QEMU flash FVB  
InstallProtocolInterface: 8F644FA9-E850-4DB1-9CE2-0B44698E8DA4 3FC38D1C  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3F9FA990  
Loading driver FEDE0A1B-BCA2-4A9F-BB2B-D9FD7DEC2E9F  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3FA637A8  
Loading driver at 0x0003FC09000 EntryPoint=0x0003FC09273 StatusCodeRuntimeDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9FA390  
InstallProtocolInterface: D2B2B828-0826-48A7-B3DF-983C006024F0 3FC0CA44  
Loading driver B601F8C4-43B7-4784-95B1-F4226CB40CEE  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3FA63628  
Loading driver at 0x0003FC04000 EntryPoint=0x0003FC04273 RuntimeDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9D1E10  
InstallProtocolInterface: B7DFB4E1-052F-449F-87BE-9818FC91B733 3FC06980  
Loading driver F80697E9-7FD6-4665-8646-88E33EF71DFC  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3FA634A8  
Loading driver at 0x0003FBD0000 EntryPoint=0x0003FBD0273 SecurityStubDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9D1910  
InstallProtocolInterface: 94AB2F58-1438-4EF1-9152-18941A3A0E68 3FBD2574

InstallProtocolInterface: A46423E3-4617-49F1-B9FF-D1BFA9115839 3FBD2578  
Loading driver 13AC6DD0-73D0-11D4-B06B-00AA00BD6DE7  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3FA63328  
Loading driver at 0x0003FBC9000 EntryPoint=0x0003FBC9273 EbcDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9D1390  
InstallProtocolInterface: 13AC6DD1-73D0-11D4-B06B-00AA00BD6DE7 3F9D1190  
InstallProtocolInterface: 2755590C-6F3C-42FA-9EA4-A3BA543CDA25 3F9D1010  
InstallProtocolInterface: AAEACCFD-F27B-4C17-B610-75CA1F2DFB52 3F9D0E90  
Loading driver 79CA4208-BBA1-4A9A-8456-E1E66A81484E  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3FA631A8  
Loading driver at 0x0003FBC6000 EntryPoint=0x0003FBC6273 Legacy8259.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9D0A90  
InstallProtocolInterface: 38321DBA-4FE0-4E17-8AEC-413055EAEDC1 3FBC7DB8  
Loading driver A19B1FE7-C1BC-49F8-875F-54A5D542443F  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3FA63028  
Loading driver at 0x0003FBC2000 EntryPoint=0x0003FBC2273 CpuIo2Dxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9D0510  
InstallProtocolInterface: AD61F191-AE5F-4C0E-B9FA-E869D288C64F 3FBC4124  
Loading driver 1A1E4886-9517-440E-9FDE-3BE44CEE2136  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CFDA8  
Loading driver at 0x0003FBB9000 EntryPoint=0x0003FBB9273 CpuDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9CE90  
InstallProtocolInterface: 26BACCB1-6F42-11D4-BCE7-0080C73C8881 3FBBEF98  
Loading driver 6F0198AA-1F1D-426D-AE3E-39AB633FCC28  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CFC28  
Loading driver at 0x0003FC00000 EntryPoint=0x0003FC00273 KbcReset.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9CEA90  
InstallProtocolInterface: 27CFAC88-46CC-11D4-9A38-0090273FC14D 0  
Loading driver C8339973-A563-4561-B858-D8476F9DEFEC4  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CFAA8  
Loading driver at 0x0003FBB6000 EntryPoint=0x0003FBB6273 Metronome.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9CE590  
InstallProtocolInterface: 26BACCB2-6F42-11D4-BCE7-0080C73C8881 3FBB7F8C  
Loading driver 22DC2B60-FE40-42AC-B01F-3AB1FAD9AAD8  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CF928  
Loading driver at 0x0003FBFB000 EntryPoint=0x0003FBFB273 EmuVariableFvbRuntimeDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9CE090  
EMU Variable FVB Started  
Disabling EMU Variable FVB since flash variables appear to be supported.  
Error: Image at 0003FBFB000 start failed: Aborted  
Loading driver FE5CEA76-4F72-49E8-986F-2CD899DFFE5D  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CF928  
Loading driver at 0x0003FBAF000 EntryPoint=0x0003FBAF273 FaultTolerantWriteDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9CE110  
Ftw: Remaining work space size - FE0  
InstallProtocolInterface: 3EBD9E82-2C78-4DE6-9786-8D4BFCB7C881 3F9A5018  
Loading driver CBD2E4D5-7068-4FF5-B462-9822B4AD8D60  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CF7A8  
Loading driver at 0x0003FBF6000 EntryPoint=0x0003FBF6273 VariableRuntimeDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9BCA90  
InstallProtocolInterface: CD3D0A05-9E24-437C-A891-1EE053DB7638 3FBFCC74  
InstallProtocolInterface: 1E5668E2-8481-11D4-BCF1-0080C73C8881 0  
InstallProtocolInterface: 6441F818-6362-4E44-B570-7DBA31DD2453 0  
Loading driver 79E4A61C-ED73-4312-94FE-E3E7563362A9  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CF628  
Loading driver at 0x0003FBAC000 EntryPoint=0x0003FBAC273 PrintDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9BC310  
InstallProtocolInterface: F05976EF-83F1-4F3D-8619-F7595D41E538 3FBAADDE8  
Loading driver 348C4D62-BFBD-4882-9ECE-C80BB1C4783B  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CF4A8  
Loading driver at 0x0003FB97000 EntryPoint=0x0003FB97273 HiiDatabase.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9A4D90  
InstallProtocolInterface: E9CA4775-8657-47FC-97E7-7ED65A084324 3FBA8AE0  
InstallProtocolInterface: 0FD96974-23AA-4CDC-B9CB-98D17750322A 3FBA8B04  
InstallProtocolInterface: EF9FC172-A1B2-4693-B327-6D32FC416042 3FBA8B18  
InstallProtocolInterface: 587E72D7-CC50-4F79-8209-CA291FC1A10F 3FBA8B44

InstallProtocolInterface: 31A6406A-6BDF-4E46-B2A2-EBAA89C40920 3FBA8AF0  
Loading driver 96B5C032-DF4C-4B6E-8232-438DCF448D0E  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CF328  
Loading driver at 0x0003FB93000 EntryPoint=0x0003FB93273 NullMemoryTestDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F9A4410  
InstallProtocolInterface: 309DE7F1-7F5E-4ACE-B49C-531BE5AA95EF 3FB94F48  
Loading driver F9D88642-0737-49BC-81B5-6889CD57D9EA  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CF1A8  
Loading driver at 0x0003FB8E000 EntryPoint=0x0003FB8E273 SmbiosDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F982E90  
InstallProtocolInterface: 03583FF6-CB36-4940-947E-B9B39F4AFAF7 3FB91144  
Loading driver 9622E42C-8E38-4A08-9E8F-54F784652F6B  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9CF028  
Loading driver at 0x0003FB85000 EntryPoint=0x0003FB85273 AcpiTableDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F982910  
InstallProtocolInterface: FFE06BDD-6107-46A6-7BB2-5A9C7EC5275C 3F981F58  
Loading driver A210F973-229D-4F4D-AA37-9895E6C9EABA  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F980DA8  
Loading driver at 0x0003FB81000 EntryPoint=0x0003FB81273 DpcDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F982390  
InstallProtocolInterface: 480F8AE9-0C46-4AA9-BC89-DB9FBA619806 3FB82E78  
Loading driver F2765DEC-6B41-11D5-8E71-00902707B35E  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F980C28  
Loading driver at 0x0003FB7E000 EntryPoint=0x0003FB7E273 Timer.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F95FE10  
InstallProtocolInterface: 26BACCB3-6F42-11D4-BCE7-0080C73C8881 3FB7FE60  
Loading driver 2383608E-C6D0-4E3E-858D-45DFAC3543D5  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F980AA8  
Loading driver at 0x0003FB77000 EntryPoint=0x0003FB77273 PciHostBridge.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F95F910  
InstallProtocolInterface: CF8034BE-6768-4D8B-B739-7CCE683A9FBE 3F95F728  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3FB7BA88  
InstallProtocolInterface: 2F707EBB-4A1A-11D4-9A38-0090273FC14D 3FA5CD64  
Loading driver 378D7B65-8DA9-4773-B6E4-A47826A833E1  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F980928  
Loading driver at 0x0003FBF0000 EntryPoint=0x0003FBF0273 PcrTc.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F95F010  
InstallProtocolInterface: 27CFAC87-46CC-11D4-9A38-0090273FC14D 0  
Loading driver AD608272-D07F-4964-801E-7BD3B7888652  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9807A8  
Loading driver at 0x0003FBEC000 EntryPoint=0x0003FBEC273 MonotonicCounterRuntimeDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F95EB10  
InstallProtocolInterface: 1DA97072-BDDC-4B30-99F1-72A0B56FFF2A 0  
Loading driver 42857F0A-13F2-4B21-8A23-53D3F714B840  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F980628  
Loading driver at 0x0003FBE8000 EntryPoint=0x0003FBE8273 CapsuleRuntimeDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F95E610  
InstallProtocolInterface: 5053697E-2CBC-4819-90D9-0580DEEE5754 0  
Loading driver FC5C7020-1A48-4198-9BE2-EAD5ABC8CF2F  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9804A8  
Loading driver at 0x0003FB4A000 EntryPoint=0x0003FB4A273 BdsDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F95E090  
Select Item: 0x0  
FW CFG Signature: 0x554D4551  
Select Item: 0x1  
FW CFG Revision: 0x1  
QemuFwCfg interface is supported.  
InstallProtocolInterface: 665E3FF6-46CC-11D4-9A38-0090273FC14D 3FB6CA60  
Loading driver EBF342FE-B1D3-4EF8-957C-8048606FF671  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F9801A8  
Loading driver at 0x0003FB34000 EntryPoint=0x0003FB34273 SetupBrowser.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F95D810  
InstallProtocolInterface: B9D4C360-BCFB-4F9B-9298-53C136982258 3FB45D3C  
InstallProtocolInterface: A770C357-B693-4E6D-A6CF-D21C728E550B 3FB45D54  
InstallProtocolInterface: 1F73B18D-4630-43C1-A1DE-6F80855D7DA4 3FB45D44  
Loading driver 4110465D-5FF3-4F4B-B580-24ED0D06747A

InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F980028  
Loading driver at 0x0003FB30000 EntryPoint=0x0003FB30273 SmbiosPlatformDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F907F10  
Loading driver 49970331-E3FA-4637-9ABC-3B7868676970  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F89DDA8  
Loading driver at 0x0003FB2B000 EntryPoint=0x0003FB2B273 AcpiPlatform.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F907B10  
Select Item: 0x0  
FW CFG Signature: 0x554D4551  
Select Item: 0x1  
FW CFG Revision: 0x1  
QemuFwCfg interface is supported.  
Select Item: 0x5  
Select Item: 0x19  
Select Item: 0x22  
ACPI S3 value: 1  
ACPI S4 value: 2  
ACPI PciWindow32: Base=0x40000000 End=0xFEEFFFFFF Length=0xBEFFFFFF0000  
ACPI PciWindow64: Base=0x00000000 End=0x00000000 Length=0x00000000  
Loading driver F099D67F-71AE-4C36-B2A3-DCEB0EB2B7D8  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F89DC28  
Loading driver at 0x0003FB28000 EntryPoint=0x0003FB28273 WatchdogTimer.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F907290  
InstallProtocolInterface: 665E3FF5-46CC-11D4-9A38-0090273FC14D 3FB29E08  
Loading driver E660EA85-058E-4B55-A54B-F02F83A24707  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F89DAA8  
Loading driver at 0x0003FB17000 EntryPoint=0x0003FB17273 DisplayEngine.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F86AD10  
InstallProtocolInterface: 9BBE29E9-FDA1-41EC-AD52-452213742D2E 3FB245B4  
Loading driver 93B80004-9FB3-11D4-9A3A-0090273FC14D  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F89D928  
Loading driver at 0x0003FB06000 EntryPoint=0x0003FB06273 PciBusDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F866D10  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FB1433C  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FB14480  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FB14474  
InstallProtocolInterface: 19CB87AB-2CB9-4665-8360-DDCF6054F79D 3FB1431C  
Loading driver 33CB97AF-6C33-4C42-986B-07581FA366D4  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F89D7A8  
Loading driver at 0x0003FB02000 EntryPoint=0x0003FB02273 BlockMmioToBlockIoDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F866410  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FB0479C  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FB04818  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FB0480C  
Loading driver 11D92DFB-3CA9-4F93-BA2E-4780ED3E03B5  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F89D628  
Loading driver at 0x0003FAFD000 EntryPoint=0x0003FAFD273 VirtioBlkDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F844F10  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAFFF94  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAFFF50  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAFFFAC  
Loading driver FAB5D4F4-83C0-4AAF-8480-442D11DF6CEA  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F89D4A8  
Loading driver at 0x0003FAF8000 EntryPoint=0x0003FAF8273 VirtioScsiDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F844990  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAFB394  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAFB348  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAFB3AC  
Loading driver 51CCF399-4FDF-4E55-A45B-E123F84D456A  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F89D328  
Loading driver at 0x0003FAF3000 EntryPoint=0x0003FAF3273 ConPlatformDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F844410  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAF5D90  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAF5E18  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAF5E0C  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAF5D78

InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAF5E18  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAF5E0C  
Loading driver 408EDCEC-CF6D-477C-A5A8-B4844E3DE281  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3F89D1A8  
Loading driver at 0x0003FAEA000 EntryPoint=0x0003FAEA273 ConSplitterDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F843B90  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAF04F0  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAF09E8  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAF09DC  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAF04A8  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAF09D0  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAF09C4  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAF0490  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAF09B8  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAF09AC  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAF04D8  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAF09A0  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAF0994  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAF04C0  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAF0988  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAF097C  
InstallProtocolInterface: 387477C1-69C7-11D2-8E39-00A0C969723B 3FAF0674  
InstallProtocolInterface: DD9E7534-7762-4698-8C14-F58517A625AA 3FAF068C  
InstallProtocolInterface: 31878C87-0B75-11D5-9A4F-0090273FC14D 3FAF06B8  
InstallProtocolInterface: 8D59D32B-C655-4AE9-9B15-F25904992A43 3FAF06F4  
InstallProtocolInterface: 387477C2-69C7-11D2-8E39-00A0C969723B 3FAF05B4  
InstallProtocolInterface: 387477C2-69C7-11D2-8E39-00A0C969723B 3FAF0514  
Loading driver CCCB0C28-4B24-11D5-9A5A-0090273FC14D  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC6C28  
Loading driver at 0x0003FAE2000 EntryPoint=0x0003FAE2273 GraphicsConsoleDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3F841210  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAE5FC0  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAE6144  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAE6138  
Loading driver 9E863906-A40F-4875-977F-5B93FF237FC6  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC6AA8  
Loading driver at 0x0003FAD9000 EntryPoint=0x0003FAD9273 TerminalDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC1A90  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FADF654  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FADF70C  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FADF700  
Loading driver 6B38F7B4-AD98-40E9-9093-ACA2B5A253C4  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC6928  
Loading driver at 0x0003FAD3000 EntryPoint=0x0003FAD3273 DiskIoDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC1510  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAD7080  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAD70F0  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAD70E4  
Loading driver 1FA1F39E-FEFF-4AAE-BD7B-38A070A3B609  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC67A8  
Loading driver at 0x0003FACC000 EntryPoint=0x0003FACC273 PartitionDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC5F90  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAD0E14  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAD0E9C  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAD0E90  
Loading driver CD3BAFB6-50FB-4FE8-8E4E-AB74D2C1A600  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC6628  
Loading driver at 0x0003FAC8000 EntryPoint=0x0003FAC8273 EnglishDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC5A10  
InstallProtocolInterface: 1D85CD7F-F43D-11D2-9A0C-0090273FC14D 3FAC9E14  
InstallProtocolInterface: A4C751FC-23AE-4C3E-92E9-4964CF63F349 3FAC9DF8  
Loading driver 0167CCC4-D0F7-4F21-A3EF-9E64B7CDCE8B  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC64A8  
Loading driver at 0x0003FAC2000 EntryPoint=0x0003FAC2273 ScsiBus.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC5390  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAC5B20

InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAC5B84  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAC5B78  
Loading driver 0A66E322-3740-4CCE-AD62-BD172CECCA35  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC6328  
Loading driver at 0x0003FABA000 EntryPoint=0x0003FABA273 ScsiDisk.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC4E90  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FABF92C  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FABFA84  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FABFA78  
Loading driver 69FD8E47-A161-4550-B01A-5594CEB2B2B2  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC61A8  
Loading driver at 0x0003FAAE000 EntryPoint=0x0003FAAE273 IdeBusDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC4910  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAB7094  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAB7248  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAB723C  
InstallProtocolInterface: 0784924F-E296-11D4-9A49-0090273FC14D 3FAB715C  
InstallProtocolInterface: 4D330321-025F-4AAC-90D8-5ED900173B63 3FAB7154  
Loading driver 99549F44-49BB-4820-B9D2-901329412D67  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC6028  
Loading driver at 0x0003FAAA000 EntryPoint=0x0003FAAA273 IdeController.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC4190  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAAC364  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAAC414  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAAC408  
Loading driver 38A0EC22-FBE7-4911-8BC1-176E0D6C1DBD  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC2DA8  
Loading driver at 0x0003FAA6000 EntryPoint=0x0003FAA6273 IsaAcpi.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC3C10  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAA841C  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAA8634  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAA8640  
Loading driver 240612B5-A063-11D4-9A3A-0090273FC14D  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC2C28  
Loading driver at 0x0003FAA0000 EntryPoint=0x0003FAA0273 IsaBusDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC3690  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FAA3A68  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FAA3AC8  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FAA3ABC  
Loading driver 93B80003-9FB3-11D4-9A3A-0090273FC14D  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC2AA8  
Loading driver at 0x0003FA99000 EntryPoint=0x0003FA99273 IsaSerialDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECC3110  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FA9D8E0  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FA9D9BC  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FA9D9B0  
Loading driver 3DC82376-637B-40A6-A8FC-A565417F2C38  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC2928  
Loading driver at 0x0003FA92000 EntryPoint=0x0003FA92273 Ps2KeyboardDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECBE890  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FA96EF8  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FA96FB0  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FA96FA4  
Loading driver 0ABD8284-6DA3-4616-971A-83A5148067BA  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC27A8  
Loading driver at 0x0003FA8B000 EntryPoint=0x0003FA8B273 IsaFloppyDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECBE610  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FA8F880  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FA8F964  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FA8F958  
Loading driver 961578FE-B6B7-44C3-AF35-6BC705CD2B1F  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC2628  
Loading driver at 0x0003FA86000 EntryPoint=0x0003FA86463  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3ECBE090  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FA86364  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FA8637C

InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FA86388  
Loading driver A2F436EA-A127-4EF8-957C-8048606FF670  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC24A8  
Loading driver at 0x0003FA7D000 EntryPoint=0x0003FA7D273 SnpDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC96B10  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FA83308  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FA83924  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FA83918  
Loading driver 025BBFC7-E6A9-4B8B-82AD-6815A1AEAF4A  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC2328  
Loading driver at 0x0003FA71000 EntryPoint=0x0003FA71273 MnpDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC96590  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FA79510  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FA7A35C  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FA7A350  
Loading driver E4F61863-FE2C-4B56-A8F4-08519BC439DF  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC21A8  
Loading driver at 0x0003FA69000 EntryPoint=0x0003FA69273 VlanConfigDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC96010  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3FA6E78C  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3FA6EC14  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3FA6EC08  
Loading driver 529D3F93-E8E9-4E73-B1E1-BDF6A9D50113  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3ECC2028  
Loading driver at 0x0003E84E000 EntryPoint=0x0003E84E273 ArpDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC95A90  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E853578  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E85361C  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E853610  
Loading driver 94734718-0BBC-47FB-96A5-EE7A5AE6A2AD  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC94DA8  
Loading driver at 0x0003E842000 EntryPoint=0x0003E842273 Dhcp4Dxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC95510  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E84A18C  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E84A730  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E84A724  
Loading driver 26841BDE-920A-4E7A-9FBE-637F477143A6  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC94C28  
Loading driver at 0x0003E838000 EntryPoint=0x0003E838273 Ip4ConfigDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC93F90  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E83E918  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E83ED0C  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E83ED00  
Loading driver 9FB1A1F3-3B71-4324-B39A-745CBB015FFF  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC94AA8  
Loading driver at 0x0003E81A000 EntryPoint=0x0003E81A273 Ip4Dxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC93A10  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E8255CC  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E825CD0  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E825CC4  
Loading driver DC3641B8-2FA8-4ED3-BC1F-F9962A03454B  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC94928  
Loading driver at 0x0003E82D000 EntryPoint=0x0003E82D273 Mtftp4Dxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC93490  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E8348EC  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E8349BC  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E8349B0  
Loading driver 6D6963AB-906D-4A65-A7CA-BD40E5D6AF4D  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC947A8  
Loading driver at 0x0003E7F4000 EntryPoint=0x0003E7F4273 Tcp4Dxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC92F10  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E801890  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E802834  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E802828  
Loading driver 6D6963AB-906D-4A65-A7CA-BD40E5D6AF2B  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC94628



Loading driver at 0x0003E80F000 EntryPoint=0x0003E80F273 Udp4Dxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC92990  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E81726C  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E817350  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E817344  
Loading driver 3B1DEAB5-C75D-442E-9238-8E2FFB62B0BB  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC944A8  
Loading driver at 0x0003E7E9000 EntryPoint=0x0003E7E9273 UefiPxeBcDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC92410  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E7F13F4  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E7F1498  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E7F148C  
Loading driver 4579B72D-7EC4-4DD4-8486-083C86B182A7  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC94328  
Loading driver at 0x0003E7C5000 EntryPoint=0x0003E7C5273 IScsiDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC91E90  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E7D2D08  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E7D2D8C  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E7D2D80  
InstallProtocolInterface: 59324945-EC44-4C0D-B1CD-9DB139DF070C 3E7D3600  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3E7D327C  
InstallProtocolInterface: 330D4706-F2A0-4E4F-A369-B66FA8D54385 3EC91A18  
Loading driver A92CDB4B-82F1-4E0B-A516-8A655D371524  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC941A8  
Loading driver at 0x0003E809000 EntryPoint=0x0003E809273 VirtioNetDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC91010  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E80CF0C  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E80CDFC  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E80CDF0  
Loading driver 2FB92EFA-2EE0-4BAE-9EB6-7464125E1EF7  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC94028  
Loading driver at 0x0003E7E0000 EntryPoint=0x0003E7E0273 UhciDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC90A90  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E7E613C  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E7E61D8  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E7E61CC  
Loading driver BDFE430E-8F2A-4DB0-9991-6F856594777E  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC8EDA8  
Loading driver at 0x0003E7BB000 EntryPoint=0x0003E7BB273 EhciDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC90510  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E7C2548  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E7C319C  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E7C3190  
Loading driver 240612B7-A063-11D4-9A3A-0090273FC14D  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC8EC28  
Loading driver at 0x0003E7B0000 EntryPoint=0x0003E7B0273 UsbBusDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC8DF90  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E7B7680  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E7B7BF0  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E7B7BE4  
Loading driver 2D2E62CF-9ECF-43B7-8219-94E7FC713DFE  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC8EAA8  
Loading driver at 0x0003E7D8000 EntryPoint=0x0003E7D8273 UsbKbDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC8DA10  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E7DD4D4  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E7DDED4  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E7DDEC8  
Loading driver 9FB4B4A7-42C0-4BCD-8540-9BCC6711F83E  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC8E928  
Loading driver at 0x0003E7A9000 EntryPoint=0x0003E7A9273 UsbMassStorageDxe.efi  
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC8D490  
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E7ADD1C  
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E7AE254  
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E7AE248  
Loading driver E3752948-B9A1-4770-90C4-DF41C38986BE  
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3EC8E7A8

```

Loading driver at 0x0003E79E000 EntryPoint=0x0003E79E273 QemuVideoDxe.efi
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EC8CF10
InstallProtocolInterface: 18A031AB-B443-4D1A-A5C0-0C09261E9F71 3E7A27C8
InstallProtocolInterface: 107A772C-D5E1-11D4-9A46-0090273FC14D 3E7A2AA8
InstallProtocolInterface: 6A7A5CFF-E8D9-4F70-BADA-75AB3025CE14 3E7A2A9C
InstallProtocolInterface: 5C198761-16A8-4E69-972C-89D67954F81D 3E7A27E0
[BdsDxe] Locate Variable Lock protocol - Success
[Variable] Lock: 8BE4DF61-93CA-11D2-AA0D-00E098032B8C:PlatformLangCodes
[Variable] Lock: 8BE4DF61-93CA-11D2-AA0D-00E098032B8C:LangCodes
[Variable] Lock: 8BE4DF61-93CA-11D2-AA0D-00E098032B8C:BootOptionSupport
[Variable] Lock: 8BE4DF61-93CA-11D2-AA0D-00E098032B8C:HwErrRecSupport
[Variable] Lock: 8BE4DF61-93CA-11D2-AA0D-00E098032B8C:OsIndicationsSupported
Variable Driver Auto Update Lang, Lang:eng, PlatformLang:en
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3FB6E364
InstallProtocolInterface: 330D4706-F2A0-4E4F-A369-B66FA8D54385 3FB6E394
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3FB6E34C
InstallProtocolInterface: 330D4706-F2A0-4E4F-A369-B66FA8D54385 3FB6E3A0
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3FB6E588
InstallProtocolInterface: 330D4706-F2A0-4E4F-A369-B66FA8D54385 3FB6E57C
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3FB6DFC4
InstallProtocolInterface: 330D4706-F2A0-4E4F-A369-B66FA8D54385 3FB6DFEC
PlatformBdsInit
Registered NotifyDevPath Event
PlatformBdsPolicyBehavior
PCI Bus First Scanning
PciBus: Discovered PCI @ [00|00|00]

PciBus: Discovered PCI @ [00|01|00]

PciBus: Discovered PCI @ [00|01|01]
    BAR[4]: Type = Io32; Alignment = 0xF; Length = 0x10; Offset = 0x20

PciBus: Discovered PCI @ [00|01|03]

PciBus: Discovered PCI @ [00|02|00]
    BAR[0]: Type = PMem32; Alignment = 0x1FFFFFF; Length = 0x2000000; Offset = 0x10
    BAR[1]: Type = Mem32; Alignment = 0xFFFF; Length = 0x1000; Offset = 0x14

PciBus: Discovered PCI @ [00|03|00]
    BAR[0]: Type = Mem32; Alignment = 0x1FFFF; Length = 0x20000; Offset = 0x10
    BAR[1]: Type = Io32; Alignment = 0x3F; Length = 0x40; Offset = 0x14

PciBus: Discovered PCI @ [00|00|00]

PciBus: Discovered PCI @ [00|01|00]

PciBus: Discovered PCI @ [00|01|01]
    BAR[4]: Type = Io32; Alignment = 0xF; Length = 0x10; Offset = 0x20

PciBus: Discovered PCI @ [00|01|03]

PciBus: Discovered PCI @ [00|02|00]
    BAR[0]: Type = PMem32; Alignment = 0x1FFFFFF; Length = 0x2000000; Offset = 0x10
    BAR[1]: Type = Mem32; Alignment = 0xFFFF; Length = 0x1000; Offset = 0x14

PciBus: Discovered PCI @ [00|03|00]
    BAR[0]: Type = Mem32; Alignment = 0x1FFFF; Length = 0x20000; Offset = 0x10
    BAR[1]: Type = Io32; Alignment = 0x3F; Length = 0x40; Offset = 0x14

PciBus: HostBridge->SubmitResources() - Success
PciBus: HostBridge->NotifyPhase(AllocateResources) - Success
PciBus: Resource Map for Root Bridge PciRoot(0x0)
    Type = Io16; Base = 0xC000; Length = 0x1000; Alignment = 0xFFFF
    Base = 0xC000; Length = 0x40; Alignment = 0x3F; Owner = PCI [00|03|00:14]
    Base = 0xC040; Length = 0x10; Alignment = 0xF; Owner = PCI [00|01|01:20]
    Type = Mem32; Base = 0x80000000; Length = 0x2100000; Alignment = 0x1FFFFFF

```

Base = 0x80000000; Length = 0x2000000; Alignment = 0x1FFFFFF; Owner = PCI [00|02|00:10]  
Base = 0x82000000; Length = 0x20000; Alignment = 0x1FFFF; Owner = PCI [00|03|00:10]  
Base = 0x82020000; Length = 0x1000; Alignment = 0xFFFF; Owner = PCI [00|02|00:14]

InstallProtocolInterface: 30CFE3E7-3DE1-4586-BE20-DEABA1B3B793 0  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB70390  
InstallProtocolInterface: 4CF5B200-68B8-4CA5-9EEC-B23E3F50029A 3EC8F018  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB70410  
InstallProtocolInterface: 4CF5B200-68B8-4CA5-9EEC-B23E3F50029A 3EC8F318  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB70490  
InstallProtocolInterface: 4CF5B200-68B8-4CA5-9EEC-B23E3F50029A 3EC8F618  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB70510  
InstallProtocolInterface: 4CF5B200-68B8-4CA5-9EEC-B23E3F50029A 3EB75C18  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB70590  
InstallProtocolInterface: 4CF5B200-68B8-4CA5-9EEC-B23E3F50029A 3EB75918  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB70210  
InstallProtocolInterface: 4CF5B200-68B8-4CA5-9EEC-B23E3F50029A 3EB75618  
PlatformBdsPolicyBehavior: not restoring NvVars from disk since flash variables appear to be supported.  
PlatformBdsGetDriverOption  
Boot Mode:0  
Found LPC Bridge device  
BdsPlatform.c+219: COM1 DevPath: PciRoot(0x0)/Pci(0x1,0x0)/Serial(0x0)/Uart(115200,8,N,1)/VenPcAnsi()  
BdsPlatform.c+248: COM2 DevPath: PciRoot(0x0)/Pci(0x1,0x0)/Serial(0x1)/Uart(115200,8,N,1)/VenPcAnsi()  
Found PCI VGA device  
QemuVideo: Cirrus 5446 detected  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB6D610  
Adding Cirrus Video Mode 0: 640x480, 32-bit, 60 Hz  
Adding Cirrus Video Mode 1: 800x600, 32-bit, 60 Hz  
Adding Cirrus Video Mode 2: 1024x768, 24-bit, 60 Hz  
PixelBlueGreenRedReserved8BitPerColor  
FrameBufferBase: 0x80000000, FrameBufferSize: 0x0  
0: shl:0 shr:0 mask:FF0000  
1: shl:0 shr:0 mask:FF00  
2: shl:0 shr:0 mask:FF  
Bytes per pixel: 4  
InstallProtocolInterface: 9042A9DE-23DC-4A38-96FB-7ADE080516A 3EB6D7A8  
InstallProtocolInterface: 64A892DC-5561-4536-92C7-799BFC183355 3EB6BD98  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB6B910  
InstallProtocolInterface: 7EE2BD44-3DA0-11D4-9A38-0090273FC14D 3EB6BA18  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB6B510  
InstallProtocolInterface: 7EE2BD44-3DA0-11D4-9A38-0090273FC14D 3EB6B618  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB6B190  
InstallProtocolInterface: 7EE2BD44-3DA0-11D4-9A38-0090273FC14D 3EB6B298  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB6AE10  
InstallProtocolInterface: 7EE2BD44-3DA0-11D4-9A38-0090273FC14D 3EB6AF18  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB6AA90  
InstallProtocolInterface: 7EE2BD44-3DA0-11D4-9A38-0090273FC14D 3EB6AB98  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB6A710  
InstallProtocolInterface: 7EE2BD44-3DA0-11D4-9A38-0090273FC14D 3EB6A818  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3EB69F10  
InstallProtocolInterface: BB25CF6F-F1D4-11D2-9A0C-0090273FC1FD 3F842D18  
InstallProtocolInterface: 9E863906-A40F-4875-977F-5B93FF237FC6 3EB69990  
Terminal - Mode 0, Column = 80, Row = 25  
Terminal - Mode 1, Column = 80, Row = 50  
Terminal - Mode 2, Column = 100, Row = 31  
[2J[01;01H[=3h[2J[01;01H[2J[01;01H[=3h[2J[01;01HInstallProtocolInterface:  
09576E91-6D3F-11D2-8E39-00A0C969723B 3EB69490  
[2J[01;01H[=3h[2J[01;01H[2J[01;01H[=3h[2J[01;01HInstallProtocolInterface:  
387477C1-69C7-11D2-8E39-00A0C969723B 3F842B24  
InstallProtocolInterface: DD9E7534-7762-4698-8C14-F58517A625AA 3F842B9C  
InstallProtocolInterface: 387477C2-69C7-11D2-8E39-00A0C969723B 3F842B30  
InstallProtocolInterface: D3B36F2B-D551-11D4-9A46-0090273FC14D 0  
InstallProtocolInterface: D3B36F2C-D551-11D4-9A46-0090273FC14D 0  
InstallProtocolInterface: D3B36F2D-D551-11D4-9A46-0090273FC14D 0  
[2J[01;01H[=3h[2J[01;01H[2J[01;01H[=3h[2J[01;01H[0m[35m[40mPixelBlueGreenRedReserved8BitPerColor  
PixelBlueGreenRedReserved8BitPerColor

PixelBlueGreenRedReserved8BitPerColor  
FrameBufferBase: 0x80000000, FrameBufferSize: 0x0  
0: shl:0 shr:0 mask:FF0000  
1: shl:0 shr:0 mask:FF00  
2: shl:0 shr:0 mask:FF  
Bytes per pixel: 4  
GraphicsConsole video resolution 800 x 600  
Graphics - Mode 0, Column = 80, Row = 25  
Graphics - Mode 1, Column = 0, Row = 0  
Graphics - Mode 2, Column = 100, Row = 31  
InstallProtocolInterface: 387477C2-69C7-11D2-8E39-00A0C969723B 3EB6829C  
InstallProtocolInterface: D3B36F2C-D551-11D4-9A46-0090273FC14D 0  
PixelBlueGreenRedReserved8BitPerColor  
PixelBlueGreenRedReserved8BitPerColor  
InstallProtocolInterface: 9042A9DE-23DC-4A38-96FB-7ADED080516A 3FAF0610  
[2J[01;01H[=3h[2J[01;01H[0m[37m[40mInstallProtocolInterface: 387477C1-69C7-11D2-8E39-00A0C969723B  
3E82A018  
InstallProtocolInterface: DD9E7534-7762-4698-8C14-F58517A625AA 3E82A024  
InstallProtocolInterface: D3B36F2B-D551-11D4-9A46-0090273FC14D 0  
PlatformBdsDiagnostics  
PlatformBdsConnectSequence  
InstallProtocolInterface: 964E5B21-6459-11D2-8E39-00A0C969723B 3F842518  
InstallProtocolInterface: CE345171-BA0B-11D2-8E4F-00A0C969723B 3E808998  
InstallProtocolInterface: 964E5B21-6459-11D2-8E39-00A0C969723B 3F842218  
InstallProtocolInterface: CE345171-BA0B-11D2-8E4F-00A0C969723B 3E808098  
InstallProtocolInterface: A1E37052-80D9-4E65-A317-3E9A55C43EC9 3FAAC348  
InstallProtocolInterface: 69FD8E47-A161-4550-B01A-5594CEB2B2B2 3E7D7A90  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3E7D7810  
InstallProtocolInterface: 964E5B21-6459-11D2-8E39-00A0C969723B 3EC8E318  
InstallProtocolInterface: D432A67F-14DC-484B-B3BB-3F0291849327 3EC8E368  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3E7D7710  
InstallProtocolInterface: 964E5B21-6459-11D2-8E39-00A0C969723B 3EC8E198  
InstallProtocolInterface: D432A67F-14DC-484B-B3BB-3F0291849327 3EC8E1E8  
InstallProtocolInterface: CE345171-BA0B-11D2-8E4F-00A0C969723B 3E77C898  
BlockSize : 512  
LastBlock : 3FFFFFFF  
Valid efi partition table header  
Valid efi partition table header  
Valid primary and Valid backup partition table  
Partition entries read block success  
Number of partition entries: 128  
start check partition entries  
End check partition entries  
Index : 0  
Start LBA : 800  
End LBA : 2F7FF  
Partition size: 2F000  
Start : 100000 End : 5EFFE00  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3E77C410  
InstallProtocolInterface: 964E5B21-6459-11D2-8E39-00A0C969723B 3E807E20  
Index : 1  
Start LBA : 2F800  
End LBA : 5F7FF  
Partition size: 30000  
Start : 5F00000 End : BEFFE00  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3E77C190  
InstallProtocolInterface: 964E5B21-6459-11D2-8E39-00A0C969723B 3E807B20  
Index : 2  
Start LBA : 5F800  
End LBA : 2FFFFFFF  
Partition size: 2A0800  
Start : BF00000 End : 5FFFFFFE00  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3E77BE90  
InstallProtocolInterface: 964E5B21-6459-11D2-8E39-00A0C969723B 3E807A20  
Index : 3  
Start LBA : 300000

End LBA : 3FF7FF  
Partition size: FF800  
Start : 60000000 End : 7FEFFE00  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3E77BB90  
InstallProtocolInterface: 964E5B21-6459-11D2-8E39-00A0C969723B 3E807920  
Prepare to Free Pool  
InstallProtocolInterface: CE345171-BA0B-11D2-8E4F-00A0C969723B 3E77B718  
BlockSize : 512  
LastBlock : 2EFFF  
InstallProtocolInterface: CE345171-BA0B-11D2-8E4F-00A0C969723B 3E77B218  
BlockSize : 512  
LastBlock : 2FFFF  
InstallProtocolInterface: 964E5B22-6459-11D2-8E39-00A0C969723B 3E779020  
InstallProtocolInterface: CE345171-BA0B-11D2-8E4F-00A0C969723B 3E77AB98  
BlockSize : 512  
LastBlock : 2A07FF  
InstallProtocolInterface: CE345171-BA0B-11D2-8E4F-00A0C969723B 3E77A698  
BlockSize : 512  
LastBlock : FF7FF  
InstallProtocolInterface: CE345171-BA0B-11D2-8E4F-00A0C969723B 3E77A218  
BlockSize : 2048  
LastBlock : 0  
InstallProtocolInterface: CE345171-BA0B-11D2-8E4F-00A0C969723B 3E77A118  
BlockSize : 2048  
LastBlock : 50FFF  
InstallProtocolInterface: 09576E91-6D3F-11D2-8E39-00A0C969723B 3E29BE10  
InstallProtocolInterface: 964E5B21-6459-11D2-8E39-00A0C969723B 3E807C20  
InstallProtocolInterface: CE345171-BA0B-11D2-8E4F-00A0C969723B 3E29B918  
BlockSize : 2048  
LastBlock : 3  
BlockSize : 2048  
LastBlock : 3  
BlockSize : 512  
LastBlock : 3FFFFFF  
Valid efi partition table header  
Valid efi partition table header  
Valid primary and Valid backup partition table  
Partition entries read block success  
Number of partition entries: 128  
start check partition entries  
End check partition entries  
Index : 0  
Start LBA : 800  
End LBA : 2F7FF  
Partition size: 2F000  
Start : 100000 End : 5EFFE00  
Index : 1  
Start LBA : 2F800  
End LBA : 5F7FF  
Partition size: 30000  
Start : 5F0000 End : BEFFE00  
Index : 2  
Start LBA : 5F800  
End LBA : 2FFFFFF  
Partition size: 2A0800  
Start : BF0000 End : 5FFFFFFE00  
Index : 3  
Start LBA : 300000  
End LBA : 3FF7FF  
Partition size: FF800  
Start : 60000000 End : 7FEFFE00  
Prepare to Free Pool  
BlockSize : 512  
LastBlock : 2EFFF  
BlockSize : 512  
LastBlock : 2A07FF

```
BlockSize : 512
LastBlock : FF7FF
BlockSize : 2048
LastBlock : 50FFF
BlockSize : 2048
LastBlock : 3
[2][01;01HSelect Item: 0x8
Select Item: 0x17
qemu -kernel was not used.
BdsLibConnectAll
BlockSize : 512
LastBlock : 3FFFFFF
Valid efi partition table header
Valid efi partition table header
Valid primary and Valid backup partition table
Partition entries read block success
Number of partition entries: 128
start check partition entries
End check partition entries
Index : 0
Start LBA : 800
End LBA : 2F7FF
Partition size: 2F000
Start : 100000 End : 5EFFE00
Index : 1
Start LBA : 2F800
End LBA : 5F7FF
Partition size: 30000
Start : 5F00000 End : BEFFE00
Index : 2
Start LBA : 5F800
End LBA : 2FFFFFF
Partition size: 2A0800
Start : BF00000 End : 5FFFFFFE00
Index : 3
Start LBA : 300000
End LBA : 3FF7FF
Partition size: FF800
Start : 60000000 End : 7FEFFE00
Prepare to Free Pool
BlockSize : 512
LastBlock : 2EFFF
BlockSize : 512
LastBlock : 2A07FF
BlockSize : 512
LastBlock : FF7FF
BlockSize : 2048
LastBlock : 50FFF
BlockSize : 2048
LastBlock : 3
BlockSize : 512
LastBlock : 3FFFFFF
Valid efi partition table header
Valid efi partition table header
Valid primary and Valid backup partition table
Partition entries read block success
Number of partition entries: 128
start check partition entries
End check partition entries
Index : 0
Start LBA : 800
End LBA : 2F7FF
Partition size: 2F000
Start : 100000 End : 5EFFE00
Index : 1
Start LBA : 2F800
```

End LBA : 5F7FF  
Partition size: 30000  
Start : 5F00000 End : BEFFE00  
Index : 2  
Start LBA : 5F800  
End LBA : 2FFFFFF  
Partition size: 2A0800  
Start : BF00000 End : 5FFFFFFE00  
Index : 3  
Start LBA : 300000  
End LBA : 3FF7FF  
Partition size: FF800  
Start : 60000000 End : 7FEFFE00  
Prepare to Free Pool  
BlockSize : 512  
LastBlock : 2EFFF  
BlockSize : 512  
LastBlock : 2A07FF  
BlockSize : 512  
LastBlock : FF7FF  
BlockSize : 2048  
LastBlock : 50FFF  
BlockSize : 2048  
LastBlock : 3  
BlockSize : 512  
LastBlock : 3FFFFFF  
Valid efi partition table header  
Valid efi partition table header  
Valid primary and Valid backup partition table  
Partition entries read block success  
Number of partition entries: 128  
start check partition entries  
End check partition entries  
Index : 0  
Start LBA : 800  
End LBA : 2F7FF  
Partition size: 2F000  
Start : 100000 End : 5EFFE00  
Index : 1  
Start LBA : 2F800  
End LBA : 5F7FF  
Partition size: 30000  
Start : 5F00000 End : BEFFE00  
Index : 2  
Start LBA : 5F800  
End LBA : 2FFFFFF  
Partition size: 2A0800  
Start : BF00000 End : 5FFFFFFE00  
Index : 3  
Start LBA : 300000  
End LBA : 3FF7FF  
Partition size: FF800  
Start : 60000000 End : 7FEFFE00  
Prepare to Free Pool  
BlockSize : 512  
LastBlock : 2EFFF  
BlockSize : 512  
LastBlock : 2A07FF  
BlockSize : 512  
LastBlock : FF7FF  
BlockSize : 2048  
LastBlock : 50FFF  
BlockSize : 2048  
LastBlock : 3  
BlockSize : 512  
LastBlock : 2EFFF

BlockSize : 512  
LastBlock : 2A07FF  
BlockSize : 512  
LastBlock : FF7FF  
BlockSize : 2048  
LastBlock : 3  
Buffer: EFI DVD/CDROM  
Buffer: EFI Hard Drive  
Select Item: 0x19  
PixelBlueGreenRedReserved8BitPerColor  
PixelBlueGreenRedReserved8BitPerColor  
Memory Previous Current Next  
Type Pages Pages Pages  
=====

0A	00000004	00000001	00000004
09	00000008	00000006	00000008
00	00000004	00000003	00000004
06	00000024	0000002E	00000039
05	00000030	0000002D	00000030
03	00000180	0000022D	000002B8
04	00000F00	00001732	00001CFE

Booting EFI Floppy  
PlatformBdsBootFail  
Boot Failed. EFI Floppy

PixelBlueGreenRedReserved8BitPerColor  
PixelBlueGreenRedReserved8BitPerColor  
Memory Previous Current Next  
Type Pages Pages Pages  
=====

0A	00000004	00000001	00000004
09	00000008	00000006	00000008
00	00000004	00000003	00000004
06	00000039	0000002E	00000039
05	00000030	0000002D	00000030
03	000002B8	0000022D	000002B8
04	00001CFE	00001732	00001CFE

Booting EFI Floppy 1  
PlatformBdsBootFail  
Boot Failed. EFI Floppy 1

PixelBlueGreenRedReserved8BitPerColor  
PixelBlueGreenRedReserved8BitPerColor  
Memory Previous Current Next  
Type Pages Pages Pages  
=====

0A	00000004	00000001	00000004
09	00000008	00000006	00000008
00	00000004	00000003	00000004
06	00000039	0000002E	00000039
05	00000030	0000002D	00000030
03	000002B8	0000022D	000002B8
04	00001CFE	00001732	00001CFE

Booting EFI DVD/CDROM  
BlockSize : 2048  
LastBlock : 50FFF  
BlockSize : 2048  
LastBlock : 3  
PlatformBdsBootFail  
Boot Failed. EFI DVD/CDROM

PixelBlueGreenRedReserved8BitPerColor  
PixelBlueGreenRedReserved8BitPerColor  
Memory Previous Current Next  
Type Pages Pages Pages  
=====



```

0A 00000004 00000001 00000004
09 00000008 00000006 00000008
00 00000004 00000003 00000004
06 00000039 0000002E 00000039
05 00000030 0000002D 00000030
03 000002B8 0000022D 000002B8
04 00001CFE 00001732 00001CFE
Booting EFI Hard Drive
BlockSize : 512
LastBlock : 3FFFFFF
Valid efi partition table header
Valid efi partition table header
Valid primary and Valid backup partition table
Partition entries read block success
Number of partition entries: 128
start check partition entries
End check partition entries
Index : 0
Start LBA : 800
End LBA : 2F7FF
Partition size: 2F000
Start : 100000 End : 5EFFF00
Index : 1
Start LBA : 2F800
End LBA : 5F7FF
Partition size: 30000
Start : 5F0000 End : BEFFF00
Index : 2
Start LBA : 5F800
End LBA : 2FFFFFF
Partition size: 2A0800
Start : BF0000 End : 5FFFFFF00
Index : 3
Start LBA : 300000
End LBA : 3FF7FF
Partition size: FF800
Start : 60000000 End : 7EFFF00
Prepare to Free Pool
BlockSize : 512
LastBlock : 2EFFF
BlockSize : 512
LastBlock : 2A07FF
BlockSize : 512
LastBlock : FF7FF
InstallProtocolInterface: 5B1B31A1-9562-11D2-8E3F-00A0C969723B 3E255DA8
Loading driver at 0x0003E23F000 EntryPoint=0x0003E23F400
InstallProtocolInterface: BC62157E-3E33-4FEC-9920-2D3B36D750DF 3EB75F10
[1m[37m[40merror: file not found.

```

error: file not found.

```

[ 0.000000] Initializing cgroup subsys cpuset
[ 0.000000] Initializing cgroup subsys cpu
[ 0.000000] Linux version 3.8.0-29-generic (bulld@akateko) (gcc version 4.6.3 (Ubuntu/Linaro
4.6.3-1ubuntu5) ) #42~precise1-Ubuntu SMP Wed Aug 14 15:31:16 UTC 2013 (Ubuntu
3.8.0-29.42~precise1-generic 3.8.13.5)
[ 0.000000] KERNEL supported cpus:
[ 0.000000] Intel GenuineIntel
[ 0.000000] AMD AuthenticAMD
[ 0.000000] NSC Geode by NSC
[ 0.000000] Cyrix CyrixInstead
[ 0.000000] Centaur CentaurHauls
[ 0.000000] Transmeta GenuineTMx86
[ 0.000000] Transmeta TransmetaCPU
[ 0.000000] UMC UMC UMC UMC
[ 0.000000] e820: BIOS-provided physical RAM map:

```

```

[ 0.000000] BIOS-e820: [mem 0x0000000000000000-0x00000000009ffff] usable
[ 0.000000] BIOS-e820: [mem 0x0000000000100000-0x0000000003e855fff] usable
[ 0.000000] BIOS-e820: [mem 0x0000000003e856000-0x0000000003e864fff] reserved
[ 0.000000] BIOS-e820: [mem 0x0000000003e865000-0x0000000003fbc4fff] usable
[ 0.000000] BIOS-e820: [mem 0x0000000003fbc5000-0x0000000003fc3cfff] reserved
[ 0.000000] BIOS-e820: [mem 0x0000000003fc3d000-0x0000000003fc44fff] ACPI data
[ 0.000000] BIOS-e820: [mem 0x0000000003fc45000-0x0000000003fc48fff] ACPI NVS
[ 0.000000] BIOS-e820: [mem 0x0000000003fc49000-0x0000000003ffcffff] usable
[ 0.000000] BIOS-e820: [mem 0x0000000003ffd0000-0x0000000003fffffff] reserved
[ 0.000000] BIOS-e820: [mem 0x000000000ffe00000-0x000000000ffffffff] reserved
[ 0.000000] Notice: NX (Execute Disable) protection missing in CPU!
[ 0.000000] efi: EFI v2.40 by EDK II
[ 0.000000] efi: ACPI=0x3fc44000 ACPI 2.0=0x3fc44014
[ 0.000000] efi: mem00: type=7, attr=0xf, range=[0x0000000000000000-0x00000000000a0000] (0MB)
[ 0.000000] efi: mem01: type=2, attr=0xf, range=[0x0000000000100000-0x000000000062c000] (5MB)
[ 0.000000] efi: mem02: type=7, attr=0xf, range=[0x000000000062c000-0x0000000000800000] (1MB)
[ 0.000000] efi: mem03: type=4, attr=0xf, range=[0x0000000000800000-0x0000000001000000] (8MB)
[ 0.000000] efi: mem04: type=7, attr=0xf, range=[0x0000000001000000-0x0000000002c9b4000] (697MB)
[ 0.000000] efi: mem05: type=2, attr=0xf, range=[0x0000000002c9b4000-0x0000000003c000000] (246MB)
[ 0.000000] efi: mem06: type=4, attr=0xf, range=[0x0000000003c000000-0x0000000003c020000] (0MB)
[ 0.000000] efi: mem07: type=7, attr=0xf, range=[0x0000000003c020000-0x0000000003e23f000] (34MB)
[ 0.000000] efi: mem08: type=1, attr=0xf, range=[0x0000000003e23f000-0x0000000003e255000] (0MB)
[ 0.000000] efi: mem09: type=4, attr=0xf, range=[0x0000000003e255000-0x0000000003e256000] (0MB)
[ 0.000000] efi: mem10: type=7, attr=0xf, range=[0x0000000003e256000-0x0000000003e26b000] (0MB)
[ 0.000000] efi: mem11: type=4, attr=0xf, range=[0x0000000003e26b000-0x0000000003e79e000] (5MB)
[ 0.000000] efi: mem12: type=3, attr=0xf, range=[0x0000000003e79e000-0x0000000003e7d7000] (0MB)
[ 0.000000] efi: mem13: type=4, attr=0xf, range=[0x0000000003e7d7000-0x0000000003e7d8000] (0MB)
[ 0.000000] efi: mem14: type=3, attr=0xf, range=[0x0000000003e7d8000-0x0000000003e807000] (0MB)
[ 0.000000] efi: mem15: type=4, attr=0xf, range=[0x0000000003e807000-0x0000000003e809000] (0MB)
[ 0.000000] efi: mem16: type=3, attr=0xf, range=[0x0000000003e809000-0x0000000003e829000] (0MB)
[ 0.000000] efi: mem17: type=4, attr=0xf, range=[0x0000000003e829000-0x0000000003e82d000] (0MB)
[ 0.000000] efi: mem18: type=3, attr=0xf, range=[0x0000000003e82d000-0x0000000003e856000] (0MB)
[ 0.000000] efi: mem19: type=6, attr=0x800000000000000f,
range=[0x0000000003e856000-0x0000000003e865000] (0MB)
[ 0.000000] efi: mem20: type=4, attr=0xf, range=[0x0000000003e865000-0x0000000003fa65000] (18MB)
[ 0.000000] efi: mem21: type=2, attr=0xf, range=[0x0000000003fa65000-0x0000000003fa69000] (0MB)
[ 0.000000] efi: mem22: type=3, attr=0xf, range=[0x0000000003fa69000-0x0000000003fbc5000] (1MB)
[ 0.000000] efi: mem23: type=5, attr=0x800000000000000f,
range=[0x0000000003fbc5000-0x0000000003fc15000] (0MB)
[ 0.000000] efi: mem24: type=6, attr=0x800000000000000f,
range=[0x0000000003fc15000-0x0000000003fc39000] (0MB)
[ 0.000000] efi: mem25: type=0, attr=0xf, range=[0x0000000003fc39000-0x0000000003fc3d000] (0MB)
[ 0.000000] efi: mem26: type=9, attr=0xf, range=[0x0000000003fc3d000-0x0000000003fc45000] (0MB)
[ 0.000000] efi: mem27: type=10, attr=0xf, range=[0x0000000003fc45000-0x0000000003fc49000] (0MB)
[ 0.000000] efi: mem28: type=4, attr=0xf, range=[0x0000000003fc49000-0x0000000003ffd0000] (3MB)
[ 0.000000] efi: mem29: type=6, attr=0x800000000000000f,
range=[0x0000000003ffd0000-0x00000000040000000] (0MB)
[ 0.000000] efi: mem30: type=6, attr=0x8000000000000001,
range=[0x000000000ffe00000-0x00000000100000000] (2MB)
[ 0.000000] DMI not present or invalid.
[ 0.000000] e820: last_pfn = 0x3ffd0 max_arch_pfn = 0x1000000
[ 0.000000] init_memory_mapping: [mem 0x00000000-0x37bfdfff]
[ 0.000000] RAMDISK: [mem 0x361b6000-0x370d2fff]
[ 0.000000] ACPI: RSDP 3fc44014 00024 (v02 OVMF )
[ 0.000000] ACPI: XSDT 3fc430e8 0003C (v01 OVMF OVMFEDK2 20130221 01000013)
[ 0.000000] ACPI: FACP 3fc42000 000F4 (v03 OVMF OVMFEDK2 20130221 OVMF 00000099)
[ 0.000000] ACPI: DSDT 3fc40000 00D57 (v01 INTEL OVMF 00000004 INTL 20100528)
[ 0.000000] ACPI: FACS 3fc48000 00040
[ 0.000000] ACPI: APIC 3fc41000 00078 (v01 OVMF OVMFEDK2 20130221 OVMF 00000099)
[ 0.000000] ACPI: SSDT 3fc3f000 00057 (v01 REDHAT OVMF 00000001 INTL 20100528)
[ 0.000000] ACPI: no DMI BIOS year, acpi=force is required to enable ACPI
[ 0.000000] ACPI: Disabling ACPI support
[ 0.000000] 131MB HIGHMEM available.
[ 0.000000] 891MB LOWMEM available.
[ 0.000000] mapped low ram: 0 - 37bfe000
[ 0.000000] low ram: 0 - 37bfe000

```

```

[ 0.000000] Zone ranges:
[ 0.000000]   DMA      [mem 0x00010000-0x00ffffff]
[ 0.000000]   Normal   [mem 0x01000000-0x37bdfcff]
[ 0.000000]   HighMem   [mem 0x37bfe000-0x3ffcff]
[ 0.000000] Movable zone start for each node
[ 0.000000] Early memory node ranges
[ 0.000000]   node 0: [mem 0x00010000-0x0009ffff]
[ 0.000000]   node 0: [mem 0x00010000-0x3e85ffff]
[ 0.000000]   node 0: [mem 0x3e865000-0x3fbe4fff]
[ 0.000000]   node 0: [mem 0x3fc49000-0x3ffcff]
[ 0.000000] Using APIC driver default
[ 0.000000] SFI: Simple Firmware Interface v0.81 http://simplefirmware.org
[ 0.000000] smpboot: Allowing 1 CPUs, 0 hotplug CPUs
[ 0.000000] Found and enabled local APIC!
[ 0.000000] PM: Registered nosave memory: 00000000000a0000 - 0000000001000000
[ 0.000000] e820: [mem 0x40000000-0xffdfcff] available for PCI devices
[ 0.000000] Booting paravirtualized kernel on bare hardware
[ 0.000000] setup_percpu: NR_CPUS:8 nr_cpumask_bits:8 nr_cpu_ids:1 nr_node_ids:1
[ 0.000000] PERCPU: Embedded 14 pages/cpu @f73e8000 s35008 r0 d22336 u57344
[ 0.000000] Built 1 zonelists in Zone order, mobility grouping on. Total pages: 259821
[ 0.000000] Kernel command line: BOOT_IMAGE=/boot/vmlinuz-3.8.0-29-generic
root=UUID=7209eb2b-e09b-43d8-9f95-3356365f1111 ro console=ttyS0,115200n8 nomodeset loglevel=7
earlyprintk
[ 0.000000] PID hash table entries: 4096 (order: 2, 16384 bytes)
[ 0.000000] Dentry cache hash table entries: 131072 (order: 7, 524288 bytes)
[ 0.000000] Inode-cache hash table entries: 65536 (order: 6, 262144 bytes)
[ 0.000000] __ex_table already sorted, skipping sort
[ 0.000000] Initializing CPU#0
[ 0.000000] allocated 2096640 bytes of page_cgroup
[ 0.000000] please try 'cgroup_disable=memory' option if you don't want memory cgroups
[ 0.000000] Initializing HighMem for node 0 (00037bfe:0003ffdf)
[ 0.000000] Memory: 979948k/1048384k available (6359k kernel code, 37772k reserved, 3033k data, 796k
init, 104768k highmem)
[ 0.000000] virtual kernel memory layout:
[ 0.000000]   fixmap  : 0xffff14000 - 0xfffff000   ( 940 kB)
[ 0.000000]   pkmap   : 0xffc00000 - 0xffe00000   (2048 kB)
[ 0.000000]   vmalloc : 0xf83fe000 - 0xffbfe000   ( 120 MB)
[ 0.000000]   lowmem   : 0xc0000000 - 0xf7bfe000   ( 891 MB)
[ 0.000000]     .init   : 0xc192d000 - 0xc19f4000   ( 796 kB)
[ 0.000000]     .data   : 0xc1635dad - 0xc192c280   (3033 kB)
[ 0.000000]     .text   : 0xc1000000 - 0xc1635dad   (6359 kB)
[ 0.000000] Checking if this processor honours the WP bit even in supervisor mode...Ok.
[ 0.000000] SLUB: Genslabs=15, HWalig=32, Order=0-3, MinObjects=0, CPUs=1, Nodes=1
[ 0.000000] Hierarchical RCU implementation.
[ 0.000000] RCU dyntick-idle grace-period acceleration is enabled.
[ 0.000000] RCU restricting CPUs from NR_CPUS=8 to nr_cpu_ids=1.
[ 0.000000] NR_IRQS:2304 nr_irqs:256 16
[ 0.000000] Console: colour dummy device 80x25
[ 0.000000] console [ttyS0] enabled
[ 0.000000] tsc: Fast TSC calibration using PIT
[ 0.000000] tsc: Detected 3392.285 MHz processor
[ 0.008248] Calibrating delay loop (skipped), value calculated using timer frequency.. 6784.57
BogoMIPS (lpj=13569140)
[ 0.008711] pid_max: default: 32768 minimum: 301
[ 0.012820] -----[ cut here ]-----
[ 0.013314] WARNING: at /build/build/linux-lts-raring-3.8.0/arch/x86/mm/ioremap.c:102
__ioremap_caller+0x430/0x460()
[ 0.013597] Modules linked in:
[ 0.013845] Pid: 0, comm: swapper/0 Not tainted 3.8.0-29-generic #42~precise1-Ubuntu
[ 0.014051] Call Trace:
[ 0.014327] [<104b7f2>] warn_slowpath_common+0x72/0xa0
[ 0.014498] [<103f280>] ? __ioremap_caller+0x430/0x460
[ 0.014640] [<103f280>] ? __ioremap_caller+0x430/0x460
[ 0.014782] [<104b842>] warn_slowpath_null+0x22/0x30
[ 0.014923] [<103f280>] __ioremap_caller+0x430/0x460
[ 0.015079] [<1153fa5>] ? __kmalloctack_caller+0x1d5/0x1e0

```

```

[ 0.015236] [<c1944552>] ? efi_enter_virtual_mode+0x17e/0x3d4
[ 0.015389] [<c103f2ff>] ioremap_cache+0x1f/0x30
[ 0.015520] [<c1944552>] ? efi_enter_virtual_mode+0x17e/0x3d4
[ 0.015672] [<c1944552>] efi_enter_virtual_mode+0x17e/0x3d4
[ 0.015820] [<c104f318>] ? put_online_cpus+0x48/0x70
[ 0.016039] [<c112e608>] ? kmem_cache_create_memcg+0x68/0x1e0
[ 0.016239] [<c192d98b>] start_kernel+0x2ec/0x37d
[ 0.016378] [<c192d620>] ? pass_bootoption.constprop.3+0xaf/0xaf
[ 0.016535] [<c192d303>] i386_start_kernel+0xa6/0xad
[ 0.018504] ---[ end trace a7919e7f17c0a725 ]---
[ 0.037390] Security Framework initialized
[ 0.041271] AppArmor: AppArmor initialized
[ 0.041398] Yama: becoming mindful.
[ 0.043429] Mount-cache hash table entries: 512
[ 0.049804] Initializing cgroup subsys cpuacct
[ 0.050022] Initializing cgroup subsys memory
[ 0.050468] Initializing cgroup subsys devices
[ 0.050615] Initializing cgroup subsys freezer
[ 0.050789] Initializing cgroup subsys blkio
[ 0.050918] Initializing cgroup subsys perf_event
[ 0.051075] Initializing cgroup subsys hugetlb
[ 0.053277] Last level iTLB entries: 4KB 0, 2MB 0, 4MB 0
[ 0.053277] Last level dTLB entries: 4KB 0, 2MB 0, 4MB 0
[ 0.053277] tlb_flushall_shift: 6
[ 0.141769] Freeing SMP alternatives: 24k freed
[ 0.161994] ftrace: allocating 28848 entries in 57 pages
[ 0.244438] smpboot: weird, boot CPU (#0) not listed by the BIOS
[ 0.244753] smpboot: SMP motherboard not detected
[ 0.244963] Enabling APIC mode: Flat. Using 0 I/O APICs
[ 0.352651] smpboot: SMP disabled
[ 0.352823] Performance Events: Broken PMU hardware detected, using software events only.
[ 0.353230] Failed to access perfctr msr (MSR c1 is 0)
[ 0.364326] Brought up 1 CPUs
[ 0.364460] smpboot: Total of 1 processors activated (6784.57 BogoMIPS)
[ 0.367329] NMI watchdog: disabled (cpu0): hardware events not enabled
[ 0.374045] devtmpfs: initialized
[ 0.378072] EVM: security.selinux
[ 0.378156] EVM: security.SMACK64
[ 0.378230] EVM: security.capability
[ 0.379089] PM: Registering ACPI NVS region [mem 0x3fc45000-0x3fc48fff] (16384 bytes)
[ 0.389784] regulator-dummy: no parameters
[ 0.391591] NET: Registered protocol family 16
[ 0.394134] EISA bus registered
[ 0.396412] PCI: Using configuration type 1 for base access
[ 0.408172] bio: create slab <bio-0> at 0
[ 0.409910] ACPI: Interpreter disabled.
[ 0.412510] vgaarb: loaded
[ 0.415295] SCSI subsystem initialized
[ 0.416555] usbcore: registered new interface driver usbfs
[ 0.416886] usbcore: registered new interface driver hub
[ 0.417242] usbcore: registered new device driver usb
[ 0.418918] PCI: Probing PCI hardware
[ 0.419564] PCI host bridge to bus 0000:00
[ 0.420000] pci_bus 0000:00: root bus resource [io 0x0000-0xffff]
[ 0.420000] pci_bus 0000:00: root bus resource [mem 0x00000000-0xffffffff]
[ 0.420000] pci_bus 0000:00: No busn resource found for root bus, will use [bus 00-ff]
[ 0.429228] pci 0000:00:01.3: quirk: [io 0xb000-0xb03f] claimed by PIIX4 ACPI
[ 0.429412] pci 0000:00:01.3: quirk: [io 0xb100-0xb10f] claimed by PIIX4 SMB
[ 0.471099] vgaarb: device added: PCI:0000:00:02.0,decodes=io+mem,owns=io+mem,locks=None
[ 0.473807] NetLabel: Initializing
[ 0.473900] NetLabel: domain hash size = 128
[ 0.473998] NetLabel: protocols = UNLABELED CIPSOv4
[ 0.474748] NetLabel: unlabeled traffic allowed by default
[ 0.475756] Switching to clocksource refined-jiffies
[ 0.553439] AppArmor: AppArmor Filesystem Enabled
[ 0.553853] pnp: PnP ACPI: disabled

```

```

[ 0.553973] PnPBIOS: Scanning system for PnP BIOS support...
[ 0.554119] PnPBIOS: PnP BIOS support was not detected.
[ 0.569397] pci 0000:00:02.0: address space collision: [mem 0xffff0000-0xffffffff pref] conflicts
with reserved [mem 0xffe00000-0xffffffff]
[ 0.569684] pci 0000:00:03.0: address space collision: [mem 0xfffe0000-0xffffffff pref] conflicts
with reserved [mem 0xffe00000-0xffffffff]
[ 0.570891] pci 0000:00:03.0: BAR 6: assigned [mem 0x40000000-0x4001ffff pref]
[ 0.571224] pci 0000:00:02.0: BAR 6: assigned [mem 0x40020000-0x4002ffff pref]
[ 0.572071] NET: Registered protocol family 2
[ 0.575129] TCP established hash table entries: 8192 (order: 4, 65536 bytes)
[ 0.575451] TCP bind hash table entries: 8192 (order: 4, 65536 bytes)
[ 0.575777] TCP: Hash tables configured (established 8192 bind 8192)
[ 0.576225] TCP: reno registered
[ 0.576403] UDP hash table entries: 512 (order: 2, 16384 bytes)
[ 0.576621] UDP-Lite hash table entries: 512 (order: 2, 16384 bytes)
[ 0.578150] NET: Registered protocol family 1
[ 0.578467] pci 0000:00:00.0: Limiting direct PCI/PCI transfers
[ 0.578657] pci 0000:00:01.0: PIIX3: Enabling Passive Release
[ 0.578901] pci 0000:00:01.0: Activating ISA DMA hang workarounds
[ 0.581954] Trying to unpack rootfs image as initramfs...
[ 1.981643] Freeing initrd memory: 15476k freed
[ 1.998004] platform rtc_cmos: registered platform RTC device (no PNP device found)
[ 2.000919] Initialise module verification
[ 2.002016] audit: initializing netlink socket (disabled)
[ 2.002641] type=2000 audit(1385194101.000:1): initialized
[ 2.087887] bounce pool size: 64 pages
[ 2.088424] HugeTLB registered 2 MB page size, pre-allocated 0 pages
[ 2.100762] VFS: Disk quotas dquot_6.5.2
[ 2.101235] Dquot-cache hash table entries: 1024 (order 0, 4096 bytes)
[ 2.107932] fuse init (API version 7.20)
[ 2.108951] msgmni has been set to 1797
[ 2.114662] Key type asymmetric registered
[ 2.114803] Asymmetric key parser 'x509' registered
[ 2.115232] Block layer SCSI generic (bsg) driver version 0.4 loaded (major 252)
[ 2.115706] io scheduler noop registered
[ 2.115834] io scheduler deadline registered (default)
[ 2.116221] io scheduler cfq registered
[ 2.117720] pci_hotplug: PCI Hot Plug PCI Core version: 0.5
[ 2.118453] pciehp: PCI Express Hot Plug Controller Driver version: 0.4
[ 2.119431] efifb: probing for efifb
[ 2.120683] efifb: framebuffer at 0x80000000, mapped to 0xfa580000, using 1408k, total 1408k
[ 2.120869] efifb: mode is 800x600x24, linelength=2400, pages=1
[ 2.121000] efifb: scrolling: redraw
[ 2.121117] efifb: Truecolor: size=0:8:8:8, shift=0:16:8:0
[ 2.138993] Console: switching to colour frame buffer device 100x37
[ 2.153450] fb0: EFI VGA frame buffer device
[ 2.155526] Serial: 8250/16550 driver, 32 ports, IRQ sharing enabled
[ 2.160105] serial8250: ttyS0 at I/O 0x3f8 (irq = 4) is a 16550A
[ 2.160105] isapnp: Scanning for PnP cards...
[ 2.219438] Linux agpgart interface v0.103
[ 2.231672] brd: module loaded
[ 2.280936] loop: module loaded
[ 2.287501] scsi0 : ata_piix
[ 2.288441] scsi1 : ata_piix
[ 2.288993] ata1: PATA max MWDMA2 cmd 0x1f0 ctl 0x3f6 bmdma 0xc040 irq 14
[ 2.289166] ata2: PATA max MWDMA2 cmd 0x170 ctl 0x376 bmdma 0xc048 irq 15
[ 2.295005] libphy: Fixed MDIO Bus: probed
[ 2.295910] tun: Universal TUN/TAP device driver, 1.6
[ 2.296027] tun: (C) 1999-2004 Max Krasnyansky <maxk@qualcomm.com>
[ 2.296113] PPP generic driver version 2.4.2
[ 2.296113] ehci_hcd: USB 2.0 'Enhanced' Host Controller (EHCI) Driver
[ 2.296113] ehci-pci: EHCI PCI platform driver
[ 2.296113] ehci-platform: EHCI generic platform driver
[ 2.296113] ohci_hcd: USB 1.1 'Open' Host Controller (OHCI) Driver
[ 2.296113] uhci_hcd: USB Universal Host Controller Interface driver
[ 2.296113] i8042: PNP: No PS/2 controller found. Probing ports directly.

```

```

[ 2.300908] serio: i8042 KBD port at 0x60,0x64 irq 1
[ 2.301161] serio: i8042 AUX port at 0x60,0x64 irq 12
[ 2.302430] mousedev: PS/2 mouse device common for all mice
[ 2.305234] input: AT Translated Set 2 keyboard as /devices/platform/i8042/serio0/input/input0
[ 2.308541] rtc_cmos rtc_cmos: rtc core: registered rtc_cmos as rtc0
[ 2.308955] rtc0: alarms up to one day, 114 bytes nvram
[ 2.309718] device-mapper: uevent: version 1.0.3
[ 2.310401] device-mapper: ioctl: 4.23.1-ioclt (2012-12-18) initialised: dm-devel@redhat.com
[ 2.310778] EISA: Probing bus 0 at eisa.0
[ 2.311228] EISA: Detected 0 cards.
[ 2.311654] cpufreq-nforce2: No nForce2 chipset.
[ 2.311850] cpuidle: using governor ladder
[ 2.311989] cpuidle: using governor menu
[ 2.312114] ledtrig-cpu: registered to indicate activity on CPUs
[ 2.312114] EFI Variables Facility v0.08 2004-May-17
[ 2.312847] ashmem: initialized
[ 2.314151] TCP: cubic registered
[ 2.315043] NET: Registered protocol family 10
[ 2.319096] NET: Registered protocol family 17
[ 2.319448] Key type dns_resolver registered
[ 2.320178] Using IPI No-Shortcut mode
[ 2.321185] Loading module verification certificates
[ 2.388343] MODSIGN: Loaded cert 'Magrathea: Glacier signing key:
760b08a5a1de9684ced1bfd52640b05fe41b6ca5'
[ 2.388749] registered taskstats version 1
[ 2.463282] ata2.00: ATAPI: QEMU DVD-ROM, 1.5.0, max UDMA/100
[ 2.464589] ata2.00: configured for MWDMA2
[ 2.481977] ata1.00: ATA-7: QEMU HARDDISK, 1.5.0, max UDMA/100
[ 2.482142] ata1.00: 4194304 sectors, multi 16: LBA48
[ 2.482615] ata1.00: configured for MWDMA2
[ 2.630200] Key type trusted registered
[ 2.723604] isapnp: No Plug & Play device found
[ 2.733063] scsi 0:0:0:0: Direct-Access ATA QEMU HARDDISK 1.5. PQ: 0 ANSI: 5
[ 2.734854] sd 0:0:0:0: Attached scsi generic sg0 type 0
[ 2.736626] scsi 1:0:0:0: CD-ROM QEMU QEMU DVD-ROM 1.5. PQ: 0 ANSI: 5
[ 2.738871] sr0: scsi3-mmc drive: 4x/4x cd/rw xa/form2 tray
[ 2.739137] cdrom: Uniform CD-ROM driver Revision: 3.20
[ 2.746183] sr 1:0:0:0: Attached scsi generic sg1 type 5
[ 2.746880] sd 0:0:0:0: [sda] 4194304 512-byte logical blocks: (2.14 GB/2.00 GiB)
[ 2.749208] sd 0:0:0:0: [sda] Write Protect is off
[ 2.749720] sd 0:0:0:0: [sda] Write cache: enabled, read cache: enabled, doesn't support DPO or FUA
[ 2.770299] sda: sda1 sda2 sda3 sda4
[ 2.781197] sd 0:0:0:0: [sda] Attached SCSI disk
[ 2.817305] Key type encrypted registered
[ 2.883417] rtc_cmos rtc_cmos: setting system clock to 2013-11-23 08:08:22 UTC (1385194102)
[ 2.883978] BIOS EDD facility v0.16 2004-Jun-25, 0 devices found
[ 2.884150] EDD information not available.
[ 2.888258] Freeing unused kernel memory: 796k freed
[ 2.905213] Write protecting the kernel text: 6360k
[ 2.905842] Write protecting the kernel read-only data: 2496k
[ 2.996559] Switching to clocksource tsc
Loading, please wait...
[ 3.548082] udevd[94]: starting version 175
Begin: Loading essential drivers ... done.
Begin: Running /scripts/init-premount ... done.
Begin: Mounting root file system ... Begin: Running /scripts/local-top ... done.
[ 5.732537] Disabling lock debugging due to kernel taint
[ 5.818667] e1000: Intel(R) PRO/1000 Network Driver - version 7.3.21-k8-NAPI
[ 5.818862] e1000: Copyright (c) 1999-2006 Intel Corporation.
[ 6.218158] e1000 0000:00:03:0 eth0: (PCI:33MHz:32-bit) 52:54:00:12:34:56
[ 6.218482] e1000 0000:00:03:0 eth0: Intel(R) PRO/1000 Network Connection
Begin: Running /scripts/local-premount ... done.
Begin: Running /scripts/local-bottom ... done.
done.
Begin: Running /scripts/init-bottom ... done.
[ 8.874480] init: ureadahead main process (210) terminated with status 5

```

[ 13.455611] Adding 523260k swap on /dev/sda4. Priority:-1 extents:1 across:523260k  
fsck from util-linux 2.20.1

fsck from util-linux 2.20.1

dosfsck 3.0.12, 29 Oct 2011, FAT32, LFN

/dev/sda3 was not cleanly unmounted, check forced.

/dev/sda2: 6 files, 262/97523 clusters

Checking disk drives for errors. This may take several minutes.

Press C to cancel all checks in progress

/dev/sda3: 55810/689520 files (1.6% non-contiguous), 821662/1377280 blocks

mountall: fsck / [227] terminated with status 1

Skipping profile in /etc/apparmor.d/disable: usr.sbin.rsyslogd

\* Starting AppArmor profiles [80G  
[74G[ OK ]

\* Stopping System V initialisation compatibility[74G[ OK ]

\* Starting System V runlevel compatibility[74G[ OK ]

\* Starting save kernel messages[74G[ OK ]

\* Starting regular background program processing daemon[74G[ OK ]

\* Starting deferred execution scheduler[74G[ OK ]

\* Starting automatic crash report generation[74G[ OK ]

\* Starting CPU interrupts balancing daemon[74G[ OK ]

\* Starting ACPI daemon[74G[ OK ]

\* Starting crash report submission daemon[74G[ OK ]

\* Stopping save kernel messages[74G[ OK ]

\* Stopping System V runlevel compatibility[74G[ OK ]