

UseTemplate()

(mPDF >= 2.3)

UseTemplate – Insert an imported page from an external PDF file

Description

```
array UseTemplate ( int $templateID [, float $x [, float $y [, float $width [, float $height ]]]])
```

Insert an imported page/template from an external PDF file into the current document. The page, or 'cropped' page, must have already been stored as a 'template' using SetSourceFile(). The template is inserted on the current page of the document. UseTemplate() returns an array of height and width of the imported page as it is printed (see Example #1).

Note: The template will be printed onto the page as the bottom 'layer' i.e. anything else written to that page by mPDF will be written on top of this template. NB If you use WriteHTML() and have a background-color set on BODY this will hide the template from view e.g. <body style="background-color:#FFFFFF;">

Note: If you are using automatic header-margins, you need to set the header before starting the first page; if you start the document with UseTemplate() this will move it to page 1, so the order needs to be:

```
$mpdf = new mPDF();
$mpdf->SetImportUse();
$mpdf->SetHTMLHeader($header);
$pagecount = $mpdf->SetSourceFile('logoheader.pdf');
$tplIdx = $mpdf->ImportPage($pagecount);
$mpdf->UseTemplate($tplIdx);
$mpdf->WriteHTML($html);
```

Parameters

templateID

This parameter specifies the ID of the page template to insert.

x

Sets the x co-ordinate (abscissa) to output the template. Value should be specified as **LENGTH** in millimetres.

DEFAULT NULL - Sets x co-ordinate to 0

BLANK or omitted - uses default (0)

-1: Uses current writing position in document

y

Sets the y co-ordinate (ordinate) to output the template. Value should be specified as **LENGTH** in millimetres.

DEFAULT NULL - Sets y co-ordinate to 0

BLANK or omitted - uses default (0)

-1: Uses current writing position in document

width

Specifies the width for the template to appear on the page. Value should be specified as **LENGTH** in millimetres.

DEFAULT or 0 will output the template at the original size (if neither *width* nor *height* are set) or if *height* is set, the *width* is automatically set to output the template in proportion to the original.

height

Specifies the height for the template to appear on the page. Value should be specified as **LENGTH** in

millimetres.

DEFAULT or 0 will output the template at the original size (if neither *width* nor *height* are set) or if *width* is set, the *height* is automatically set to output the template in proportion to the original.

Return Value

UseTemplate() returns an array of the calculated *width* and *height*.

Changelog

Version	Description
2.3	Function was added.

Examples

Example #1

```
<?php
include("../mpdf.php");

$mpdf=new mPDF();
$mpdf->SetImportUse();

// Add First page
$mpdf->AddPage();

$pagecount = $mpdf->SetSourceFile('logoheader.pdf');
$tplId = $mpdf->ImportPage($pagecount);

$actualsize = $mpdf->UseTemplate($tplId);

// The height of the template as it was printed is returned as $actualsize['h']
// The width of the template as it was printed is returned as $actualsize['w']

$mpdf->WriteHTML('Hallo World');

$mpdf->Output();

?>
```

Example #2 - Using a 'cropped' page

```
<?php
include("../mpdf.php");

$mpdf=new mPDF();
$mpdf->SetImportUse();

$pagecount = $mpdf->SetSourceFile('testfile.pdf');
$tplId = $mpdf->ImportPage($pagecount, 50, 50, 100, 100);

$mpdf->UseTemplate($tplId, '', '', 100, 100);

$mpdf->Output();

?>
```

See Also

- **SetImportUse()** - Enable the use of imported PDF files or templates
- **Thumbnail()** - Print thumbnails of an external PDF file
- **SetSourceFile()** - Specify the source PDF file used to import pages into the document
- **ImportPage()** - Import a page from an external PDF file
- **SetPageTemplate()** - Specify a page from an external PDF file to use as a template
- **SetDocTemplate()** - Specify an external PDF file to use as a template
- **RestartDocTemplate()** - Re-start the use of a Document template from the next page