



Outbound BOD Mapping and Descriptions

M3 Business Engine BODs

Copyright © 2014 Infor

All rights reserved. The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or related affiliates and subsidiaries. All rights reserved. All other trademarks listed herein are the property of their respective owners.

Important Notices

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above.

Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Publication Information

Release: M3 Business Engine BODs

Publication Date: October 22, 2014

Version: 15.3.0.0

AccountingBookDefinition

AccountingBookDefinition/DocumentID/ID

CMNDIV.CCDIVI; MNS100MI/GetBasicData

The field indicates a division. This is an identity for a legal unit within a company group. Division is a key value in the financial system in M3. One division may consist of several facilities. Facilities are used in material and production management and for purchasing purposes.

AccountingBookDefinition/Name

CMNDIV.CCCONM; MNS100MI/GetBasicData

The field indicates the name of the company.
The information is displayed in the top line of all M3 panels as information for users signed in to this company.

AccountingBookDefinition/AccountingChartReference/Name

@languageID

CMNDIV.CCTX15; MNS100MI/GetBasicData

The field indicates a name for the current ID. It contains 15 positions. When you edit descriptions and names, and no name is entered, the first 15 positions from the description field will automatically be proposed as the name.

AccountingBookDefinition/FinancialCalendarReference/DocumentID/ID

CSYTAB.CTSTCO; CRS175MI/GetGeneralCode

This field is hardcoded in the program and you can only add this but not modify or update. To create a record of this field, you must set this inside the program in order to make this available in the user.

@accountingEntity

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

The field indicates a description of the current identity.

AccountingBookDefinition/BookTypeCode

@listID

CMNDIV.CCLOCD; MNS100MI/GetBasicData

The field indicates the local currency, that is, the basic currency used by the division.

AccountingChart

AccountingChart/IDs/ID	Constant = 'AccountingChartStandard'
@accountingEntity	M3 BE DIVI
@variationID	MEC Variation ID
AccountingChart/Status/Code	Constant = 'Open'
@listID	Constant = 'AccountingChartStatus'
AccountingChart/AccountDisplayLength	Constant = '8', Display length = 8 characters
AccountingChart/DimensionSequence/SequencedDimension @sequence	Constant from '1' to '6' (Dimension numbers)
AccountingChart/DimensionSequence/SequencedDimension/ListID CSYTAB.multiple; CRS175MI/GetGeneralCode	Dimension names from CSYTAB, fields YGAI52, YGAI53, YGAI54, YGAI55, YGAI56, YGAI57
AccountingChart/DimensionProfileSet/ID	Constant = 'DimensionProfileSetStandard'
AccountingChart/DimensionProfileSet/DimensionProfile/ID	Constant = 'DimensionProfileStandard'
AccountingChart/DimensionProfileSet/DimensionProfile/DimensionUsage/ListID CSYTAB.multiple; CRS175MI/GetGeneralCode	Dimension names from CSYTAB, fields YGAI52, YGAI53, YGAI54, YGAI55, YGAI56, YGAI57
AccountingChart/DimensionProfileSet/DimensionProfile/DimensionUsage/Usage	Field 2-7 = OPTIONAL

AccountingEntity

AccountingEntity/IDs/ID

CMNDIV.CCDIVI; MNS100MI/GetBasicData

The field indicates a the accounting entity.
M3 publish the division as accounting entity, and the ID is a concatenation from CONO and DIVI (e.g. 780_AAA).
It is possible to translate it through CRS881, but we recommend to use the default value.

AccountingEntity/Description

CMNDIV.CCCONM; MNS100MI/GetBasicData

This is the name of the M3 division

AccountingEntity/Name

CMNDIV.CCTX15; MNS100MI/GetBasicData

This is the short name of the M3 division

AccountingEntity/CurrencyCode

CMNDIV.CCLOCD; MNS100MI/GetBasicData

The field indicates the local currency of the country or division used.

AccountingEntity/Location/Address/AddressLine

CMNDIV.CCCOA1, CCCOA2, CCCOA3, CCCOA4; MNS100MI/GetBasicData

The field indicates address lines 1-4 for the M3 division

AccountingEntity/Location/Address/CityName

CMNDIV.CCTOWN; MNS100MI/GetBasicData

The field indicates the city

AccountingEntity/Location/Address/CountrySubDivisionCode

CMNDIV.CCECAR; MNS100MI/GetBasicData

The field indicates the state/region/countrysubdivision

@listID

.; -/-

The field indicates the list ID for country subdivisions, and it is different depending on country:
- Canada has list ID "Canadian Provinces"
- France has list ID "France - Departements"
- United States has list ID "US States"
- Other countries have list ID "Country Sub-divisions"

AccountingEntity/Location/Address/CountryCode

CMNDIV.CCCSCD; MNS100MI/GetBasicData

The field indicates a country.

@listID

.; -/-

The field indicates the list ID for countries
It is set to "Countries".

AccountingEntity/Location/Address/PostalCode

CMNDIV.CCPONO; MNS100MI/GetBasicData

The field indicates the postal code.

AccountingEntity/BaseCurrency

CMNDIV.CCLOCD; MNS100MI/GetBasicData

The field indicates the local currency of the country or division used.

AccountingEntity/FinancialCalendarReference/DocumentID/ID

N/A.N/A; -/-

Constant = 'Financial Calendar'

@accountingEntity

N/A.; -/-

0

AccountingJournal

AccountingJournal/DocumentID/ID

CSYTAB.CTSTCO; CRS175MI/GetGeneralCode

This field is hardcoded in the program and you can only add this but not modify or update. To create a record of this field, you must set this inside the program in order to make this available in the user.

AccountingJournal/AlternateDocumentID/ID

CSYTAB.CTSTKY; CRS175MI/GetGeneralCode

The field indicates an entry function within FAM. These values are predetermined and cannot be changed. For each program, certain settings that control processing can be created. For certain functions, it is possible to specify different types of journal vouchers, invoices, etc. The abbreviation is based on the name of the module in English.

The type of value entered is determined by what is entered in the 'Key type' field.

AccountingJournal/Description

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

The field indicates a description of the current identity.

AccountingJournal/Name

CSYTAB.CTTX15; CRS175MI/GetGeneralCode

The field indicates a name for the current ID. It contains 15 positions.

When you edit descriptions and names, and no name is entered, the first 15 positions from the description field will automatically be proposed as the name.

AccountingJournal/DocumentCode

CSYTAB.CTPARM; CRS175MI/GetGeneralCode

This field is equivalent to three fields: function, module and journal heading. When you change this field, it automatically inserts the two fields. For example if you function is AP10, module is AP, and journal heading is AcctsPayable. This field displays the AP10APAcctsPayable.

AdvanceShipNotice

AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentID/ID MHEXRH.RIDN; MHS800MI/LstExpRec	Partner + Warehouse + Transaction type + Order number + Receiving number
@accountingEntity	Accounting entity for this order
@location MHEXRH.WHLO; MHS800MI/LstExpRec	Warehouse
AdvanceShipNotice/AdvanceShipNoticeHeader/AlternateDocumentID/ID MHEXRH.TTYP + RIDN; MHS800MI/LstExpRec	Order Number.
AdvanceShipNotice/AdvanceShipNoticeHeader/DisplayID MHEXRH.RIDN; MHS800MI/LstExpRec	Order number
AdvanceShipNotice/AdvanceShipNoticeHeader/LastModificationDate/Time MHEXRH.LMDT; MHS800MI/LstExpRec	The field indicates the date the record was last changed. Note: Time zone conversion is therefore not done.
AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentDate/Time MHEXRH.RGDT + RGTM; MHS800MI/LstExpRec	Date and time created expressed in UTC
AdvanceShipNotice/AdvanceShipNoticeHeader/Note MHEXRH.USD1+USD2+USD3+USD4+USD5; MHS800MI/LstExpRec	The five user-defined fields concatenated. Each field is 15 positions alphanumeric. Those fields will typically be blank but can be used for customer-specific functionality
AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference @type MHEXRH.TTYP; MHS800MI/LstExpRec	If TTYP = 25 set @type="PurchaseOrder", if TTYP = 30, set @type="CustomerReturn", TTYP = 10, set @type="Production" If TTYP = 50, set @type="Transfer" If TTYP = 40, set @type="Transfer" If
AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference/DocumentID/ID MHEXRH.RIDN; MHS800MI/LstExpRec	The field indicates an order number.
@accountingEntity	The accounting entity that owns the reference order
@location MHEXRH.WHLO; MHS800MI/LstExpRec	The field indicates the warehouse ID.
AdvanceShipNotice/AdvanceShipNoticeHeader/Status/Code MHEXRH.CMND; MHS800MI/LstExpRec	// If CMND="ADD", "CHG" then set Status Code="Open" // If CMND="DLT" then set Status Code="Canceled" // If CMND="PRC" then status will NOT trigger a BOD to be sent // If CMND="CLS" then set Status Code="Closed"
@listID	Code listID ="ShipmentStatus"
AdvanceShipNotice/AdvanceShipNoticeHeader/GrossWeightMeasure MHEXRH.GRWE; MHS800MI/LstExpRec	The field indicates the total weight for all items that have been entered on the order. The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity.
AdvanceShipNotice/AdvanceShipNoticeHeader/CountryOfOriginCode MHEXRH.CSCD; MHS800MI/LstExpRec	Taken from the suppliers country or the country where the shipment is sent from. TTYP = 10 (Manufacturing Order); 20 (Purchase Order); 30 (Customer Order Returns); 40 (Requisition Order); 50 (Distribution Order)
AdvanceShipNotice/AdvanceShipNoticeHeader/TransportationMethodCode MHEXRH.MODL; MHS800MI/LstExpRec	Delivery method. Can be translated using CRS881 if required.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/PartyIDs/ID MHEXRH.SUNO; MHS800MI/LstExpRec	If 20 (Purchase Order) then get the information in supplier master (CRS620).
@accountingEntity	The accounting entity associated with the supplier
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Name MHEXRH.CONM; CRS620MI/GetBasic	SUNO from ShipFromParty equal to CRS620MI.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/ID MHEXRH.SUNO; MHS800MI/LstExpRec	If Transaction Type = 10 (Manufacturing Order), 40 (Requisition Order), 50 (Distribution Order) then display the Warehouse
@accountingEntity	The accounting entity associated with the supplier
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Name MHEXRH.WHNM; MMS005MI/GetWarehouse	SUNO from ShipFromParty equal to WHLO in MMS005MI.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/AddressLine MHEXRH.ADR1 to ADR4; MHS800MI/LstExpRec	Get address number.

AdvanceShipNotice

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/CountryCode MHEXRH.CSCD; MHS800MI /LstExpRec	The field indicates a country. Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/PostalCode MHEXRH.PONO; MHS800MI /LstExpRec	The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Contact/Name MHEXRH.YREF; MHS800MI/LstExpRec	The field indicates the customer's contact person.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Contact/Communication/DialNumber MITWHL.PHNO or PHN2; MMS005MI/GetWarehouse	The field indicates the telephone number of the customer or supplier.
AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/PartyIDs/ID MHEXRH.SUNO; MHS800MI/LstExpRec	If TTYP = 30 (Customer Order Returns), this will indicate the customer which is sending back goods as return.
AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/Name ; CRS610MI/GetWarehouse	SUNO from ReturntoShipFromParty equal to WHLO in MMS005MI.
AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/Location/Address/AddressLine MHEXRH.ADR1 to ADR4; MHS800MI /LstExpRec	Get address number.
AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/Location/Address/CountryCode MHEXRH.CSCD; MHS800MI /LstExpRec	The field indicates a country. Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/Location/Address/PostalCode MHEXRH.PONO; MHS800MI /LstExpRec	The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipToParty/Location/ID MHEXRH.WHLO; MHS800MI/LstExpRec @accountingEntity	The field indicates the warehouse ID. Accounting Entity associated with the warehouse
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipToParty/Location/Name MITWHL.WHNM; MMS005MI/GetWarehouse	Warehouse name
AdvanceShipNotice/AdvanceShipNoticeHeader/TransportationTerm/IncotermsCode MHEXRH.TEDL; MHS800MI/LstExpRec	Delivery Terms. It's recommended to set up the delivery terms in M3 to correspond to standardized Incoterms. If this isn't done, the values can be translated into Incoterms using CRS881. The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer. The following codes are recommended according to Incoterms: N.B. The text within parentheses indicates the delivery term's text on line 2. EXW Ex Works (Manufacturing location) FCA Free Carrier (Transport ID) FAS Free Alongside Ship (Loading port) FOB Free On Board (Loading port) CFR Cost & Freight (Destination) CIF Cost Insurance & Freight (Destination) CPT Carriage Paid To (Destination) CIP Carriage & Insurance Paid to (Destination) DAF Delivered At Frontier (Customs location) DES Delivered Ex Ship (Destination) DEQ Delivered Ex Quay (Customs port) DDU Delivered Duty Unpaid (Import location country) DDP Delivered Duty Paid (Destination country) XXX Other (Name) Example: Code Delivery text line1 Delivery text line 2 CIF Cost, Insurance & Freight Rotterdam DDP Delivered duty unpaid Milan, Italy Both the code and the text can be changed during order entry. For freight documents created from the transportation planning routines, the delivery terms are retrieved from the selected route, and managed by the shipment regardless of this value.
AdvanceShipNotice/AdvanceShipNoticeItem/ItemID/ID MHEXRD.ITNO; MHS800MI/LstExpRecDetail @accountingEntity	The field indicates the item number which is a unique ID for an individual item. Items are entered and maintained. Item number can consist up to 15 alphanumeric characters in M3. The accounting entity that owns the item

AdvanceShipNotice

AdvanceShipNotice/AdvanceShipNoticeltem/Note MHEXRD.USD1+USD2+USD3+USD4+USD5; MHS800MI/LstExpRec	5 used-defined fields concatenated. Each field is 15 characters alphanumeric. Those fields are typically blank but can be used for customer-specific modifications. Note: Add "-" between each field to separate them.
AdvanceShipNotice/AdvanceShipNoticeltem/ShippedQuantity MHEXRD.TRQA; MHS800MI/LstExpRecDetail	Add field TRQA in MHS800MI LstExpRecDetail output where the formula is TRQT DMCF COFA. In order to get TRQA, read MMS015 to get DMCF (Conversion Form) and COFA (Conversion Factor). Note: If conversion form = 1 then divide else multiply. Needs to add in API
@unitCode MHEXRD.ALUN; MHS800MI/LstExpRecDetail	The field indicates an alternate unit of measure (U/M) for the basic U/M for an item.
AdvanceShipNotice/AdvanceShipNoticeltem/ShippedBaseUOMQuantity MHEXRD.TRQT; MHS800MI/LstExpRecDetail	The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.
@unitCode MHEXRD.UNMS; MHS800MI/LstExpRecDetail	The field indicates the basic unit of measure in which each item is recorded in inventory.
AdvanceShipNotice/AdvanceShipNoticeltem/RequisitionReference/DocumentID/ID MHEXRD.TTYP + RIDN + RIDX; MHS800MI/LstExpRecDetail	If Transaction Type = 40 (Requisition Order) then display Order number.
@location MHEXRD.WHLO; MHS800MI/LstExpRecDetail	The field indicates the warehouse ID.
AdvanceShipNotice/AdvanceShipNoticeltem/RequisitionReference/LineNumber MHEXRD.RIDL; MHS800MI/LstExpRecDetail	The field indicates the order line number.
AdvanceShipNotice/AdvanceShipNoticeltem/PurchaseOrderReference/DocumentID/ID MHEXRD.TTYP + RIDN + RIDX; MHS800MI/LstExpRecDetail	If Transaction Type = 25 (Purchase Order) then display Order number.
@location MHEXRD.WHLO; MHS800MI/LstExpRecDetail	The field indicates the warehouse ID.
@lid MHEXRD.RIDL; MHS800MI/LstExpRecDetail	The field indicates the order line number.
AdvanceShipNotice/AdvanceShipNoticeltem/PurchaseOrderReference/LineNumber MHEXRD.RIDL + PNLS; MHS800MI/LstExpRecDetail	The field indicates the order line number and purchase order line subnumber.
AdvanceShipNotice/AdvanceShipNoticeltem/SalesOrderReference/DocumentID/ID MHEXRD.RIDN; MHS800MI/LstExpRecDetail	If Transaction Type = 30 (Customer Order Returns) then display Order number.
@location MHEXRD.WHLO; MHS800MI/LstExpRecDetail	The field indicates the warehouse ID.
AdvanceShipNotice/AdvanceShipNoticeltem/SalesOrderReference/LineNumber MHFRNS.RIDL + RIDX; MHS800MI/LstExpRecDetail	If Transaction Type = 30 (Customer Order Returns) then display RIDX;
AdvanceShipNotice/AdvanceShipNoticeltem/DocumentReference @type MHEXRD.TTYP; MHS800MI/LstExpRecDetail	If Transaction Type = 10 (Manufacturing Order), 50 (Distribution Order) then display the Transaction type
AdvanceShipNotice/AdvanceShipNoticeltem/DocumentReference/DocumentID/ID MHEXRD.RIDN + RIDI; MHS800MI/LstExpRecDetail	Order number and delivery number separated by slash
@location MHEXRD.WHLO; MHS800MI/LstExpRecDetail	The field indicates the warehouse ID.
AdvanceShipNotice/AdvanceShipNoticeltem/DocumentReference/LineNumber MHEXRD.RIDX or RIDL + RORX or RORX; MHS800MI/LstExpRecDetail	If Transaction Type = 50 (Distribution Order) then display RIDL + RORX; If Transaction Type = 10 (Manufacturing Order) then display RORX.
AdvanceShipNotice/AdvanceShipNoticeltem/SerializedLot/Lot/LotIDs/ID MHEXRD.BANO; MHS800MI/LstExpRecDetail	If item is lot-controlled. The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics. Serial numbers can be used for lot numbering.
AdvanceShipNotice/AdvanceShipNoticeltem/SerializedLot/Lot/SerialNumber MHEXRD.BANO; MHS800MI/LstExpRecDetail	If item is serial number controlled. The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics. Serial numbers can be used for lot numbering.
AdvanceShipNotice/AdvanceShipNoticeltem/LineNumber MHEXRD.RELI; MHS800MI/LstExpRecDetail	If TTYP = 30 (Customer Order) then display RELI. This field also contain the same value as in following references to order: RequisitionReference/LineNumber PurchaseOrderReference/LineNumber

AdvanceShipNotice

	SalesOrderReference/LineNumber DocumentReference/LineNumber
AdvanceShipNotice/AdvanceShipNoticeUnit/ContainerID MHEXRD.PANR; MHS800MI/LstExpRecPacDet	Package number.
AdvanceShipNotice/AdvanceShipNoticeUnit/GrossWeightMeasure MHEXRD.GRWE; MHS800MI/LstExpRecDet	The field indicates the total weight for all items that have been entered on the order. The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ItemID/ID MHFRNS.ITNO; MHS800MI/LstExpRecPacDet	The field indicates the item number (for Maintenance, the item number or equipment number), which is a unique ID for an individual item. Items are entered and maintained. Item number can consist up to 15 alphanumeric characters.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ShippedQuantity MHFRNS.DLQT; MHS800MI/LstExpRecPacDet	Delivered quantity- basic UoM.
@unitCode MHEXRD.UNIT; MHS800MI/LstExpRecPacDet	If UNIT is null display LstExpRecDetail UNMS
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/RequisitionReference/DocumentID/ID MHEXRD.RIDN; MHS800MI/LstExpRecPacDet	If TTYP = 40 (Requisition Order). The field indicates the order line number and sequence number within an order line.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/RequisitionReference/LineNumber MHFRNS.RIDL + RIDX; MHS800MI/LstExpRecPacDet	If TTYP = 40 (Requisition Order). The field indicates the order line number and sequence number within an order line.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/PurchaseOrderReference/DocumentID/ID MHEXRD.RIDN; MHS800MI/LstExpRecPacDet	If TTYP = 25 (PurchaseOrder). The field indicates the order line number and sequence number within an order line.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/PurchaseOrderReference/LineNumber MHFRNS.RIDL + RIDX; MHS800MI/LstExpRecPacDet	If TTYP = 25 (PurchaseOrder). The field indicates the order line number and sequence number within an order line.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SalesOrderReference/DocumentID/ID MHEXRD.RIDN; MHS800MI/LstExpRecPacDet	If TTYP = 30 (Customer Order). The field indicates the order line number and sequence number within an order line.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/DocumentReference @type MHEXRD.TTYP; MHS800MI/LstExpRecDetail	If Transaction Type = 10 (Manufacturing Order), 50 (Distribution Order) then display the Transaction type
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/DocumentReference/DocumentID/ID MHEXRD.RIDN; MHS800MI/LstExpRecPacDet	The field indicates the order line number and sequence number within an order line.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/DocumentReference/LineNumber MHFRNS.RIDL + RIDX; MHS800MI/LstExpRecPacDet	If TTYP = 10, set @type="Production" If TTYP = 50, set @type= "Transfer"
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ExtendedSalePriceAmount MHFRNS.SAP1; MHS800MI/LstExpRecPacDet	Read MMS001 to get SAPR (Sale Price) and multiply to TRQT, add field SAP1 in MHS800MI LstExpRecPacDet.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SerializedLot/Lot/LotIDs/ID MHFRNS.BANO; MHS800MI/LstExpRecPacDet	If item is lot controlled. The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics. Serial numbers can be used for lot numbering.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SerializedLot/Lot/SerialNumber MHEXRD.BANO; MHS800MI/LstExpRecDet	If item is serial controlled. The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics. Serial numbers can be used for lot numbering.
AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentID/ID MHEXRH.RIDN; MHS800MI/LstExpRec	Partner + Warehouse + Transaction type + Order number + Receiving number
@accountingEntity	Accounting entity for this order
@location MHEXRH.WHLO; MHS800MI/LstExpRec	Warehouse
AdvanceShipNotice/AdvanceShipNoticeHeader/AlternateDocumentID/ID MHEXRH.TTYP + RIDN; MHS800MI/LstExpRec	Write the full description of the Transaction Type Description + ":" + Order Number. The field indicates different types of stock transactions.

AdvanceShipNotice

	<p>Alternatives</p> <p>10 = Manufacturing order receipt</p> <p>25 = Purchase put-away</p> <p>30 = Customer order returns</p> <p>40 = Requisition order return</p> <p>50 = Distribution order receipt</p>
AdvanceShipNotice/AdvanceShipNoticeHeader/DisplayID MHEXRH.TTYP + RIDN; MHS800MI/LstExpRec	Order number
AdvanceShipNotice/AdvanceShipNoticeHeader/LastModificationDateTime MHEXRH.LMDT; MHS800MI/LstExpRec	<p>The field indicates the date the record was last changed.</p> <p>Note: Time zone conversion is therefore not done.</p>
AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentDateTime MHEXRH.RGDT + RGTMI; MHS800MI/LstExpRec	Date and time created expressed in UTC
AdvanceShipNotice/AdvanceShipNoticeHeader/Note MHEXRH.USD1+USD2+USD3+USD4+USD5; MHS800MI/LstExpRec	The five user-defined fields concatenated. Each field is 15 positions alphanumeric. Those fields will typically be blank but can be used for customer-specific functionality
AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference @type MHEXRH.TTYP; MHS800MI/LstExpRec	<p>If TTYP = 25 set @type= "PurchaseOrder",</p> <p>if TTYP = 30, set @type= "CustomerReturn",</p> <p>TTYP = 10, set @type="Production"</p> <p>If TTYP = 50, set @type= "Transfer"</p> <p>If TTYP = 40, set @type = "Transfer"</p>
AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference/DocumentID/ID MHEXRH.RIDN; MHS800MI/LstExpRec	The field indicates an order number.
@accountingEntity	The accounting entity that owns the reference order
@location MHEXRH.WHLO; MHS800MI/LstExpRec	The field indicates the warehouse ID.
AdvanceShipNotice/AdvanceShipNoticeHeader/Status/Code MHEXRH.CMND; MHS800MI/LstExpRec	<p>// If CMND="**ADD" , "**CHG" then set Status Code="Open" // If CMND= "**DLT" then set Status Code = "Canceled" // If CMND = "**PRC" then status will NOT trigger a BOD to be sent // If CMND="**CLS" then set Status Code="Closed"</p>
@listID	Code listID ="ShipmentStatus"
AdvanceShipNotice/AdvanceShipNoticeHeader/GrossWeightMeasure MHEXRH.GRWE; MHS800MI/LstExpRec	<p>The field indicates the total weight for all items that have been entered on the order.</p> <p>The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity.</p>
@unitCode MHEXRH.UNMS; MHS800MI/LstExpRec	Needs to be added to API.
AdvanceShipNotice/AdvanceShipNoticeHeader/CountryOfOriginCode MHEXRH.CSCD; MHS800MI/LstExpRec	Taken from the suppliers country or the country where the shipment is sent from. TTYP = 10 (Manufacturing Order); 20 (Purchase Order); 30 (Customer Order Returns); 40 (Requisition Order); 50 (Distribution Order)
AdvanceShipNotice/AdvanceShipNoticeHeader/TransportationMethodCode MHEXRH.MODL; MHS800MI/LstExpRec	Delivery method. Can be translated using CRS881 if required.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/PartyIDs/ID MHEXRH.SUNO; MHS800MI /LstExpRec	If Transaction Type = 10 (Manufacturing Order), 20 (Purchase Order), 40 (Requisition Order), 50 (Distribution Order) then display the Supplier number.
@accountingEntity	The accounting entity associated with the supplier
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Name CIDMAS.SUNM; CRS620MI/GetBasicData	The field indicates supplier name, most often the supplier's company name.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/AddressLine MHEXRH.ADR1 to ADR4; MHS800MI /LstExpRec	Get address number.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/CountryCode MHEXRH.CSCD; MHS800MI /LstExpRec	<p>The field indicates a country.</p> <p>Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.</p>
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/PostalCode MHEXRH.PONO; MHS800MI /LstExpRec	

AdvanceShipNotice

	The field indicates a postal code for a specific address.
	The postal code is an address element that can be part of an address line if address formatting rules are used.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Contact/Name MHEXRH.YREF; MHS800MI/LstExpRec	The field indicates the customer's contact person.
AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/PartyIDs/ID MHEXRH.SUNO; MHS800MI/LstExpRec	If TTYP = 30 (Customer Order Returns), this will indicate the customer who is sending back goods as return.
@accountingEntity	0
AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/Location/Address/AddressLine MHEXRH.ADR1 to ADR4; MHS800MI /LstExpRec	Get address number.
AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/Location/Address/CountryCode MHEXRH.CSCD; MHS800MI /LstExpRec	The field indicates a country.
	Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/Location/Address/PostalCode MHEXRH.PONO; MHS800MI /LstExpRec	The field indicates a postal code for a specific address.
	The postal code is an address element that can be part of an address line if address formatting rules are used.
AdvanceShipNotice/AdvanceShipNoticeHeader/ShipToParty/Location/ID MHEXRH.WHLO; MHS800MI/LstExpRec	The field indicates the warehouse ID.
@accountingEntity	Accounting Entity associated with the warehouse
AdvanceShipNotice/AdvanceShipNoticeHeader/TransportationTerm/IncotermsCode MHEXRH.TEDL; MHS800MI/LstExpRec	<p>Delivery Terms. It's recommended to set up the delivery terms in M3 to correspond to standardized Incoterms. If this isn't done, the values can be translated into Incoterms using CRS881. The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.</p> <p>The following codes are recommended according to Incoterms: N.B. The text within parentheses indicates the delivery term's text on line 2.</p> <p>EXW Ex Works (Manufacturing location) FCA Free Carrier (Transport ID) FAS Free Alongside Ship (Loading port) FOB Free On Board (Loading port) CFR Cost & Freight (Destination) CIF Cost Insurance & Freight (Destination) CPT Carriage Paid To (Destination) CIP Carriage & Insurance Paid to (Destination) DAF Delivered At Frontier (Customs location) DES Delivered Ex Ship (Destination) DEQ Delivered Ex Quay (Customs port) DDU Delivered Duty Unpaid (Import location country) DDP Delivered Duty Paid (Destination country) XXX Other (Name)</p> <p>Example: Code Delivery text line1 Delivery text line 2 CIF Cost, Insurance & Freight Rotterdam DDP Delivered duty unpaid Milan, Italy</p> <p>Both the code and the text can be changed during order entry. For freight documents created from the transportation planning routines, the delivery terms are retrieved from the selected route, and managed by the shipment regardless of this value.</p>
AdvanceShipNotice/AdvanceShipNoticeItem/ItemID/ID MHEXRD.ITNO; MHS800MI/LstExpRecDetail	The field indicates the item number which is a unique ID for an individual item.
	Items are entered and maintained. Item number can consist up to 15 alphanumeric characters in M3.
@accountingEntity	The accounting entity that owns the item
AdvanceShipNotice/AdvanceShipNoticeItem/Note MHEXRD.USD1+USD2+USD3+USD4+USD5; MHS800MI/LstExpRec	5 user-defined fields concatenated. Each field is 15 characters alphanumeric. Those fields are typically blank but can be used for customer-specific modifications. Note: Add "." between each field to separate them.
AdvanceShipNotice/AdvanceShipNoticeItem/ShippedQuantity MHEXRD.TRQA; MHS800MI/LstExpRecDetail	Add field TRQA in MHS800MI LstExpRecDetail output where the formula is TRQT DMCF COFA. In order to get TRQA, read MMS015 to get DMCF (Conversion Form) and COFA (Conversion Factor). Note: If conversion form = 1 then divide else multiply. Needs to add in API

AdvanceShipNotice

@unitCode MHEXRD.ALUN; MHS800MI/LstExpRecDetail	The field indicates an alternate unit of measure (U/M) for the basic U/M for an item.
AdvanceShipNotice/AdvanceShipNoticeItem/ShippedBaseUOMQuantity MHEXRD.TRQT; MHS800MI/LstExpRecDetail	The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.
@unitCode MHEXRD.UNMS; MHS800MI/LstExpRecDetail	The field indicates the basic unit of measure in which each item is recorded in inventory.
AdvanceShipNotice/AdvanceShipNoticeItem/RequisitionReference/DocumentID/ID MHEXRD.TTYP + RIDN + RIDX; MHS800MI/LstExpRecDetail	If Transaction Type = 40 (Requisition Order) then display Transaction type plus Order number plus Line suffix.
@accountingEntity	0
@location MHEXRD.WHLO; MHS800MI/LstExpRecDetail	The field indicates the warehouse ID.
AdvanceShipNotice/AdvanceShipNoticeItem/RequisitionReference/LineNumber MHEXRD.RIDL; MHS800MI/LstExpRecDetail	The field indicates the order line number.
AdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/DocumentID/ID MHEXRD.TTYP + RIDN + RIDX; MHS800MI/LstExpRecDetail	If Transaction Type = 25 (Purchase Order) then display Transaction type plus Order number plus Line suffix.
@accountingEntity	0
@location MHEXRD.WHLO; MHS800MI/LstExpRecDetail	The field indicates the warehouse ID.
@lid MHEXRD.RIDL; MHS800MI/LstExpRecDetail	The field indicates the order line number.
AdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/LineNumber MHEXRD.RIDL + PNLS; MHS800MI/LstExpRecDetail	The field indicates the order line number and purchase order line subnumber.
AdvanceShipNotice/AdvanceShipNoticeItem/SalesOrderReference/DocumentID/ID @accountingEntity	0
AdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference/DocumentID/ID MHEXRD.TTYP + RIDN; MHS800MI/LstExpRecDetail	If Transaction Type = 10 (Manufacturing Order), 30 (Customer Order Returns), 50 (Distribution Order) then display the Transaction type plus Order number.
@accountingEntity	0
@location MHEXRD.WHLO; MHS800MI/LstExpRecDetail	The field indicates the warehouse ID.
AdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference/LineNumber MHEXRD.RIDX or RIDL + RORX or RORX; MHS800MI/LstExpRecDetail	If Transaction Type = 30 (Customer Order Returns) then display RIDX; If Transaction Type = 50 (Distribution Order) then display RIDL + RORX; If Transaction Type = 10 (Manufacturing Order) then display RORX.
AdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/LotIDs/ID MHEXRD.BANO; MHS800MI/LstExpRecDetail	If item is lot-controlled. The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics. Serial numbers can be used for lot numbering.
AdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/SerialNumber MHEXRD.BANO; MHS800MI/LstExpRecDetail	If item is serial number controlled. The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics. Serial numbers can be used for lot numbering.
AdvanceShipNotice/AdvanceShipNoticeItem/LineNumber MHEXRD.RELI; MHS800MI/LstExpRecDetail	If TTYP = 30 (Customer Order) then display RELI. Note: Line number is only existing when transaction type is customer order.
AdvanceShipNotice/AdvanceShipNoticeUnit/ContainerID MHEXRD.CAMU; MHS800MI/LstExpRecPacDet	The field indicates the object on which deliveries and receipts are loaded. Along with an item number, container could be a number that makes a unique balance identity. Containers are managed in the combination of item and warehouse. An example of container is a pallet on which items have been loaded from stock. The purpose of this is, for instance, to enable handling of automatic stock to give pallets going in and out of the stock-specific balance identities.

AdvanceShipNotice

AdvanceShipNotice/AdvanceShipNoticeUnit/GrossWeightMeasure

MHEXRD.GRWE; MHS800MI/LstExpRecPacDet

The field indicates the total weight for all items that have been entered on the order.

The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ItemID/ID

MHFRNS.ITNO; MHS800MI/LstExpRecPacDet

The field indicates the item number (for Maintenance, the item number or equipment number), which is a unique ID for an individual item.

Items are entered and maintained. Item number can consist up to 15 alphanumeric characters.

@accountingEntity

0

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ShippedQuantity

MHFRNS.DLQA; MHS800MI/LstExpRecPacDet

Delivered quantity- basic UoM.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/PurchaseOrderReference/LineNumber

MHFRNS.RIDL/RIDX; MHS800MI/LstExpRecPacDet

If TTYP = 25 (PurchaseOrder). The field indicates the order line number and sequence number within an order line.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/DocumentReference/LineNumber

MHFRNS.RIDL; MHS800MI/LstExpRecPacDet

If TTYP = 25 set @type=

"PurchaseOrder",

if TTYP = 30, set @type=

"CustomerReturn",

TTYP = 10, set

@type="Production"

If TTYP = 50, set @type=

"Transfer"

If TTYP = 40, set @type = "Transfer"

If

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ExtendedSalePriceAmount

N/A.N/A; MHS800MI/LstExpRecPacDet

Read MMS001 to get SAPR (Sale Price) and multiply to TRQA, add field SAP1 in MHS800MI LstExpRecPacDet.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SerializedLot/Lot/LotIDs/ID

MHFRNS.BANO; MHS800MI/LstExpRecPacDet

If item is lot controlled. The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics.

Serial numbers can be used for lot numbering.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SerializedLot/Lot/SerialNumber

MHEXRD.BANO; MHS800MI/LstExpRecPacDet

If item is serial controlled. The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics.

Serial numbers can be used for lot numbering.

AssetMaster

AssetMaster/IDs/ID

FFASMA.ASID SBNO; FAS001MI/GetAsset

The field indicates the unique alpha-numeric ID of a fixed asset.

A fixed asset can be identified either by the ID or the subnumber. The subnumber is a serial number for identification of one or several fixed assets under a specific fixed asset number.

When you enter a supplier invoice and select an account defined as a fixed asset account, FA program is activated. There you can either add costs to an existing asset by selecting its ID, or create a new, preliminary asset by entering some basic data.

In the latter case, the asset automatically receives status 5 (Preliminary) and a preliminary asset ID in the form of a sequence number. When you change the status of the asset to definite, you can select a new ID. The preliminary number is then saved in the fixed asset master file, which enables you to use it for inquiries.

AssetMaster/LastModificationDateTime

FFASMA.LMDT; FAS001MI/GetAsset

Change date. The field indicates the date the record last was changed.

AssetMaster/DocumentDateTime

FFASMA.RGDT; FAS001MI/GetAsset

Entry date. The field indicates the date that the object was created. This date is set automatically.

AssetMaster/Description

FFASMA.TXT1, TXT2; FAS001MI/GetAsset

The field indicates an optional text that can be printed on different order documents together with the current material line.

AssetMaster/Note

FFASMA.PPER + APER; FAS001MI/GetAsset

Specify: "Acquisition Period" = PPER

AssetMaster/Status/Code

FFASMA.FAST; FAS001MI/GetAsset

If status = 1, 5, 7, 8 is OPEN ; 9 = CLOSED

AssetMaster/Status/EffectiveDateTime

FFASMA.RGDT + RGTM; FAS001MI/GetAsset

Entry date and entry time.

AssetMaster/Name

FFASMA.FADS; FAS001MI/GetAsset

Name. The field indicates a shorter name of the fixed asset.

AssetMaster/DepreciationStatusCode

FFASMA.FAST; FAS001MI/GetAsset

if 1 = Depreciable; 8 = Fully Depreciated; 9 = Nondepreciable

AssetMaster/ItemInstance/ItemID/ID

FFASMA.ITNO; FAS001MI/GetAsset

Item number

AssetMaster/OwnedQuantity

FFASMA.FAQT; FAS001MI/GetAsset

FA Quantity. The field indicates the number of physical objects represented by the fixed asset.

AssetMaster/DocumentReference/DocumentID/ID

FFASMA.VONO + VSER; FAS001MI/GetAsset

Voucher number + Voucher series number. Note: Voucher number consume 8char and Voucher series number consumes 3char.

AssetMaster/AcquisitionDateTime

FFASMA.PPER; FAS001MI/GetAsset

Acquisition period. The field indicates the date on which the fixed asset was purchased.

The date is used as a basis for calculating depreciation and for information purposes when printing reports of assets purchased during a certain period.

AssetMaster/CommissionDateTime

FFASMA.APER; FAS001MI/GetAsset

Activation period. The field indicates from which period the fixed asset has been used. If period type Activation period is selected for the depreciation type in the setup, this period is the starting point for depreciation.

AssetMaster/Cost/CurrencyExchangeRate/SourceCurrencyCode

FFASMA.CUCD; FAS001MI/GetAsset

The field indicates the abbreviation for the currency. The abbreviation must follow ISO standards.

AssetMaster/Cost/CurrencyExchangeRate/RateNumeric

FFASMA.ARAT; FAS001MI/GetAsset

The field indicates the exchange rate for the chosen currency.

AssetMaster/AssetTypeCode

FFASMA.FATP; FAS001MI/GetAsset

The field indicates the type of equipment used to classify fixed assets.

AssetMaster/CostCenterCode

FFASMA.AIT2; FAS001MI/GetAsset

Accounting dimension 2. The field indicates an accounting identity in an accounting dimension.

An accounting dimension is a part of the accounting string used to describe financial events in detail. M3 accounting strings contain seven dimensions.

Accounting IDs are specified for each accounting dimension. An accounting identity can contain a total of eight alphanumeric

characters. Accounting dimensions function as a guide for an accounting ID. Examples of accounting IDs are account, cost center and product group. Accounting dimension 1, the first part of the accounting string, is required and always reserved for an account in business accounting. The remaining 6 can be used for company-specific accounting and follow-up.

The seven dimensions can be given names specific to the company in the setup. These names will be shown on panels and printouts.

Accounting identities are assigned for each accounting dimension. These IDs may consist of 8 alphanumeric characters.

BillOfMaterials

BillOfMaterials/BillOfMaterialsHeader/DocumentID/ID

MPDHED.PHPRNO; PDS001MI.Get

This field indicates the product number. The product number is the same as the in-house manufacturing item number and is always used together with structures to describe what a product consists of and how it is manufactured.

@accountingEntity

..

@variationID

..

@lid

..

This attribute indicates the company division.

This attribute indicates the number of variations for the object.

This attribute indicates the lid of the system where the object is maintained.

BillOfMaterials/BillOfMaterialsHeader/DocumentID/RevisionID

MITMAS.MMECVE; PDS001MI.Get

This field indicates the revision number (edition) for an item or document.

BillOfMaterials/BillOfMaterialsHeader/DisplayID

MPDHED.PHPRNO; PDS001MI.Get

This field indicates the product number. The product number is the same as the in-house manufacturing item number and is always used together with structures to describe what a product consists of and how it is manufactured.

BillOfMaterials/BillOfMaterialsHeader/Description

MITMAS.MMITDS; PDS001MI.Get

This field indicates the product number description.

BillOfMaterials/BillOfMaterialsHeader/Note

MPDHED.PHPRTX; PDS001MI.Get

This field indicates an optional text of at most 30 characters.

BillOfMaterials/BillOfMaterialsHeader/Status/Code

MPDHED.PHSTAT; PDS001MI.Get

This field indicates the status of the record.

10 - Hold
20 - Open
90 - Deleted

BillOfMaterials/BillOfMaterialsHeader/OutputItem/ItemID/ID

MPDHED.PHPRNO; PDS001MI.Get

This field indicates the product number. The product number is the same as the in-house manufacturing item number and is always used together with structures to describe what a product consists of and how it is manufactured.

@accountingEntity

..

This attribute indicates the company division.

BillOfMaterials/BillOfMaterialsHeader/OutputItem/ItemID/RevisionID

MITMAS.MMECVE; MMS200MI.GetItmTech

The field indicates the revision number (edition) for an item or document.

BillOfMaterials/BillOfMaterialsHeader/OutputItem/UPCID

MITPOP.MPPOPN; MMS025MI.LstAlias

Correspond to GTIN-12 and UCC-12. This is a 12-digit number used for identifying goods.

Alias qualifier = UPC

BillOfMaterials/BillOfMaterialsHeader/OutputItem/Description

MPDHED.PHITDS; PDS001MI.Get

This field indicates the description of the item.

BillOfMaterials/BillOfMaterialsHeader/OutputItem/Classification/Codes/Code

MITMAS.MMITGR

1) Item group

The field indicates the item group.

2) Product group

The field indicates the product group.

3) Business area

The field indicates the business area.

4) Item type

The item type is mandatory and cannot be changed after the item is created. The only time an item type can be changed is when you copy template items.

The functions connected to the item type include:

-A template item that contains default values for creating items.

-A numbering rule for assigning the correct item number

-A warehouse/item type to set the item/warehouse records generated when you create an item.

-An alias/item type that is used to set the alias numbers generated when you create an item.

5) Item category

The field indicates the item category.

Alternatives

00 = Normal item

02 = Phantom item

03 = Subcontracted item

MMITCL

MMBUAR

MMITTY

MMTPCD

MMPRGP; MMS200MI.GetItmBasic

BillOfMaterials

	04 = Tool 05 = Fixed machine 07 = Repairable item 08 = Recyclable item 11 = Extended Catalog Item (ECI) 12 = Non-coded Extended Catalog Item 13 = Non-material item 6) Procurement grp The field indicates the procurement group for an item.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/Classification/Description CSYTAB CSLGHN.CTTX40 JTTX60; CRS175MI.LstCodesByLng @languageID CSLGHN.JLLNCD; CRS175MI.LstCodesByLng	This field indicates a description of the classification. It is retrieved from table CSYTAB (generic description) and table CSLGHN (language-specific description) This field indicates the language id.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/HazardousMaterial/ID MITMAS.MMITNO; MMS200MI.GetItmBasic	This field indicates the item number which is tagged as hazardous material (HAZI = 1). If HAZI = 0, this field is blank.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/HazardousMaterial/Description MITMAS.MMFUDS; MMS200MI.LstItemDescLang	This field indicates the general item description. If description also exists in specific languages, this is provided together with the language ID
BillOfMaterials/BillOfMaterialsHeader/OutputItem/Type MITMAS.MMBYPR; MMS200MI.GetItmBasic	This field indicates the product type. 0 - Normal item 1 - By-product 2 - Co-product 3 - Main product
BillOfMaterials/BillOfMaterialsHeader/OutputItem/YieldPercent MPDHED.PHEXPC; PDS001MI.Get	This field indicates the yield percentage. (Rule :if blank or '0%', transfer '100%') The field indicates the product's theoretical yield, expressed as a percentage to two decimal places. You can specify either the yield percentage or the yield quantity manually. If you leave this value blank, it will be calculated automatically. The yield is calculated as the quotient between the yield quantity and the batch quantity.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/Yield MPDHED.PHBAQT; PDS001MI.Get	This field indicates the yield quantity. (Rule: if blank or '0', transfer '1') The field indicates the net outcome of the production process for each production batch.
@unitCode MPDHED.PHUNMS; PDS001MI.Get	This field indicates the unit of measure (translate according to CRS881).
BillOfMaterials/BillOfMaterialsHeader/OutputItem/ProducedBaseUOMQuantity MPDHED.PHEOQT; PDS001MI.Get	This field indicates the normal order quantity of each item/warehouse, that is the quantity that should be ordered when a requirement arises. The quantity often refers to the economical quantity. Order quantity is always expressed in the basic U/M of each item.
@unitCode MITMAS.MMUNMS; PDS001MI.Get	This field indicates the unit of measure (translate according to CRS881).
BillOfMaterials/BillOfMaterialsHeader/OutputItem/OrderBaseUOMQuantity MPDHED.PHEOQT; PDS001MI.Get	This field indicates the normal order quantity of each item/warehouse, that is the quantity that should be ordered when a requirement arises. The quantity often refers to the economical quantity. Order quantity is always expressed in the basic U/M of each item.
@unitCode MITMAS.MMUNMS; PDS001MI.Get	This field indicates the unit of measure (translate according to CRS881).
BillOfMaterials/BillOfMaterialsHeader/PhantomIndicator MITMAS.TPCD; MMS200MI .GetItmBasic	This field indicates if the object is a phantom item or not. Set to '1' if TPCD =2.
BillOfMaterials/BillOfMaterialsHeader/ParentBillOfMaterialsReference/DocumentID/ID MPDHED.DWNO; PDS001MI.Get	This field indicates a unique ID for the drawing used in designing the item.

BillOfMaterials

	The drawing number is set per item and can also be used as a search key in both the item file and product structures.
BillOfMaterials/BillOfMaterialsHeader/Name MITMAS.MMITDS; PDS001MI.Get	The field indicates the name for each item.
BillOfMaterials/BillOfMaterialsHeader/Location/ID MPDHED.PMFACI; PDS001MI.Get	This field indicates the facility used.
@accountingEntity MPDHED.PHCONO CMNDIV.CCDIVI.; N/A.	This attribute indicates the company division.
BillOfMaterials/BillOfMaterialsHeader/Location/Name CFACIL.CFFACN; CRS008MI.Get	This field indicate the name of the facility.
BillOfMaterials/BillOfMaterialsHeader/Yield MPDHED.PHBAQT; PDS001MI.Get	This field indicates the yield quantity. (Rule: if blank or '0', transfer '1')
@unitCode MPDHED.PHUNMS; PDS001MI.Get	The field indicates the net outcome of the production process for each production batch. Unit of measure (translate according to CRS881).
BillOfMaterials/BillOfMaterialsLine/LineNumber MPDMAT.PMMSEQ; PDS002MI.LstComponent	This field indicates the sequence number for material used in BOM.
BillOfMaterials/BillOfMaterialsLine/Description MITMAS.MMITDS; PDS002MI.LstComponent	This field indicates the description of the item.
BillOfMaterials/BillOfMaterialsLine/Note MPDMAT.PMFMT1; PDS002MI.LstComponent	This field is used to enter optional text.
BillOfMaterials/BillOfMaterialsLine/Status/Code MPDMAT.PMSTAT; PDS002MI.LstComponent	This field indicates the status of material line. 10 - Hold 20 - Open 90 - Deleted
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/ItemID/ID MPDMAT.PMMTNO; PDS002MI.LstComponent	This field indicates a component number.
@schemeName .; PDS002MI.LstComponent	Send BLANK in Scheme name
@accountingEntity .; .	This attribute indicates the company and division.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/ItemID/RevisionID MPDMAT.PMFECV; PDS002MI.LstComponent	This field indicates the revision number.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/UPCID MITPOP.MPPOPN; MMS025MI.GetAlias	Correspond to GTIN-12 and UCC-12. This is a 12-digit number used for identifying goods.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Description MITMAS.MMITDS; PDS002MI.LstComponent	This field indicates the description of the item.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Note MPDMAT.PMFMT1; PDS002MI.LstComponent	This field is used to enter optional text.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/LineNumber MPDMAT.PMMSEQ; PDS002MI.LstComponent	This field indicates the sequence number for material used in BOM.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Status/Code MPDMAT.PMSTAT; PDS002MI.LstComponent	This field indicates the status of material line. 10 - Hold 20 - Open 90 - Hold
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Status/EffectiveDate/Time MPDMAT.PMFDAT; PDS002MI.LstComponent	This field indicates the date the material becomes effective.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Name MITMAS.MMITDS; MMS200MI.GetItemBasic	This field indicates the name for each item.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Quantity MPDMAT.PMCNQT; PDS002MI.LstComponent	This field indicates the quantity of each component used in the bill of material/structure of a product.
@unitCode MITMAS.MMUNMS; PDS002MI.LstComponent	Unit of measure for material (translate according to CRS881).
BillOfMaterials/BillOfMaterialsHeader/DocumentID/ID MPDHED.PRNO; PDS001MI.Get	This field indicates the product number. The product number is the same as the in-house manufacturing item number and is always used together with structures to describe what a product consists of and how it is manufactured.
BillOfMaterials/BillOfMaterialsHeader/Status/Code MPDHED.PHSTAT; PDS001MI.Get	This field indicates the status of the record. 10 - Hold

BillOfMaterials

	20 - Open 90 - Hold
BillOfMaterials/BillOfMaterialsHeader/OutputItem/ItemID/ID MPDHED.PHPRNO; PDS001MI.Get	This field indicates the product number. The product number is the same as the in-house manufacturing item number and is always used together with structures to describe what a product consists of and how it is manufactured.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/Description @languageID MPDHED.PHITDS; PDS001MI.Get	This field indicates the description of the item.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/YieldPercent MPDHED.PHEXPC; PDS001MI.Get	This field indicates the yield percentage. (Rule :if blank or '0%', transfer '100%') The field indicates the product's theoretical yield, expressed as a percentage to two decimal places. You can specify either the yield percentage or the yield quantity manually. If you leave this value blank, it will be calculated automatically. The yield is calculated as the quotient between the yield quantity and the batch quantity.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/Yield MPDHED.PHBAQT; PDS001MI.Get	This field indicates the yield quantity. (Rule: if blank or '0', transfer '1') The field indicates the net outcome of the production process for each production batch.
@unitCode MPDHED.PHUNMS; PDS001MI.Get	Unit of measure (translate according to CRS881)
BillOfMaterials/BillOfMaterialsLine/LineNumber MPDMAT.PMMSEQ; PDS002MI.LstComponent	This field indicates the sequence number for material used in BOM.
BillOfMaterials/BillOfMaterialsLine/Description @languageID MPDMAT.PMITDS; PDS002MI.LstComponent	This field indicates the description of the item.
BillOfMaterials/BillOfMaterialsLine/Status/Code MPDMAT.PMSTAT; PDS002MI.LstComponent	This field indicates the status of material line. 10 - Hold 20 - Open 90 - Hold
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/ItemID/ID MPDMAT.PMMTNO; PDS002MI.LstComponent	This field indicates a component number, which is identical to a subordinated item number. It is used to enter items that are included during preparation of product structures and orders.
@schemeName ..	Send BLANK in Scheme name
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Quantity MPDMAT.PMCNQT; PDS002MI.LstComponent	This field indicates the quantity of each component used in the bill of material/structure of a product.
@unitCode MPDMAT.PMUNMS; PDS002MI.LstComponent	Unit of measure for material (translate according to CRS881).

BillToPartyMaster

BillToPartyMaster/PartyIDs/ID

OCUSMA.OKCUNO; CRS610MI/GetBasicData
@accountingEntity
CMNDIV.CCDIVI; N/A/

The field indicates the Customer number

Customer records in M3 BE are managed on company level.
M3 BE generates one BOD per division.

DIVI is translated and assigned to the accountingEntity attribute.

@variationID

The field indicates the variationID

@lid

The logical ID of the system that is SOR for this noun instance.

BillToPartyMaster/Name

OCUSMA.OKCUNM; CRS610MI/GetBasicData

This field indicates the customer name

BillToPartyMaster/Location/Address/AttentionOfName

OCUSAD
OCUSMA.OKYREF; CRS610MI/LstAddresses
GetBasicData

The field indicates the customer's contact person

BillToPartyMaster/Location/Address/AddressLine

OCUSAD
OCUSMA.OKCUA1-OKCUA4; CRS610MI/LstAddresses
GetBasicData

This indicates the address lines for the customer address

@sequence

The field indicates the Address Line sequence

BillToPartyMaster/Location/Address/CityName

OCUSAD
OCUSMA.OKTOWN; CRS610MI/LstAddresses
GetBasicData

The field indicates the city

BillToPartyMaster/Location/Address/CountrySubDivisionCode

OCUSAD
OCUSMA.OKECAR; CRS610MI/LstAddresses
GetBasicData

The field indicates the state/region/countrysubdivision

@listID

M3 BE field State has different list ID depending on country:
- Canada has list ID "Canadian Provinces"
- France has list ID "France - Departements"
- United States has list ID "US States"
- Other countries have list ID "Country Sub-divisions"

BillToPartyMaster/Location/Address/CountryCode

OCUSAD
OCUSMA.OKCSCD; CRS610MI/LstAddresses
GetBasicData

The field indicates the country code

@listID

M3 BE field Country has list ID "Countries"

BillToPartyMaster/Location/Address/PostalCode

OCUSAD
OCUSMA.OKPONO; CRS610MI/LstAddresses
GetBasicData

The field indicates the postal code

BillToPartyMaster/Location/Address/PreferenceIndicator

This field is set to true

BillToPartyMaster/PaymentTermID

OCUSMA.OKTEPY/CCUDIV.OKTEPY.; CRS610MI/GetOrderInfo

The field indicates the payment terms id for the customer
Data is retrieved from customer master, table OCUSMA, or, if applicable, from customer local exceptions, table CCUDIV.

BillToPartyMaster/Status/Code

OCUSMA.OKSTAT; CRS610MI/GetBasicData

The field indicates the status of the customer.

If M3 status is 10, set element to "Pending"
If M3 status is 20, set element to "Open"
If M3 status is 90, set element to "Closed"

BillToPartyMaster/Classification/Codes/Code

- 1) OCUSMA.OKCUTP; CRS610MI/GetBasicData
- 2) OCUSMA.OKTEDL/CCUDIV.OKTEDL; CRS610MI/GetOrderInfo
- 3) OCUSMA.OKSDST; CRS610MI/GetOrderInfo

The field indicates the Classification.

- 1) If Customer type field is filled, populate Code with this value
- 2) If Delivery terms field is filled, populate Code with this value
Data is retrieved from customer master, table OCUSMA, or, if applicable, from customer local exceptions, table CCUDIV.
- 3) If District field is filled, populate Code with this value

@listID

The field indicates the Classification code listID.

- 1) If Customer type field is filled, set listID to "Customer Types"
- 2) If Delivery terms field is filled, set listID to "Incoterms"
- 3) If District field is filled, set listID to "District"

@sequence

BillToPartyMaster

	The sequence attribute identifies the hierarchical position of the identifier in the case of multi-level codes
BillToPartyMaster/CustomerParty/PartyIDs/ID OCUSMA.OKCUNO; CRS610MI/LstByInvoiceRec	This is a list of customers that uses BillToParty as the invoice recipient. (The BillToParty itself is also included in the list)
@accountingEntity	Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity. To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID. E.g. m3be.orbit1412 330
BillToPartyMaster/CustomerParty/Name OCUSMA.OKCUNM; CRS610MI/GetBasicData	This field indicates the name of the CustomerPartyMaster
BillToPartyMaster/ShipToParty/PartyIDs/ID OCUSMA.OKCUNO; CRS610MI/LstByInvoiceRec	This is a list of ShipToParties for the BillToParty id. It reflects the same data as CustomerParty (The BillToParty itself is also included in the list)
@accountingEntity OCUSMA.OKCONO CMNDIV.CCDIVI.; N/A/	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 780_AAA It is possible to translate using CRS881, but we recommend NOT to translate.
BillToPartyMaster/ShipToParty/Name OCUSMA.OKCUNM; CRS610MI/GetBasicData	This field indicates name of the ShipToPartyMaster

CarrierParty

CarrierParty/PartyIDs/ID

@accountingEntity

.CONO+DIVI; -/

The field indicates the company and division

@variationID

.-; -/

The field indicates the variation ID

@lid

.-; -/

The field indicates the logical ID

CarrierParty/PartyIDs/TaxID

CIDVEN.ITINO; CRS620MI/GetBasicData

The field indicates the tax registration number of the company.

CarrierParty/PartyIDs/SCACID

CIDMAS.IDFWSC; CRS620MI/GetBasicData

The field indicates Standard Carrier Alpha Code (SCAC). The SCAC is a four-letter alpha code that uniquely identifies a forwarder. SCAC codes are assigned and maintained by the National Motor Freight Traffic Association (NMFTA). The SCAC is printed on the bill of lading documents.

CarrierParty/Name

CIDMAS.IDSUNM; CRS620MI/GetBasicData

The field indicates supplier name, most often the supplier's company name.

CarrierParty/Contact/ID

CIDREF.IRRFTY; CRS620MI/ListSupplierRef

The field indicates which of the following supplier references to be used.

Alternatives

10 = Purchase

15 = Repair or subcontract

20 = Delivery receipt

25 = Claim

30 = Financial

35 = Agreement.

The field indicates the ID of the current record in the reference file.

CarrierParty/Contact/Name

CIDREF.IRYRE1; CRS620MI/ListSupplierRef

The field indicates the name of the person to be contacted for issues regarding customer orders or purchase orders.

The name is obtained from the customer or supplier file. This is displayed by default when you enter customer orders or purchase orders.

CarrierParty/Contact/Communication/DialNumber

CIDREF.IRPHNO; CRS620MI/ListSupplierRef

The field indicates the telephone number of the customer or supplier.

CarrierParty/Contact/Communication/URI

CIDREF.IREMAL; CRS620MI/ListSupplierRef

The field indicates an e-mail address for the customer, supplier, etc. entered.

ChartOfAccounts

ChartOfAccounts/IDs/ID	
FCHACC.AITM; CRS630MI/GetAccountID	Account ID
ChartOfAccounts/LastModificationDateTime	
FCHACC.LMDT; CRS630MI/GetAccountID	LMDT converted to DateTime
ChartOfAccounts/DocumentDateTime	
FCHACC.RGDT; CRS630MI/GetAccountID	Combination of RGDT and RGTM
ChartOfAccounts/Description	
FCHACC.TX40; CRS630MI/GetAccountID	TX40 from FCHACC
ChartOfAccounts/Status/Code	
FCHACC.LCCD; CRS630MI/GetAccountID	LCCD = 0 then 'OPEN'. If LCCD = 1 then 'CLOSED'
ChartOfAccounts/BaseChartOfAccounts/GLNominalAccount	
FCHACC.AITM; CRS630MI/GetAccountID	0
ChartOfAccounts/BaseChartOfAccounts/EffectiveTimePeriod/StartDateTime	
FCHACC.VFDT; CRS630MI/GetAccountID	0
ChartOfAccounts/BaseChartOfAccounts/EffectiveTimePeriod/EndDateTime	
FCHACC.VTDT; CRS630MI/GetAccountID	0
ChartOfAccounts/BaseChartOfAccounts/AccountType	
FCHACC.AT01, AT02; CRS630MI/GetAccountID	If AT01 = 1 then 'BalanceSheet'. If AT02 = 1 then 'ProfitAndLoss'
ChartOfAccounts/BaseChartOfAccounts/CurrencyCode	
FCHACC.CUCD; CRS630MI/GetAccountID	0
@listID	
Constant.; /	Constant = 'Currency'
ChartOfAccounts/BaseChartOfAccounts/Description	
FCHACC.TX40; CRS630MI/GetAccountID, GetAccountLng	The standard description is fetched from FCHACC, the description in different languages from FCAIDL
ChartOfAccounts/Name	
FCHACC.TX40; CRS630MI/	The standard description is fetched from FCHACC, the description in different languages from FCAIDL
ChartOfAccounts/ShortName	
FCHACC.TX15; CRS630MI/	The standard name is fetched from FCHACC, the description in different languages from FCAIDL
ChartOfAccounts/RevaluationIndicator	
FCHACC.AT06; CRS630MI/	True/false
ChartOfAccounts/DimensionProfileSet/ID	
Constant.; /	Constant = 'DimensionProfileSetStandard'
ChartOfAccounts/DimensionProfileSet/DimensionProfile/ID	
FCHACC.ACR2-7; CRS630MI/GetAccountID	Concatination of ACR2, ACR3, ACR4, ACR5, ACR6, ACR7
ChartOfAccounts/DimensionProfileSet/DimensionProfile/Status/Code	
Constant.; /	Constant = 'Open'
ChartOfAccounts/DimensionProfileSet/DimensionProfile/DimensionUsage/ListID	
CSYTAB.multiple; CRS175MI/GetGeneralCode	YGAI51, YGAI52, YGAI53, YGAI54, YGAI55, YGAI56, YGAI57
ChartOfAccounts/DimensionProfileSet/DimensionProfile/DimensionUsage/Usage	
FCHACC.ACR2-7; CRS630MI/GetAccountID	if ACR# = 0, 5, 6, 7, 8 then Optional else Mandatory

CodeDefinition

CodeDefinition/DocumentID/ID

For Accounting Dimension:
FCHACC.EAAITM; CRS630MI/GetAccountID

For AR Payment Methods:
CSYTAB.CTSTKY; N/A/

For Delivery Terms:
CSYTAB.CTSTKY; N/A/

For Dynamic Dimensions:
FCHACC.EAAITM; CRS630MI /GetAccountID

For General Code:
CSYTAB.CTSTKY; /

For Harbor / Airports:
CSYTAB.CTSTKY; N/A/

For Item Types:
MITTTY.TYITTY; N/A/

For Payment Terms:
CSYTAB.CTSTKY; N/A/

For Product Structure Types:
CSYTAB.CTSTKY; N/A/

For Purchase Order Types:
MPORDT.OTORTY; N/A/

For Routes:
DROUTE.DRROUT; N/A/

For Transportation Methods:
CSYTAB.CTSTKY; N/A/

For Unit Codes:
CSYTAB.CTSTKY; N/A/

For Feature Options:
MPDFHE.FTID; PDS055MI/Get

For Accounting Dimension:
The field indicates an accounting identity in an accounting dimension.
An accounting dimension is a part of the accounting string used to describe financial events in detail. M3 accounting strings contain seven dimensions.

For AR Payment Methods:
This is the payment method id. If constant value (STCO) = 'PYCD' then display payment method.

For Delivery Terms:
This indicates the code id

For Dynamic Dimensions:
The field indicates an accounting identity in an accounting dimension.
An accounting dimension is a part of the accounting string used to describe financial events in detail. M3 accounting strings contain seven dimensions.

For General Code:
This indicates the code id

For Harbor / Airports:
This is the harborairport id. If constant value (STCO) = 'HAFE' then display HarborAirport.

For Item Types:
This is the item type id
(retrieved from the M3 event through Event Hub)

For Payment Terms:
This indicates the code id

For Product Structure Types:
This indicates the product structure type id. It is retrieved via the M3 BE event.

For Purchase Order Types:
This indicates the code id

For Routes:
This is the route id.

For Transportation Methods:
This is the harborairport id. If constant value (STCO) = 'MODL' then display Transportation method.

For Unit Codes:
This indicates the unit of measure code id. It is retrieved via the M3 BE event.
It should be according to the X12 ANSI standard

For Feature Options:
The field indicates the fashion feature.

For Accounting Dimension:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For AR Payment Methods:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Delivery Terms:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate

For Dynamic Dimensions:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 770_AAA
It is possible to translate using CRS881, but we recommend NOT to

@accountingEntity

For Accounting Dimension:
FCHACC.EACONO
CMNDIV.CCDIVI.; CRS630MI/GetAccountID

For AR Payment Methods:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Delivery Terms:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Dynamic Dimensions:
N/A.; CRS630MI /GetAccountID

For General Code:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Harbor / Airports:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

CodeDefinition

For Item Types:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Payment Terms:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; /

For Purchase Order Types:
MPORDT.OTCONO
CMNDIV.CCDIVI.; N/A/

For Routes:
DROUTE.DRCONO
DROUTE.DRDIVI.; N/A/

For Transportation Methods:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Unit Codes:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Feature Options:
MPDFHE.PECONO
CMNDIV.CCDIVI.; /

translate.

For General Code:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Harbor / Airports:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Item Types:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Payment Terms:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Product Structure Types:
Accounting entity corresponds to M3 BE company and division. It is presented as CONO_DIVI, e.g. 780_AAA.

For Purchase Order Types:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Routes:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Transportation Methods:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Unit Codes:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Feature Options:
The field indicates the company and division.

For AR Payment Methods:
This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Delivery Terms:
This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Dynamic Dimensions:
A sequence number to ensure documents are processed in correct order.

For General Code:
This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Harbor / Airports:
This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Item Types:
This indicates the sequence number. Sequence number is an internal

@variationID

CodeDefinition

@lid

number to ensure documents are processed in correct order.

For Product Structure Types:

This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Purchase Order Types:

This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Routes:

This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Transportation Methods:

This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Unit Codes:

This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Feature Options:

The field indicates the sequence number that identifies the number of times that this BOD has been published.

For Accounting Dimension:

The logical ID of the system that is this SOR for this noun instance. Used with the global ID- no schemeNameAttribute.

For AR Payment Methods:

The logical ID of the system that is SOR for this noun instance.

For Delivery Terms:

The logical ID of the system that is SOR for this noun instance.

For Dynamic Dimensions:

The logical ID of the system that is this SOR for this noun instance. Used with the global ID- no schemeNameAttribute.

For General Code:

The logical ID of the system that is SOR for this noun instance.

For Harbor / Airports:

The logical ID of the system that is SOR for this noun instance.

For Item Types:

The logical ID of the system that is SOR for this noun instance.

For Product Structure Types:

The logical ID of the system that is SOR for this noun instance.

For Purchase Order Types:

The logical ID of the system that is SOR for this noun instance.

For Routes:

The logical ID of the system that is SOR for this noun instance.

For Transportation Methods:

The logical ID of the system that is SOR for this noun instance.

For Unit Codes:

The logical ID of the system that is SOR for this noun instance.

For Feature Options:

The field indicates the logical ID of the system.

CodeDefinition/LastModificationDateTime

For Unit Codes:

CSYTAB.CTLMTS; N/A/

For Unit Codes:

This indicates the date and time the code was last modified. It is retrieved via the M3 BE event.

CodeDefinition/LastModificationPerson/IDs/ID

For Unit Codes:

CSYTAB.CTCHID; N/A/

For Unit Codes:

This indicates the person who last modified the code. It is retrieved via the M3 BE event.

CodeDefinition/EffectiveTimePeriod/StartDateTime

For Accounting Dimension:

FCHACC.EAVFDT; CRS630MI/GetAccountID

For Accounting Dimension:

Valid From Date from CRS630

CodeDefinition

CodeDefinition/EffectiveTimePeriod/EndDateTime

For Accounting Dimension:
FCHACC.EAVTDT; CRS630MI/GetAccountID

For Accounting Dimension:
Valid To Date from CRS630

CodeDefinition/Status/Code

For Accounting Dimension:
FCHACC.EALCCD; CRS630MI/GetAccountID

For Accounting Dimension:
Blocked from CRS630

For AR Payment Methods:
This indicates the Status of the code id.
It is always set to "Open"

For Delivery Terms:
This indicates the Status of the code id.
It is hardcoded to "Open"

For General Code:
This indicates the Status of the code id.
It is hardcoded to "Open"

For Harbor / Airports:
This indicates the Status of the code id.
It is always set to "Open"

For Item Types:
This indicates the Status of the code id.
It is always set to "Open"

For Product Structure Types:
This indicates the Status of the code id.
It is always set to "Open".

For Purchase Order Types:
This indicates the Status of the code id.
It is always set to "Open"

For Routes:
This indicates the Status of the code id.
It is always set to "Open"

For Transportation Methods:
This indicates the Status of the code id.
It is always set to "Open"

For Unit Codes:
This indicates the Status of the code id.
It is always set to "Open".

For Feature Options:
The field indicates the status of the object. Hardcoded to "Open".

For Feature Options:
The field indicates the list ID for the status code. Hardcoded to "Code Definition Status".

@listID

CodeDefinition/ReadOnlyIndicator

For AR Payment Methods:
This indicates that this instance is ReadOnly, but if this instance is for a Dimension Type instance it is not inherited by the children. Default value is false

For Delivery Terms:
This indicates that this instance is ReadOnly, but if this instance is for a Dimension Type instance it is not inherited by the children. Default value is false

For General Code:
This indicates that this instance is ReadOnly, but if this instance is for a Dimension Type instance it is not inherited by the children. Default value is false

For Harbor / Airports:
This indicates that this instance is ReadOnly, but if this instance is for a Dimension Type instance it is not inherited by the children. Default value is false

For Item Types:
This indicates that this instance is ReadOnly, but if this instance is for a Dimension Type instance it is not inherited by the children. Default value is false

For Product Structure Types:
This is set to "false" for codes and "true" for code dimensions.

For Purchase Order Types:
This indicates that this instance is ReadOnly, but if this instance is for a Dimension Type instance it is not inherited by the children. Default value is false

For Routes:
This indicates that this instance is ReadOnly, but if this instance is for a Dimension Type instance it is not inherited by the children. Default value is false

For Transportation Methods:
This indicates that this instance is ReadOnly, but if this instance is for a Dimension Type instance it is not inherited by the children. Default value is false

For Unit Codes:
This is set to "false" for codes and "true" for code dimensions.

CodeDefinition/ListID

CSYTAB.CTPARM; CRS175MI/GetGeneralCode

For Accounting Dimension:
Loop through fields YGAI51, YGAI52, YGAI53, YGAI54, YGAI55, YGAI56, YGAI57

For AR Payment Methods:
This indicates the list id, it is always set to "Payment Methods"

For Delivery Terms:
This indicates the list id for Delivery term.

M3 BE field Delivery term has list ID "Incoterms"

For Dynamic Dimensions:
Loop through fields YGAI51, YGAI52, YGAI53, YGAI54, YGAI55, YGAI56, YGAI57

For General Code:
This indicates the list id for the General code.
Currently we support following list id's:

M3 BE field Item group has list ID "Item Groups"
M3 BE field Product group has list ID "Product Groups"
M3 BE field Business area has list ID "Business Sectors"
M3 BE field Procurement group has list ID "Buying Groups"
M3 BE field Country has list ID "Countries"
M3 BE field State has different list ID depending on country:
- Canada has list ID "Canadian Provinces"
- France has list ID "France - Departements"
- United States has list ID "US States"
- Other countries have list ID "Country Sub-divisions"
M3 BE field District has list ID "District"

For Harbor / Airports:
This indicates the list id for HarborAirports.

For Item Types:
This indicates the list id, it is always set to "Item Types"

For Product Structure Types:
This indicates the list id, and is set to "Product Structure Types".

For Purchase Order Types:
This indicates the list id for the General code.
This is set to "Purchase Order Types"

For Routes:
This indicates the list id; Always set display to "Routes"

For Transportation Methods:
This indicates the list id for TransportationMethods.

For Unit Codes:
This indicates the list id, and is set to "Unit Codes".

For Feature Options:
The field indicates the list ID. Hardcoded to "StyleFeatures".

CodeDefinition

CodeDefinition/CodeValue

For Accounting Dimension:
FCHACC.EAAITM; CRS630MI /GetAccountID

For AR Payment Methods:
CSYTAB.CTSTKY; N/A/

For Delivery Terms:
CSYTAB.CTSTKY; /

For Dynamic Dimensions:
FCHACC.EAAITM; CRS630MI /GetAccountID

For General Code:
CSYTAB.CTSTKY; N/A/

For Harbor / Airports:
CSYTAB.CTSTKY; N/A/

For Item Types:
MITTTY.TYITTY; N/A/

For Payment Terms:
CSYTAB.CTSTKY; /

For Product Structure Types:
CSYTAB.CTSTKY; N/A/

For Purchase Order Types:
MPORDT.OTORTY; N/A/

For Routes:
DROUTE.DRROUT; N/A/

For Transportation Methods:
CSYTAB.CTSTKY; N/A/

For Unit Codes:
CSYTAB.CTSTKY; N/A/

For Feature Options:
MPDFHE.PEFTID; PDS055MI/Get

For Accounting Dimension:
Accounting ID from CRS630

For AR Payment Methods:
This indicates the code value.

For Delivery Terms:
This indicates the code value.

For Dynamic Dimensions:
Accounting ID from CRS630

For General Code:
This indicates the code value.

For Harbor / Airports:
This indicates the code value.
If constant value (STCO) = 'HAFE'

For Item Types:
This indicates the code value.
(retrieved from the M3 event through Event Hub)

For Payment Terms:
This indicates the code value.

For Product Structure Types:
This indicates the product structure type id.It is retrieved via the M3 BE event.

For Purchase Order Types:
This indicates the code value.

For Routes:
This indicates the code value.

For Transportation Methods:
This indicates the code value.
If constant value (STCO) = 'MODL'

For Unit Codes:
This indicates the unit of measure code value.It is retrieved via the M3 BE event.
It should be according to the X12 ANSI standard

For Feature Options:
The field indicates the fashion feature.

@accountingEntity

For AR Payment Methods:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Delivery Terms:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For General Code:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Harbor / Airports:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Item Types:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Payment Terms:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; /

For Purchase Order Types:
MPORDT.OTCONO
CMNDIV.CCDIVI.; N/A/

For Routes:

For AR Payment Methods:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Delivery Terms:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For General Code:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Harbor / Airports:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Item Types:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

CodeDefinition

DROUTE.DRCONO
DROUTE.DRDIVI.; N/A/

For Transportation Methods:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Unit Codes:
CSYTAB.CTCONO
CMNDIV.CCDIVI.; N/A/

For Feature Options:
MPDFHE.PECONO
CMNDIV.CCDIVI.; /

For Payment Terms:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Product Structure Types:
Accounting entity corresponds to M3 BE company and division. It is presented as CONO_DIVI, e.g. 780_AAA.

For Purchase Order Types:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Routes:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Transportation Methods:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Unit Codes:
AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

For Feature Options:
The field indicates the company and division.

CodeDefinition/Name

For Accounting Dimension:
FCHACC, FCAIDL.EATX40, ELTX40; CRS630MI/GetAccountID,
LstAccountIDLng

For AR Payment Methods:
CSYTAB.CTTX15; N/A/

For Delivery Terms:
CSYTAB.CTTX15; CRS175MI/GetGeneralCode

For Dynamic Dimensions:
FCHACC.EAAITM; CRS630MI /GetAccountID

For General Code:
CSYTAB.CTTX15; CRS175MI/LstCodesByLng

For Harbor / Airports:
CSYTAB.CTTX15; N/A/

For Item Types:
MITTTY.TYTX15; N/A/

For Payment Terms:
CSYTAB.CTTX15; CRS175MI/GetGeneralCode

For Product Structure Types:
CSYTAB.CTTX15; N/A/

For Purchase Order Types:
MPORDT.OTTX15; N/A/

For Routes:
DROUTE.DRTX15; N/A/

For Transportation Methods:
CSYTAB.CTTX15; N/A/

For Unit Codes:
CSYTAB.CTTX15; N/A/

For Accounting Dimension:
Name from CRS630 or Description from CRS012

For AR Payment Methods:
The field indicates the code name. If constant value (STCO) = 'PYCD' then display the following: Get the first character in the parameter field (CTPARM) then display if: 0 = Cash; 2 = Cheque; 3 = CreditCard/DebitCard/ElectronicFundsTransfer; 4 = BankDraft

For Delivery Terms:
The field indicates a name of the code.

For Dynamic Dimensions:
Name from CRS630 or Description from CRS012

For General Code:
The field indicates the code name.

For Harbor / Airports:
The field indicates the code name.

For Item Types:
The field indicates the code name.
(retrieved from the M3 event through Event Hub)

For Payment Terms:
The field indicates a name of the code.

For Product Structure Types:
The field indicates a name of the code.

For Purchase Order Types:
The field indicates the code name.

For Routes:
The field indicates the code name.

For Transportation Methods:
The field indicates the code name.

CodeDefinition

For Feature Options:
MPDFHE.PETX10; PDS055MI/Get

For Unit Codes:
The field indicates a name of the code.

@languageID

For Accounting Dimension:
FCAIDL.ELLNCD; CRS630MI/LstAccountIDLng

For Feature Options:
The field indicates the name of the feature.

For Accounting Dimension:
System Language from CRS012

For Delivery Terms:
CSYTAB.CTLNCD; N/A/

For Delivery Terms:
The field indicates the language.
It is retrieved from the event data.

For General Code:
CSYTAB.CTLNCD; CRS175MI/LstCodesByLng

For General Code:
The field indicates the language

For Payment Terms:
CSYTAB.CTLNCD; N/A/

For Payment Terms:
The field indicates the language.
It is retrieved from the event data.

CodeDefinition/Description

For Accounting Dimension:
FCHACC.EATX40; CRS630MI/GetAccountID

For Accounting Dimension:
Description

For AR Payment Methods:
CSYTAB.CTTX40; N/A/

For AR Payment Methods:
The field indicates the code description.

For Delivery Terms:
CSYTAB.CTPARM; CRS175MI/GetGeneralCode

For Delivery Terms:
The field indicates Payment terms text.
It is a substring of the first 72 characters of field PARM.

For Dynamic Dimensions:
FCHACC.EAAITM; CRS630MI /GetAccountID

For Dynamic Dimensions:
Name from CRS630 or Description from CRS012

For General Code:
CSYTAB.CTTX40; CRS175MI/LstCodesByLng

For General Code:
The field indicates the code description.

For Harbor / Airports:
CSYTAB.CTTX40; N/A/

For Harbor / Airports:
The field indicates the code description.

For Item Types:
MITTTY.TYTX40; N/A/

For Item Types:
The field indicates the code description.
(retrieved from the M3 event through Event Hub)

For Payment Terms:
CSYTAB.CTPARM; CRS175MI/GetGeneralCode

For Payment Terms:
The field indicates Payment terms text.
It is a substring of the first 72 characters of field PARM.

For Product Structure Types:
CSYTAB.CTTX40; N/A/

For Product Structure Types:
The field indicates a description of the code.

For Purchase Order Types:
MPORTD.OTTX40; N/A/

For Purchase Order Types:
The field indicates the code description.

For Routes:
DROUTE.DRTX40; N/A/

For Routes:
The field indicates the code description.

For Transportation Methods:
CSYTAB.CTTX40; N/A/

For Transportation Methods:
The field indicates the code description.

For Unit Codes:
CSYTAB.CTTX40; N/A/

For Unit Codes:
The field indicates a description of the code.

For Feature Options:
MPDFHE.PETX30; PDS055MI/Get

For Feature Options:
The field indicates the description of the feature.

@languageID

For Delivery Terms:
CSYTAB.CTLNCD; N/A/

For Delivery Terms:
The field indicates the language.
It is retrieved from the event data.

For General Code:
CSYTAB.CTLNCD; CRS175MI/LstCodesByLng

For General Code:
The field indicates the language

For Payment Terms:
CSYTAB.CTLNCD; N/A/

For Payment Terms:
The field indicates the language.
It is retrieved from the event data.

CodeDefinition/Property

@sequence

For Feature Options:

CodeDefinition

MPDVOF.PLSQNU; PDS056MI/List	For Feature Options: The field indicates the sequence number for sorting.
CodeDefinition/Property/NameValue For Feature Options: MPDFHE.PEFGRP MPDVOF.PFOPTN.; PDS055MI PDS056MI/Get List	For Feature Options: The field indicates the Feature group or Option depending on the name attribute. The feature group can be used for selection and as additional information for a feature. The set groups X, Y and Z must be used for features that will be displayed in matrix form, where they represent the axes. The option provides a selection that can be applied for the feature.
@name	For Feature Options: The field indicates the name of the property. Hardcoded to "StyleFeatureTypes" for Feature Group and "StyleOption" for Options.
CodeDefinition/Property/Description For Feature Options: MPDVOF.PFOPTX; PDS056MI/List	For Feature Options: The field indicates the description of the Option.

ConfiguredAssetMaster

ConfiguredAssetMaster/IDs/ID MILOIN.ITNO/SERN; MMS240MI/LstByComp (or input to bod)	This field indicate the primary key for the equipment master Item + Serial number
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; N/A/	This field indicate the accounting entity combination of company and division.
ConfiguredAssetMaster/DisplayID MILOIN.LIITNO/SERN; MMS240MI/LstByComp (or input to bod)	This field indicate the primary key for the equipment master Item + Serial number
ConfiguredAssetMaster/Description MILOIN.LIALII; MMS240MI/GetBasic	This field indicate the description for the equipment
ConfiguredAssetMaster/Note @entryDateTime MILOIN.LITXID; MMS240MI/GetBasic	This field indicate the text or note associated with the equipment retived from TXID
ConfiguredAssetMaster/Status/ArchiveIndicator MILOIN.LISTAT; MMS240MI/GetBasic	This field indicate the status of the equipment
ConfiguredAssetMaster/CustomerParty/ReceivingContact/Communication @sequence MILOIN.LICUNO; MMS240MI/GetBasic	This field indicate the customer number
ConfiguredAssetMaster/ItemInstance/ItemID/ID @accountingEntity MILOIN.LIITNO; MMS240MI/GetBasic (input)	This field indicate the item number for the equipment
ConfiguredAssetMaster/ItemInstance/Description MITMAS.MMITDS; MMS200MI/Get	This field indicate the item description for the equipment
ConfiguredAssetMaster/ItemInstance/SerializedLot/Lot/LotIDs/ID MILOIN.LISERN; MMS240MI/GetBasic (input)	This field indicate the serial number for the equipment
ConfiguredAssetMaster/ItemInstance/SerializedLot/Lot/SerialNumber @schemeName MILOIN.LISERN; MMS240MI/GetBasic (input)	This field indicate the serial number for the equipment
ConfiguredAssetMaster/ItemInstance/SerializedLot/SerialNumber MILOIN.LISERN; MMS240MI/GetBasic (input)	This field indicate the serial number for the equipment
ConfiguredAssetMaster/AssetTypeCode MITMAS.MMINDI; MMS200MI/Get	This field indicate the asset type code for the equipment
ConfiguredAssetMaster/DepartmentCode MILOIN.LIPLGR; MMS240MI/GetBasic	This field indicate the planning group/work center for the equipment

CreditTransfer

CreditTransfer/CreditTransferHeader/DocumentID/ID

FPSUGH.PRPN + PYON; APS130MI/GetHead

Payment proposal number and payment order number are key fields to M3 payment proposal. They are taken from Event together with M3 company and M3 division. PYON is padded with zeros to length 5.

@accountingEntity

AccountingEntity is defaulted as a combination of company and division CONO_DIVI. E.g. 780_AAA
It is possible to translate it using CRS881, but we do NOT recommend to translate it

@variationID

Variation ID is retrieved from the message manifest. Manifest element com:ionVariationId is used.

@lid

Logical ID

CreditTransfer/CreditTransferHeader/DocumentDateTime

from /EventData/SentTimestamp

CreditTransfer/CreditTransferHeader/Status/Code

FPSUGH.PYST; APS130MI/GetHead

Set to "Open". In case of status of payment equals to 8 (Preliminary/copy) set to "Copy"

CreditTransfer/CreditTransferHeader/AuthorizationID

CBANAC.BKAG; CRS692MI/GetBasicData

Bank agreement number

CreditTransfer/CreditTransferHeader/BatchBookingIndicator

Set to "false"
Set internal grp indicator to "true" when APS130MI.GetHead.GRPP is equal to 1 or 2

CreditTransfer/CreditTransferHeader/TotalTransactions

Counter. Number of occurrences of payment transaction. For not grouped payment proposals it is a number of invoices that are not stopped (has Customer stop [BLCD] = 0. For grouped payments it is equal to number of lines returned by transaction LstPayeeTotals2 with number of payments > 0.

CreditTransfer/CreditTransferHeader/InitiatingParty/PartyIDs/ID

FPSUGH.FICU; APS130MI/GetHead

Customer number at financial institution

@schemeName

"BankPartyIdentification"

@schemeAgencyName

Currently not in use.
Mapped for future usage.

@accountingEntity

Currently not in use.
Mapped for future usage.

CreditTransfer/CreditTransferHeader/InitiatingParty/PartyIDs/TaxID

CMNDIV.VRNO; MNS100MI/GetBasicData

Company's VAT Registration number

@schemeName

"TaxIdentificationNumber"

@schemeAgencyName

Currently not in use.
Mapped for future usage.

CreditTransfer/CreditTransferHeader/InitiatingParty/Name

FPSUGH.CONM; APS130MI/GetHeadAddress

Company name

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Name

FPSUGH.COA1; APS130MI/GetHeadAddress

Company address lines 1 - normally contains the name of the location

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address/AddressLine

FPSUGH.COA2, COA3; APS130MI/GetHeadAddress

Company address lines 2 and 3.
COA2 is placed in AddressLine with sequence equal to 1.
COA3 is placed in AddressLine with sequence equal to 3.

NB: As the length of COA2 is less then 64 characters - Address line@2 is not used.

@sequence

Sequence number of the address line: values 1 and 3
AddressLine@sequence = 1 for COA2
AddressLine@sequence = 3 for COA3

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address/CityName

FPSUGH.TOWN; APS130MI/GetHeadAddress

City name if available in M3

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address/CountrySubDivisionCode

FPSUGH.ECAR; APS130MI/GetHeadAddress

State code

@listID

General value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR" : "France - Departements"

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address/CountryCode

FPSUGH.CSCD; APS130MI/GetHeadAddress

Country code. Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-2

@listID

CreditTransfer

	Set to "Countries"
CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address/PostalCode FPSUGH.PONO; APS130MI/GetHeadAddress	Postal code
CreditTransfer/CreditTransferHeader/ForwardingAgentParty/PartyIDs/ID FPSUGH.BKNO; APS130MI/GetHead	Bank number
@schemeName	BankPartyIdentification
@schemeAgencyName	Currently not in use. Mapped for future usage.
@accountingEntity	AccountingEntity is defaulted as a combination of company and division CONO_DIVI. E.g. 780_AAA It is possible to translate it using CRS881, but we do NOT recommend to translate it
CreditTransfer/CreditTransferHeader/ForwardingAgentParty/PartyIDs/TaxID CBANMA.VRNO; CRS690MI/GetBasicData	Company's banks VAT Registration number
@schemeName	"TaxIdentificationNumber"
CreditTransfer/CreditTransferHeader/ForwardingAgentParty/PartyIDs/BICID CBANMA.SWIC; CRS690MI/GetBasicData	Swift code
CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Name FPSUGH.BKNM; APS130MI/GetHeadAddress	Bank name
CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Name FPSUGH.BKA1; APS130MI/GetHeadAddress	Bank address 1 - normally contains name or additional information about the address
CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address/AddressLine FPSUGH.BKA2, BKA3; APS130MI/GetHeadAddress	Bank address 2 and 3. BKA2 is placed in AddressLine with sequence equal to 1. BKA3 is placed in AddressLine with sequence equal to 3. NB: As the length of BKA2 is less then 64 characters - Address line@2 is not used.
@sequence	Sequence number of the address line: values 1 and 3 AddressLine@sequence = 1 for BKA2 AddressLine@sequence = 3 for BKA3
CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address/CityName FPSUGH.TOWB; APS130MI/GetHeadAddress	City name of company's bank
CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address/CountrySubDivisionCode FPSUGH.ECAB; APS130MI/GetHeadAddress	Area cod of company's bank
@listID	General value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR" : "France - Departements"
CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address/CountryCode FPSUGH.CSCB; APS130MI/GetHeadAddress	Country code. Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-2
@listID	Set to "Countries"
CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address/PostalCode FPSUGH.PONB; APS130MI/GetHeadAddress	Postal code of the company's bank
CreditTransfer/CreditTransferPayment/ID FPSUGH.PRPN+PYON; APS130MI/GetBasicData	Payment proposal number and payment order number are key fields to M3 payment proposal. They are taken from the Event data together with M3 company and M3 division. PYON is padded with zeros to length 5. Counter is added at the end of the ID. Counter is also padded with zeros to length 5.
@schemeName	Currently not in use. Mapped for future usage.
@accountingEntity	AccountingEntity is defaulted as a combination of company and division CONO_DIVI. E.g. 780_AAA It is possible to translate it using CRS881, but we do NOT recommend to translate it
CreditTransfer/CreditTransferPayment/RequestedExecutionDateTime FPSUGD.PYDT; APS130MI/LstInvByPayDate	Payment date, format YYYY-MM-DD
CreditTransfer/CreditTransferPayment/FirstAgentPaymentMethodCode	Set to "TRF"
CreditTransfer/CreditTransferPayment/DebtorParty/PartyIDs/ID FPSUGH.FICU; APS130MI/GetHead	Customer number at financial institution. SchemeName = "BankPartyIdentification"
@schemeName	

CreditTransfer

@schemeAgencyName	SchemeName = "BankPartyIdentification"
@accountingEntity	Currently not in use. Mapped for future usage.
CreditTransfer/CreditTransferPayment/DebtorParty/PartyIDs/TaxID CMNDIV.VRNO; MNS100MI/GetBasicData	Company's VAT Registration number
@schemeName	schemeName = "TaxIdentificationNumber"
@schemeAgencyName	Currently not in use. Mapped for future usage.
CreditTransfer/CreditTransferPayment/DebtorParty/Name FPSUGH.CONM; APS130MI/GetHeadAddress	Company name
CreditTransfer/CreditTransferPayment/DebtorParty/Location/Name FPSUGH.COA1; APS130MI/GetHeadAddress	Company address lines 1 - normally contains the name of the location
CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address/AddressLine FPSUGH.COA2, COA3; APS130MI/GetHeadAddress	Company address lines 2 and 3. COA2 is placed in AddressLine with sequence equal to 1. COA3 is placed in AddressLine with sequence equal to 3.
@sequence	NB: As the length of COA2 is less then 64 characters - Address line@2 is not used. Sequence number of the address line: values 1 and 3 AddressLine@sequence = 1 for COA2 AddressLine@sequence = 3 for COA3
CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address/CityName FPSUGH.TOWN; APS130MI/GetHeadAddress	City name if available in M3
CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address/CountrySubDivisionCode FPSUGH.ECAR; APS130MI/GetHeadAddress	State code
@listID	General value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR" : "France - Departements"
CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address/CountryCode FPSUGH.CSCD; APS130MI/GetHeadAddress	Country code. Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-2
@listID	Set to "Countries"
CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address/PostalCode FPSUGH.PONO; APS130MI/GetHeadAddress	Postal code
CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount/ID CBANAC.FIAN; CRS692MI/GetBasicData	Account number at financial institution. Alternative: based on a CRS881 translation of BKIN to a code string indicating how BAF1-BAF5 fields are used
CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount/BBANID FPSUGS.BAF1-BAF5; APS130MI/GetHead	Based on a CRS881 translation of BKIN to a code string indicating how BAF1-BAF5 fields are used
CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount/IBANID CBANAC.IBAN; CRS692MI/GetBasicData	International bank account number
CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount/CurrencyCode FPSUGH.CUCD; APS130MI/GetHead	Currency code
CreditTransfer/CreditTransferPayment/FirstAgentParty/PartyIDs/ID FPSUGH.BKNO; APS130MI/GetHead	Bank number
@schemeName	schemeName = "BankPartyIdentification"
@schemeAgencyName	Currently not in use. Mapped for future usage
@accountingEntity	AccountingEntity is defaulted as a combination of company and division CONO_DIVI. E.g. 780_AAA It is possible to translate it using CRS881, but we do NOT recommend to translate it
CreditTransfer/CreditTransferPayment/FirstAgentParty/PartyIDs/TaxID CBANMA.VRNO; CRS690MI/GetBasicData	Company's banks VAT Registration number
@schemeName	schemeName = "TaxIdentificationNumber"
CreditTransfer/CreditTransferPayment/FirstAgentParty/PartyIDs/BICID CBANMA.SWIC; CRS690MI/GetBasicData	Swift code

CreditTransfer

CreditTransfer/CreditTransferPayment/FirstAgentParty/Name FPSUGH.BKNM; APS130MI/GetHeadAddress	Bank name
CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Name FPSUGH.BKA1; APS130MI/GetHeadAddress	Bank address 1 - normally contains name or additional information about the address
CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Address/AddressLine FPSUGH.BKA2, BKA3; APS130MI/GetHeadAddress	Bank address 2 and 3. BKA2 is placed in AddressLine with sequence equal to 1. BKA3 is placed in AddressLine with sequence equal to 3. NB: As the length of BKA2 is less then 64 characters - Address line@2 is not used.
@sequence	Sequence number of the address line: values 1 and 3 AddressLine@sequence = 1 for BKA2 AddressLine@sequence = 3 for BKA3
CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Address/CityName FPSUGH.TOWB; APS130MI/GetHeadAddress	City name of company's bank
CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Address/CountrySubDivisionCode FPSUGH.ECAB; APS130MI/GetHeadAddress	Area cod of company's bank
@listID	General value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR" : "France - Departements"
CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Address/CountryCode FPSUGH.CSCB; APS130MI/GetHeadAddress	Country code. Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-2
@listID	Set to "Countries"
CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Address/PostalCode FPSUGH.PONB; APS130MI/GetHeadAddress	Postal code of the company's bank
CreditTransfer/CreditTransferPayment/FirstAgentParty/ClearingSystemMemberID FPSUGS.BAF1-BAF5; APS130MI/GetHead	Based on a CRS881 translation of BKIN to a code string indicating how BAF1-BAF5 fields are used
@schemeName	schemaName = "ClearingIdentificationNumber"
@schemeAgencyName	Currently not in use. Mapped for future usage.
CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/PartyIDs/ID CBANAC.BRNO; CRS692MI/GetBasicData	Branch number
@schemeName	Currently not in use. Mapped for future usage.
@accountingEntity	AccountingEntity is defaulted as a combination of company and division CONO_DIVI. E.g. 780_AAA It is possible to translate it using CRS881, but we do NOT recommend to translate it
CreditTransfer/CreditTransferPayment/PaymentTransaction @sequence	Counter implemented within the BOD mapping. When BatchBookingIndicator is equal to false PaymentTransaction is created for each supplier invoice not stopped by initiating party/debtor party. When BatchBookingIndicator is equal to true PaymentTransaction is created for each record returned by APS130MI.LstPayeeTotals2
CreditTransfer/CreditTransferPayment/PaymentTransaction/InstructionID FPSUGD.PRPN+PYON+PDNB; APS130MI/LstInvByPayDate	Payment proposal number and payment order number are key fields to M3 payment proposal. They are taken from Event Data together with M3 company and M3 division. PYON is padded with zeros to length 5. Counter is added at the end of the ID. Counter is also padded
@schemeName	Mapped as a blank value for future use
CreditTransfer/CreditTransferPayment/PaymentTransaction/TransactionID FPSUGD.SINO; APS130MI/LstInvByPayDate	When BatchBookingIndicator is equal to false: Supplier invoice number When BatchBookingIndicator is equal to true: Payment document number (LstPayeeTotal2.PRPN+PYON+PDNB)
CreditTransfer/CreditTransferPayment/PaymentTransaction/PaymentPurposeCode	Currently not in use. Mapped for future usage.
@listID	

CreditTransfer

	Currently not in use. Mapped for future usage.
CreditTransfer/CreditTransferPayment/PaymentTransaction/InstructedAmount FPSUGD.PYAM; APS130MI/LstInvByPayDate	Payment amount When BatchBookingIndicator is equal to true: Foreign currency amount (LstPayeeTotal2.CUAM)
@currencyID FPSUGD.CUCD; APS130MI/LstInvByPayDate	Currency code When BatchBookingIndicator is equal to true: Currency code (LstPayeeTotal2.CUCD)
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/PartyIDs/ID CBANMA.CORG, OUCN; CRS620MI/GetBasicData	CORG = Supplier's organisation number with schemeName "CountryIdentificationNumber"; OUCN = Company's customer number at supplier with schemeName "Customer"
@schemeName	CORG = Supplier's organisation number with schemeName "CountryIdentificationNumber"; OUCN = Company's customer number at supplier with schemeName "Customer"
@schemeAgencyName	Currently not in use. Mapped for future usage.
@accountingEntity	AccountingEntity is defaulted as a combination of company and division CONO_DIVI. E.g. 780_AAA It is possible to translate it using CRS881, but we do NOT recommend to translate it
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/PartyIDs/TaxID CIDMAS.VRNO; CRS620MI/GetBasicData	Supplier's VAT registration number
@schemeName	schemaName = "TaxIdentificationNumber"
@schemeAgencyName	Currently not in use. Mapped for future usage.
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Name FPSUGS.SUNM; APS130MI/GetPayeeTotal	Supplier name
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Name FPSUGS.ADR1; APS130MI/GetPayeeTotal	Supplier's address line 1 = normally contains location name
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Address/AddressLine FPSUGS.ADR2, ADR3; APS130MI/GetPayeeTotal	Supplier's address lines 2 and 3. ADR2 is placed in AddressLine with sequence equal to 1. ADR3 is placed in AddressLine with sequence equal to 3. NB: As the length of ADR2 is less than 64 characters - Address line@2 is not used.
@sequence	Sequence number of the address line: values 1 and 3 AddressLine@sequence = 1 for ADR2 AddressLine@sequence = 3 for ADR3
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Address/CityName FPSUGS.TOWN; APS130MI/GetPayeeTotal	City name if available in M3
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Address/CountrySubDivisionCode FPSUGS.ECAR; APS130MI/GetPayeeTotal	State code
@listID	General value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR": "France - Departements"
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Address/CountryCode FPSUGS.CSCD; APS130MI/GetPayeeTotal	Country code. Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-2
@listID	Set to "Countries"
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Address/PostalCode FPSUGS.PONO; APS130MI/GetPayeeTotal	Postal code
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/FinancialAccount/ID CBANAC.FIAN; CRS692MI/GetBasicData	Account number at financial institution. Alt: based on a CRS881 translation of BKIN to a code string indicating how BAF1-BAF5 fields are used
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/FinancialAccount/BBANID FPSUGS.BAF1-BAF5; CRS692MI/GetBasicData	Based on a CRS881 translation of BKIN to a code string indicating how BAF1-BAF5 fields are used
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/FinancialAccount/IBANID CBANAC.IBAN; CRS692MI/GetBasicData	International bank account number
CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/FinancialAccount/CurrencyCode FPSUGS.CUCD; CRS692MI/GetBasicData	Currency code

CreditTransfer

@listID	Set to "Currency"
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/PartyIDs/ID CBANAC.BKNO; CRS692MI/GetBasicData	Bank number
@schemeName	schemeName = "BankPartyIdentification"
@schemeAgencyName	Currently not in use. Mapped for future usage.
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/PartyIDs/BICID CBANMA.SWIC; CRS690MI/GetBasicData	Swift code
@lid	Logical ID, the same as for DocumentID/ID
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Name FPSUGS.BKNM; APS130MI/GetPayeeTotal	Bank name
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Name FPSUGS.BKA1; APS130MI/GetPayeeTotal	Supplier's address line 1 = normally contains location name
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/AddressLine FPSUGS.BKA2, BKA3; APS130MI/GetPayeeTotal	Supplier's address lines 2 and 3. BKA2 is placed in AddressLine with sequence equal to 1. BKA3 is placed in AddressLine with sequence equal to 3. NB: As the length of BKA2 is less then 64 characters - Address line@2 is not used.
@sequence	Sequence number of the address line: values 1 and 3 AddressLine@sequence = 1 for BKA2 AddressLine@sequence = 3 for BKA3
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/CityName FPSUGS.TOWB; APS130MI/GetPayeeTotal	City name if available in M3
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/CountrySubDivisionCode FPSUGS.ECAB; APS130MI/GetPayeeTotal	State code
@listID	General value: "Country Sub-divisions"; for ECAB = "US": "US States"; for ECAB = "CA": "Canadian Provinces"; for ECAB = "FR" : "France - Departements"
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/CountryCode FPSUGS.CSCB; APS130MI/GetPayeeTotal	Country code. Generic translation is used to translate CSCB to alpha-2 country code according to ISO 3166-2
@listID	Set to "Countries"
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/PostalCode FPSUGS.PONB; APS130MI/GetPayeeTotal	Postal code
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/ClearingSystemMemberID FPSUGS.BAF1-BAF5; CRS692MI/GetBasicData	Based on a CRS881 translation of BKIN to a code string indicating how BAF1-BAF5 fields are used
@schemeName	schemeName = "ClearingIdentificationNumber"
@schemeAgencyName	Currently not in use. Mapped for future usage.
CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/PartyIDs/ID CBANAC.BRNO; CRS692MI/GetBasicData	Branch number
@schemeName	Currently not in use. Mapped for future usage.
@accountingEntity	AccountingEntity is defaulted as a combination of company and division CONO_DIVI. E.g. 780_AAA It is possible to translate it using CRS881, but we do NOT recommend to translate it
CreditTransfer/CreditTransferPayment/PaymentTransaction/ChargeBearerCode FPSUGS.CSTC; APS130MI/GetPayeeTotal	Cost allocation code. This code has to be translated. Values: "Debtor", "Creditor", "Shared" or ServiceLevel". CSTC = "00" - "Shared" CSTC = "01" - "Debtor" CSTC = "02" - "Creditor"
@listID	Currently not in use. Mapped for future usage.
CreditTransfer/CreditTransferPayment/PaymentTransaction/RegulatoryReporting/Code FPSUGD.TDCD; APS130MI/LstInvByPayDate	Trade code When BatchBookingIndicator is equal to true: not mapped
CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/UnstructuredRemittanceText	

CreditTransfer

FPSUGD.SINO; APS130MI/LstInvByPayDate	Supplier invoice number of single invoice When BatchBookingIndicator is equal to true: Supplier invoice number of all invoices for one payment document number truncated after 1024 characters
CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/DocumentReference @type	Noun = SupplierInvoice
CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/DocumentReference/DocumentID/ID FPSUGD.SINO; APS130MI/LstInvByPayDate	Supplier invoice number; schemeName = "CommercialInvoice" When BatchBookingIndicator is equal to true: not mapped
CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/RemittanceReferredDocumentAmounts/DiscountAppliedAmount FPSUGD.CDCU; APS130MI/LstInvByPayDate	Cash discount amount currency, 17, numeric When BatchBookingIndicator is equal to true: not mapped
@currencyID FPSUGD.CUCD; APS130MI/LstInvByPayDate	Currency code When BatchBookingIndicator is equal to true: not mapped
CreditTransfer/CreditTransferPayment/PaymentTransaction/Description FPSUGD.TX51-TX55; APS130MI/GetInvLineText	External text 1-5
CreditTransfer/CreditTransferPayment/PaymentTransaction/Note FPSUGD.AW10; APS130MI/GetInvLineText	Detailed description 1-3, size is 140, type is Alpha

CurrencyExchangeRateMaster

CurrencyExchangeRateMaster/IDs/ID

CCURRA.CONCATENATE(CUCUCD+CULOCD+CUCUTD); CRS055MI/SelExchangeRate	The field indicates an ID. The ID is a concatenation of the fields currency, local currency and validity date.
@accountingEntity -CONO+DIVI; -/	The field indicates the company and division
@variationID -; -/	The field indicates the variation ID
@lid -; -/	The field indicates the logical ID

CurrencyExchangeRateMaster/CurrencyExchangeRate/SourceCurrencyCode

CCURRA.CUCUCD; CRS055MI/SelExchangeRate	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
---	--

CurrencyExchangeRateMaster/CurrencyExchangeRate/TargetCurrencyCode

CCURRA.CULOCD; CRS055MI/SelExchangeRate	The field indicates the currency relative to which the currency rate is given. Normally this is the local currency for the division. However, in an EMU installation in status 2, the rate is always stated towards the Monetary Union currency.
---	---

CurrencyExchangeRateMaster/CurrencyExchangeRate/RateNumeric

CCURRA.CUARAT; CRS055MI/SelExchangeRate	The field indicates the exchange rate for the chosen currency. The rate may be entered with up to six decimal places. The result, however, will be displayed with two decimal places.
---	--

CurrencyExchangeRateMaster/CurrencyExchangeRate/SetDateTime

CCURRA.CUCUTD; CRS055MI/SelExchangeRate	The field indicates the date from which the registered data becomes valid.
---	--

CurrencyExchangeRateMaster/CurrencyExchangeRate/EffectiveTimePeriod/StartDateTime

CCURRA.CUCUTD; CRS055MI/SelExchangeRate	The field indicates the date from which the registered data becomes valid.
---	--

CurrencyExchangeRateMaster/DecimalPlacesNumeric

CSYTAB.YQDCCD; CRS175MI/GetGeneralCode	The field indicates the number of decimal places to be used for the respective currency. Permitted values are 0-2.
--	--

CurrencyExchangeRateMaster/CurrencyRateTypeReference/DocumentID/ID

CCURRA.CUCRTP; CRS055MI/SelExchangeRate	The field indicates the exchange rate type, such as variable rate, budget exchange rate, or rate used for group consolidation. Exchange rate types are used for budgeting and annual financial statements and can be connected to customers, suppliers, and price lists.
---	--

CurrencyExchangeRateMaster/Tolerance

CSYTAB.YQADPR; CRS175MI/GetGeneralCode	The field indicates the accepted deviation when rate is entered or changed manually in connection with transaction entry. The information is entered as a percentage for each currency. A warning is displayed at entry of transactions if the manually entered rate deviates more than the entered percentage. The information is only relevant for the functions where manual entry or change of currency rate is allowed.
--	--

CurrencyRateType

CurrencyRateType/DocumentID/ID

CSYTAB.CTSTKY; CRS175MI/GetGeneralCode

The field indicates the exchange rate type, such as variable rate, budget exchange rate, or rate used for group consolidation.

@accountingEntity

.CONO+DIVI; -/

This field indicates M3 BE division

@variationID

-.; -/

This is a sequence number for the BOD

@lid

-.; -/

The logical ID of the system that is SOR for this noun instance, set to lid://infor.m3be.<environment instance>
E.g. lid://infor.m3be.orbit1412_330

CurrencyRateType/LastModificationDateTime

CSYTAB.CTLMTS; -/

Retrieved from M3 BE field LMTS and normalized to UTC

CurrencyRateType/DocumentDateTime

CSYTAB.CTRGDT+CTRGTM; -/

Concatenated from M3 BE fields RGDT + RGTM, and normalized to UTC

CurrencyRateType/Description

CSYTAB.CTPARM; CRS175MI/GetGeneralCode

The field indicates optional text for the currency rate type

CurrencyRateType/Status/Code

-.; -/

Always set to "Open"

@listID

-.; -/

Set to "Currency Rate Type Status"

CurrencyRateType/Name

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

The field indicates optional text for the currency rate type

CurrencyRateType/ShortName

CSYTAB.CTTX15; CRS175MI/GetGeneralCode

The field indicates a name for currency rate type

CustomerPartyMaster

CustomerPartyMaster/PartyIDs/ID

OCUSMA.OKCUNO; CRS610MI/GetBasicData

This field indicates the customer number

@accountingEntity

OCUSMA.OKCONO
CMNDIV.CCDIV1.; N/A

"AccountingEntity for M3 is defaulted as a combination of CONO_DIV1.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate."

@variationID

The field indicates the variationID

@lid

The logical ID of the system that is SOR for this noun instance.

CustomerPartyMaster/PartyIDs/DisplayID

OCUSMA.OKCUNO; CRS610MI/GetBasicData

CustomerPartyMaster/PartyIDs/TaxID

OCUSMA.OKCORG
OKVRNO; CRS610MI/GetFinancial

If organization number or VAT registration number exists for a customer these values are identified with different schemenames.
CORG, "CountryIdentificationNumber"
VRNO, "TaxIdentificationNumber"

@schemeName

CORG; CountryIdentificationNumber
VRNO; TaxIdentificationNumber

CustomerPartyMaster/LastModificationDateTime

OCUSMA.OKLMTS; N/A/N/A

This is retrieved from EventData. LMTS is converted to Date and Time.

CustomerPartyMaster/LastModificationPerson/IDs/ID

OCUSMA.OKCHID; N/A/N/A

This is retrieved from EventData.

CustomerPartyMaster/LastModificationPerson/Name

.NAME; MNS150MI/GetUserData

CustomerPartyMaster/Name

OCUSMA.OKCUNM; CRS610MI/GetBasicData

This field indicates the customer name

CustomerPartyMaster/Location/Address/AttentionOfName

OCUSMA.OKYREF; CRS610MI/GetBasicData

The field indicates the customer's contact person

CustomerPartyMaster/Location/Address/AddressLine

OCUSMA.OKCUA1-OKCUA4; CRS610MI/GetBasicData

This indicates the address lines for the customer address

@sequence

The field indicates the Address Line sequence

CustomerPartyMaster/Location/Address/CityName

OCUSMA.OKTOWN; CRS610MI/GetBasicData

This field indicates the city

CustomerPartyMaster/Location/Address/CountrySubDivisionCode

OCUSMA.OKECAR; CRS610MI/GetBasicData

The field indicates the state/region/countrysubdivision

@listID

M3 BE field State has different list ID depending on country:
- Canada has list ID "Canadian Provinces"
- France has list ID "France - Departements"
- United States has list ID "US States"
- Other countries have list ID "Country Sub-divisions"

CustomerPartyMaster/Location/Address/CountryCode

OCUSMA.OKCSCD; CRS610MI/GetBasicData

The field indicates the country code

@listID

M3 BE field Country has list ID "Countries"

CustomerPartyMaster/Location/Address/PostalCode

OCUSMA.OKPONO; CRS610MI/GetBasicData

This field indicates the postal code

CustomerPartyMaster/Location/Address/Preference/Indicator

This field is set to true

CustomerPartyMaster/Communication

@preferredIndicator

This field is set to false

CustomerPartyMaster/Communication/ChannelCode

M3 BE field Telephone number 1 has code "Phone"
M3 BE field Telephone number 2 has code "Phone"
M3 BE field Facsimile number has code "Fax"
M3 BE field E-Mail address has code "EMail"

@listID

ListID is set to "Communication Channels"

CustomerPartyMaster/Communication/UseCode

Currently, M3 BE does not keep information about use code for different communication alternatives.

We do though hardcode UseCodes according to:
M3 BE field Telephone number 1 has UseCode "Office"
M3 BE field Telephone number 2 has UseCode "Office"
M3 BE field Facsimile number has UseCode "Fax"
M3 BE field E-Mail address has UseCode "Office"

CustomerPartyMaster

@listID	ListID is set to "Communication Use Codes"
CustomerPartyMaster/Communication/DialNumber OCUSMA.OKPHNO/OKPHN2/OKTFNO; CRS610MI/GetBasicData	The field indicates the telephone/telefax number of the customer. PHNO & PHN2 is phone numbers TFNO is fax number
CustomerPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData	The field indicates an e-mail address for the customer
CustomerPartyMaster/Contact/Communication/Preference/Indicator	This field is always set to false
CustomerPartyMaster/PaymentTermID OCUSMA.OKTEPY; CRS610MI/GetOrderInfo	The field indicates the payment terms id for the customer
CustomerPartyMaster/Status/Code OCUSMA.OKSTAT; CRS610MI/GetBasicData	The field indicates the status of the customer. If M3 status is 10, element is set to "Pending" If M3 status is 12, element is set to "Pending" If M3 status is 20, set element to "Open" If M3 status is 90, set element to "Closed"
CustomerPartyMaster/CurrencyCode OCUSMA.OKCUCD; CRS610MI/GetBasicData	Currency code.
CustomerPartyMaster/Classification/Codes/Code 1) OCUSMA.OKCUTP; CRS610MI/GetBasicData 2) OCUSMA.OKTEDL; CRS610MI/GetOrderInfo 3) OCUSMA.OKSDST; CRS610MI/GetOrderInfo	The field indicates the Classification. 1) If Customer type field is filled, populate Code with this value 2) If Delivery terms field is filled, populate Code with this value 3) If District field is filled, populate Code with this value
@listID	The field indicates the Classification code listID. 1) If Customer type field is filled, set listID to "Customer Types" 2) If Delivery terms field is filled, set listID to "Incoterms" 3) If District field is filled, set listID to "District"
@sequence	The sequence attribute identifies the hierarchical position of the identifier in the case of multi-level codes
CustomerPartyMaster/DefaultShipFromWarehouseLocation/ID OCUSMA.OKWHLO; CRS610MI/GetOrderInfo	// from ECOM description: The default ship-from warehouse when shipping to this customer.
@accountingEntity OCUSMA.OKCONO CMNDIV.CCDIVI.; /	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 780_AAA It is possible to translate using CRS881, but we recommend NOT to translate.
CustomerPartyMaster/CustomerAccount/TotalCreditLimitAmount OCUSMA.OKCRL3/OKCRL2/OKCRLM; CRS610MI/GetFinancial	The field indicates the highest credit limit for the customer. It is retrieved, in priority order, from, Credit limit 3, Credit limit 2 or Credit limit field.
CustomerPartyMaster/SalesPersonReference/IDs/ID OCUSMA.OKSMCD or OKRESP; CRS610MI/GetOrderInfo	The field indicates the person responsible for sales to a customer.
@accountingEntity OCUSMA.OKCONO CMNDIV.CCDIVI.; /	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 780_AAA It is possible to translate using CRS881, but we recommend NOT to translate.
CustomerPartyMaster/SalesPersonReference/Name CSYTAB.CTTX40; CRS100MI or MNS150MI/Get	// The field indicates the full name of the current identity.
CustomerPartyMaster/SalesPersonReference/SalesPersonRole	If the field used in SalesPersonReference/ID is SMCD then display "External" and if RESP then display "Internal"
@listID	"Sales Person Roles"

CustomerReturn

CustomerReturn/CustomerReturnHeader/DocumentID/ID OCHEAD.OCREPN; OIS390MI/GetHead	This field indicates the receiving number which identifies a customer return.
@accountingEntity OCHEAD.CONO+DIVI; N/A/	The field indicates the company and division
@location OCHEAD.WHLO; N/A/	The field indicates the warehouse.
@variationID	The field indicates the variation ID
CustomerReturn/CustomerReturnHeader/AlternateDocumentID/ID OCHEAD.OCORNO; OIS390MI/GetHead	The field indicates the customer order number
@accountingEntity OCHEAD.CONO+DIVI; -/	The field indicates the company and division
CustomerReturn/CustomerReturnHeader/Status/Code OCHEAD.OCRESH; OIS390MI/GetHead	The field indicates the lowest status of a line in a customer return. 5=Open 11=Open 12, 13=PartiallyReceived 2=Credited 22, 23, 33=Received 99=Canceled
CustomerReturn/CustomerReturnHeader/CustomerParty/PartyIDs/ID OCHEAD.OCUNO; OIS390MI/GetHead	The field indicates the customer number.
@accountingEntity OCHEAD.CONO+DIVI; -/	The field indicates the company and division
CustomerReturn/CustomerReturnHeader/CustomerParty/Name OCUSMA.OKCUNM; CRS610MI/GetBasicData	The field indicates the customer name.
CustomerReturn/CustomerReturnHeader/CustomerParty/Location/Address/AttentionOfName OCUSMA.OKYREF; CRS610MI/GetBasicData	The field indicates the contact person.
CustomerReturn/CustomerReturnHeader/CustomerParty/Location/Address/AddressLine OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3 OCUSMA.OKCUA4.; CRS610MI/GetBasicData	The field indicates the line address.
CustomerReturn/CustomerReturnHeader/CustomerParty/Location/Address/CityName OCUSMA.OKTOWN; CRS610MI/GetBasicData	The field indicates the city in an address
CustomerReturn/CustomerReturnHeader/CustomerParty/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; CRS610MI/GetBasicData	The field indicates a state or province within a country.
CustomerReturn/CustomerReturnHeader/CustomerParty/Location/Address/CountryCode OCUSMA.OKCSCD; CRS610MI/GetBasicData	The field indicates a country.
CustomerReturn/CustomerReturnHeader/CustomerParty/Location/Address/PostalCode OCUSMA.OKPONO; CRS610MI/GetBasicData	The field indicates a postal code for a specific address.
CustomerReturn/CustomerReturnHeader/BillToParty/PartyIDs/ID OCHEAD.OCPYNO; OIS390MI/GetHead	The field indicates the customer ID who receives the invoice.
@accountingEntity OCHEAD.CONO+DIVI; N/A/	The field indicates the company and division
CustomerReturn/CustomerReturnHeader/BillToParty/Name OCUSMA.OKCUNM; CRS610MI/GetBasicData	The field indicates the customer who receives the invoice.
CustomerReturn/CustomerReturnHeader/BillToParty/Location/Address/AttentionOfName OCUSMA.OKYREF; OIS100MI/GetAddress	The field indicates the contact person.
CustomerReturn/CustomerReturnHeader/BillToParty/Location/Address/AddressLine OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3 OCUSMA.OKCUA4.; OIS100MI/GetAddress	The field indicates the line address.
CustomerReturn/CustomerReturnHeader/BillToParty/Location/Address/CityName OCUSMA.OKTOWN; OIS100MI/GetAddress	The field indicates the city in an address
CustomerReturn/CustomerReturnHeader/BillToParty/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; OIS100MI/GetAddress	The field indicates a state or province within a country.
CustomerReturn/CustomerReturnHeader/BillToParty/Location/Address/CountryCode OCUSMA.OKCSCD; OIS100MI/GetAddress	The field indicates a country.
CustomerReturn/CustomerReturnHeader/BillToParty/Location/Address/PostalCode OCUSMA.OKPONO; OIS100MI/GetAddress	The field indicates a postal code for a specific address.
CustomerReturn/CustomerReturnHeader/TransportationTerm/IncotermsCode OOHEAD.OATEDL; OIS100MI/GetHead	The field indicates delivery terms, which control when transport responsibility shifts from supplier to customer.
@listID	The field indicates the list ID
CustomerReturn/CustomerReturnHeader/PaymentTerm/Term/ID OOHEAD.OATEPY; OIS100MI/GetHead	The field indicates how the due date is to be calculated.
CustomerReturn/CustomerReturnHeader/PromisedReturnDateTime OCHEAD.OCEPDT; OIS390MI/GetHead	

CustomerReturn

	The field indicates the date of a customer return to stock, either when it arrives or when it is expected to arrive.
CustomerReturn/CustomerReturnHeader/RequiredReturnDateTime OCHEAD.OCEPDT; OIS390MI/GetHead	The field indicates the date of a customer return to stock, either when it arrives or when it is expected to arrive.
CustomerReturn/CustomerReturnLine/LineNumber OCLINE.ODREL1; OIS390MI/LstLine	The field indicates a line number, which is a sequence number that identifies each line of a customer return.
CustomerReturn/CustomerReturnLine/Status/Code OCLINE.ODREST; OIS390MI/GetLine	The field indicates the status of a line in a customer return. Alternatives: 2 - Credited 5, 11 - Open 12, 13 - PartiallyReceived 22, 23, 33 - Received 99 - Cancelled
CustomerReturn/CustomerReturnLine/Item/ItemID/ID OCLINE.ODITNO; OIS390MI/LstLine	The field indicates the item number
@accountingEntity OCLINE.CONO+DIVI; N/A/	The field indicates the company and division
CustomerReturn/CustomerReturnLine/Item/Description MITMAS.MMFUDS; MMS200MI/GetItemBasic	The field indicates the description of the item.
CustomerReturn/CustomerReturnLine/Item/SerializedLot/Lot/LotIDs/ID OCLINE.ODBANO; OIS390MI/LstLine	The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item.
CustomerReturn/CustomerReturnLine/Item/SerializedLot/SerialNumber OCLINE.ODBANO; OIS390MI/LstLine	The field indicates the unique serial number assigned by the manufacturer.
CustomerReturn/CustomerReturnLine/Quantity OCLINE.ODREQ1; OIS390MI/GetLine	The field indicates the returned quantity.
@unitCode OCLINE.ODUNMS; OIS390MI/GetLine	The field indicates the unit of measure.
CustomerReturn/CustomerReturnLine/BaseUOMQuantity OCLINE.ODREQ1; OIS390MI/GetLine	The field indicates the quantity in basic unit of measure.
@unitCode OCLINE.ODUNMS; OIS390MI/GetLine	The field indicates the basic unit of measure.
CustomerReturn/CustomerReturnLine/UnitPrice/Amount OCLINE.ODSAPR; OIS390MI/GetLine	The field indicates the sales price.
@currencyID OCHEAD.OCCUCD; OIS390MI/GetHead	The field indicates the currency.
CustomerReturn/CustomerReturnLine/UnitPrice/PerQuantity OCLINE.ODSAPR; OIS390MI/GetLine	The field indicates the unit price.
@unitCode OCHEAD.OCCUCD; OIS390MI/GetHead	The field indicates the currency.
CustomerReturn/CustomerReturnLine/ExtendedAmount OCLINE.ODSAPR * ODREQ1; OIS390MI/GetLine	The field indicates the extended amount.
@currencyID OCHEAD.OCCUCD; OIS390MI/GetHead	The field indicates the currency.
CustomerReturn/CustomerReturnLine/ExtendedBaseAmount OCLINE.OCCUPR, OCREQ1; OIS390MI/GetLine	The field indicates the extended base amount.
@currencyID OCHEAD.OCCUCD; OIS390MI/GetLine	The field indicates the local currency.
CustomerReturn/CustomerReturnLine/TransportationTerm/IncotermsCode OOHEAD.OATEDL; OIS100MI/GetHead	The field indicates delivery terms, which control when transport responsibility shifts from supplier to customer.
@listID	The field indicates the list ID

FinancialCalendar

FinancialCalendar/FinancialCalendarID/ID	Hardcode to 'Financial Calendar'.
FinancialCalendar/Name	Hardcode to 'accountingEntity +Financial Calendar'.
FinancialCalendar/Status/Code	Hardcode to 'Open'.
FinancialCalendar/CalendarYear/Year CSYPER.CPYEA4; CRS910MI/Select	The field indicates the year. It is entered using four positions, for example, 2002.
FinancialCalendar/CalendarYear/Period/PeriodID CSYPER.CPPERI; CRS910MI/Select	The field indicates the period within the calendar year.
FinancialCalendar/CalendarYear/Period/Name CSYPER.CPNAME; CRS910MI/Select	This field indicates the name of the period.
FinancialCalendar/CalendarYear/Period/ShortName CSYPER.CPNAME; CRS910MI/Select	This field indicates the name of the period.
FinancialCalendar/CalendarYear/Period/EffectiveTimePeriod/StartDateTime CSYPER.CPFDAT; CRS910MI/Select	<p>The field indicates the start date for the system period.</p> <p>The date must be later than the start date of the previous period, but need not be within the current calendar year. This allows handling split financial years, for example.</p> <p>The date must be earlier than the start date of the next period, even if the next period is in another year. Validation is performed to be sure that these two conditions are met.</p> <p>The end date is always entered automatically as the day before the start date of the next period, except for the last period. The end date for the last period must be entered manually.</p>
FinancialCalendar/CalendarYear/Period/EffectiveTimePeriod/EndDateTime CSYPER.CPTDAT; CRS910MI/Select	<p>The field indicates the date when the system period ends.</p> <p>This date is calculated as the date before the start date of the next period, except for the last period where the end date must be entered.</p>

InventoryAdjustment

InventoryAdjustment/InventoryAdjustmentHeader/LastModificationDateTime .; MWS070MI/GetServerTime	Current date/time.
InventoryAdjustment/InventoryAdjustmentHeader/DocumentDateTime .; MWS070MI/GetServerTime	Current date/time.
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/ID MITTRA.MLWHLO; MWS070MI/GetStockTrans	The field indicates the warehouse ID.
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/Name MITWHL.MWVHNM; MMS005MI/GetWarehouse	The field indicates optional text.
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/Address/AddressLine CIADDR.OAADR1 OAADR2 OAADR3 OAADR4; MMS005MI/GetWarehouse	The field indicates an address line.
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/Address/CityName CIADDR.OATOWN; MMS005MI/GetWarehouse	The field indicates the city in an address.
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/Address/CountrySubDivisionCode CIADDR.OAECAR; MMS005MI/GetWarehouse	The field indicates an area, province or state within a country.
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/Address/CountryCode CIADDR.OACSCD; MMS005MI/GetWarehouse	The field indicates a country.
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/Address/PostalCode CIADDR.OAPONO; MMS005MI/GetWarehouse	The field indicates a postal code for a specific address.
InventoryAdjustment/InventoryAdjustmentLine/Item/ItemID/ID MITTRA.MTITNO; MWS070MI/GetStockTrans	The field indicates the item number.
InventoryAdjustment/InventoryAdjustmentLine/Item/SerialNumber MITTRA.MTBANO; MWS070MI/GetStockTrans	The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics.
InventoryAdjustment/InventoryAdjustmentLine/Quantity MITTRA.MTTRQT; MWS070MI/GetStockTrans	The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.
InventoryAdjustment/InventoryAdjustmentLine/TransactionDateTime .MTTRDT; MWS070MI/GetStockTrans	The field indicates the transaction date which may be entered manually during entry of certain transactions. When this is possible, the current date is always proposed by default for the transaction date.

InventoryCount

InventoryCount/InventoryCountHeader/DocumentDateTime MITTKV.; MMS307MI/GetServerTime	Current date/time.
InventoryCount/InventoryCountHeader/WarehouseLocation/ID MITTKV.SVWHLO; MMS307MI/GetPhysInvVar	The field indicates the warehouse ID.
InventoryCount/InventoryCountHeader/WarehouseLocation/Name MITWHL.MWWHNM; MMS005MI/GetWarehouse	The field indicates optional text .
InventoryCount/InventoryCountHeader/WarehouseLocation/Address/AddressLine CIADDR.OAADR1,OAADR2,OAADR3,OAADR4; MMS005MI/GetWarehouse	The field indicates an address line.
InventoryCount/InventoryCountHeader/WarehouseLocation/Address/CityName CIADDR.OATOWN; MMS005MI/GetWarehouse	The field indicates the city in an address.
InventoryCount/InventoryCountHeader/WarehouseLocation/Address/CountrySubDivisionCode CIADDR.OAECAR; MMS005MI/GetWarehouse	The field indicates an area, province or state within a country.
InventoryCount/InventoryCountHeader/WarehouseLocation/Address/CountryCode CIADDR.OACSCD; MMS005MI/GetWarehouse	The field indicates a country.
InventoryCount/InventoryCountHeader/WarehouseLocation/Address/PostalCode CIADDR.OAPONO; MMS005MI/GetWarehouse	The field indicates a postal code for a specific address.
InventoryCount/InventoryCountLine/LineNumber MITTKV.SVSTRN; MMS307MI/GetPhysInvVar	Value set to sequence number; Set constant '00001'
InventoryCount/InventoryCountLine/Item/ItemID/ID MITTKV.SVITNO; MMS307MI/GetPhysInvVar	The field indicates the item number.
InventoryCount/InventoryCountLine/Item/Description MITMAS.MMITDS; MMS200MI/GetItemBasic	The field indicates a supplementary description of the item.
InventoryCount/InventoryCountLine/Item/SerialNumber MITTKV.SVBANO; MMS307MI/GetPhysInvVar	The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics. Serial numbers can be used for lot numbering.
InventoryCount/InventoryCountLine/Quantity MITTKV.SVSTQI; MMS307MI/GetPhysInvVar	The field indicates physical counted quantity in the basic U/M of the item.
@unitCode MITMAS.MMUNMS; MMS200MI/GetItemBasic	The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
InventoryCount/InventoryCountLine/AdjustmentQuantity MITTKV.SVDFQT; MMS307MI/GetPhysInvVar	The field indicates the delta between previous and current quantity.

InventoryHold

InventoryHold/LastModificationDateTime .; MWS070MI/GetServerTime	Current date/time
InventoryHold/DocumentDateTime .; MWS070MI/GetServerTime	Current date/time
InventoryHold/ItemInstance/ItemID/ID MITTRA.MTITNO; MWS070MI/GetStockTrans	The field indicates the item number.
InventoryHold/ItemInstance/Description MITMAS.MMITDS; MWS070MI/GetStockTrans	The field indicates a supplementary description of the item.
InventoryHold/ItemInstance/SerialNumber MITTRA.MTBANO; MWS070MI/GetStockTrans	The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics.
InventoryHold/ItemInstance/SerializedLot/Lot/SerialNumber MITTRA.MTBANO; MWS070MI/GetStockTrans	The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics.
InventoryHold/TransactionDateTime MITTRA.MTTRDT; MWS070MI/GetStockTrans	The field indicates the transaction date which may be entered manually during entry of certain transactions. When this is possible, the current date is always proposed by default for the transaction date.
InventoryHold/HoldQuantity MITTRA.MTTRQT; MWS070MI/GetStockTrans	The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.
InventoryHold/HoldBaseUOMQuantity MITMAS.MMUNMS; MWS070MI/GetStockTrans	The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.

Invoice

Invoice/InvoiceHeader/DocumentID/ID OINVOH.UHEXIN; OIS350MI/GetInvHead	This contains Invoice prefix and Invoice number.
Invoice/InvoiceHeader/AlternateDocumentID/ID OINVOH.UHIVNO; N/A/-	The field indicates an invoice number. An invoice number is automatically assigned when a record is invoiced or when an advance invoice is created in (OIS105) or (COS105). The number is obtained from the invoice number series defined for the order type.
Invoice/InvoiceHeader/DisplayID OINVOH.UHEXIN; OIS350MI/GetInvHead	This contains the prefix and the Invoice number.
Invoice/InvoiceHeader/LastModificationDateTime OINVOH.UHLMDT; OIS350MI/GetInvHead	0
Invoice/InvoiceHeader/DocumentDateTime	Registered date and time.
Invoice/InvoiceHeader/Description OINVOH.UHRXIN; OIS350MI/GetInvHead	Reference Invoice number
Invoice/InvoiceHeader/Note OINVOH.UHIDAT; OIS350MI/GetInvHead	This field indicates year the invoice was created.
Invoice/InvoiceHeader/ExtendedAmount OINVOL.UHIVAM; OIS350MI/GetInvLine	Display total where IVTP = '31'. This is the total net value of the transaction.
Invoice/InvoiceHeader/ExtendedBaseAmount OINVOL.UHIIVLA; OIS350MI/GetInvLine	Display total AMT1 where IVTP = '31'. This is the total net value of the transaction.
Invoice/InvoiceHeader/TotalAmount OINVOH.UHAMT2; OIS350MI/GetInvHead	The field indicates the amount including taxes, charges and allowances in foreign currency;
Invoice/InvoiceHeader/TotalBaseAmount OINVOH.UHAMT1; OIS350MI/GetInvHead	The field indicates the amount including taxes, charges and allowances in local currency.
Invoice/InvoiceHeader/SupplierParty/PartyIDs/ID CMNDIV.CCCONO + CCDIVI; MNS100MI/GetBasicData	The field indicates a company and division.
Invoice/InvoiceHeader/SupplierParty/PartyIDs/TaxID	Constant = "Taxing Agency"
Invoice/InvoiceHeader/SupplierParty/Name CMNDIV.CCCONM; MNS100MI/GetBasicData	The field indicates the name of the company.
Invoice/InvoiceHeader/SupplierParty/Location/Name CMNDIV.CCWHLO; MNS100MI/GetBasicData	The field indicates the warehouse ID. Warehouse is a stock zone which is used to distinguish different geographical locations within a company. The warehouse is used as a planning level for material and production. Stock zones, stock locations and items are connected to the warehouse.
Invoice/InvoiceHeader/SupplierParty/Location/Address/AttentionOfName CMNDIV.CCOCREF; MNS100MI/GetBasicData	The field indicates the person who the customer may contact regarding customer.
Invoice/InvoiceHeader/SupplierParty/Location/Address/AddressLine CMNDIV.Various; MNS100MI/GetBasicData	The field indicates address line for each company.
Invoice/InvoiceHeader/SupplierParty/Location/Address/CityName CMNDIV.CCTOWN; MNS100MI/GetBasicData	The field indicates the city in an address. The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule). Address formatting rules are defined for each country.
Invoice/InvoiceHeader/SupplierParty/Location/Address/CountrySubDivisionCode CMNDIV.CCECAR; MNS100MI/GetBasicData	The field indicates an area, province or state within a country. The information is used for addresses, U.S. sales tax and for trade statistics. When editing addresses, the information is validated when state is used as an address element according to the address formatting rule, used for the country to which the address applies. Address formatting rules are stated for each country.
Invoice/InvoiceHeader/SupplierParty/Location/Address/CountryCode CMNDIV.CCCSCD; MNS100MI/GetBasicData	The field indicates a country. Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
Invoice/InvoiceHeader/SupplierParty/Location/Address/PostalCode CMNDIV.CCPONO; MNS100MI/GetBasicData	The field indicates a postal code for a specific address.

Invoice

	The postal code is an address element that can be part of an address line if address formatting rules are used.
Invoice/InvoiceHeader/SupplierParty/Contact/Name CMNDIV.CCOCREF; MNS100MI/GetBasicData	The field indicates the person who the customer may contact regarding customer.
Invoice/InvoiceHeader/SupplierParty/SalesContact/Name CMNDIV.CCOCREF; MNS100MI/GetBasicData	The field indicates the person who the customer may contact regarding customer.
Invoice/InvoiceHeader/CustomerParty/PartyIDs/ID OINVOH.UHCUNO; OIS350MI/GetInvHead	The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric.
Invoice/InvoiceHeader/CustomerParty/PartyIDs/TaxID OCUSMA.UHVRNO; CRS610MI/GetFinancial	<p>The field indicates the VAT registration number. VAT registration numbers are entered for each customer, supplier and in the company file of companies based in an EU member country.</p> <p>The VAT registration number is used by companies within the EU to account for sales (trade) within the EU without VAT being charged. EU regulations state that VAT should be charged when invoicing a customer within the EU if the registration number is not known, that is, it is up to the salesman to verify the registration number of the customer (payer) to avoid charging VAT.</p>
Invoice/InvoiceHeader/CustomerParty/Name OINVOH.UHCUNM; OIS350MI/GetInvHead	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
Invoice/InvoiceHeader/CustomerParty/Location/Address/AttentionOfName OINVOH.UHINRC; OIS350MI/GetInvHead	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
Invoice/InvoiceHeader/CustomerParty/Location/Address/AddressLine OCUSMA.Various; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA.
Invoice/InvoiceHeader/CustomerParty/Location/Address/CityName OCUSMA.OKTOWN; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceHeader/CustomerParty/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceHeader/CustomerParty/Location/Address/CountryCode OCUSMA.OKCSCD; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceHeader/CustomerParty/Location/Address/PostalCode OCUSMA.OKPONO; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceHeader/CustomerParty/Contact/ID .; CMS055MI/LstByCustomer	Display field if ADRT = 3 (Invoice address)
Invoice/InvoiceHeader/CustomerParty/Contact/Name .; CMS055MI/LstByCustomer	The field indicates the name of the customer's contact.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/ChannelCode	Constant = 'Phone'
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/DialNumber .; CRS618MI/Get	The field indicates the telephone number of the customer.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Address/AddressLine .; CRS618MI/Get	The field indicate an Address Line
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Address/CityName .; CRS618MI/Get	The field indicates the city in an address. The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Address/CountrySubDivisionCode .; CRS618MI/Get	The field indicates an area, province or state within a country
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Address/CountryCode .; CRS618MI/Get	The field indicates a country
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Address/PostalCode .; CRS618MI/Get	The field indicates a postal code for a specific address
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/URI	

Invoice

.; CRS618MI/Get	The field indicates an e-mail address for the customer, supplier, etc. entered.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/HTMLPreferredIndicator Constant = 'true'	
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Preference/Sequence Constant = '1'	
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Preference/Indicator Constant = 'true'	
Invoice/InvoiceHeader/PaymentTerm/Description CSYTAB.CTPARM; CRS175MI/GetGeneralCode	Read CSYTAB where STCO = TEPY and STKY = value in Invoice/InvoiceHeader/Term/ID
Invoice/InvoiceHeader/PaymentTerm/Note CSYTAB.CTTX15; CRS175MI/GetGeneralCode	The field indicates a name for the current ID. It contains 15 positions. When you edit descriptions and names, and no name is entered, the first 15 positions from the description field will automatically be proposed as the name.
Invoice/InvoiceHeader/PaymentTerm/Term/ID OOHEAD.UHTEPY; OIS100MI/GetHead	The field indicates the payment term.
Invoice/InvoiceHeader/PaymentTerm/Term/Description CSYTAB.CTPARM; CRS175MI/GetGeneralCode	Read CSYTAB. Get PaymentTerm/Term/ID, store in CTSTKY. If CTSTCO = 'TEPY' and read CTSTKY then display CTPARM.
Invoice/InvoiceHeader/PaymentTerm/Term/EffectiveDateTime OINVOH.UHIDAT; OIS350MI/GetInvHead	Invoice date
Invoice/InvoiceHeader/PaymentTerm/Term/DueDateTime OINVOH.UHDUDT; OIS350MI/GetInvHead	The field indicates the date the invoice is due for payment.
Invoice/InvoiceHeader/PaymentTerm/Term/Amount OINVOH.UHAMT2; OIS350MI/GetInvHead	Amount in foreign currency.
Invoice/InvoiceHeader/PaymentTerm/Term/BaseAmount OINVOL.UHIIVLA; OIS350MI/LstInvLine	Amount in local currency.
Invoice/InvoiceHeader/PaymentTerm/Discount/ID OOHEAD.OATECD; OIS100MI/GetHead	The field indicates the discount based on the invoice payment term.
Invoice/InvoiceHeader/Tax/ID OINVOL.ONVTCD; OIS350MI/LstInvLine	The field indicates the VAT Code. Read LstInvLineByType by getting all IVTP = 40 records.
Invoice/InvoiceHeader/Tax/Description CSYTAB.CTTX40; CRS175MI/Get	CHANGE TO CSYTAB to get the description
Invoice/InvoiceHeader/Tax/Amount OINVOH.UHAMT2; OIS350MI/GetInvHead	If IVTP = 40
Invoice/InvoiceHeader/Tax/BaseAmount OINVOL.UHIIVLA; OIS350MI/LstInvLineByType	If IVTP = 40
Invoice/InvoiceHeader/Charge/ID OCUSMA.OKTOWN; OIS350MI/LstInvLine	Get all Records with IVTP = 60, 65, If IVTP = 65 set ID to "Service Charge" else "Order Charge"
Invoice/InvoiceHeader/Charge/Description	if IVTP = 65 or 60 display OIS350MI LstInvLine IVRF
Invoice/InvoiceHeader/Charge/Amount OINVOH.UHAMT2; OIS350MI/GetInvHead	IVTP = 60, 65. The fields indicates the Charge Amount
Invoice/InvoiceHeader/Charge/BaseAmount OINVOL.UHIIVLA; OIS350MI/LstInvLineByType	IVTP = 60, 65. The fields indicates the Charge Base Amount (local)
Invoice/InvoiceHeader/Status/Code OINVOH.UHINST; OIS350MI/GetInvHead	The field indicates how far an invoice has progressed in the invoicing flow. INST >= 80 = "Open"
Invoice/InvoiceHeader/Status/EffectiveDateTime OINVOH.UHRGDT + UHRGTM; OIS350MI/GetInvHead	The field indicates the date and time that the object was created. This date is set automatically.
Invoice/InvoiceHeader/Status/ArchiveIndicator	Constant = "False"
Invoice/InvoiceHeader/CurrencyExchangeRate/SourceCurrencyCode OINVOH.UHCUCD; OIS350MI/GetInvHead	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards. Example: GBP British pounds USD United States dollars SEK Swedish kronor.
Invoice/InvoiceHeader/CurrencyExchangeRate/SourceUnitBaseNumeric	Always "1.00"
Invoice/InvoiceHeader/CurrencyExchangeRate/TargetCurrencyCode CMNDIV.CCLOCD; OIS350MI/GetInvHead	

Invoice

	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
Invoice/InvoiceHeader/CurrencyExchangeRate/TargetUnitBaseNumeric .; CRS055MI/SelExchangeRate	The field indicates the exchange rate for the chosen currency. The rate may be entered with up to six decimal places. The result, however, will be displayed with two decimal places.
Invoice/InvoiceHeader/CurrencyExchangeRate/RateNumeric OINVOH.UHRAIN; OIS350MI/GetInvHead	<p>The field indicates the relationship between foreign and domestic currency.</p> <p>Alternatives 1 = 1000:1 2 = 100:1 3 = 10:1 4 = 1:1 5 = 1:10 6 = 1:100 7 = 1:1000</p> <p>The use of the rate factor makes it is easier to enter exchange rates between widely differing currencies, e g GBP/ITL. In addition, the use of the rate factor eliminates the need to enter multiple zeroes for an exchange rate.</p>
Invoice/InvoiceHeader/SelfBillingIndicator	Constant = "False"
Invoice/InvoiceHeader/ShipToParty/PartyIDs/ID OOHEAD.OADECU; OIS100MI/Get Head	If ADRT = 1 consist of one address only then display in InvoiceHeader else display in InvoiceLine. Display field if ADRT = '1' (Delivery address). The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric. The field indicates the unique
Invoice/InvoiceHeader/ShipToParty/PartyIDs/TaxID OCUSMA.UHVRNO; CRS610MI/GetFinancial	<p>The field indicates the VAT registration number. VAT registration numbers are entered for each customer, supplier and in the company file of companies based in an EU member country.</p> <p>The VAT registration number is used by companies within the EU to account for sales (trade) within the EU without VAT being charged. EU regulations state that VAT should be charged when invoicing a customer within the EU if the registration number is not known, that is, it is up to the salesman to verify the registration number of the customer (payer) to avoid charging VAT.</p>
Invoice/InvoiceHeader/ShipToParty/Name OCUSMA.UHCUNM; OIS350MI/GetInvHead	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
Invoice/InvoiceHeader/BillToParty/PartyIDs/ID OINVOH.UHINRC; OIS350MI/GetInvHead	The field indicates the person/business who is the recipient of the invoice.
Invoice/InvoiceHeader/BillToParty/PartyIDs/TaxID OCUSMA.UHTAXC; CRS610MI/GetFinancial	<p>The field indicates if an item, charge, customer or ship-to location is taxable or not.</p> <p>The tax code is used to calculate US sales tax.</p>
Invoice/InvoiceHeader/BillToParty/Name OINVOH.UHCUN2; OIS350MI/GetInvHead	The field indicates the invoice receiver, which is used as complementary information to the customer number on panels and documents.
Invoice/InvoiceHeader/BillToParty/Location/Address/AttentionOfName OINVOH.Various; OIS100MI CRS610MI/GetAddress GetBasicData	The field indicates the invoice receiver, which is used as complementary information to the customer number on panels and documents.
Invoice/InvoiceHeader/BillToParty/Location/Address/AddressLine OCUSMA.Various; OIS100MI CRS610MI/GetAddress GetBasicData	The field indicate an Address Line
Invoice/InvoiceHeader/BillToParty/Location/Address/CityName OCUSMA.OKTOWN; OIS100MI CRS610MI/GetAddress GetBasicData	The field indicates the City in an address
Invoice/InvoiceHeader/BillToParty/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; OIS100MI CRS610MI/GetAddress GetBasicData	The field indicates an area, province or state within a country

Invoice

Invoice/InvoiceHeader/BillToParty/Location/Address/CountryCode OCUSMA.OKCSCD; OIS100MI CRS610MI/GetAddress GetBasicData	The field indicates a country
Invoice/InvoiceHeader/BillToParty/Location/Address/PostalCode OCUSMA.OKPONO; OIS100MI CRS610MI/GetAddress GetBasicData	The field indicates a postal code for a specific address
Invoice/InvoiceHeader/BillToParty/Location/Status/Code OCUSMA.UHSTAT; CRS610MI/GetBasicData	The field indicates the status of the customer. If M3 status is 10, set element to "Pending" If M3 status is 20, set element to "Open" If M3 status is 90, set element to "Closed"
Invoice/InvoiceHeader/BillToParty/Contact/ID N/A.; CMS055MI/LstByCustomer	Display field if ADRT = '3' (Payment address)
Invoice/InvoiceHeader/BillToParty/Contact/Name N/A.; CMS055MI/LstByCustomer	The field indicates the name of the customer's contact.
Invoice/InvoiceHeader/BillToParty/Contact/Communication/DialNumber N/A.-; CRS618MI/Get	The field indicate an Address Line
Invoice/InvoiceHeader/PayFromParty/PartyIDs/ID OOHEAD.; OIS100MI/GetHead	The field indicates the person/business who has paid or will pay the invoice. The payer is specified when an invoice should be sent somewhere other than to the customer placing the order. For order and sales statistics, the payer is used as a statistic ID. For total statistics, the payer is one of the key IDs.
Invoice/InvoiceHeader/PayFromParty/Name OCUSMA.UHCUNM; CRS610MI/GetBasicData	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
Invoice/InvoiceHeader/PayFromParty/Location/Address/AttentionOfName OCUSMA.UHCUNM; CRS610MI/GetBasicData	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
Invoice/InvoiceHeader/PayFromParty/Location/Address/AddressLine OINVOH.-; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceHeader/PayFromParty/Location/Address/CityName OCUSMA.OKTOWN; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceHeader/PayFromParty/Location/Address/CountrySubDivisionCode OINVOH.OKECAR; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceHeader/PayFromParty/Location/Address/CountryCode OINVOH.OKCSCD; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceHeader/PayFromParty/Location/Address/PostalCode OINVOH.OKPONO; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/Note N/A.Variou; OIS350MI/LstInvLineByTyp	This contains concatenated values of the following: company, division, year, invoice prefix, invoice number, information type, order number, delivery number, warehouse, invoice reference.
Invoice/InvoiceLine/DocumentReference/DocumentID/ID ODLINE.UBORNO; OIS350MI/LstInvLineByTyp	The field indicates a unique identity for a customer order. Different order number series can be used, which are controlled by an assigned order type. Number series are connected to an order type
Invoice/InvoiceLine/DocumentReference/LineNumber	Increment integer starting with 1.
Invoice/InvoiceLine/Item/ItemID/ID ODLINE.UBITNO; OIS350MI/LstDelLine	The field indicates the item number (for Maintenance, the item number or equipment number), which is a unique ID for an individual
Invoice/InvoiceLine/Item/ItemID/RevisionID MITMAS.MMECVE; MMS200MI/GetltnTech	

Invoice

	The field indicates the revision number (edition) for an item or document.
Invoice/InvoiceLine/Item/UPCID MITPOP.MPPOP; MMS025MI/LstAlias	Correspond to GTIN-12 and UCC-12. This is a 12-digit number used for identifying goods. Alias qualifier = UPC
Invoice/InvoiceLine/Item/GTIN MITPOP.MPPOP; MMS025MI/LstAlias	The Global Trade Item Number is a 14-digit number which includes various EAN/UCC numbering structures. Alias qualifier = GTIN
Invoice/InvoiceLine/Item/Description MITMAS.MMITDS; MMS200MI/GetItmBasic	The field indicates the name for each item.
Invoice/InvoiceLine/Item/Classification/Codes/Code 1) MITMAS 2) MITMAS 3) MITMAS 4) MITMAS 5) MITMAS 6) MITMAS 7) MITMAS 8) MITMAS.MMITGR MMITCL MMBUAR MMITTY MMTPCD MMPRGP MMDIGI MMCHCD; MMS200MI MMS200MI MMS200MI MMS200MI MMS200MI MMS200MI MMS200MI/GetItmBasic GetItmBasic GetItmBasic GetItmBasic GetItmBasic GetItmBasic GetItmPrice GetItmBasic	1) Item group The field indicates the item group. 2) Product group The field indicates the product group. 3) Business area The field indicates the business area. 4) Item type The item type is mandatory and cannot be changed after the item is created. The only time an item type can be changed is when you copy template items. The functions connected to the item type include: -A template item that contains default values for creating items. -A numbering rule for assigning the correct item number -A warehouse/item type to set the item/warehouse records generated when you create an item. -An alias/item type that is used to set the alias numbers generated when you create an item. 5) Item category The field indicates the item category. Alternatives 00 = Normal item 02 = Phantom item 03 = Subcontracted item 04 = Tool 05 = Fixed machine 07 = Repairable item 08 = Recyclable item 11 = Extended Catalog Item (ECI) 12 = Non-coded Extended Catalog Item 13 = Non-material item 6) Procurement grp The field indicates the procurement group for an item." 7) Item discount group Item discount groups are entered per item in M3 and may be used as a control object for calculating customer order line discounts. 8) Configuration code The field indicates if the item is configured when ordered or configured as a maintenance item.
Invoice/InvoiceLine/Item/Classification/Description CSYTAB.CTTX40; CRS175MI/LstCodesByLng	The field indicates a description of the classification. It is retrieved from table CSYTAB (generic description), table CSLGHN (language-specific description) or hardcoded.
Invoice/InvoiceLine/Item/SerializedLot/Lot/LotIDs/ID OOLINE.OBBANO; OIS100MI/GetLine	The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics. Serial numbers can be used for lot numbering.
Invoice/InvoiceLine/Item/SerializedLot/Lot/SerialNumber OOLINE.OBSERN; OIS100MI/GetLine	The field indicates the unique serial number of each item. Lot number and lot/serial number can also be used.
Invoice/InvoiceLine/Item/SerializedLot/SerialNumber OOLINE.OBSERN; OIS100MI/GetLine	The field indicates the unique serial number of each item. Lot number and lot/serial number can also be used.
Invoice/InvoiceLine/CountryOfOriginCode OOLINE.OBORCO; OIS100MI/GetLine	The field indicates the item's country of origin. The information can be used for trade statistics reported to the authorities.
Invoice/InvoiceLine/Quantity ODLINE.UBQTY5; OIS350MI/GetDelLine	

Invoice

	<p>The field indicates the invoiced quantity in a basic U/M for the delivery line.</p> <p>Invoiced quantity is updated at invoicing.</p> <p>During invoice updating, delivered quantity on the delivery line is transferred to the invoiced quantity on the order line and to the invoiced quantity on the delivery line.</p> <p>Delivered quantity on the order line is reduced by the transferred delivered quantity on the delivery line.</p>
Invoice/InvoiceLine/BaseUOMQuantity ODLINE.UBQTY4; OIS350MI/GetDelLine	Quantity of an invoice line
Invoice/InvoiceLine/UnitPrice/Amount ODLINE.UBSAPR; OIS350MI/GetDelLine	The field indicates the invoice amount in the local currency.
Invoice/InvoiceLine/UnitPrice/BaseAmount ODLINE.UBSAP1; OIS350MI/GetDelLine	unit price in local currency.
Invoice/InvoiceLine/UnitPrice/PerQuantity ODLINE.UBSAPR; OIS350MI/GetDelLine	The field indicates the quantity to which the sales price applies. Sales price quantity is defined for each item and is expressed in the item unit of measure.
Invoice/InvoiceLine/ExtendedAmount OINVOH.UHAMT2; OIS350MI/GetInvHead	Display AMT2 if IVTP = '31'.
Invoice/InvoiceLine/ExtendedBaseAmount OINVOL.UHIVLA; OIS350MI/LstInvLine	Display AMT1 if IVTP = '31'.
Invoice/InvoiceLine/TotalAmount OINVOH.UHAMT2; OIS350MI/GetInvHead	Display AMT2 if IVTP = '31'. Should include + charge, - invoice allowance, + extended amount .
Invoice/InvoiceLine/TotalBaseAmount OINVOL.ONIVLA; OIS350MI/LstInvLine	Display AMT1 if IVTP = '31'.
Invoice/InvoiceLine/Tax/ID OINVOL.ONVTCD; OIS350MI/GetInvLine	The field indicates a VAT code. The VAT code controls what VAT method and VAT rate to apply.
Invoice/InvoiceLine/InvoiceCharge/ID OOLINE.OBCRID; OIS100MI/LstConnCOCharge	The field indicates the unique ID of a charge.
Invoice/InvoiceLine/InvoiceCharge/Description OOLINE.OBCRD0; OIS100MI/LstConnCOCharge	The field indicates the charge description
Invoice/InvoiceLine/InvoiceCharge/Amount OINVOH.UHAMT2; OIS350MI/GetInvHead	Get all Records with IVTP = 67, 60, 65. The fields indicates the Charge Amount
Invoice/InvoiceLine/InvoiceCharge/BaseAmount OINVOL.ONIVLA; OIS350MI/LstInvLine	Get all Records with IVTP = 67, 60, 65. The fields indicates the Charge Amount
Invoice/InvoiceLine/InvoiceCharge/Calculation/RateNumeric OOLINE.OBCRFA; OIS100MI/LstConnCOCharge	The field indicates the calculation factor that is used to calculate the charge amount. The field is used in combination with calculation method 1-5. A charge is calculated by multiplying the calculation factor and the base selected in the Calculation method field. The calculation is made when the customer order is invoiced.
Invoice/InvoiceLine/InvoiceCharge/ReasonCode OOLINE.OBCRD0; OIS100MI/LstConnCOCharge	The field indicates the name or description of the charge to be printed on the external document.
Invoice/InvoiceLine/InvoiceAllowance/Amount OINVOH.UHAMT2; OIS350MI/GetInvHead	Display data if IVTP = 32,33,34. The fields indicates the Allowance Amount in foreign
Invoice/InvoiceLine/InvoiceAllowance/BaseAmount OINVOL.ONIVLA; OIS350MI/LstInvLine	Display data if IVTP = 32,33,34. The fields indicates the Allowance Amount in local currency.
Invoice/InvoiceLine/CustomerParty/PartyIDs/ID OINVOH.UHCUNO; OIS350MI/GetInvHead	The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric.
Invoice/InvoiceLine/CustomerParty/PartyIDs/TaxID OINVOL.ONVTCD; OIS350MI/GetInvLine	The field indicates a VAT code. The VAT code controls what VAT method and VAT rate to apply.
Invoice/InvoiceLine/CustomerParty/Name ODLINE.UNCUN1; OIS350MI/GetDelLine	The field indicates the name of the customer.
Invoice/InvoiceLine/CustomerParty/Location/Address/AttentionOfName OOHEAD.OARESP; OIS100MI/GetHead	Person responsible
Invoice/InvoiceLine/CustomerParty/Location/Address/AddressLine OCUSMA.Various; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/CustomerParty/Location/Address/CityName OCUSMA.OKTOWN; OIS100MI OIS100MI	

Invoice

CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/CustomerParty/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/CustomerParty/Location/Address/CountryCode OCUSMA.OKCSCD; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/CustomerParty/Location/Address/PostalCode OCUSMA.OKPONO; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/CustomerParty/Contact/ID --; CMS055MI/LstByCustomer	The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric. For temporary customers (customer type 9), the customer number must be within a defined range where only customers with customer type 9 can be entered.
Invoice/InvoiceLine/CustomerParty/Contact/Communication/DialNumber --; CRS618MI/Get	The field indicates the telephone number of the customer.
Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address/AddressLine OCUSMA.Various; CRS618MI/Get	The field indicate an Address Line
Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address/CityName OCUSMA.OKTOWN; CRS618MI/Get	The field indicates the city in an address. The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.
Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address/CountrySubDivisionCode .; CRS618MI/Get	The field indicates an area, province or state within a country
Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address/CountryCode .; CRS618MI/Get	The field indicates a country
Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address/PostalCode .; CRS618MI/Get	The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used.
Invoice/InvoiceLine/CustomerParty/Contact/Communication/URI .; CRS618MI/Get	The field indicates an e-mail address for the customer, supplier, etc. entered.
Invoice/InvoiceLine/CustomerParty/Contact/Communication/HTMLPreferredIndicator	Constant = 'true'
Invoice/InvoiceLine/CustomerParty/Contact/Communication/Preference/Sequence	Constant = '1'
Invoice/InvoiceLine/CustomerParty/Contact/Communication/Preference/Indicator	Constant = 'true'
Invoice/InvoiceLine/SalesOrderReference/DocumentID/ID ODLINE.ONORNO; OIS350MI/GetDelLine	The field indicates a unique identity for a customer order. Different order number series can be used, which are controlled by an assigned order type. Number series are connected to an order type
Invoice/InvoiceLine/SalesOrderReference/LineNumber ODLINE.UBPONR; OIS350MI/GetDelLine	This field indicates the line number
Invoice/InvoiceLine/SalesOrderReference/SubLineNumber ODLINE.UBPOSX; OIS350MI/GetDelLine	The field indicates a sequence number within a line number. The suffix is used in kit order handling. The kit order line has the suffix 00, and the suffix of the detail lines may vary from 01 to 99.
Invoice/InvoiceLine/ExtendedCost/Amount ODLINE.UBDCOS; OIS350MI/GetDelLine	This field indicates the Extended Cost . (Issued cost amount found in OIS356/F).
Invoice/InvoiceLine/ExtendedCost/BaseAmount ODLINE.UHIVAM; OIS350MI/GetDelLine	This field indicates the Extended Cost Converted to local currency
Invoice/InvoiceLine/ShipToParty/PartyIDs/ID OOHEAD.OADECUC; OIS100MI/GetLineAddress GetLine	If ADRT = 1 consists of two data then display in InvoiceLine. Display field if ADRT = '1' (Delivery address). The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric. The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric.
Invoice/InvoiceLine/ShipToParty/PartyIDs/TaxID	

Invoice

OCUSMA.UHVRNO; CRS610MI/GetFinancial	The field indicates a VAT code. The VAT code controls what VAT method and VAT rate to apply.
Invoice/InvoiceLine/ShipToParty/Name ODLINE.UNCUN1; OIS350MI/GetDelLine	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
Invoice/InvoiceLine/ShipToParty/Location/Address/AttentionOfName OCUSMA.Various; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/ShipToParty/Location/Address/AddressLine OCUSMA.Various; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/ShipToParty/Location/Address/CityName OCUSMA.OKTOWN; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/ShipToParty/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/ShipToParty/Location/Address/CountryCode OCUSMA.OKCSCD; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/ShipToParty/Location/Address/PostalCode OCUSMA.OKPONO; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
Invoice/InvoiceLine/ShipToParty/Contact/ID N/A.; CRS055MI/LstByCustomer	Display field if ADRT = '1' (Delivery address)
Invoice/InvoiceLine/ShipToParty/Contact/Name N/A.; CRS055MI/LstByCustomer	The field indicates the name of the customer's contact.
Invoice/InvoiceLine/ShipToParty/Contact/Communication/DialNumber N/A.; CRS618MI/Get	The field indicates the telephone number of the customer.
Invoice/InvoiceLine/ShipToParty/Contact/Communication/URI N/A.; CRS618MI/Get	The field indicates an e-mail address for the customer, supplier, etc. entered.
Invoice/InvoiceLine/Reference/NameValue ODLINE.UBORNO; OIS350MI/GetDelLine	The field indicates a unique identity for a customer order. Different order number series can be used, which are controlled by an assigned order type. Number series are connected to an order type.

ItemMaster

ItemMaster/ItemMasterHeader/ItemID/ID

MITMAS.MMITNO; MMS200MI/GetItmBasic

The field indicates the item number which, is a unique ID for an individual item. Item number can consist up to 15 alphanumeric characters.

@accountingEntity

MITMAS.MMCONO
CMNDIV.CCDIV1.; N/A/

The field indicates the company and division. AccountingEntity for M3 is defaulted as a combination of CONO_DIV1.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

@variationID

The field indicates the sequence number to ensure documents are processed in correct order.

@lid

The field indicates the logical ID of the system.

ItemMaster/ItemMasterHeader/ItemID/RevisionID

MITMAS.MMECVE; MMS200MI/GetItmTech

The field indicates the revision number (edition) for an item or document.

ItemMaster/ItemMasterHeader/UPCID

MITPOP.MPPOP; MMS025MI/LstAlias

Correspond to GTIN-12 and UCC-12. This is a 12-digit number used for identifying goods.

Alias qualifier = UPC

ItemMaster/ItemMasterHeader/GTIN

MITPOP.MPPOP; MMS025MI/LstAlias

The Global Trade Item Number is a 14-digit number which includes various EAN/UCC numbering structures.

Alias qualifier = GTIN

ItemMaster/ItemMasterHeader/ServiceIndicator

Set to false for all items.

ItemMaster/ItemMasterHeader/Description

- 1) MITMAS.MMFUDS; MMS200MI/GetItmBasic
- 2) MITMAS.MMITDS; MMS200MI/GetItmBasic
- 3) MITLAD.MDFUDS; MMS200MI/LstItemDescLang
- 4) MITLAD.MDITDS; MMS200MI/LstItemDescLang; /

This is the item name and description.

- 1) Generic item description is published without any attribute
- 2) Generic item name is published with attribute type="Short Name"
- 3) Language specific item description is published with attribute languageID=language code
- 4) Language specific item name is published with attributes: type="Short Name" and languageID=language code

@languageID

MITLAD.MDLNCD; MMS200MI/LstItemDescLang

The field indicates the language ID

ItemMaster/ItemMasterHeader/Classification/Codes/Code

- 1) MITMAS.MMITGR; MMS200MI/GetItmBasic
- 2) MITMAS.MMITCL; MMS200MI/GetItmBasic
- 3) MITMAS.MMBUAR; MMS200MI/GetItmBasic
- 4) MITMAS.MMITTY; MMS200MI/GetItmBasic
- 5) MITMAS.MMTPCD; MMS200MI/GetItmBasic
- 6) MITMAS.MMPRGP; MMS200MI/GetItmBasic
- 7) MITMAS.MMDIGI; MMS200MI/GetItmPrice
- 8) MITMAS.MMCHCD; MMS200MI/GetItmBasic
- 9) MITMAS.MMRUID; MMS200MI/GetItmBasic
- 10) MITMAS.MMITNO/MMHDPR/MMTPLI; MMS200MI/GetItmBasic

1) Item group

The field indicates the item group.

2) Product group

The field indicates the product group.

3) Business area

The field indicates the business area.

4) Item type

The item type is mandatory and cannot be changed after the item is created. The only time an item type can be changed is when you copy template items.

The functions connected to the item type include:

- A template item that contains default values for creating items.
- A numbering rule for assigning the correct item number
- A warehouse/item type to set the item/warehouse records generated when you create an item.
- An alias/item type that is used to set the alias numbers generated when you create an item.

5) Item category

The field indicates the item category.

Alternatives

- 00 = Normal item
- 02 = Phantom item
- 03 = Subcontracted item
- 04 = Tool
- 05 = Fixed machine
- 07 = Repairable item
- 08 = Recyclable item
- 11 = Extended Catalog Item (ECI)
- 12 = Non-coded Extended Catalog Item
- 13 = Non-material item

6) Procurement grp

ItemMaster

	<p>The field indicates the procurement group for an item."</p> <p>7) Item discount group Item discount groups are entered per item in M3 and may be used as a control object for calculating customer order line discounts.</p> <p>8) Configuration code The field indicates if the item is configured when ordered or configured as a maintenance item.</p> <p>9) Ruleset ID The field indicates the identification of the ruleset in PCM (Product Configuration Management) to use when the product is configured.</p> <p>10) Styles The field indicates the Style item number. Retrieved from ITNO for Style and HDPR or TPLI for SKU.</p>
@listID	<p>1) M3 BE field Item group has list ID "Item Groups" 2) M3 BE field Product group has list ID "Product Groups" 3) M3 BE field Business area has list ID "Business Sectors" 4) M3 BE field Procurement group has list ID "Buying Groups" 5) M3 BE field Item type has list ID "Item Types" 6) M3 BE field Item category group has list ID "Item Classes" 7) M3 BE field Item discount group has list ID "Item Rebate Groups" 8) M3 BE field Configuration code has list ID "Configuration Code" 9) M3 BE field Configuration code has list ID "Configured Ruleset" 10) M3 BE field Style has list ID "Styles"</p>
@sequence	<p>The sequence attribute is used for the ordering of elements within a document. It identifies the hierarchical position of the identifier in the case of multi-level codes.</p>
ItemMaster/ItemMasterHeader/Classification/Description CSYTAB.CTTX40/CSLGHN.JLTX60; CRS175MI/LstCodesByLng	<p>The field indicates a description of the classification. It is retrieved from table CSYTAB (generic description), table CSLGHN (language-specific description) or hardcoded.</p>
@languageID CSLGHN.JLLNCD; CRS175MI/LstCodesByLng	<p>The field indicates the language ID</p>
ItemMaster/ItemMasterHeader/HazardousMaterial/ID MITMAS.MMITNO; MMS200MI/GetItmBasic	<p>The field indicates the item number which is tagged as hazardous material (HAZI = 1). If HAZI = 0, this field is blank.</p>
ItemMaster/ItemMasterHeader/TrackingIndicator MITMAS.MMSTCD; MMS200MI/GetItmBasic	<p>Inventory Accounting The field indicates whether the stock kept for the item is accounted in inventory. 1 = true; 0, 2, 3 = false</p> <p>0 = No. 1 = Yes, the item is inventory accounted. 2 = No, the item is not inventory accounted, but it is planned as demand in the material planning process in (MMS080 - Material Plan. Open). 3 = No, the item is not inventory accounted, but it is planned as a function number. A function number is a dummy number for items that can replace each other. So material planning for the item is done on the function number level instead of the item level.</p>
ItemMaster/ItemMasterHeader/ItemStatus/Code MITMAS.MMSTAT; MMS200MI/GetItmBasic	<p>The field indicates the item's status. M3 BE status is translated according to : 10 = Pending 15 = Pending 20 = Open 30 = Open 40 = Open 50 = DoNotReorder 80 = Obsolete 90 = Obsolete 99 = Deleted</p>
ItemMaster/ItemMasterHeader/ItemStatus/Description MITMAS.MMSTAT; MMS200MI/GetItmBasic	<p>The field indicates the Item status description. M3 BE status description is translated according to: 10 = Preliminary Item 15 = Replacement Item 20 = Released Item 30 = Alternate Items Available 40 = Low Turnover Item</p>

ItemMaster

	<p>50 = Discontinued Item 80 = Not Carried 90 = No Longer Stocked 99 = Item Number Changed</p>
ItemMaster/ItemMasterHeader/BaseUOMCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	<p>The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.</p>
ItemMaster/ItemMasterHeader/StorageUOMCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	<p>The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.</p> <p>In M3BE, the StorageUOMCode is the same as Base UOM Code</p>
ItemMaster/ItemMasterHeader/LastModificationDateTime MITMAS.MMLMDT; MMS200MI/GetItmBasic	<p>The field indicates the date and time on which the object was last modified.</p>
ItemMaster/ItemMasterHeader/UOMCodeConversion/FromUOMPackage/UOMCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	<p>The field indicates the basic unit of measure.</p>
ItemMaster/ItemMasterHeader/UOMCodeConversion/RateNumeric MITAUN.MUCOFA; MMS200MI/LstItmAltUnitMs	<p>The field indicates a factor that is used to convert a basic U/M to an alternate U/M.</p>
ItemMaster/ItemMasterHeader/UOMCodeConversion/ToUOMPackage/UOMCode MITAUN.MUALUN; MMS200MI/LstItmAltUnitMs	<p>The field indicates an alternate unit of measure (U/M) for the basic U/M for an item.</p>
ItemMaster/ItemMasterHeader/SerialControlIndicator MITMAS.MMINDI; MMS200MI/GetItmBasic	<p>The field indicates if and how serial control is to be applied for each item. 0,1,3 = false; 2,5 = true</p>
ItemMaster/ItemMasterHeader/LotControlIndicator MITMAS.MMINDI; MMS200MI/GetItmBasic	<p>The field indicates if and how lot control is to be applied for each item. 0 = false 1,2,3,5 = true</p>
ItemMaster/ItemMasterHeader/ConfiguredItemIndicator MITMAS.MMCHCD; MMS200MI/GetItmBasic	<p>The field indicates if the item is configured when ordered or configured as a maintenance item.</p> <p>0, 3, 4, 5 = false 1, 2 = true</p>
ItemMaster/ItemMasterHeader/CatchWeightIndicator MITMAS.MMACTI; MMS200MI/GetItmBasic	<p>The field indicates whether this is a catch weight item.</p> <p>0, 1 = false 2, 3, 4 = true</p>
ItemMaster/ItemMasterHeader/UserArea	<p>UserArea is used to identify if the Item is Style or SKU. This is also used to connect the Style to an existing Feature/Option. These information are defined under UserArea >Property >NameValue which are determined by different name attributes.</p> <p>Name attributes:</p> <p>To identify if the item is Style or SKU "StyleItemtype" - the NameValue can either be Style or SKU.</p> <p>For SKU "StyleOptionX", "StyleOptionY", "StyleOptionZ" - indicates the options (MMS019MI Get OPTX, OPTY, OPTZ) "StyleOptionXSequence", "StyleOptionYSequence", "StyleOptionZSequence" - indicates the option sequence number (MMS019MI Get SQNX, SQNY, SQNZ) "StyleFeatureX", "StyleFeatureY", "StyleFeatureZ" - indicates the feature to connect to Style (MMS019MI Get FTIX, FTIY, FTIZ)</p> <p>For connecting Feature to Style "StyleFeatureX", "StyleFeatureY", "StyleFeatureZ" - indicates the feature to connect to Style (MMS017MI List FTID)</p>
ItemMaster/ItemMasterHeader/SellableIndicator MITMAS.MMSALE; MMS200MI/GetItmBasic	<p>The field indicates if the item is a sales item. 0 = false 1,2 = true</p>
ItemMaster/ItemMasterHeader/PackagingUnit/UnitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	<p>The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.</p>
ItemMaster/ItemMasterHeader/PackagingUnit/Dimensions/WidthMeasure	

ItemMaster

MITMAS.MMIWID; MMS200MI/GetltnBasic	The field indicates the item's width.
@unitCode CSYPAR.CPPARM; CRS175MI/GetltnFreeFlds	The field indicates the general unit of measure for width. It is stored in M3 BE, program CRS703 General Units of Measure.
ItemMaster/ItemMasterHeader/PackagingUnit/Dimensions/LengthMeasure	
MITMAS.MMILEN; MMS200MI/GetltnBasic	The field indicates the item's length.
@unitCode CSYPAR.CPPARM; CRS175MI/GetltnFreeFlds	The field indicates the general unit of measure for length. It is stored in M3 BE, program CRS703 General Units of Measure.
ItemMaster/ItemMasterHeader/PackagingUnit/Dimensions/HeightMeasure	
MITMAS.MMIHEI; MMS200MI/GetltnBasic	The field indicates the item's height.
@unitCode CSYPAR.CPPARM; CRS175MI/GetltnFreeFlds	The field indicates the general unit of measure for height. It is stored in M3 BE, program CRS703 General Units of Measure.
ItemMaster/ItemMasterHeader/PackagingUnit/NetWeightMeasure	
MITMAS.MMNEWE; MMS200MI/GetltnTech	The field indicates the item's net weight per basic U/M.
@unitCode CSYPAR.CPPARM; CRS175MI/GetltnFreeFlds	The field indicates the general unit of measure for weights. It is stored in M3 BE, program CRS703 General Units of Measure.
ItemMaster/ItemMasterHeader/PackagingUnit/GrossWeightMeasure	
MITMAS.MMGRWE; MMS200MI/GetltnTech	The field indicates the item's weight per basic U/M including the weight of any product packaging material. The information is used when creating packages for transportation purposes, and should not include the transportation packaging material such as transportation boxes, pallets, containers etc.
@unitCode CSYPAR.CPPARM; CRS175MI/GetltnFreeFlds	The field indicates the general unit of measure for weights. It is stored in M3 BE, program CRS703 General Units of Measure.
ItemMaster/ItemMasterHeader/PackagingUnit/TotalVolumeMeasure	
MITMAS.MMVOL3; MMS200MI/GetltnTech	The field indicates the item volume per basic U/M including any product packaging material
@unitCode CSYPAR.CPPARM; CRS175MI/GetltnFreeFlds	The field indicates the general unit of measure for volumes . It is stored in M3 BE, program CRS703 General Units of Measure.
ItemMaster/ItemMasterHeader/ProcurementParameters/ProcurementMethodCode	
MITMAS.MMMABU; MMS200MI/GetltnBasic	The field indicates whether the item is manufactured in-house or purchased. 1 = Manufacture 2 = Purchase
ItemMaster/ItemMasterHeader/Substitutions	
@EffectiveDate Time MITALT.MASTDT; MMS020MI/LstltnRelation	The field indicates the start date when the substitution becomes valid
ItemMaster/ItemMasterHeader/Substitutions/Components/ItemID/ID	
MITALT.MAALIT; MMS020MI/LstltnRelation	The field indicates a related item. A related item can replace an item that is out of stock or has been deleted.
@accountingEntity MITMAS.MMCONO CMNDIV.CCDIV1.; N/A/	The field indicates the company and division. AccountingEntity for M3 is defaulted as a combination of CONO_DIV1. E.g. 780_AAA It is possible to translate using CRS881, but we recommend NOT to translate.
ItemMaster/ItemLocation/Classification/Codes/Code	
1) MITBAL.MBABCD; MMS200MI/GetltnWhsBasic 2) MITFAC.M9ORCO; MMS200MI/GetltnFac	1) ABC Code The field indicates a code, usually A, B or C, used to group items according to how they affect the total sales volume 2) Country of Origin The field indicates the item's country of origin
@listID	1) M3 BE field ABC code has list ID "ABC Codes" 2) M3 BE field Country of Origin has list ID "CountryOfOrigin"
@sequence	The sequence attribute is used for the ordering of elements within a document. It identifies the hierarchical position of the identifier in the case of multi-level codes.
ItemMaster/ItemLocation/Classification/Description	
CSYTAB.CTTX40; CRS175MI/LstCodesByLng	The field indicates a description of the classification. It is retrieved from table CSYTAB (generic description) or hardcoded.
@languageID CSLGHN.JLLNCD; CRS175MI/LstCodesByLng	The field indicates the language ID
ItemMaster/ItemLocation/MaximumLotSizeBaseUOMQuantity	
MITBAL.MBMOQT; MMS200MI/GetltnWhsBasic	The field indicates maximum order quantity, which is the maximum allowed order quantity for each combination of item/warehouse.

ItemMaster

	The information is used at calculation of batch size in connection with requirement calculation.
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Unit of Measure
ItemMaster/ItemLocation/MinimumLotSizeBaseUOMQuantity MITBAL.MBLOQT; MMS200MI/GetItmWhsBasic	<p>The field indicates minimum order quantity, which is the minimum order quantity allowed for each combination of item/warehouse.</p> <p>The information is used at calculation of batch size in connection with requirements calculation, but only if it is greater than zero.</p>
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Unit of Measure.
ItemMaster/ItemLocation/LeadTimeDuration MITBAL.MBLEAT; MMS200MI/GetItmWhsBasic	<p>The field indicates the lead time for each item. This is the time required to meet a requirement from the time acquisition activities are started to the time the requirement is fulfilled.</p> <p>Lead time includes administrative time, postal lead time, supply lead time, transportation time, and inspection time.</p> <p>Note that lead time is always expressed in the unit five (5) days per week when it refers to production or distribution supply. For purchased items, the lead time can be as above or be expressed in calendar days (7 day per week).</p>
ItemMaster/ItemLocation/ItemValue/UnitValue/Amount 1) MITFAC.M9UCOS; MMS200MI/GetItmFac 2) MITFAC.M9APPR; MMS200MI/GetItmFac	<p>The ItemValue is either Standard cost or Average cost.</p> <p>1) Standard cost The field indicates the standard cost expressed in the item cost quantity, calculated per item/facility</p> <p>2) Average cost The field indicates the average cost saved per item/facility in the local currency. The average cost is the cost of items issued from stock. This cost is calculated using the moving weighted average cost method. It is updated using the acquisition cost for each positive inventory transaction in M3.</p>
@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the currency id for the cost amount.
ItemMaster/ItemLocation/ItemValue/UnitValue/PerQuantity MITFAC.M9COCD; MMS200MI/GetItmFac	The field indicates the default item cost quantity per item/facility. The item cost quantity is always entered in the basic unit of measure of the item.
@unitCode MITMAS.MMCPUN; MMS200MI/GetItmBasic	The field indicates the Item cost unit of measure.
ItemMaster/ItemLocation/ItemValue/CostingMethodCode MITFAC.M9VAMT; MMS200MI/GetItmFac	<p>The field indicates the inventory accounting method that defines how the cost of an item is determined per item/facility.</p> <p>1 = Standard Cost 2 = WeightedAverage Cost</p>
@listID	M3 BE field Inventory accounting method has list ID "Costing Methods".
ItemMaster/ItemLocation/WarehouseLocation/ID MITBAL.MBWHLO; MMS200MI/GetItmWhsBasic	<p>The field indicates a warehouse.</p> <p>Warehouse is a stock zone which is used to distinguish different geographical locations within a company. The warehouse is used as a planning level for material and production. Stock zones, stock locations and items are connected to the warehouse.</p>
@accountingEntity MITBAL.MBCONO MITBAL.MBDIVI.; MMS005MI/LstWarehouses	<p>The field indicates the company and division. AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 780_AAA It is possible to translate using CRS881, but we recommend NOT to translate.</p>
ItemMaster/ItemLocation/WarehouseLocation/Name MITWHL.MWWHNM; MMS200MI/GetItmWhsBasic	The field indicates the name of the warehouse.

Location

Location/ID

For Facility:
CFACIL.CFFACI; CRS008MI/Get

For Facility:
This is the M3 facility

For Warehouse:
MITWHL.MWWHLO; MMS005MI/GetWarehouse

For Warehouse:
The field indicates the warehouse ID.

@accountingEntity

For Facility:
CFACIL.CFCONO + CFACIL.CFDIVI.; N/A/

For Facility:
M3 publishes the accounting entity by default as a concatenation from CONO_DIVI.
However, it is possible to translate to any string, but we recommend to use the default value.

@variationID

For Facility:
This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

@lid

For Facility:
The logical ID of the system that is SOR for this noun instance.

Location/DisplayID

For Facility:
CFACIL.CFFACI; CRS008MI/Get

For Facility:
This is the M3 facility

Location/LastModificationDateTime

For Facility:
CFACIL.CFLMTS; N/A/

For Facility:
The datetime on which the object was last modified.

Location/Name

For Facility:
CFACIL.CFFACN; CRS008MI/Get

For Facility:
This is the name of the M3 facility

For Warehouse:
MITWHL.MWWHNM; MMS005MI/GetWarehouse

For Warehouse:
The field indicates optional text

Location/Address/AddressLine

For Warehouse:
CIADDR.OAADR1
OAADR2
OAADR3
OAADR4; MMS005MI/GetWarehouse

For Warehouse:
The field indicates an address line.

Location/Address/CityName

For Warehouse:
CIADDR.OATOWN; MMS005MI/GetWarehouse

For Warehouse:
The field indicates the city in an address.

Location/Address/CountrySubDivisionCode

For Warehouse:
CIADDR.OAECAR; MMS005MI/GetWarehouse

For Warehouse:
The field indicates an area, province or state within a country.

Location/Address/CountryCode

For Warehouse:
CIADDR.OACSCD; MMS005MI/GetWarehouse

For Warehouse:
The field indicates a country.

Location/Address/PostalCode

For Warehouse:
CIADDR.OAPONO; MMS005MI/GetWarehouse

For Warehouse:
The field indicates a postal code for a specific address.

Location/ParentLocation/ID

For Warehouse:
MITWHL.MWFACI; MMS005MI/GetWarehouse

For Warehouse:
This field indicates the facility.

@accountingEntity

For Warehouse:
This field indicates the company and division.

Location/ParentLocation/Name

For Warehouse:
CFACIL.CFFACN; CRS008MI/Get

For Warehouse:
This field indicates the name of the facility.

Location/Classification/Codes/Code

@listID

For Warehouse:
Hardcoded to 'Location Sub Type'

Location/TimeZone

For Warehouse:
CITZON.TZTIZO; MMS005MI/Select

For Warehouse:
The field indicates an international time zone such as Central European Time (CET) or CET+1. When no time zone is entered for a location, local time is used. This means that no conversion of time is done.

Location/TimeZone/TimeZoneOffset

For Warehouse:
CITZON.TZTGMT; MMS005MI/Select

For Warehouse:
The field indicates the number of hours and minutes by which the current time zone deviates from UTC (Universal Time Coordinated). Note that UTC replaces Greenwich Mean Time (GMT). You should enter any time zone that is earlier than UTC with a minus sign after the number of hours.

Location

Location/TimeZone/TimeZoneDaylightStartDate

For Warehouse:
CITZON.TZVFDT; MMS005MI/SelTimezone

For Warehouse:
The field indicates the date when Daylight Saving Time takes effect or ends.
When applied on the Northern hemisphere, it describes the date when Daylight Saving Time takes effect.
When applied on the Southern hemisphere, it describes the date when Daylight Saving Time ends.

Location/TimeZone/TimeZoneDaylightStart/Month

For Warehouse:
CITZON.TZVFDT; MMS005MI/SelTimezone

For Warehouse:
The field indicates the date when Daylight Saving Time takes effect or ends.
When applied on the Northern hemisphere, it describes the date when Daylight Saving Time takes effect.
When applied on the Southern hemisphere, it describes the date when Daylight Saving Time ends.

Location/TimeZone/TimeZoneDaylightStart/WeekNumber

For Warehouse:
CITZON.TZVFDT; MMS005MI/SelTimezone

For Warehouse:
The field indicates the date when Daylight Saving Time takes effect or ends.
When applied on the Northern hemisphere, it describes the date when Daylight Saving Time takes effect.
When applied on the Southern hemisphere, it describes the date when Daylight Saving Time ends.

Location/TimeZone/TimeZoneDaylightEndDate

For Warehouse:
CITZON.TZVTDT; MMS005MI/SelTimezone

For Warehouse:
The field indicates the date when Daylight Saving Time takes effect or ends.
When applied on the Northern hemisphere, it describes the date when Daylight Saving Time takes effect.
When applied on the Southern hemisphere, it describes the date when Daylight Saving Time ends.

Location/TimeZone/TimeZoneDaylightEnd/Month

For Warehouse:
CITZON.TZVTDT; MMS005MI/SelTimezone

For Warehouse:
The field indicates the date when Daylight Saving Time takes effect or ends.
When applied on the Northern hemisphere, it describes the date when Daylight Saving Time takes effect.
When applied on the Southern hemisphere, it describes the date when Daylight Saving Time ends.

Location/TimeZone/TimeZoneDaylightEnd/WeekNumber

For Warehouse:
CITZON.TZVTDT; MMS005MI/SelTimezone

For Warehouse:
The field indicates the date when Daylight Saving Time takes effect or ends.
When applied on the Northern hemisphere, it describes the date when Daylight Saving Time takes effect.
When applied on the Southern hemisphere, it describes the date when Daylight Saving Time ends.

Location/TimeZone/TimeZoneDaylightEnd/DayOfWeek

For Warehouse:
CITZON.TZVTDT; MMS005MI/SelTimezone

For Warehouse:
The field indicates the date when Daylight Saving Time takes effect or ends.
When applied on the Northern hemisphere, it describes the date when Daylight Saving Time takes effect.
When applied on the Southern hemisphere, it describes the date when Daylight Saving Time ends.

Location/TimeZone/Description

For Warehouse:
CITZON.TZTX40; MMS005MI/Select

For Warehouse:
The field indicates a description of the current identity.

Location/Status/Code

For Facility:
This indicates the Status of the code id.
It is hardcoded to "Open"

@listID

For Facility:
This is set to "Location status"

PayFromPartyMaster

PayFromPartyMaster/PartyIDs/ID

@accountingEntity

OCUSMA.OKCONO
CMNDIV.CCDIVI.; N/A/

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

@lid

The logical ID of the system that is SOR for this noun instance.

PayFromPartyMaster/Name

OCUSMA.OKCUNM; CRS610MI/GetBasicData

This field indicates the customer name

PayFromPartyMaster/Location/Address/AttentionOfName

OCUSMA.OKYREF; CRS610MI/GetBasicData

The field indicates the customer's contact person

PayFromPartyMaster/Location/Address/AddressLine

OCUSMA.OKCUA1-OKCUA4; CRS610MI/GetBasicData

This indicates the address lines for the customer address

@sequence

The field indicates the Address Line sequence

PayFromPartyMaster/Location/Address/CityName

OCUSMA.OKTOWN; CRS610MI/GetBasicData

This field indicates the city

PayFromPartyMaster/Location/Address/CountrySubDivisionCode

The field indicates the state/region/countrysubdivision

@listID

M3 BE field State has different list ID depending on country:
- Canada has list ID "Canadian Provinces"
- France has list ID "France - Departements"
- United States has list ID "US States"
- Other countries have list ID "Country Sub-divisions"

PayFromPartyMaster/Location/Address/CountryCode

OCUSMA.OKCSCD; CRS610MI/GetBasicData

The field indicates the country code

@listID

M3 BE field Country has list ID "Countries"

PayFromPartyMaster/Location/Address/PostalCode

OCUSMA.OKPONO; CRS610MI/GetBasicData

This field indicates the postal code

PayFromPartyMaster/Location/Address/Preference/Indicator

This is hardcoded to true.

PayFromPartyMaster/PaymentTermID

OCUSMA.OKTEPY/CCUDIV.OKTEPY.; CRS610MI/GetOrderInfo

The field indicates the payment terms id for the customer
Data is retrieved from customer master, table OCUSMA, or, if applicable, from customer local exceptions, table CCUDIV.

PayFromPartyMaster/Status/Code

OCUSMA.OKSTAT; CRS610MI/GetBasicData

The field indicates the status of the customer.

If M3 status is 10, set element to "Pending"
If M3 status is 20, set element to "Open"
If M3 status is 90, set element to "Closed"

PayFromPartyMaster/Classification/Codes/Code

1) OCUSMA.OKCUTP; CRS610MI/GetBasicData

The field indicates the Classification.

1) If Customer type field is filled, populate Code with this value

2) OCUSMA.OKTEDL/CCUDIV.OKTEDL; CRS610MI/GetOrderInfo

2) If Delivery terms field is filled, populate Code with this value
Data is retrieved from customer master, table OCUSMA, or, if applicable, from customer local exceptions, table CCUDIV.

3) OCUSMA.OKSDST; CRS610MI/GetOrderInfo

3) If District field is filled, populate Code with this value

@listID

The field indicates the Classification code listID.

1) If Customer type field is filled, set listID to "Customer Types"
2) If Delivery terms field is filled, set listID to "Incoterms"
3) If District field is filled, set listID to "District"

@sequence

The sequence attribute identifies the hierarchical position of the identifier in the case of multi-level codes

PayFromPartyMaster/BillToParty/PartyIDs/ID

OCUSMA.OKCUNO; BODCSSMI/LstBillToParty

This is a list of customer records from M3 BE that is the invoice recipient for the PayFromPartyMaster.

It is retrieved in two steps using BODCSSMI/LstBillToParty:

1) All customer records (OKCUNO) that uses the PayFromPartyMaster id as Payer (OKPYNO)
2) For each customer record (OKCUNO), retrieve the invoice recipient (OKINRC) if it is populated, otherwise retrieve the payer (OKPYNO)

@accountingEntity

OCUSMA.OKCONO.; N/A/

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

PayFromPartyMaster

PayFromPartyMaster/BillToParty/Name
OCUSMA.OKCUNM; BODCSSMI/LstBillToParty

This is the customer name of the BillToParty

PayableTransaction

PayableTransaction/PayableTransactionHeader/DocumentID/ID FPLEDG.CONO + DIVI + YEA4 + JRNO + JSNO; APS200MI/GetInvoice	Transaction code = 40; Unique key in FPLEDG; Company + Division + Year + Journal Number + Journal Sequence Number
PayableTransaction/PayableTransactionHeader/AlternateDocumentID/ID FPLEDG.SUNO + SPYN + SINO + INYR; APS200MI/GetInvoice	Supplier invoice number
PayableTransaction/PayableTransactionHeader/DisplayID ; APS200MI/GetInvoice	0
PayableTransaction/PayableTransactionHeader/DocumentDateTime FPLEDG.IVDT; APS200MI/GetInvoice	The field indicates the date from which the invoice is valid.
PayableTransaction/PayableTransactionHeader/Description FPLEDG.TDSC; APS200MI/GetInvoice	The field indicates the transaction description from the user-defined accounting options for manual payments. The description allows for a more detailed voucher description.
PayableTransaction/PayableTransactionHeader/Status/Code FPLEDG.Various; APS200MI/GetInvoice	PAID --> Reconciliation code = 9 and Invoice Amount less Paid Amount = 0 and Transaction Code = 50; PARTIAL PAID --> Reconciliation code <> 9 and Paid amount less than Invoice Amount and Transaction Code = 50; VOID --> Reconciliation code = 9 and Payment status = 4 (blocked) and Transaction Code = 40; DISPUTE --> Payment Stop > 0; PREPAID --> Paid amount greater than Invoice Amount or Transaction Code = 40 and Information type = AP; OPEN --> Reconciliation code = 0 and Payment status = 0 and Payment stop = 0
PayableTransaction/PayableTransactionHeader/SupplierParty/PartyIDs/ID FPLEDG.SUNO; APS200MI/GetInvoice	The field indicates the unique identity of a supplier.
PayableTransaction/PayableTransactionHeader/SupplierParty/PartyIDs/SCACID CIDMAS.FWSC; CRS620MI/GetBasicData	The field indicates Standard Carrier Alpha Code (SCAC). The SCAC is a four-letter alpha code that uniquely identifies a forwarder. SCAC codes are assigned and maintained by the National Motor Freight Traffic Association (NMFTA). The SCAC is printed on the bill of lading documents.
PayableTransaction/PayableTransactionHeader/SupplierParty/Name CIDMAS.SUNM; CRS620MI/GetBasicData	The field indicates supplier name, most often the supplier's company name.
PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/AttentionOfName CIDMAS.SUNM; CRS620MI/GetBasicData	The field indicates supplier name, most often the supplier's company name.
PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/AddressLine CIDMAS.ADR1 to ADR4; CRS620MI/GetAddress	Get address number. Then include the following: Get ADTE = 01 Postal address, if this is blank then get ADTE = 02 Street address
PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/CityName CIDMAS.TOWN; CRS620MI/GetAddress	The field indicates the city in an address. The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.
PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/CountrySubDivisionCode CIDMAS.ECAR; CRS620MI/GetAddress	The field indicates an area, province or state within a country. The information is used for addresses, U.S. sales tax and for trade statistics. When editing addresses, the information is validated when state is used as an address element according to the address formatting rule, used for the country to which the address applies. Address formatting rules are stated for each country.
PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/CountryCode CIDMAS.CSCD; CRS620MI/GetAddress	The field indicates a country. Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/PostalCode CIDMAS.PONO; CRS620MI/GetAddress	The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used.
PayableTransaction/PayableTransactionHeader/SupplierParty/Contact/Communication/UseCode	Constant "Telephone no."
PayableTransaction/PayableTransactionHeader/SupplierParty/Contact/Communication/DialNumber CIDMAS.PHNO or PHN2; CRS620MI/GetBasicData	The field indicates the telephone number of the customer or supplier.
PayableTransaction/PayableTransactionHeader/RemitToParty/PartyIDs/ID FPLEDG.SPIN; APS200MI/GetInvoice	Payee is used.
PayableTransaction/PayableTransactionHeader/RemitToParty/PartyIDs/SCACID CIDMAS.FWSC; CRS620MI/GetBasicData	

PayableTransaction

	The field indicates Standard Carrier Alpha Code (SCAC). The SCAC is a four-letter alpha code that uniquely identifies a forwarder. SCAC codes are assigned and maintained by the National Motor Freight Traffic Association (NMFTA). The SCAC is printed on the bill of lading documents.
PayableTransaction/PayableTransactionHeader/RemitToParty/Name CIDMAS.SUNM; CRS620MI/GetBasicData	The field indicates supplier name, most often the supplier's company name.
PayableTransaction/PayableTransactionHeader/RemitToParty/Location/Address/AttentionOfName CIDMAS.SUNM; CRS620MI/GetBasicData	The field indicates supplier name, most often the supplier's company name.
PayableTransaction/PayableTransactionHeader/RemitToParty/Location/Address/AddressLine CIDMAS.ADR1 to ADR4; CRS620MI/GetAddress	Get address number. Then include the following: Get ADTE = 01 Postal address, if this is blank then get ADTE = 02 Street address
PayableTransaction/PayableTransactionHeader/RemitToParty/Location/Address/CityName CIDMAS.TOWN; CRS620MI/GetAddress	The field indicates the city in an address. The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.
PayableTransaction/PayableTransactionHeader/RemitToParty/Location/Address/CountrySubDivisionCode CIDMAS.ECAR; CRS620MI/GetAddress	The field indicates an area, province or state within a country. The information is used for addresses, U.S. sales tax and for trade statistics. When editing addresses, the information is validated when state is used as an address element according to the address formatting rule, used for the country to which the address applies. Address formatting rules are stated for each country.
PayableTransaction/PayableTransactionHeader/RemitToParty/Location/Address/CountryCode CIDMAS.CSCD; CRS620MI/GetAddress	The field indicates a country. Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
PayableTransaction/PayableTransactionHeader/RemitToParty/Location/Address/PostalCode CIDMAS.PONO; CRS620MI/GetAddress	The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used.
PayableTransaction/PayableTransactionHeader/PayableStyle	If invoice amount is negative then "Credit Memo". If the transaction is applied on On-Account then "Prepaid". If the two conditions are not met, it is "Invoice".
PayableTransaction/PayableTransactionHeader/InvoiceReference/DocumentID/ID FPLEDX.PEXI; APS251MI/LstInvInfo	If MI returns any record from FPLEDX, information category = 416 then use PEXI (original invoice number) else invoice number = SINO; 416 is "splitted AP invoice"
PayableTransaction/PayableTransactionHeader/ExtendedAmount FGLEDG.CUAM - TXCU; APS200MI/GetInvTotInfo @currencyID FGLEDG.CUCD; APS200MI/GetInvTotInfo	Invoice current amount less tax currency amount The field indicates the abbreviation for the invoice currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/ExtendedBaseAmount FGLEDG.ACAM - TXAM; APS200MI/GetInvTotInfo @currencyID FGLEDG.LOCD; APS200MI/GetInvTotInfo	Invoice local amount minus Tax local amount. The field indicates the abbreviation for the invoice local currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/ExtendedLocalAmount FGLEDG.ACAM-TXAM; APS200MI/GetInvTotInfo @currencyID FGLEDG.CUCD; APS200MI/GetInvTotInfo	Invoice local amount minus Tax local amount The field indicates the abbreviation for the company currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/TotalAmount FGLEDG.CUAM; APS200MI/GetInvTotInfo @currencyID FGLEDG.CUCD; APS200MI/GetInvTotInfo	Invoice amount for TRCD = 40 The field indicates the abbreviation for the invoice foreign currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/TotalBaseAmount FGLEDG.ACAM; APS200MI/GetInvTotInfo @currencyID FGLEDG.LOCD; APS200MI/GetInvTotInfo	Invoice local amount for TRCD = 40. The field indicates the abbreviation for the company local currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/TotalLocalAmount FGLEDG.ACAM; APS200MI/GetInvTotInfo @currencyID	Invoice local amount for TRCD = 40

PayableTransaction

FGLEDG.CUCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the company currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/Tax/BasisAmount FGLEDG.TBCU; APS200MI/GetInvTotInfo	Sum of FGLEDG transaction with transaction code = 41 and AT04 > 2
@currencyID FGLEDG.CUCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the invoice currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/Tax/Amount FGLEDG.TXCU; APS200MI/GetInvTotInfo	Summary of FGLEDG transactions with TRCD = 41 and AT04 = 1 or 2
@currencyID FGLEDG.CUCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/DiscountStatus/DiscountAllowedAmount FGLEDG.CDCU; APS200MI/GetInvTotInfo	Cash discount for an invoice payment. Cash discount taken is in foreign currency.
@currencyID FGLEDG.CUCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/DiscountStatus/DiscountAllowedBaseAmount FGLEDG.CDAM; APS200MI/GetInvTotInfo	The field indicates the amount that is the cash discount in the specified currency. Cash discount means that a customer has been granted a certain discount from the invoiced amount if the payment is received within a specified number of days, calculated from the accounting date of the invoice.
@currencyID FGLEDG.LOCU; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the local discount currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/DiscountStatus/DiscountTakenAmount FGLEDG.CDCU; APS200MI/GetInvTotInfo	Cash discount for an invoice payment. Cash discount taken is in foreign currency.
@currencyID FPLEDG.CUCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign invoice currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/DiscountStatus/DiscountTakenBaseAmount FGLEDG.CDAM; APS200MI/GetInvTotInfo	The field indicates the amount that is the cash discount in the specified currency. Cash discount means that a customer has been granted a certain discount from the invoiced amount if the payment is received within a specified number of days, calculated from the accounting date of the invoice.
@currencyID FGLEDG.LOCU; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the local discount currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/PayableAmount FGLEDG.CUAM; APS200MI/GetInvTotInfo	Outstanding foreign amount. This is the amount of an invoice less payments.
@currencyID FGLEDG.CUCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the invoice currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/PayableBaseAmount FGLEDG.ACAM; APS200MI/GetInvTotInfo	Outstanding amount in local currency. This is the amount of an invoice less payments.
@currencyID FGLEDG.LOCU; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the invoice local currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/PaidAmount FGLEDG.PCUA; APS200MI/GetInvTotInfo	Paid foreign amount
@currencyID FGLEDG.CUCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/PaidBaseAmount FGLEDG.PAMT; APS200MI/GetInvTotInfo	Paid amount in local currency
@currencyID FGLEDG.LOCU; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the paid amount in local currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/PaymentMethodCode CSYTAB.PARM; CRS175MI/GetGeneralCode	First payment method AP is read (PYME), then payment type connected to the method (PYTP) is read. If payment class (PYCL) in payment type is: 0 = "Cash"; 1 = "Cheque"; 2 = "Cheque"; 3 = "GIRO"; 4 = "BankDraft"; 5 = "Credit Transfer"; everything else "Cash".

PayableTransaction

PayableTransaction/PayableTransactionHeader/PaymentTerm/Term/ID	
FPLEDG.TEPY; CRS175MI/GetGeneralCode	Payment Term (TEPY))
PayableTransaction/PayableTransactionHeader/PaymentTerm/Term/Description	
CSYTAB.TX40; CRS175MI/GetGeneralCode	The field indicates a description of the current identity.
PayableTransaction/PayableTransactionHeader/PaymentTerm/Term/DueDateTime	
FPLEDG.DUDT; APS200MI/GetInvTotlInfo	The field indicates the date the invoice is due for payment according to payment or cash discount terms.
PayableTransaction/PayableTransactionHeader/PaymentTerm/Discount/ID	
FPCASH.CDP1 + CDP2 + CDP3; APS200MI/GetCashDiscInfo	The field indicates the cash discount as a percentage. Include "%" after field display. Cash discount means that a certain discount from the invoiced amount has been granted if payment is made within a specified number of days, calculated from the accounting date of the invoice.
PayableTransaction/PayableTransactionHeader/PaymentTerm/Discount/Description	
N/A.N/A; CRS175MI/GetGeneralCode	Cash Discount Term (TECD) + "-" + PARM
PayableTransaction/PayableTransactionHeader/PaymentTerm/Discount/EffectiveDateTime	
FPCASH.CDT1 + CDT2 + CDT3; APS200MI/GetCashDiscInfo	The field indicates the date when cash discount is due. The conditions for cash discount can be predefined and connected to a customer in or to a supplier.
PayableTransaction/PayableTransactionHeader/PaymentTerm/Discount/Amount	
FPCASH.CDAM; APS200MI/GetCashDiscInfo	Cash discount - foreign currency
@currencyID	
FPCASH.CUCD; APS200MI/GetCashDiscInfo	The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/PaymentTerm/Discount/BaseAmount	
FPCASH.LDAM; APS200MI/GetCashDiscInfo	Cash discount - local currency (converted from Cash discount - foreign currency)
@currencyID	
FPCASH.LOCD; APS200MI/GetCashDiscInfo	The field indicates the abbreviation for the local currency. The abbreviation should follow ISO standards.

Person

Person/ID

CMNUSR.USID; MNS150MI/GetUserData

The field indicates a unique identity of a user in the M3 system. A new user is created automatically in the operating system as well. If the user is already entered in the operating system, the existing name is used.

This ID must be used when reporting work performed. It is also used as a basis for the Payroll Administration and Time and Attendance modules.

The field indicates the company and division

The field indicates the variation ID

The field indicates list ID

@accountingEntity

CMNUSR.; /

@variationID

@lid

Person/DisplayID

CMNUSR.USID; MNS150MI/GetUserData

The field indicates a unique identity of a user in the M3 system. A new user is created automatically in the operating system as well. If the user is already entered in the operating system, the existing name is used.

This ID must be used when reporting work performed. It is also used as a basis for the Payroll Administration and Time and Attendance modules.

Person/Name

CMNUSR.NAME; MNS150MI/GetUserData

The field indicates the name of the user.

Person/Description

CMNUSR.TX40; MNS150MI/GetUserData

The field indicates the company description

Person/LanguageCode

CSYUSR.LANC
CMNUSR.LANC.; MNS150MI/GetUserData

The field indicates the code for the languages that this installation covers. It is possible to install M3 with several different system languages in the same installation. The system language is connected to each M3 user to define what language should be used. The language will first be retrieved from table CSYUSR, if it does not exist in CSYUSR, it will retrieve it in table CMNUSR

Person/Communication

@preferredIndicator

fixed value = "False"; /

The field is set to false

Person/Communication/ChannelCode

M3 BE field Telephone number 1 has code "Phone"
M3 BE field Telephone number 2 has code "Phone"
M3 BE field Facsimile number has code "Fax"
M3 BE field E-Mail address has code "EMail"

@listID

ListID is set to "Communication Channels"

Person/Communication/UseCode

Currently, M3 BE does not keep information about use code for different communication alternatives.

We do though hardcode UseCodes according to:
M3 BE field Telephone number 1 has UseCode "Office"
M3 BE field Telephone number 2 has UseCode "Office"
M3 BE field Facsimile number has UseCode "Fax"
M3 BE field E-Mail address has UseCode "Office"

@listID

ListID is set to "Communication Use Codes"

Person/Communication/URI

CEMAIL.EMAL
CEAEMP.PHNO
CEAEMP.CAPH.; CRS111M
CRS530MI
CRS530MI/Get
LstEmployee
LstEmployee

The field indicates an e-mail address, telephone number and mobile number for the user/employee entered.

Person/Communication/Preference/Sequence

Incremental value starting with 1.; /

The field indicates the incremental value starting with 1

Person/Communication/Preference/Indicator

Fixed value = "True"; /

The field is set to true

Person/PersonnelReference/ID

CEAEMP.EMNO; CRS530MI/LstEmployee

The field indicates the reference employee number

@accountingEntity

CMNUSR.CONO+DIVI; /

The field indicates the company and division

Person/PersonnelReference/Name

CEAEMP.EMNM; CRS530MI/LstEmployee

The field indicates the reference employee name

Person

Person/Classification

@type	CMNUSR.USTP; MNS150MI/GetUserData	The field indicates which type the user is to be classified as.
--------------	-----------------------------------	---

Person/Status/Code

CMNUSR.USTA; MNS150MI/GetUserData	The field indicates the user status
-----------------------------------	-------------------------------------

ProductionOrder

ProductionOrder/ProductionOrderHeader
@type

Hardcoded to 'Production'.

ProductionOrder/ProductionOrderHeader/DocumentID/ID

The unique keys are combination of Facility (FACI) + Product (PRNO) + Manufacturing order number (MFNO).

MWOHED
MWOHED
MWOHED.VHFACI
VHPRNO
VHMFNO; PMS100MI/Get

@accountingEntity

This attribute indicates the company and division.

MWOHED.VHCONO
MWOHED.VHDIVI.; /

ProductionOrder/ProductionOrderHeader/DisplayID

This field indicates the unique identity for a manufacturing order.

MWOHED.VHMFNO; PMS100MI/Get

ProductionOrder/ProductionOrderHeader/Description

This field indicates the product description.

MWOHED.VHITDS; PMS100MI/Get

ProductionOrder/ProductionOrderHeader/Status/Code

This field indicates the status of the Production order.

MWOHED.VHWHST; PMS100MI/Get

Planned = 10
Firm = (N/A)
Released = 20
Active = 40, 50, 60
Stopped = 25, 26, 45,46, 55, 56, 65, 66
Cancelled = (N/A)
Completed = 80
History = (N/A)
Closed = 90

Note: (N/A) = not available

ProductionOrder/ProductionOrderHeader/OrderBaseUOMQuantity

This field indicates the ordered quantity in the basic unit of measure (U/M).

MWOHED.VHORQT; PMS100MI/Get

@unitCode

This field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.

MWOHED.VHUNMS; MMS200MI/GetItmBasic

ProductionOrder/ProductionOrderHeader/RequiredQuantity

This field indicates the ordered quantity in an alternate unit of measure.

MWOHED.VHORQA; PMS100MI/Get

@unitCode

This field indicates the unit of measure in which the ordered quantity is specified.

MWOHED.VHMAUN; PMS100MI/Get

ProductionOrder/ProductionOrderHeader/ExecutionTimePeriod/StartDateTime

This field indicates the actual start date.

MWOHED.VHRSMT; PMS100MI/Get

ProductionOrder/ProductionOrderHeader/ExecutionTimePeriod/EndDateTime

This field indicates the actual finish date.

MWOHED.VHREFD; PMS100MI/Get

ProductionOrder/ProductionOrderHeader/ForecastedTimePeriod/StartDateTime

This field indicates the date from which this record is valid. (STDT)

MWOHED
MWOHED.VHSTDT
VHMSTI; PMS100MI/Get

This field indicates the time the work order is planned to start. (MSTI)

ProductionOrder/ProductionOrderHeader/ForecastedTimePeriod/EndDateTime

This field indicates the date the balance ID is planned to be available, that is inspected or analyzed. (FIDT)

MWOHED
MWOHED.VHFIDT
VHMFTI; PMS100MI/Get

This field indicates the planned completion time of an operation. (MFTI)

ProductionOrder/ProductionOrderDetail/Sequence

This field indicates the schedule number for an order in a work center.

MWOHED.VHSCHN; PMS100MI/Get

ProductionOrder/Operations/ID

This field indicates an operation number, which forms a unique ID for an operation when combined with a product number.

MWOMAT.VMOPNO; PMS100MI/SelOperations

ProductionOrder/Operations/NextID

This field contains the next operations ID.

MWOMAT.VMOPNO; PMS100MI/SelOperations

ProductionOrder/Operations/Description

This field contains a brief name of what is to be performed. It is entered for each operation.

MWOMAT.VMOPDS; PMS100MI/SelOperations

ProductionOrder/Operations/OutputItem/ItemID/ID

Output item does not exist in M3, thus use the product no from the Production header.

MWOHED.VHPRNO; PMS100MI/Get

ProductionOrder/Operations/OutputItem/Description

This field indicates the name for each item.

MWOMAT.WMITDS; PMS100MI/SelOperations

ProductionOrder/Operations/OutputItem/Type

Hardcoded to "Product"

ProductionOrder

ProductionOrder/Operations/OutputItem/LineNumber	Increment variable
ProductionOrder/Operations/OutputItem/ProducedBaseUOMQuantity MWOOPE.VOQAQT; PMS100MI/SelOperations	This field indicates the manufactured quantity.
@unitCode MITMAS.VHUNMS; MMS200MI/GetItmBasic	This field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
ProductionOrder/Operations/OutputItem/OrderBaseUOMQuantity MWOOPE.VOORQT; PMS100MI/SelOperations	This field indicates the ordered quantity in the basic unit of measure (U/M).
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	This field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
ProductionOrder/Operations/OutputItem/Rejection/RejectBaseUOMQuantity MWOOPE.VOSCQT; PMS100MI/SelOperations	This field indicates the total scrapped quantity for the order, displayed in the manufacturing U/M.
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	This field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
ProductionOrder/Operations/OutputItem/Costing @rateCode	Hardcode to 'Labor' for UMAT. Hardcode to 'Machine' for UPIT.
@type	Hardcoded to 'Actual'.
ProductionOrder/Operations/OutputItem/PlannedRejectQuantity MWOOPE.VOORQT VOSCPC; PDS100MI/SelOperations/GetOperations	This field indicates the planned scrap quantity. This is calculated using Order quantity and Scrap percentage.
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	This field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.

PulseAlert

PulseAlert/Description CMAILB.CBMSGT; N/A/	This is the alert text. It consists of 2 parts: 1. Hardcoded text "M3 BE application message: " 2. Application message from M3 BE M3 BE application messages are categorized in Ming.le and Activity Deck as "M3BE app msg"
PulseAlert/DistributionPerson/PersonReference/IDs/ID CMAILB.CBREC2; N/A/	This is the user id of the application message receiver in M3 BE.
PulseAlert/DistributionPerson/PersonReference/Name	Deprecated in v 15.3.0.0

PulseNotification

PulseNotification/Description

CMAILB.CBMSGT; N/A/

This is the notification text.
It consists of 2 parts:
1. Hardcoded text "M3 BE application message: "
2. Application message from M3 BE

PulseNotification/DistributionPerson/PersonReference/IDs/ID

CMAILB.CBREC2; N/A/

This is the user id of the application message receiver in M3 BE.

PurchaseOrder

PurchaseOrder/PurchaseOrderHeader/DocumentID/ID

MPHEAD.IAPUNO; PPS200MI/GetHead

The field indicates the unique number that is assigned to a purchase order when it is created.

@accountingEntity

.CONO+DIVI; -/

Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity.
To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID.
E.g. m3be.orbit1412_330

@location

MPHEAD.IAWHLO; PPS200MI/GetHead

The field indicates the warehouse.

PurchaseOrder/PurchaseOrderHeader/DocumentID/RevisionID

MPLINE.IBREVN; PPS200MI/GetHead

The field indicates a revision.
By using the revision number, it is possible to ascertain which purchase order lines are connected to a certain revision by updating them with the revision number.

PurchaseOrder/PurchaseOrderHeader/DisplayID

MPHEAD.IAPUNO; PPS200MI/GetHead

The field indicates the unique number that is assigned to a purchase order when it is created.

PurchaseOrder/PurchaseOrderHeader/DocumentDateTime

MPHEAD.IAPUDT; PPS200MI/GetHead

The field indicates when the purchase order was placed.

PurchaseOrder/PurchaseOrderHeader/Note

MSYTXH.THTX40; PPS200MI/LstHeadTxt

The field indicates the notes or remarks.

PurchaseOrder/PurchaseOrderHeader/Status/Code

MPHEAD.IAPUSL; PPS200MI/GetHead

The field indicates the lowest or highest status.

PurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerContact/Name

CMNUSR.JUTX40; MNS150MI/GetUserData

The field indicates a description of the current identity.

PurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerContact/Communication/URI

CEMAIL.CBEMAL; CRS111MI/Get

The field indicates an e-mail address for the user/employee entered.

PurchaseOrder/PurchaseOrderHeader/SupplierParty/PartyIDs/ID

MPHEAD.IASUNO; PPS200MI/GetHead

The field indicates the unique identity of a supplier.

@accountingEntity

.CONO+DIVI; -/

Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity.
To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID.
E.g. m3be.orbit1412_330

PurchaseOrder/PurchaseOrderHeader/SupplierParty/Name

CIDMAS.IDSUNM; PPS200MI/GetAddresses

The field indicates the unique identity of a supplier.

PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address/AddressLine

MPPOAD.ADADR1,
ADADR2,
ADADR3,
ADADR4; PPS200MI/GetAddresses

The field indicates an address line

PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address/CityName

MPPOAD.ADTOWN; PPS200MI/GetAddresses

The field indicates the city in an address.

PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address/CountryCode

MPPOAD.ADCSCD; PPS200MI/GetAddresses

The field indicates a country.

PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address/PostalCode

MPPOAD.ADPONO; PPS200MI/GetAddresses

The field indicates a postal code for a specific address.

PurchaseOrder/PurchaseOrderHeader/ShipToParty/PartyIDs/ID

MPPOAD.ADADK2; PPS200MI/GetAddresses

The field indicates the address type.

@accountingEntity

.CONO+DIVI; -/

Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity.
To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID.
E.g. m3be.orbit1412_330

PurchaseOrder/PurchaseOrderHeader/ShipToParty/Name

MPPOAD.ADCONM; PPS200MI/GetAddresses

The field indicates the name of the company.

PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/ID

MPPOAD.ADADK2; PPS200MI/GetAddresses

The field indicates the address type.

PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/AddressLine

MPPOAD.ADADR1,
ADADR2,
ADADR3,
ADADR4; PPS200MI/GetAddresses

The field indicates an address line

PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/CityName

MPPOAD.ADTOWN; PPS200MI/GetAddresses

The field indicates the city in an address.

PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/CountryCode

PurchaseOrder

MPPOAD.ADCSCD; PPS200MI/GetAddresses	The field indicates a country.
PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/PostalCode	
MPPOAD.ADPONO; PPS200MI/GetAddresses	The field indicates a postal code for a specific address.
PurchaseOrder/PurchaseOrderHeader/ShipFromParty/PartyIDs/ID	
MPHEAD.IASUNO; PPS200MI/GetHead	The field indicates the unique identity of a supplier.
@accountingEntity	
.CONO+DIVI; -/	Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity. To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID. E.g. m3be.orbit1412_330
PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/AddressLine	
MPPOAD.ADADR1, ADADR2, ADADR3, ADADR4; PPS200MI/GetAddresses	The field indicates an address line
PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/CityName	
MPPOAD.ADTOWN; PPS200MI/GetAddresses	The field indicates the city in an address.
PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/CountryCode	
MPPOAD.ADCSCD; PPS200MI/GetAddresses	The field indicates a country.
PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/PostalCode	
MPPOAD.ADPONO; PPS200MI/GetAddresses	The field indicates a postal code for a specific address.
PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Contact/Communication/URI	
CIDREF.IREMAL; CRS620MI/LstSupplierRef	The field indicates an e-mail address for the contact
PurchaseOrder/PurchaseOrderHeader/ContractReference/DocumentID/ID	
MPHEAD.IAOURR; PPS200MI/GetHead	The field indicates the contract/agreement number
PurchaseOrder/PurchaseOrderHeader/ExtendedAmount	
MPHEAD.IACOAM; PPS200MI/GetHead	The field indicates Net amount
@currencyID	
MPHEAD.IACUCD; PPS200MI/GetHead	The field indicates currency used.
PurchaseOrder/PurchaseOrderHeader/BillToParty/Name	
MPPOAD.ADCONM; PPS200MI/GetAddresses	The field indicates the invoice receiver name.
PurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Address/AddressLine	
MPPOAD.ADADR1, ADADR2, ADADR3, ADADR4; PPS200MI/GetAddresses	The field indicates the invoice receiver address.
PurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Address/CityName	
MPPOAD.ADTOW; PPS200MI/GetAddresses	The field indicates the invoice receiver city.
PurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Address/CountryCode	
MPPOAD.ADCSCD; PPS200MI/GetAddresses	The field indicates the invoice receiver country code.
PurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Address/PostalCode	
MPPOAD.ADPONO; PPS200MI/GetAddresses	The field indicates the invoice receiver postal code.
PurchaseOrder/PurchaseOrderHeader/TransportationTerm/IncotermsCode	
MPHEAD.IATEDL; PPS200MI/GetHead	The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
@listID	
.; -/	The field indicates the list ID
PurchaseOrder/PurchaseOrderHeader/TransportationTerm/FreightTermCode	
MPHEAD.IATEAF; PPS200MI/GetHead	The field indicates the freight terms which apply for the delivered goods.
PurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/ID	
MPHEAD.IATEPY; PPS200MI/GetHead	The field indicates how the due date is to be calculated.
PurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/Description	
CSYTAB.CTPARM; PPS200MI/GetHead	The field indicates the description of the payment term.
PurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/Amount	
MPHEAD.IACOAM; PPS200MI/GetHead	The field indicates the total order cost for the purchase order.
@currencyID	
MPHEAD.IACUCD; PPS200MI/GetHead	The field indicates the currency.
PurchaseOrder/PurchaseOrderHeader/RequestedShipDateTime	
MPHEAD.IADWDT; PPS200MI/GetHead	The field indicates requested delivery date.
PurchaseOrder/PurchaseOrderHeader/OrderDateTime	
MPHEAD.IAPUDT; PPS200MI/GetHead	The field indicates when the purchase order was placed.
PurchaseOrder/PurchaseOrderHeader/RFQReference/DocumentID/ID	
MPHEAD.IAOURR; PPS200MI/GetHead	The field indicates the reference number that is found on the purchase order lines.
PurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID	
MPHEAD.IAPRSU; PPS200MI/GetHead	The field indicates a valid supplier number for the supplier that should receive the payment. Payee is entered only if the supplier and the payee are not the same legal entity.

PurchaseOrder

@accountingEntity
.CONO+DIVI; -/

Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity.
To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID.
E.g. m3be.orbit1412 330

PurchaseOrder/PurchaseOrderLine/LineNumber
MPLINE.IBPNNLI; PPS200MI/LstLine

The field indicates the sequence number assigned to the purchase order line.

PurchaseOrder/PurchaseOrderLine/Note
MSYTXL.TLTX60; PPS200MI/LstLineTxt

The field indicates the notes or remarks.

PurchaseOrder/PurchaseOrderLine/Status/Code
MPLINE.IBPUST; PPS200MI/LstLine

The field indicates the following status of the Purchase Order line:
15-Open
20-Open
25-Open
31-Open
32-Open
33-Unconfirmed
35-Open
40-Open
45-Open
50-Received
51-Received
60-Received
64-Received
65-Received
69-Received
70-Partially Received
75-Received
80-Invoiced
85-Invoiced
90-Invoiced
99-Cancelled

PurchaseOrder/PurchaseOrderLine/Item/ItemID/ID
MPLINE.IBITNO; PPS200MI/LstLine
@accountingEntity
.CONO+DIVI; -/

The field indicates the item number.

Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity.
To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID.
E.g. m3be.orbit1412 330

PurchaseOrder/PurchaseOrderLine/Item/Description
MPLINE.IBPITT; PPS200MI/LstLine

The field indicates the description of an item in a purchase order.

PurchaseOrder/PurchaseOrderLine/Quantity
MPLINE.IBORQA; PPS200MI/LstLine
@unitCode
MPLINE.IBPUUN; PPS200MI/LstLine

The field indicates the ordered quantity .

The field indicates the unit of measure (U/M) in which the purchase price is expressed.

PurchaseOrder/PurchaseOrderLine/BaseUOMQuantity
MPLINE.IBORQT; PPS200MI/LstLine
@unitCode
MPLINE.IBUNMS; PPS200MI/LstLine

The field indicates the quantity.

The field indicates the unit of measure (U/M) in which the purchase price is expressed.

PurchaseOrder/PurchaseOrderLine/UnitPrice/Amount
MPLINE.IBPUPR; PPS200MI/LstLine
@currencyID
MPHEAD.IACUCD; PPS200MI/GetHead

The field indicates the purchase price.

The field indicates the currency.

PurchaseOrder/PurchaseOrderLine/UnitPrice/BaseAmount
MPLINE.CUPR; PPS200MI/LstLine
@currencyID
MPHEAD.LOCOD; PPS200MI/GetHead

The field indicates the purchase price in local currency

The field indicates the local currency.

PurchaseOrder/PurchaseOrderLine/UnitPrice/PerQuantity
MPLINE.IBPUCD; PPS200MI/LstLine

The field indicates the purchase price quantity. This is specified per item and is the quantity expressed in the purchase price U/M that the purchase price refers to.

@unitCode
MPLINE.IBPUUN; PPS200MI/LstLine

The field indicates the unit of measure (U/M) in which the purchase price is expressed.

PurchaseOrder/PurchaseOrderLine/ExtendedAmount
MPLINE.IBLNAM; PPS200MI/LstLine
@currencyID
MPHEAD.IACUCD; PPS200MI/GetHead

The field indicates the order value for the purchase order line.

The field indicates the currency.

PurchaseOrder

PurchaseOrder/PurchaseOrderLine/ExtendedBaseAmount MPLINE.IBSAAM; PPS200MI/LstLine	The field indicates the order value for the purchase order line.
@currencyID MPLINE.IBLOCD; PPS200MI/LstLine	The field indicates the currency.
PurchaseOrder/PurchaseOrderLine/RequiredDeliveryDateTime MPLINE.IBDWDT+IBTIHM; PPS200MI/LstLine	The field indicates the delivery date that is to be specified for the supplier on the purchase order document.
PurchaseOrder/PurchaseOrderLine/ShipToParty/PartyIDs/ID MPPOAD.ADADK2; PPS200MI/GetDelAddress	The field indicates the address type.
@accountingEntity .CONO+DIVI; -/	Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity. To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID. E.g. m3be.orbit1412_330
PurchaseOrder/PurchaseOrderLine/ShipToParty/Name MPPOAD.ADCONM; PPS200MI/GetDelAddress	The field indicates the name of the company.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/ID MPPOAD.ADADK2; PPS200MI/GetDelAddress	The field indicates the address type.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Address/AddressLine MPPOAD.ADR1, ADR2, ADR3, ADR4; PPS200MI/GetDelAddress	The field indicates an address line
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Address/CityName MPPOAD.ADTOWN; PPS200MI/GetDelAddress	The field indicates the city in an address.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Address/CountryCode MPPOAD.ADCSCD; PPS200MI/GetDelAddress	The field indicates a country.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Address/PostalCode MPPOAD.ADPONO; PPS200MI/GetDelAddress	The field indicates a postal code for a specific address.
PurchaseOrder/PurchaseOrderLine/TransportationTerm/IncotermsCode MPLINE.IBTEDL; PPS200MI/ListLine	The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
@listID ;-/	The field indicates the list ID
PurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT+IBTIHM; PPS200MI/LstLine	The field indicates the confirmed delivery date and time
PurchaseOrder/PurchaseOrderLine/ReceivedQuantity MPLINE.IBRVQA; PPS200MI/LstLine	The field indicates the received quantity
@unitCode MPLINE.IBPUUN; PPS200MI/LstLine	The field indicates the unit of measure of the received quantity
PurchaseOrder/PurchaseOrderLine/ReceivedBaseUOMQuantity MPLINE.IBRVQT; PPS200MI/LstLine	The field indicates the received quantity in basic unit of measure
@unitCode MPLINE.IBUNMS; PPS200MI/LstLine	The field indicates the received quantity basic unit of measure.
PurchaseOrder/PurchaseOrderLine/OpenQuantity MPLINE.IBORQA - IBRVQA; PPS200MI/LstLine	The field indicates the pending quantity.
@unitCode MPLINE.IBPUUN; PPS200MI/LstLine	The field indicates the pending quantity unit of measure..
PurchaseOrder/PurchaseOrderLine/OpenBaseUOMQuantity MPLINE.IBORQT-IBRVQT; PPS200MI/LstLine	The field indicates the pending quantity in basic unit of measure
@unitCode MPLINE.IBUNMS; PPS200MI/LstLine	The field indicates the pending quantity basic unit of measure.
PurchaseOrder/PurchaseOrderLine/SalesOrderReference/DocumentID/ID MPLINE.IBRORN; PPS200MI/LstLine	The field indicates the sales order number.
PurchaseOrder/PurchaseOrderLine/SalesOrderReference/LineNumber MPLINE.IBRORL; PPS200MI/LstLine	The field indicates a sales order line.
PurchaseOrder/PurchaseOrderLine/SalesOrderReference/BaseUOMQuantity OOLINE.OBORQA; OIS100MI/GetLine	The field indicates the sales quantity.
@unitCode OOLINE.OBALUN; OIS100MI/GetLine	The field indicates the sales quantity unit of measure.
PurchaseOrder/PurchaseOrderLine/BuyerParty/PartyIDs/ID MPLINE.IBBUYE; PPS200MI/LstLine	The field indicates the buyer normally responsible for purchasing.
@accountingEntity .CONO+DIVI; -/	Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity. To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID. E.g. m3be.orbit1412_330
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/LineNumber	

PurchaseOrder

MPLINE.IBPNLS; PPS200MI/LstLine	The field indicates the number of the subline.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Item/ItemID/ID	
MPLINE.IBITNO; PPS200MI/LstLine	The field indicates the item number.
@accountingEntity	
.CONO+DIVI; -/	Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity. To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID. E.g. m3be.orbit1412_330
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Item/Description	
MPLINE.IBPITT; PPS200MI/LstLine	The field indicates the description of an item in a purchase order.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Quantity	
MPLINE.IBORQA; PPS200MI/LstLine	The field indicates the ordered quantity.
@unitCode	
MPLINE.IBPUUN; PPS200MI/LstLine	The field indicates the unit of measure (U/M) in which the quantity on the purchase order is expressed.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/BaseUOMQuantity	
MPLINE.IBORQT; PPS200MI/LstLine	The field indicates the ordered quantity in basic unit of measure
@unitCode	
MPLINE.IBUNMS; PPS200MI/LstLine	The field indicates the basic unit of measure
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/ParentLineNumber	
MPLINE.IBPNLI; PPS200MI/LstLine	The field indicates the sequence number assigned to the purchase order line.
PurchaseOrder/PurchaseOrderLine/ContractReference/DocumentID/ID	
MPLINE.IBOURR; PPS200MI/LstLine	The field indicates the agreement number.
PurchaseOrder/PurchaseOrderLine/SupplierParty/PartyIDs/ID	
MPLINE.IBSUNO; PPS200MI/LstLine	The field indicates the unique identity of a supplier.
@accountingEntity	
.CONO+DIVI; -/	Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity. To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID. E.g. m3be.orbit1412_330
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/AddressLine	
MPPOAD.ADADR1, ADADR2, ADADR3, ADADR4; PPS200MI/GetAddresses	The field indicates an address line
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/CityName	
MPPOAD.ADTOWN; PPS200MI/GetAddresses	The field indicates the city in an address.
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/CountryCode	
MPPOAD.ADCSCD; PPS200MI/GetAddresses	The field indicates a country.
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/PostalCode	
MPPOAD.ADPONO; PPS200MI/GetAddresses	The field indicates a postal code for a specific address.
PurchaseOrder/PurchaseOrderLine/ShipFromParty/PartyIDs/ID	
MPLINE.IBSUNO; PPS200MI/LstLine	The field indicates the unique identity of a supplier.
@accountingEntity	
.CONO+DIVI; -/	Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity. To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID. E.g. m3be.orbit1412_330
PurchaseOrder/PurchaseOrderLine/ShipFromParty/Location/Address/AddressLine	
MPPOAD.ADADR1, ADADR2, ADADR3, ADADR4; PPS200MI/GetAddresses	The field indicates an address line
PurchaseOrder/PurchaseOrderLine/ShipFromParty/Location/Address/CityName	
MPPOAD.ADTOWN; PPS200MI/GetAddresses	The field indicates the city in an address.
PurchaseOrder/PurchaseOrderLine/ShipFromParty/Location/Address/CountryCode	
MPPOAD.ADCSCD; PPS200MI/GetAddresses	The field indicates a country.
PurchaseOrder/PurchaseOrderLine/ShipFromParty/Location/Address/PostalCode	
MPPOAD.ADPONO; PPS200MI/GetAddresses	The field indicates a postal code for a specific address.
PurchaseOrder/PurchaseOrderLine/ProductionOrderReference/DocumentID/ID	
MPLINE.IBRORN; PPS200MI/LstLine	The field indicates the manufacturing order number.

Quote

Quote/QuoteHeader/DocumentID/ID

OOQUOH.OFORNO; OIS100MI/GetQuot

The field indicates a unique identity for a customer order.

Different order number series can be used, which are controlled by an assigned order type. Number series are connected to an order type

@accountingEntity

OOQUOH.QFCONO
OOQUOH.QFDIVI.; /

The field indicates the company and division.

@variationID

The field indicates the sequence number that identifies the number of times that the BOD, for this object has been published.

@lid

The field indicates the logical ID of the system.

Quote/QuoteHeader/Status/Code

OOQUOH.QFSTAT; OIS100MI/GetQuot

The field indicates the status.

10 - Open
20 - Open
30 - Lost
40 - Open
50 - Open
60 - Awarded
90 - Deleted

Quote/QuoteHeader/CustomerParty/PartyIDs/ID

OOQUOH.OFCUNO; OIS100MI/GetQuot

The field indicates the customer.

Quote/QuoteHeader/CustomerParty/Name

OCUSMA.OKCUNM; CRS610MI/GetBasicData

The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.

Quote/QuoteHeader/CustomerParty/Location/Address/AddressLine

OCUSMA.OKCUA1
OCUSMA.OKCUA2
OCUSMA.OKCUA3
OCUSMA.OKCUA4.; CRS610MI/GetBasicData

The field indicates an address line. A maximum of 36 characters may be used.

@sequence

The field indicates the address line sequence number.

Quote/QuoteHeader/CustomerParty/Location/Address/CityName

OCUSMA.OKTOWN; CRS610MI/GetBasicData

The field indicates the city in an address. The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.

Quote/QuoteHeader/CustomerParty/Location/Address/CountrySubDivisionCode

OCUSMA.OKECAR; CRS610MI/GetBasicData

The field indicates an area, province or state within a country. The information is used for addresses, U.S. sales tax and for trade statistics.

When editing addresses, the information is validated when state is used as an address element according to the address formatting rule, used for the country to which the address applies. Address formatting rules are stated for each country.

@listID

N/A.; MRS001MI/GetFieldInfo

The field indicates the list ID.

Quote/QuoteHeader/CustomerParty/Location/Address/CountryCode

OCUSMA.OKCSCD; CRS610MI/GetBasicData

The field indicates a country.

Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.

@listID

N/A.; MRS001MI/GetFieldInfo

The field indicates the list ID.

Quote/QuoteHeader/CustomerParty/Location/Address/PostalCode

OCUSMA.OKPONO; CRS610MI/GetBasicData

The field indicates a postal code for a specific address.

The postal code is an address element that can be part of an address line if address formatting rules are used.

Quote/QuoteHeader/SupplierParty/Location

OOHEAD.OAWHLO; OIS100MI/GetHead

The field indicates the warehouse.

Quote/QuoteHeader/ShipToParty/PartyIDs/ID

OOHEAD.OADEC
OOHEAD.OAADID.
; OIS100MI
OIS100MI/GetAddress
GetHead

The field indicates the ship to party. If Address ID (ADID) is blank in the order header, ShipToPartyID = DECU else ShipToPartyID = DECU+ADID. DECU and ADID will be concatenated without separator. DECU has exactly 10 characters while ADID can have maximum of 6.

@accountingEntity

OOQUOH.OFCONO
OOQUOH.QFDIVI.; /

This field indicates the company and division.

Quote

Quote/QuoteHeader/ShipToParty/Name OOADRE.ODCUNM; OIS100MI/GetAddress	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
Quote/QuoteHeader/ShipToParty/Location/Address/AddressLine OOADRE.ODCUA1 OOADRE.ODCUA2 OOADRE.ODCUA3 OOADRE.ODCUA4.; OIS100MI/GetAddress @sequence	The field indicates an address line. A maximum of 36 characters may be used. This field indicates the address line sequence number.
Quote/QuoteHeader/ShipToParty/Location/Address/CityName OOADRE.ODTOWN; OIS100MI/GetAddress	The field indicates the city in an address. The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.
Quote/QuoteHeader/ShipToParty/Location/Address/CountrySubDivisionCode OOADRE.ODECAR; OIS100MI/GetAddress	The field indicates an area, province or state within a country. The information is used for addresses, U.S. sales tax and for trade statistics. When editing addresses, the information is validated when state is used as an address element according to the address formatting rule, used for the country to which the address applies. Address formatting rules are stated for each country.
@listID N/A.; MRS001MI/GetFieldInfo	The field indicates the list ID.
Quote/QuoteHeader/ShipToParty/Location/Address/CountryCode OOADRE.ODCSCD; OIS100MI/GetAddress	The field indicates a country. Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
@listID N/A.; MRS001MI/GetFieldInfo	The field indicates the list ID.
Quote/QuoteHeader/ShipToParty/Location/Address/PostalCode OOADRE.ODPONO; OIS100MI/GetAddress	The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used.
Quote/QuoteHeader/ExtendedAmount OOHEAD.OANTAM; OIS100MI/GetHead	The field indicates the net order value, including any discounts, expressed in the domestic currency. No charges is included in the amount.
@currencyID OOHEAD.OACUCD; OIS100MI/GetHead	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
Quote/QuoteHeader/TotalAmount OOHEAD.OATOPY; OIS100MI/GetOrderValue @currencyID OOHEAD.OACUCD; OIS100MI/GetHead	The field indicates the total amount. The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
Quote/QuoteHeader/PayFromParty/PartyIDs/ID OOHEAD.OAPYNO; OIS100MI/GetHead	The field indicates the person/business who has paid or will pay the invoice. The payer is specified when an invoice should be sent somewhere other than to the customer placing the order. For order and sales statistics, the payer is used as a statistic ID. For total statistics, the payer is one of the key IDs.
@accountingEntity OOQUOH.OFCONO OOQUOH.QFDIVI.; /	The field indicates the company and division.
Quote/QuoteHeader/TransportationTerm/IncotermsCode OOHEAD.OATEDL; OIS100MI/GetHead	The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
Quote/QuoteHeader/RFQReference/DocumentID/ID OOHEAD.OAOFNO; OIS100MI/GetHead	The field indicates a reference to the quotation number belonging to a customer order, service order or agreement.
Quote/QuoteHeader/EffectiveTimePeriod/EndDateTime OOQUOH.QFGIDT; OIS100MI/GetQuot	The field indicates how long a quotation is valid.
Quote/QuoteHeader/ExpectedDeliveryDate OOHEAD.OARLDZ; OIS100MI/GetHead	

Quote

	<p>The field indicates the date the customer wants the delivery to arrive at the final destination.</p> <p>The information is expressed in the time zone of the unloading location at the final destination.</p> <p>If the loading and unloading locations are in different time zones, this date can be different from what applies for the local time zone.</p>
Quote/QuoteHeader/SalesPersonReference/IDs/ID OOHEAD.OASMCD; OIS100MI/GetHead	<p>The field indicates the person responsible for sales to a customer.</p> <p>The salesperson can be used as a statistical category in order entry and for sales statistics.</p> <p>During customer order entry, the salesperson from the customer file is defaulted but can be changed.</p>
Quote/QuoteLine/LineNumber OOHEAD.OAPONR; OIS100MI/LstLine	<p>The field indicates the line number, defining each line in a customer order. A line number is assigned automatically when entering order lines.</p>
Quote/QuoteLine/Status/Code OOQUOH.QFSTAT; OIS100MI/GetQuot	<p>The field indicates the highest line status among the customer order lines.</p> <p>The lowest status in the order header shows the lowest line status among the order lines.</p> <p>10 - Open 20 - Open 30 - Lost 40 - Open 50 - Open 60 - Awarded 90 - Deleted</p>
Quote/QuoteLine/Item/ItemID/ID OOLINE.OBITNO; OIS100MI/LstLine	<p>The field indicates the item number (for Maintenance, the item number or equipment number), which is a unique ID for an individual item.</p>
@accountingEntity OOQUOH.OFCONO OOQUOH.OFDIVI.; /	<p>The field indicates the company and division.</p>
Quote/QuoteLine/Item/Description OOLINE.OBITDS; OIS100MI/LstLine	<p>The field indicates the name for each item.</p>
Quote/QuoteLine/Quantity OOLINE.OBORQA; OIS100MI/LstLine	<p>The field indicates the ordered quantity in an alternate unit of measure.</p>
@unitCode OOLINE.OBALUN; OIS100MI/LstLine	<p>The field indicates an alternate unit of measure (U/M) for the basic U/M for an item. An unlimited number of alternate U/Ms may be defined for each item.</p>
Quote/QuoteLine/UnitPrice/Amount OOLINE.OBSAPR; OIS100MI/LstLine	<p>The field indicates the sales price for each sales price quantity.</p> <p>If no value is specified in the sales price quantity, the sales price per unit applies.</p> <p>The sales price per unit is calculated as: Price per unit= Sales price/ Sales price quantity.</p>
@currencyID OOLINE.OBCUCD; OIS100MI/LstLine	<p>The field indicates the abbreviation for the currency.</p>
Quote/QuoteLine/UnitPrice/PerQuantity OOLINE.OBSACD; OIS100MI/LstLine	<p>The field indicates the quantity to which the sales price applies. Sales price quantity is defined for each item and is expressed in the item unit of measure.</p>
@unitCode OOLINE.OBSPUN; OIS100MI/LstLine	<p>The field indicates the sales price U/M. This is the U/M on which the item's price is based. Every item has a standard sales price U/M specified. However, order lines can be entered using a different U/M.</p>
Quote/QuoteLine/ExtendedAmount OOLINE.OBNLAM; OIS100MI/LstLine	<p>The field indicates the net amount for an invoice line.</p>
@currencyID OOLINE.OBCUCD; OIS100MI/LstLine	<p>The field indicates the abbreviation for the currency.</p>
Quote/QuoteLine/PromisedDeliveryDateTime OOLINE.OBCODT OOLINE.OBCOHM.; OIS100MI/LstLine	<p>The field indicates the confirmed delivery date and time.</p>

ReceivableTransaction

ReceivableTransaction/ReceivableTransactionHeader/DocumentID/ID FSLEDG.YEA4+JRNO+JSNO; ARS200MI/GetInvTotInfo @accountingEntity FSLEDG.DIVI; ARS200MI/GetInvTotInfo	Unique key in FSLEDG The field indicates a division. This is an identity for a legal unit within a company group. Division is a key value in the financial system in M3. One division may consist of several facilities. Facilities are used in material and production management and for purchasing purposes.
@location	An attribute of the location ID used.
@lid	An information with ://infor.m3be.orbit1412 330.
ReceivableTransaction/ReceivableTransactionHeader/AlternateDocumentID/ID FSLEDG.CUNO+PYNO+CINO+INYS; ARS200MI/GetInvTotInfo	Alternate key in FSLEDG
ReceivableTransaction/ReceivableTransactionHeader/DocumentDateTime FSLEDG.RGDT + RGTM; ARS200MI/GetInvTotInfo	The field indicates the date and time that the object was created. This date and time is set automatically.
ReceivableTransaction/ReceivableTransactionHeader/Description FSLEDG.TDSC; ARS200MI/GetInvTotInfo	Transaction description from the invoice record in FSLEDG
ReceivableTransaction/ReceivableTransactionHeader/Status/Code FSLEDG.Variou; ARS200MI/GetInvTotInfo	If reconciliation code = 9 then status is set to "Paid". If paid amount > invoice amount then status is set to "UnappliedCash". If paid amount < invoice amount and reconciliation code < 9 then status is set to "PartialPaid". If all amounts is 0 then status is set to "Void". If a stop date (BLDT) is set then status = "Dispute". For all other conditions status is set to "Open".
ReceivableTransaction/ReceivableTransactionHeader/CustomerParty/PartyIDs/ID FSLEDG.CUNO; ARS200MI/GetInvTotInfo	The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric. For temporary customers (customer type 9), the customer number must be within a defined range where only customers with customer type 9 can be entered.
ReceivableTransaction/ReceivableTransactionHeader/CustomerParty/Name OCUSMA.CUNM; CRS610MI/GetBasicData	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
ReceivableTransaction/ReceivableTransactionHeader/CustomerParty/Location/Address/AttentionOfName OCUSMA.CUNM; CRS610MI/GetBasicData	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
ReceivableTransaction/ReceivableTransactionHeader/CustomerParty/Location/Address/AddressLine OCUSMA.CUA1-4; CRS610MI/GetBasicData	The field indicates an address line. A maximum of 36 characters may be used.
@sequence N/A.N/A; CRS610MI/GetBasicData	The sequence number of an address.
ReceivableTransaction/ReceivableTransactionHeader/CustomerParty/Location/Address/CityName OCUSMA.TOWN; CRS610MI/GetBasicData	The field indicates the city in an address. The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.
ReceivableTransaction/ReceivableTransactionHeader/CustomerParty/Location/Address/CountrySubDivisionCode OCUSMA.ECAR; CRS610MI/GetBasicData	The field indicates an area, province or state within a country. The information is used for addresses, U.S. sales tax and for trade statistics. When editing addresses, the information is validated when state is used as an address element according to the address formatting rule, used for the country to which the address applies. Address formatting rules are stated for each country.
@listID	Constant "State"
ReceivableTransaction/ReceivableTransactionHeader/CustomerParty/Location/Address/CountryCode OCUSMA.CSCD; CRS610MI/GetBasicData	The field indicates a country. Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
ReceivableTransaction/ReceivableTransactionHeader/CustomerParty/Location/Address/PostalCode OCUSMA.PONO; CRS610MI/GetBasicData	The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used.
@listID	

ReceivableTransaction

	Constant "Postal code"
ReceivableTransaction/ReceivableTransactionHeader/BillToParty/PartyIDs/ID FSLEDG.PYNO; ARS200MI/GetInvTotInfo	BillTo is not available in Accounts Receivable, Payer is used
ReceivableTransaction/ReceivableTransactionHeader/BillToParty/Location/Address/AttentionOfName OCUSMA.CUNM; CRS610MI/GetBasicData	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
ReceivableTransaction/ReceivableTransactionHeader/BillToParty/Location/Address/AddressLine OCUSMA.CUA1-4; CRS610MI/GetBasicData	The field indicates an address line. A maximum of 36 characters may be used.
@sequence	Incrementing number of an address field "1", "2", "3", and "4"
ReceivableTransaction/ReceivableTransactionHeader/BillToParty/Location/Address/CityName OCUSMA.TOWN; CRS610MI/GetBasicData	The field indicates the city in an address. The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.
ReceivableTransaction/ReceivableTransactionHeader/BillToParty/Location/Address/CountrySubDivisionCode OCUSMA.ECAR; CRS610MI/GetBasicData	The field indicates an area, province or state within a country. The information is used for addresses, U.S. sales tax and for trade statistics. When editing addresses, the information is validated when state is used as an address element according to the address formatting rule, used for the country to which the address applies. Address formatting rules are stated for each country.
ReceivableTransaction/ReceivableTransactionHeader/BillToParty/Location/Address/CountryCode OCUSMA.CSCD; CRS610MI/GetBasicData	The field indicates a country. Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
ReceivableTransaction/ReceivableTransactionHeader/BillToParty/Location/Address/PostalCode OCUSMA.PONO; CRS610MI/GetBasicData	The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used.
ReceivableTransaction/ReceivableTransactionHeader/PayFromParty/PartyIDs/ID FSLEDG.PYNO; ARS200MI/GetInvTotInfo	The field indicates the person/business who has paid or will pay the invoice. The payer is specified when an invoice should be sent somewhere other than to the customer placing the order. For order and sales statistics, the payer is used as a statistic ID. For total statistics, the payer is one of the key IDs.
ReceivableTransaction/ReceivableTransactionHeader/PayFromParty/Location/Address/AttentionOfName OCUSMA.CUNM; CRS610MI/GetBasicData	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
ReceivableTransaction/ReceivableTransactionHeader/PayFromParty/Location/Address/AddressLine OCUSMA.CUA1-4; CRS610MI/GetBasicData	The field indicates an address line. A maximum of 36 characters may be used.
@sequence	Incrementing number of an address field "1", "2", "3", and "4"
ReceivableTransaction/ReceivableTransactionHeader/PayFromParty/Location/Address/CityName OCUSMA.TOWN; CRS610MI/GetBasicData	The field indicates the city in an address. The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.
ReceivableTransaction/ReceivableTransactionHeader/PayFromParty/Location/Address/CountrySubDivisionCode OCUSMA.ECAR; CRS610MI/GetBasicData	The field indicates an area, province or state within a country. The information is used for addresses, U.S. sales tax and for trade statistics. When editing addresses, the information is validated when state is used as an address element according to the address formatting rule, used for the country to which the address applies. Address formatting rules are stated for each country.
ReceivableTransaction/ReceivableTransactionHeader/PayFromParty/Location/Address/CountryCode OCUSMA.CSCD; CRS610MI/GetBasicData	The field indicates a country. Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
ReceivableTransaction/ReceivableTransactionHeader/PayFromParty/Location/Address/PostalCode	

ReceivableTransaction

OCUSMA.PONO; CRS610MI/GetBasicData	The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Term/ID CSYTAB.STKY; CRS175MI/GetGeneralCode	The field indicates a key value, which is a value included in the group of items displayed in this panel. The type of value entered is determined by what is entered in the 'Key type' field.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Term/Description CSYTAB.PARM; CRS175MI/GetGeneralCode	First 72 characters of PARM
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Term/DueDateTime FSLEDG.DUDT; ARS200MI/GetInvTotInfo	The field indicates the date the invoice is due for payment according to payment or cash discount terms.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Discount FPCASH.TECD; ARS200MI/GetCashDisclInfo	The field indicates the cash discount as a percentage. Cash discount means that a certain discount from the invoiced amount has been granted if payment is made within a specified number of days, calculated from the accounting date of the invoice.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Discount/ID FPCASH.CDP1 + CDP2 + CDP3; ARS200MI/GetCashDisclInfo	The field indicates the cash discount as a percentage. Cash discount means that a certain discount from the invoiced amount has been granted if payment is made within a specified number of days, calculated from the accounting date of the invoice.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Discount/Description	Display: If CDP1 then "Cash discount 1"; If CDP2 then "Cash discount 2"; If CDP3 then "Cash discount 3";
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Discount/EffectiveDateTime FPCASH.CDT1 + CDT2 + CDT3; ARS200MI/GetCashDisclInfo	The field indicates the date when cash discount is due. The conditions for cash discount can be predefined and connected to a customer in or to a supplier.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Discount/Amount FPCASH.CDAM; ARS200MI/GetCashDisclInfo @currencyID FPCASH.CUCD; ARS200MI/GetCashDisclInfo	Cash discount - foreign currency The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Discount/BaseAmount FPCASH.LDAM; ARS200MI/GetCashDisclInfo @currencyID FPCASH.LOCD; ARS200MI/GetCashDisclInfo	Cash discount - local currency (converted from Cash discount - foreign currency) The field indicates the abbreviation for the local currency. The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/ReceivableStyle FSLEDG.SLOP; ARS200MI/GetInvTotInfo	If SLOP = 12 then ReceivableStyle = "CreditMemeo" If SLOP = 16 then ReceivableStyle = "DebitMemo" If SLOP > 18 > 99 then ReceivableStyle = "Miscellaneous" For all other SLOP ReceivableStyle = "Invoice"
ReceivableTransaction/ReceivableTransactionHeader/ReceivableStyleCategory FSLEDG.TRCD; ARS200MI/ GetInvoice	If TRCD = 10 then ReceivableStyleCategory = "I" If TRCD = 20 then ReceivableStyleCategory = "P"
ReceivableTransaction/ReceivableTransactionHeader/InvoiceReference/DocumentID/ID FSLEDX.SEXI; ARS251MI/LstInvInfo	If the MI returns any records from FSLEDX, infor category = 228 then use SEXI (original invoice number) else invoice number = CINO
ReceivableTransaction/ReceivableTransactionHeader/ExtendedAmount FSLEDG/FGLEDG.CUAM; ARS200MI/GetInvTotInfo @currencyID FSLEDG.CUCD; ARS200MI/GetInvTotInfo	Invoice currency amount minus tax currency amount The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/ExtendedLocalAmount FSLEDG/FGLEDG.ACAM; ARS200MI/GetInvTotInfo @currencyID FSLEDG.LOCD; ARS200MI/GetInvTotInfo	Invoice local amount minus tax local amount The field indicates the abbreviation for the local currency. The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/TotalAmount FSLEDG.CUAM; ARS200MI/GetInvTotInfo @currencyID FSLEDG.CUCD; ARS200MI/GetInvTotInfo	Invoice foreign amount The field indicates the abbreviation for the invoice foreign currency. The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/TotalBaseAmount FSLEDG.ACAM; ARS200MI/GetInvTotInfo @currencyID FSLEDG.LOCD; ARS200MI/GetInvTotInfo	Invoice local amount. The field indicates the abbreviation for the invoice local currency. The abbreviation should follow ISO standards.

ReceivableTransaction

ReceivableTransaction/ReceivableTransactionHeader/TotalLocalAmount

FGLEDG.ACAM; ARS200MI/GetInvTotInfo

Invoice local amount

@currencyID

FSLEDG.LOCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the invoice local currency. The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/Tax/BasisAmount

FGLEDG.CUAM; ARS200MI/GetInvTotInfo

Sum of FGLEDG transactions with TRCD = 11 and AT04 > 2

@currencyID

FSLEDG.CUCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the invoice foreign currency. The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/Tax/Amount

FGLEDG.CUAM; ARS200MI/GetInvTotInfo

Sum of FGLEDG transactions with TRCD = 11 and AT04 = 1 or 2

@currencyID

FSLEDG.CUCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountAllowedAmount

FGLEDG.CDCU; ARS200MI/GetInvTotInfo

Cash discount for an invoice payment. Cash discount taken is in foreign currency.

@currencyID

FSLEDG.CUCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the invoice foreign currency. The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountAllowedBaseAmount

FGLEDG.CDAM; ARS200MI/GetInvTotInfo

The field indicates the amount that is the cash discount in the specified currency.

Cash discount means that a customer has been granted a certain discount from the invoiced amount if the payment is received within a specified number of days, calculated from the accounting date of the invoice.

@currencyID

FSLEDG.LOCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the invoice local currency. The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountTakenAmount

FSLEDG.CDCU; ARS200MI/GetInvTotInfo

The split payment parameter on the payment FAM function (AR30) needs to be set to "several AR payments" (WWSPAR = 1) or else cash discounts cannot be detected. Sum of FSLEDG record with TRCD = 20 and SLOP = 18

@currencyID

FSLEDG.CUCD; ARS200MI/GetInvTotInfo

The split payment parameter on the payment FAM function (AR30) needs to be set to "several AR payments" or else cash discounts cannot be detected

ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountTakenBaseAmount

FSLEDG.CDAM; ARS200MI/GetInvTotInfo

The field indicates the amount that is the cash discount in the specified currency.

Cash discount means that a customer has been granted a certain discount from the invoiced amount if the payment is received within a specified number of days, calculated from the accounting date of the invoice.

@currencyID

FSLEDG.LOCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the invoice local currency. The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/ReceivableAmount

FSLEDG.CUAM; ARS200MI/GetInvTotInfo

Outstanding foreign currency amount.

@currencyID

FSLEDG.CUCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/ReceivableBaseAmount

FSLEDG.ACAM; ARS200MI/GetInvTotInfo

The field indicates the amount in the local currency. It is the local currency used by the company to which all transactions are converted in the General Ledger.

@currencyID

FSLEDG.LOCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the invoice local currency. The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/ReceivedAmount

FGLEDG.CUAM; ARS200MI/GetInvTotInfo

Paid amount

@currencyID

FSLEDG.CUCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/PaymentMethodCode

CSYTAB.PARM; CRS175MI/GetGeneralCode

First Payment method AR is read (STKY = PYCD), then the payment type connected to the method is read. If Payment class in payment type is:
0 - "Cash"
1 - "Cheque"

ReceivableTransaction

	2 - "Cheque" 3 - If the credit card flag is set on the payment method then "CreditCard" else "ElectronicFundsTransfer" 4 - "BankDraft" 5 - "CreditTransfer" everything else "Cash"
ReceivableTransaction/ReceivableTransactionHeader/WriteOff/Amount FGLEDG.CUAM; ARS200MI/GetInvTotInfo @currencyID FSLEDG.CUCD; ARS200MI/GetInvTotInfo	Payment transactions with 98 > SLOP > 18 The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/WriteOff/BaseAmount FGLEDG.WRAM; ARS200MI/GetInvTotInfo @currencyID FGLEDG.LOCD; ARS200MI/GetInvTotInfo	WriteOff accounted amount in local currency. The field indicates the abbreviation for the invoice local currency. The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/WriteOff/ReasonCode FSLEDG.TDSC; ARS200MI/GetInvTotInfo	The field indicates the transaction description from the user-defined accounting options for manual payments. The description allows for a more detailed voucher description.
ReceivableTransaction/ReceivableTransactionHeader/CurrencyExchangeRate/SourceCurrencyCode FSLEDG.CUCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/CurrencyExchangeRate/TargetCurrencyCode CMNDIV.LOCD; MNS100MI/GetBasicData	The field indicates the local currency, that is, the basic currency used by the division. The local currency is defined per division.
ReceivableTransaction/ReceivableTransactionHeader/CurrencyExchangeRate/RateNumeric FSLEDG.ARAT; ARS200MI/GetInvTotInfo	The field indicates the exchange rate for the chosen currency. The rate may be entered with up to six decimal places. The result, however, will be displayed with two decimal places.

ReceiveDelivery

ReceiveDelivery/ReceiveDeliveryHeader/DocumentID/ID MPLIND.ICREPN; PPS200MI/GetLineTrans	The field indicates the receiving number which is assigned automatically for each item received in goods receiving.
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division
@location .WHLO; -/	The field indicates the warehouse locaiton
@variationID .; -/	The field indicates the variation ID
ReceiveDelivery/ReceiveDeliveryHeader/DocumentDateTime MPLIND.ICTRDT; PPS200MI/GetLineTrans	The field indicates the receipt date.
ReceiveDelivery/ReceiveDeliveryHeader/DocumentReference/DocumentID/ID MPLIND.ICPUNO; PPS200MI/GetLineTrans	The field indicates the unique number that is assigned to a purchase order when it is created.
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division
ReceiveDelivery/ReceiveDeliveryHeader/DocumentReference/LineNumber MPLIND.ICPNLI; PPS200MI/GetLineTrans	The field indicates the sequence number assigned to the purchase order line.
ReceiveDelivery/ReceiveDeliveryHeader/Status/Code MPLIND.ICPUOS; PPS200MI/GetLineTrans	The field indicates the status of the receipt transaction. 50-Received 51-Received 70-Received 75-Received
ReceiveDelivery/ReceiveDeliveryHeader/Status/EffectiveDateTime MPLIND.ICRGDT; ICRGTM; PPS200MI/GetLineTrans	The field indicates the date and time that the object was created.
ReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/ID MPLIND.ICWHLO; PPS200MI/GetLineTrans	The field indicates the warehouse ID.
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division
ReceiveDelivery/ReceiveDeliveryHeader/ActualShipDateTime MPLIND.ICSMdT; PPS200MI/GetLineTrans	The field indicates the shipment date
ReceiveDelivery/ReceiveDeliveryHeader/ActualDeliveryDateTime MPLIND.ICARDT; PPS200MI/GetLineTrans	The field indicates when a transfer from the subsidiary company has arrived to the parent company.
ReceiveDelivery/ReceiveDeliveryHeader/ShipFromParty/PartyIDs/ID MPLINE.IBSUNO; PPS200MI/GetLine	The field indicates the unique identity of a supplier.
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division
ReceiveDelivery/ReceiveDeliveryHeader/CarrierParty/Name MPLIND.ICCARN; PPS200MI/GetLineTrans	The field indicates the name of the carrier used.
ReceiveDelivery/ReceiveDeliveryHeader/ReceivedDateTime MPLIND.ICTRDT; PPS200MI/GetLineTrans	The field indicates the receive date.
ReceiveDelivery/ReceiveDeliveryHeader/BillOfLadingID MPLIND.ICBOLN; PPS200MI/GetLineTrans	The field indicates the number of the delivery's bill of lading.
ReceiveDelivery/ReceiveDeliveryHeader/Container/ContainerID MPLIND.ICCAMU; PPS200MI/GetLineTrans	The field indicates the object on which deliveries and receipts are loaded.
ReceiveDelivery/ReceiveDeliveryHeader/ReceivingLocation/ID MPLIND.ICWHSL; PPS200MI/GetLineTrans	The field indicates the warehouse ID.
ReceiveDelivery/ReceiveDeliveryItem/ItemID/ID MPLINE.IBITNO; PPS200MI/GetLine	The field indicates the item number.
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division
ReceiveDelivery/ReceiveDeliveryItem/Description MPLINE.IBPITT; PPS200MI/GetLine	The field indicates the description of an item in a purchase order.
ReceiveDelivery/ReceiveDeliveryItem/OrderQuantity MPLINE.IBORQA; PPS200MI/GetLine	The field indicates the order quantity.
@unitCode MPLINE.IBPUUN; PPS200MI/GetLine	The field indicates the unit of measure.
ReceiveDelivery/ReceiveDeliveryItem/ShippedQuantity MPLIND.ICRPQA; PPS200MI/GetLineTrans	The field indicates shipped quantity.
@unitCode MPLINE.IBPUUN; PPS200MI/GetLine	The field indicates the unit of measure.
ReceiveDelivery/ReceiveDeliveryItem/ShippedBaseUOMQuantity @unitCode MPLINE.IBPUUN; PPS200MI/GetLine	The field indicates the unit of measure.
ReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/DocumentID/ID MPLIND.ICPUNO; PPS200MI/GetLineTrans	The field indicates the purchase order number.
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division

ReceiveDelivery

ReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/LineNumber MPLIND.ICPNLI; PPS200MI/GetLineTrans	The field indicates the purchase order line.
ReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/SubLineNumber MPLIND.ICPNLS; PPS200MI/GetLineTrans	The field indicates the purchase order sub-line.
ReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/Quantity MPLINE.IBORQA; PPS200MI/GetLine	The field indicates the order quantity.
@unitCode MPLINE.IBPUUN; PPS200MI/GetLine	The field indicates the unit of measure.
ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/DocumentID/ID MPLINE.IBRORN; PPS200MI/GetLine	The field indicates the customer order number.
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division
ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/DocumentDate/Time OOHEAD.OACUDT; OIS100MI/GetHead	The field indicates the customer order date.
ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/LineNumber MPLINE.IBRORL; PPS200MI/GetLine	The field indicates the customer order line number
ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/SubLineNumber MPLINE.IBRORX; PPS200MI/GetLine	The field indicates the customer order sub-line number
ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/Quantity OOLINE.OBORQT; OIS100MI/GetLine	The field indicates the customer order quantity.
@unitCode OOLINE.OBALUN; OIS100MI/GetLine	The field indicates the customer order quantity unit of measure.
ReceiveDelivery/ReceiveDeliveryItem/Status/Code MPLIND.ICPUOS; PPS200MI/GetLineTrans	The field indicates the status of the receipt transaction. 50-Received 51-Received 70-Received 75-Received
ReceiveDelivery/ReceiveDeliveryItem/ReceivedQuantity MPLIND.ICRVQA; PPS200MI/GetLineTrans	This indicates the received quantity.
@unitCode MPLINE.IBPUUN; PPS200MI/GetLine	This indicates the received quantity unit of measure.
ReceiveDelivery/ReceiveDeliveryUnit/CarrierParty/Name MPLIND.ICCARN; PPS200MI/GetLineTrans	The field indicates the name of the carrier used.
ReceiveDelivery/ReceiveDeliveryUnit/ShipFromParty/PartyIDs/ID MPLINE.IBSUNO; PPS200MI/GetLine	The field indicates the unique identity of a supplier.
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division
ReceiveDelivery/ReceiveDeliveryUnit/ShipmentDate/Time MPLIND.ICSDMT; PPS200MI/GetLineTrans	The field indicates the shipment date.
ReceiveDelivery/ReceiveDeliveryUnit/Status/Code MPLIND.ICPUOS; PPS200MI/GetLineTrans	The field indicates the status of the receipt transaction. 50-Received 51-Received 70-Received 75-Received
ReceiveDelivery/ReceiveDeliveryUnit/Container/ContainerID MPLIND.ICCAMU; PPS200MI/GetLineTrans	The field indicates the container ID.
ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/ItemID/ID MPLINE.IBITNO; PPS200MI/GetLine	The field indicates the item number.
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division
ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/Description MPLINE.IBPITT; PPS200MI/GetLine	The field indicates the description of an item in a purchase order.
ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/OrderQuantity MPLINE.IBORQA; PPS200MI/GetLine	The field indicates the order quantity.
@unitCode MPLINE.IBPUUN; PPS200MI/GetLine	The field indicates the unit of measure.
ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/ShippedQuantity MPLIND.ICRPQA; PPS200MI/GetLineTrans	The field indicates shipped quantity.
@unitCode MPLINE.IBPUUN; PPS200MI/GetLine	The field indicates the unit of measure.
ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/Status/Code MPLIND.ICPUOS; PPS200MI/GetLineTrans	The field indicates the status of the purchase order transaction.
ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/ReceivedQuantity MPLIND.ICRVQA; PPS200MI/GetLine	This indicates the received quantity.
@unitCode MPLINE.IBPUUN; PPS200MI/GetLine	This indicates the received quantity unit of measure.

RemitToPartyMaster

RemitToPartyMaster/PartyIDs CIDMAS.IDSUNO; CRS620MI/GetBasicData	SUTY = 0, 1, 2, 3, 6, 8 (exclude Forwarding agent => CarrierPartyMaster)
RemitToPartyMaster/PartyIDs/DisplayID CIDMAS.IDSUNO; CRS620MI/GetBasicData	The field indicates the unique identity of a supplier.
RemitToPartyMaster/PartyIDs/TaxID @schemeAgencyName CIDMAS.IDCORG; CRS620MI/GetBasicData	The field indicates the supplier's organization number.
RemitToPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC; CRS620MI/GetBasicData	The field indicates Standard Carrier Alpha Code (SCAC).
RemitToPartyMaster/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicates supplier name.
RemitToPartyMaster/Location @type CIDADR.SAADTE; CRS620MI/LstAddresses	The field indicates the type of address to use. Alternatives 01 = Postal address 02 = Street address 05 = Final delivery address 10 = Bank address
RemitToPartyMaster/Location/Address/AddressLine CIDADR.SAADR1 SAADR2 SAADR3 SAADR4; CRS620MI/LstAddresses	The field indicates an address line. Address line 3 and 4 may be concatenated from other address information. It is controlled in M3 BE whether the country is set up with a formatting rule or not.
RemitToPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; CRS620MI/LstAddresses @listID N/A.; MRS001MI/GetFieldInfo	The field indicates an area, province or state within a country. Code list ID = "State"
RemitToPartyMaster/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses @listID N/A.; MRS001MI/GetFieldInfo	The field indicates a country. Code list ID = "Country"
RemitToPartyMaster/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses	The field indicates a postal code for a specific address.
RemitToPartyMaster/Location/Status/EffectiveDateTime CIDADR.SASTDT; CRS620MI/LstAddresses	The field indicates the date from which this record is valid.
RemitToPartyMaster/Contact/ID CIDREF.IRRFTY IRRFID; CRS620MI/LstSupplierRef	The field indicates the ID of the contact. It is concatenated from IRRFTY and IRRFID
RemitToPartyMaster/Contact/Name CIDREF.IRYRE1; CRS620MI/LstSupplierRef	The field indicates the name of the contact.
RemitToPartyMaster/Contact/Communication/ChannelCode @listID	M3 BE field Telephone number 1 has code "Phone" M3 BE field Telephone number 2 has code "Phone" M3 BE field Facsimile number has code "Fax" M3 BE field E-Mail address has code "EMail" ListID is set to "Communication Channels"
RemitToPartyMaster/Contact/Communication/DialNumber CIDREF.IRPHNO/IRTFNO; CRS620MI/LstSupplierRef	The field indicates the telephone or facsimile number of the contact
RemitToPartyMaster/Note MSYTXL.TLTX60; CRS980MI/	Need to create a MEC utility that retrieves all text blocks, text lines etc. Should be based on CRS980MI
RemitToPartyMaster/FinancialParty/Contact/Communication/URI CIDREF.IREMA1; CRS620MI/LstSupplierRef	The field indicates an e-mail address for the contact
RemitToPartyMaster/Status/Code CIDMAS.IDSTAT; CRS620MI/GetBasicData	The field indicates the supplier status. 10 = Pending 20 = Open 30 = Hold 90 = Deleted

Requisition

Requisition/RequisitionHeader/DocumentID/ID

MPOPLP.POPLPN
POPLPS; PPS170MI/GetPlannedPO

PO Proposal number = PLPN, Subnumber Proposal=PLPS

This field indicates an internal number on the planned order and a subnumber which is set automatically when the planned order is created.

@accountingEntity

MPOPLP.POCONO
CMNDIV.CCDIV1.; N/A/

This field indicates the company and division.

Requisition/RequisitionHeader/DocumentDateTime

MPOPLP.PORGDT
PORGTM; PPS170MI/GetPlannedPO

This field indicates the date and time the document was created. These are set automatically and transformed to UTC timezone.

Requisition/RequisitionHeader/DocumentReference**@type**

MPOPLP.PORORC; PPS170MI/GetPlannedPO

This field indicates the origin of the reference order number.

0 = Used in many areas within M3, for example M3 Maintenance for work scope creation
1 = Manufacturing order
2 = Purchase order
3 = Customer order
4 = Requisition order
5 = Distribution order
6 = Work order
7 = Service order
8 = Project order
9 = Claim order

Requisition/RequisitionHeader/DocumentReference/DocumentID/ID

MPOPLP.PORORN; PPS170MI/GetPlannedPO

This field indicates a reference order number.

@accountingEntity

MPOPLP.POCONO
CMNDIV.CCDIV1.; N/A/

This field indicates the company and division.

Requisition/RequisitionLine/LineNumber

MPOPLP.POPLPS; PPS170MI/GetPlannedPO

This field indicates a subnumber which is set automatically when the planned order is created. The subnumber is used internally by the system.

Requisition/RequisitionLine/Status/Code

MPOPLP.POPSTS; PPS170MI/GetPlannedPO

This field indicates the status of the planned order.

00 - Pending
05 - Pending
10 - Open
15 - Open
20 - Open
30 - Open
40 - Open
50 - Open
55 - Open
60 - Approved

Requisition/RequisitionLine/Quantity

MPOPLP.POPPQT; PPS170MI/GetPlannedPO

This field indicates the quantity that has been calculated to cover a future requirement. The quantity is expressed in purchase order unit of measure

@unitCode

MPOPLP.POPUUN; PPS170MI/GetPlannedPO

This field indicates the unit of measure (U/M) in which the quantity on the purchase order is expressed.

The purchase order U/M can be the alternate U/M or the item's standard purchase U/M, if an alternate does exist. If there is no standard purchase U/M, the item's basic U/M is used.

Requisition/RequisitionLine/BaseUOMQuantity

MPOPLP.POTRQT; PPS170MI/GetPlannedPO

This field indicates the quantity in the basic unit of measure for the planned or actual transaction.

@unitCode

MPOPLP.POUNMS; PPS170MI/GetPlannedPO

This field indicates the unit in which each item is recorded in inventory.

Requisition/RequisitionLine/ExtendedBaseAmount

MPOPLP.POCUPR; PPS170MI/GetPlannedPO

This field indicates the sales price expressed in the service order's currency or the agreement price in the agreement's currency.

@currencyID

CMNDIV.CCLOCD; PPS170MI/GetPlannedPO

This field indicates the local currency, that is, the basic currency used by the division.

SalesOrder

SalesOrder/SalesOrderHeader/DocumentID/ID OOHEAD.OAORNO; OIS100MI/GetHead	The field indicates the Customer Order Number
@accountingEntity OOHEAD.OACONO+OADIVI; N/A/	The field indicates the company and division
@location OOHEAD.OAWHLO; N/A/	The field indicates the location/warehouse
@variationID	The field indicates the number of variation for the object
@lid	The field indicates the logical ID
SalesOrder/SalesOrderHeader/AlternateDocumentID/ID OOHEAD.OACUOR; OIS100MI/GetHead	The field indicates the customer's order number. The customer's order number acts as a reference to the customer's own order number and is printed on external documents.
@schemeName	Customer is published.
SalesOrder/SalesOrderHeader/DisplayID OOHEAD.OAORNO; OIS100MI/GetHead	The field indicates the document ID.
SalesOrder/SalesOrderHeader/LastModificationDateTime OOHEAD.OALMTS; OIS100MI/GetHead	This indicates the last modification date and time of the BOD
SalesOrder/SalesOrderHeader/DocumentDateTime OOHEAD.OAORDT; OIS100MI/GetHead	This indicates the date and time of the sales order.
SalesOrder/SalesOrderHeader/Note OSYTXH.THTX40; OIS100MI/LstHeadTxt	The field indicates the remarks or notes.
@type	For Pre-text field, "Pre-Text" is published. For Post-Text field, "Post-text" is published. And for Text field, "Text" is published
SalesOrder/SalesOrderHeader/Status/Code OOHEAD.OAORSL; OIS100MI/GetHead	The field indicates the customer orders lowest status, M3 BE field ORSL. It is translated according to: 22, 23, 24, 29, 33, 39, 44 or 49 = Approved 26, 27, 36, 37, 46 or 47 = PartiallyShipped 66, 67 or 69 = Shipped 77 or 79 = Invoiced 90 = Deleted 99= Canceled
SalesOrder/SalesOrderHeader/Status/EffectiveDateTime OOHEAD.OAORDT; OIS100MI/GetHead	If Status is equal to 'Approved' or 'In Process', the Order Date field is published. If Status is equal to 'Closed' or 'Canceled', the transaction time of the last entry in Sales Order History is taken. Default filled with the UTC number of the Date and Time when the BOD is published.
SalesOrder/SalesOrderHeader/Status/ArchiveIndicator	If the Sales Order is deleted and the Order Status is equal to 'Closed' or 'Released', 'true' is published. Otherwise, 'false' is published.
SalesOrder/SalesOrderHeader/CustomerParty/PartyIDs/ID OOHEAD.OACUNO; OIS100MI/GetHead	The field indicates the customer identity.
@accountingEntity OOHEAD.OACONO+OADIVI; N/A/	The field indicates the company and division
SalesOrder/SalesOrderHeader/CustomerParty/PartyIDs/TaxID OCUSMA.OKVRNO; CRS610MI/GetFinancial	The field indicates the VAT registration number
SalesOrder/SalesOrderHeader/CustomerParty/Name OCUSMA.OKCUNM; CRS610MI/GetHead	The field indicates the Customer name
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/AttentionOfName OOHEAD.OKRESP; CRS610MI/GetBasicData	The field indicates the Customer Order Responsible
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/AddressLine OCUSMA.OKCUA1/OKCUA2/OKCUA3/OKCUA4.; CRS610MI/GetBasicData	The field indicates the Address fields (4 fields)
@sequence	The field indicates the sequence number
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/CityName OCUSMA.OKTOWN; CRS610MI/GetBasicData	The field indicates the City
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; CRS610MI/GetBasicData	The field indicates the state
@listID	The field indicates the list ID
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/CountryCode OCUSMA.OKCSCD; CRS610MI/Getbasicdata	The field indicates the CountryCode
@listID	The field indicates the list ID

SalesOrder

SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/PostalCode OCUSMA.OKPONO; CRS610MI/GetBasicData	The field indicates the Postal code
SalesOrder/SalesOrderHeader/CustomerParty/Contact/Name OCUSCO.CCCNPE; CMS055MI/LstByCustomer	The field indicates the contact person
SalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID OOHEAD.OADECUCU OOHEAD.OADECUCU+OAAIDID.; OIS100MI/GetAddress	The field indicates the Customer shipping address code
@accountingEntity OOHEAD.OACONO+OADIVI; N/A/	The field indicates the company and division
SalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/TaxID OCUSMA.OKVRNO; CRS610MI/GetFinancial	The field indicates the Tax ID
SalesOrder/SalesOrderHeader/ShipToParty/Name OCUSAD.OPCUNM OCUSMA.OKCUNM.; OIS100MI/GetAddress	The field indicates the Customer identity.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/AttentionOfName OCUSAD.OPYREF OCUSMA.OKYREF+OKYRE1.; OIS100MI/GetAddress	The field indicates the Customer responsible
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/AddressLine OCUSAD.OPCUA1/OPCUA2/OPCUA3/OPCUA4 OCUSMA.OKCUA1/OKCUA2/OKCUA3/OKCUA4.; OIS100MI/GetAddress	The field indicates the Address fields (4 fields).
@sequence	The field indicates the line sequence of the address.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/CityName OCUSAD.OPTOWN OCUSMA.OKTOWN.; OIS100MI/GetAddress	The field indicates the City.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/CountrySubDivisionCode OCUSAD.OPECAR OCUSMA.OKECAR.; OIS100MI/GetAddress	The field indicates the state.
@listID	The field indicates the list ID
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/CountryCode OCUSAD.OPCSCD OCUSMA.OKCSCD.; OIS100MI/GetAddress	The field indicates the CountryCode.
@listID	The field indicates the list ID
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/PostalCode OCUSAD.OPPONO OCUSMA.OPPONO.PONO; OIS100MI/GetAddress	The field indicates the Postalcode.
SalesOrder/SalesOrderHeader/ShipToParty/Contact/Name OCUSCO.CCCNPE.; CMS055MI/LstByCustomer	The field indicates the contact name.
SalesOrder/SalesOrderHeader/ShipFromParty/PartyIDs/ID OOHEAD.OAWHLO.WHLO; OIS100MI/GetHead	The field indicates the warehouse
@accountingEntity OOHEAD.OACONO+OADIVI; N/A/	The field indicates the company and division
SalesOrder/SalesOrderHeader/ShipFromParty/Name MITWHL.MWVWHNM; MMS005/GetWarehouse	The field indicates the warehouse name
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address/AddressLine MITWHL.MWADR1, MWADR2, MWADR3, MWADR4; MMS005/GetWarehouse	The field indicates the Address fields (4 fields)
@sequence	The field indicates the address sequence number
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address/CityName MITWHL.MWTOWN; MMS005/GetWarehouse	The field indicates the City
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address/CountrySubDivisionCode MITWHL.MWECAR; MMS005/GetWarehouse	The field indicates the Area
@listID	The field indicates the list ID
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address/CountryCode MITWHL.MWCSCD; MMS005/GetWarehouse	The field indicates the CountryCode
@listID	The field indicates the list ID
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address/PostalCode MITWHL.MWPONO; MMS005/GetWarehouse	The field indicates the Postal code
SalesOrder/SalesOrderHeader/ExtendedAmount OOHEAD.OANTAM+OAINET; OIS100MI/GetLine2	The field indicates the Net Order Value
@currencyID OOHEAD.OACUCD; OIS100MI/Gethead	The field indicates the Currency of the NetOrderValue
SalesOrder/SalesOrderHeader/TotalAmount OOHEAD.OATOPY+OAITOP; OIS100MI/GetOrderValue	The field indicates the Total value
@currencyID OOHEAD.OACUCD; OIS100MI/Gethead	The field indicates the Currency of the Total value

SalesOrder

SalesOrder/SalesOrderHeader/BillToParty/PartyIDs/ID OOHEAD.OAINRC; OIS100MI/Gethead	The field indicates the Invoice Recipient
@accountingEntity OOHEAD.OACONO+OADIVI; N/A/	The field indicates the company and division
SalesOrder/SalesOrderHeader/BillToParty/Name OCUSAD.OPCUNM OCUSMA.OKCUNM.; OIS100MI /GetAddress	The field indicates the invoice recipient.
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/AttentionOfName OCUSAD.OPYREF OCUSMA.OKYREF+OKYRE1.; OIS100MI /GetAddress	The field indicates the Customer responsible.
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/AddressLine OCUSAD.OPCUA1, OPCUA2, OPCUA3, OPCUA4 OCUSMA.OKCUA1, OKCUA2, OKCUA3, OKCUA4.; OIS100MI /GetAddress	The field indicates the Address fields (4 fields) for (Invoice recipient).
@sequence	The field indicates the sequence number of the address line
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/CityName OCUSAD.OPTOWN OCUSMA.OKTOWN.; OIS100MI /GetAddress	The field indicates the City (Invoice recipient).
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/CountrySubDivisionCode OCUSAD.OPECAR OCUSMA.OKECAR.; OIS100MI /GetAddress	The field indicates the Area
@listID	The field indicates the list ID
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/CountryCode OCUSAD.OPCSCD OCUSMA.OKCSCD.; OIS100MI /GetAddress	The field indicates the CountryCode (invoice recipient).
@listID	The field indicates the list ID
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/PostalCode OCUSAD.OPPONO OCUSMA.OKPONO.; OIS100MI /GetAddress	The field indicates the Postalcode (Invoice recipient).
SalesOrder/SalesOrderHeader/BillToParty/Location/Status/Code OCUSMA.OKSTAT; CRS610MI/GetBasicData	The field indicates the customer status, M3 BE field STAT. It is translated according to: 10, 11 or 12 = Pending 20 = Open 90 = Closed
SalesOrder/SalesOrderHeader/BillToParty/Contact/Name OCUSCO.CCCNPE; CMS055MI/LstByCustomer	The field indicates the Our reference person number 1 and number 2.
SalesOrder/SalesOrderHeader/PayFromParty/PartyIDs/ID OOHEAD.OAPYNO; OIS100MI/Gethead	The field indicates the Payer
@accountingEntity OOHEAD.OACONO+OADIVI; N/A/	The field indicates the company and division
SalesOrder/SalesOrderHeader/PayFromParty/PartyIDs/TaxID OCUSMA.OKVRNO; CRS610MI/GetFinancial	The field indicates the Tax ID
SalesOrder/SalesOrderHeader/PayFromParty/Name OCUSMA.OKCUNM; CRS610MI/GetBasicData	The field indicates the Customer name (Payer)
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/AttentionOfName OCUSMA.OKYREF; CRS610MI/GetBasicData	The field indicates the Customer responsible
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/AddressLine OCUSMA.OKCUA1, OKCUA2, OKCUA3, OKCUA4; CRS610MI/ GetBasicData	The field indicates the Address fields (4 fields) for (Payer)
@sequence	The field indicates the sequence number of the address line
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/CityName OCUSMA.OKTOWN; CRS610MI/GetBasicData	The field indicates the City (Payer)
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; CRS610MI/GetBasicData	The field indicates the state
@listID	The field indicates the list ID
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/CountryCode OCUSMA.OKCSCD; CRS610MI/GetBasicData	The field indicates the CountryCode
@listID	The field indicates the list ID
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/PostalCode OCUSMA.OKPONO; CRS610MI/GetBasicData	The field indicates the Postalcode (Payer)

SalesOrder

SalesOrder/SalesOrderHeader/PayFromParty/Location/Status/Code OCUSMA.OKSTAT; CRS610MI/GetBasicData	The field indicates the customer status, M3 BE field STAT. It is translated according to: 10, 11 or 12 = Pending 20 = Open 90 = Closed
SalesOrder/SalesOrderHeader/PayFromParty/Contact/Name OCUSCO.CCCNPE; CMS055MI/LstByCustomer	The field indicates the Our reference person number 1 and number 2 (Payer)
SalesOrder/SalesOrderHeader/TransportationTerm/IncotermsCode OOHEAD.OKTEDL; OIS100MI/GetHead	The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
@listID	The field indicates the list ID
SalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOwnershipTransferLocation/Description CSYTAB.CTTX40; CRS065MI/GetDelyTerm	The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Alternatives 1 = The buyer assumes liability when the goods leave the supplier's inventory. 2 = The buyer assumes liability when the goods are received at the buyer's transport address. 3 = The buyer assumes liability when the goods are received at the buyer's final address.
SalesOrder/SalesOrderHeader/PaymentTerm/Term/ID OOHEAD.OATEPY; OSI100MI/GetHead	The field indicates the payment term ID
SalesOrder/SalesOrderHeader/DistributedCharge/Description OOCHRG.OECRDO; OIS100MI/LstOrderCharges	The field indicates the charge description
SalesOrder/SalesOrderHeader/DistributedCharge/Amount OOCHRG.OECRAM; OIS100MI/LstOrderCharges	The field indicates the charge amount
@currencyID OOCHRG.OECUCD; OIS100MI/LstOrderCharges	The field indicates the Currency
SalesOrder/SalesOrderHeader/DistributedCharge/ReasonCode OOCHRG.OECRD0; OIS100MI/LstOrderCharges	The field indicates the charge description
SalesOrder/SalesOrderHeader/DistributedCharge/CalculationMethodCode OOCHRG.OECRME; OIS100MI/LstConnCOCharge	The field indicates how a charge is to be calculated or entered for each item charge. Alternatives 0 = Amount, no calculation is made 1 = Calculation factor * gross price 2 = Calculation factor * net price 3 = Calculation factor * gross weight 4 = Calculation factor * net weight 5 = Calculation factor * volume 6 = Amount per quantity.
SalesOrder/SalesOrderHeader/DistributedCharge/GrossWeightIndicator	The field is set to false
SalesOrder/SalesOrderHeader/DistributedTax/ID	The field has a fixed value of "Tax"
SalesOrder/SalesOrderHeader/DistributedTax/Description	The field is set to Tax
SalesOrder/SalesOrderHeader/DistributedTax/Amount OOHEAD.OAVTAM; OIS100MI/GetOrderValue	The field indicates the Tax amount
@currencyID OOHEAD.OACUCD; OIS100MI/GetOrderValue	The field indicates the currency
SalesOrder/SalesOrderHeader/EarliestDeliveryDateTime OOHEAD.OAFDDT; OIS100MI/GetHead	The field indicates the Earliest Delivery Date
SalesOrder/SalesOrderHeader/RequiredDeliveryDateTime OOHEAD.OARLDT & OARLHM; OIS100MI/GetHead	The field indicates the Requested Delivery Date and Time
SalesOrder/SalesOrderHeader/PaymentMethodCode OOHEAD.OATEPY; OIS100MI/GetHead	The field indicates the the payment term
SalesOrder/SalesOrderHeader/PricingRequiredIndicator	The field is set to false
SalesOrder/SalesOrderHeader/SalesPersonReference/IDs/ID OOHEAD.OASMCD; OIS100MI/GetHead	The field indicates the Salesman
@accountingEntity OOHEAD.OACONO+OADIVI; N/A/	The field indicates the company and division
SalesOrder/SalesOrderHeader/SalesPersonReference/Name CSYTAB.CTTX15; CRS100MI/Get	The field indicates the Name of Salesperson
SalesOrder/SalesOrderHeader/ExtendedPretaxAmount OOHEAD.OAORVA+OAIRVA; OIS100MI/GetOrderValue	The field indicates the pre-tax amount.

SalesOrder

@currencyID OOHEAD.OACUCD; OIS100MI/GetHead	The field indicates the currency.
SalesOrder/SalesOrderHeader/SubTotalAmount OOHEAD.OATOAM+OAITOA; OIS100MI/GetOrderValue	The field indicates the sub-total amount.
@currencyID OOHEAD.OACUCD; OIS100MI/GetHead	The field indicates the currency.
SalesOrder/SalesOrderLine/LineNumber OOLINE.OAPONR; OIS100MI/LstLine	The field indicates the Order Line number
SalesOrder/SalesOrderLine/Note OSYTXL.TLTX40; OIS100MI/LstLineTxt	The field indicates the remarks or notes.
@type	For Pre-text field, "Pre-Text" is published. For Post-Text field, "Post-text" is published.
SalesOrder/SalesOrderLine/Status/Code OOLINE.OBORST; OIS100MI/LstLine	The field indicates the customer order lines status, M3 BE field ORST. It is translated according to: 22, 23, 24, 29, 33, 34, 39, 44 or 49 = Approved 26, 27, 36, 37, 46 or 47 = PartiallyShipped 66, 67 or 69 = Shipped 77 or 79 = Invoiced 90 = Deleted 99= Canceled
SalesOrder/SalesOrderLine/Status/EffectiveDateTime OOHEAD.OBORDT; OIS100MI/GetHead	If Status is equal to 'Approved' or 'In Process', the Order Date field is published. If Status is equal to 'Closed' or 'Canceled', the transaction time of the last entry in Sales Order History is taken. Default filled with the UTC number of the Date and Time when the BOD is published.
SalesOrder/SalesOrderLine/Status/ArchiveIndicator	If the Sales Order Line is deleted or the Sales Order is deleted and the Order Status is equal to 'Closed' or 'Released', 'true' is published. Otherwise, 'false' is published.
SalesOrder/SalesOrderLine/Item/ItemID/ID OOLINE.OBITNO; OIS100MI/LstLine	The field indicates the Item Number
@accountingEntity OOLINE.OBCONO+OBDIVI; N/A/	The field indicates the company and division
SalesOrder/SalesOrderLine/Item/Description OOLINE.OBITDS; OIS100MI/GetLine	The field indicates the Item description
SalesOrder/SalesOrderLine/Item/SerialNumber OOLINE.OBBANO; OIS100MI/LstLine	The field indicates the Serial number
SalesOrder/SalesOrderLine/Item/SerializedLot/Lot/LotIDs/ID OOLINE.OBBANO; OIS100MI/LstLine	The field indicates the lot number.
SalesOrder/SalesOrderLine/Quantity OOLINE.OBORQA; OIS100MI/LstLine	The field indicates the Quantity for Orderline (in Basic Unit of Measure)
@unitCode OOLINE.OBALUN; OIS100MI/LstLine	The field indicates the Unit of Measure
SalesOrder/SalesOrderLine/BaseUOMQuantity OOLINE.OBORQT; OIS100MI/LstLine	The field indicates the Quantity for Orderline (in Basic Unit of Measure)
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Unit of Measure
SalesOrder/SalesOrderLine/UnitPrice/Amount OOLINE.OBSAPR; OIS100MI/LstLine	The field indicates the unit sales price amount.
@currencyID OOLINE.OBCUCD; OIS100MI/LstLine	The field indicates the currency
SalesOrder/SalesOrderLine/UnitPrice/BaseAmount OOLINE.OBSAAM/OBORQT; OIS100MI/LstLine	The field indicates the unit base price amount
@currencyID OOLINE.OBLOCD; OIS100MI/LstLine	The field indicates the currency
SalesOrder/SalesOrderLine/UnitPrice/PerQuantity OOLINE.OBSACD; OIS100MI/LstLine	The field indicates the quantity to which the sales price applies. Sales price quantity is defined for each item and is expressed in the item unit of measure.
@unitCode OOLINE.OBSPUN; OIS100MI/LstLine	The field indicates the Unit of Measure
SalesOrder/SalesOrderLine/ExtendedAmount OOLINE.OBNLAM; OIS100MI/LstLine	The field indicates the gross line amount
@currencyID OOLINE.OBCUCD; OIS100MI/LstLine	The field indicates the Currency
SalesOrder/SalesOrderLine/ExtendedBaseAmount OOLINE.OBSAAM; OIS100MI/GetLine2	The field indicates the net line amount in local currency.
@currencyID	

SalesOrder

OOLINE.OBLOCD; OIS100MI/LstLine	The field indicates the local currency.
SalesOrder/SalesOrderLine/TotalAmount OOLINE.OBNLAM; OIS100MI/LstLine	The field indicates the Net Line Amount
@currencyID OOLINE.OBCUCD; OIS100MI/LstLine	The field indicates the Currency
SalesOrder/SalesOrderLine/RequiredDeliveryDate/Time OOLINE.OBDWDZ+OBDWHZ; OIS100MI/GetLine	The field indicates the Requested Delivery date
SalesOrder/SalesOrderLine/ShipToParty/PartyIDs/ID OOHEAD.OBDECU OOHEAD.OBDECU +OBADID.; OIS100MI/GetLineAddress	The field indicates the Customer shipping address code
@accountingEntity OOLINE.OBCONO+OBDIVI; N/A/	The field indicates the company and division
SalesOrder/SalesOrderLine/ShipToParty/PartyIDs/TaxID OCUSMA.OKVRNO; CRS610MI/GetFinancial	The field indicates the Tax ID
SalesOrder/SalesOrderLine/ShipToParty/Name OOADRE.ODCUNM OCUSAD.OPCUNM OCUSMA.OKCUNM.; OIS100MI/GetLineAddress	The field indicates the Customer name.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/AttentionOfName OOADRE.ODYREF, ODYRE1 OCUSAD. OPYREF, OPYRE1 OCUSMA. OKYREF, OKYRE1.; OIS100MI/GetLineAddress	The field indicates the Customer responsible.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/AddressLine OOADRE.ODCUA1, ODCUA2, ODCUA3, ODCUA4 OCUSAD.OPCUA1, OPCUA2, OPCUA3, OPCUA4 OCUSMA.OKCUA1, OKCUA2, OKCUA3, OKCUA4.; OIS100MI/GetLineAddress	The field indicates the Address fields (4 fields).
@sequence	The field indicates the address line sequence number.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/CityName OOADRE.ODTOWN OCUSAD.OPTOWN OCUSMA.OKTOWN.; OIS100MI/GetLineAddress	The field indicates the City.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/CountrySubDivisionCode OOADRE.ODECAR OCUSAD.OPECAR OCUSMA.OKECAR.; OIS100MI/GetLineAddress	The field indicates the Area.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/CountryCode OOADRE.ODESCD OCUSAD.OPESCD OCUSMA.OKESCD.; OIS100MI/GetLineAddress	The field indicates the CountryCode.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/PostalCode OOADRE.ODPONO OCUSAD.OPPONO OCUSMA.OKPONO.; OIS100MI/GetLineAddress	The field indicates the PostalCode.
SalesOrder/SalesOrderLine/ShipToParty/Contact/Name OCUSCO.CCCNPE; CMS055MI/LstByCustomer	The field indicates the Customer responsible.
SalesOrder/SalesOrderLine/TransportationTerm/IncotermsCode OOLINE.OBTEDL; OIS100MI/GetLine2	The field indicates delivery terms, which control when transport responsibility shifts from supplier to customer.
@listID	The field indicates the list ID
SalesOrder/SalesOrderLine/TransportationTerm/PlaceOfOwnership/TransferLocation/Description CSYTAB.CTTX40; CRS065MI/GetDelyTerm	The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Alternatives 1 = The buyer assumes liability when the goods leave the supplier's inventory. 2 = The buyer assumes liability when the goods are received at the buyer's transport address. 3 = The buyer assumes liability when the goods are received at the buyer's final address.
SalesOrder/SalesOrderLine/PaymentTerm/Description CSYTAB.TX40; CRS175MI/GetGeneralCode	The field indicates the payment term description
SalesOrder/SalesOrderLine/PaymentTerm/Term/ID OOLINE.OBTEPY; OIS100MI/GetLine2	The field indicates the payment term
SalesOrder/SalesOrderLine/DistributedCharge	

SalesOrder

@sequence	The field indicates the sequence number
SalesOrder/SalesOrderLine/DistributedCharge/Description	The field is set to Discount
SalesOrder/SalesOrderLine/DistributedCharge/Amount OOLINE.OBDIA1, OBDIA2, OBDIA3, OBDIA4, OBDIA5, OBDIA6; GetLine/	The field indicates the discount amount
@currencyID OOLINE.OBCUCD; GetLine/	The field indicates the currency of the discount
SalesOrder/SalesOrderLine/DistributedCharge/Calculation/RateNumeric OOLINE.OBDIP1, OBDIP2, OPDIB3, OBDIP4, OBDIP5, OBDIP6; GetLine/	The field indicates the discount rate
SalesOrder/SalesOrderLine/DistributedCharge/ReasonCode	The field is set to Discount
SalesOrder/SalesOrderLine/PromisedShipDate/Time OOLINE.OBDSDT+OBDSHM; OIS100MI/GetLine2	The field indicates the Confirmed deliverydate + time
SalesOrder/SalesOrderLine/PromisedDeliveryDate/Time OOLINE.OBCODZ+OBDOHZ; OIS100MI/GetLine	The field indicates the Confirmed deliverydate + time
SalesOrder/SalesOrderLine/PurchaseOrderReference/DocumentID/ID OOLINE.OBRIDN; OIS100MI/GetLine2	The indicates the purchase order number
SalesOrder/SalesOrderLine/PurchaseOrderReference/LineNumber OOLINE.OBRIDL; OIS100MI/GetLine2	The field indicates the purchase order line number
SalesOrder/SalesOrderLine/PurchaseOrderReference/SubLineNumber OOLINE.OBRIDX; OIS100MI/GetLine2	The field indicates the purchase order sub-line number
SalesOrder/SalesOrderLine/SalesOrderSubLine/LineNumber OOLINE.OBPOSX; OIS100MI/LstLine	The field indicates the subline number
SalesOrder/SalesOrderLine/SalesOrderSubLine/Item/ItemID/ID OOLINE.OBITNO; OIS100MI/LstLine	The field indicates the Item Number
SalesOrder/SalesOrderLine/SalesOrderSubLine/Item/Description MITMAS.MMITDS; MMS200MI/GetItemBasic	The field indicates the Item description
SalesOrder/SalesOrderLine/SalesOrderSubLine/Item/SerialNumber OOLINE.OBSERN; OIS100MI/LstLine	The field indicates the Serial number
SalesOrder/SalesOrderLine/SalesOrderSubLine/Item/SerializedLot/Lot/LotIDs/ID OOLINE.OBBANO; OIS100MI/LstLine	The field indicates the lot number.
SalesOrder/SalesOrderLine/SalesOrderSubLine/Quantity OOLINE.OBORQA; OIS100MI/LstLine	The field indicates the Quantity for Orderline (in Basic Unit of Measure)
@unitCode OOLINE.OBALUN; OIS100MI/LstLine	The field indicates the currency
SalesOrder/SalesOrderLine/SalesOrderSubLine/BaseUOMQuantity OOLINE.OBORQT; OIS100MI/LstLine	The field indicates the Quantity for Orderline (in Basic Unit of Measure)
@unitCode MITMAS.MMUNMS; MMS200MI/GetItemBasic	The field indicates the currency
SalesOrder/SalesOrderLine/QuoteReference/DocumentID/ID OOHEAD.OAOFNO; OIS100MI/GetHead	The field indicates the quote number
SalesOrder/SalesOrderLine/ShipFromParty/PartyIDs/ID OOLINE.OBWHLO; OIS100MI/LstLine	The field indicates the warehouse where the item is from.
SalesOrder/SalesOrderLine/ShipFromParty/Name MITWHL.MWWHNM; MMS005/GetWarehouse	The field indicates the warehouse name.
SalesOrder/SalesOrderLine/ShipFromParty/Location/Address/AddressLine MITWHL.MWADR1, MWADR2, MWADR3, MWADR4; MMS005/GetWarehouse	The field indicates the warehouse address line
@sequence	The field indicates the address line sequence number.
SalesOrder/SalesOrderLine/ShipFromParty/Location/Address/CityName MITWHL.MWTOWN; MMS005/GetWarehouse	The field indicates the city where the warehouse is located.
SalesOrder/SalesOrderLine/ShipFromParty/Location/Address/CountrySubDivisionCode MITWHL.MWECAR; MMS005/GetWarehouse	The field indicates the state
SalesOrder/SalesOrderLine/ShipFromParty/Location/Address/CountryCode MITWHL.MWCSCD; MMS005/GetWarehouse	The field indicates the country code.
SalesOrder/SalesOrderLine/ShipFromParty/Location/Address/PostalCode MITWHL.MWPONO; MMS005/GetWarehouse	The field indicates the postal code.
SalesOrder/SalesOrderLine/AllocatedBaseUOMQuantity OOLINE.OBALQT, OBPLQT; OIS100MI/LstLine	The field indicates the Allocated quantity
@unitCode MITMAS.MMUNMS; MMS200MI/	The field indicates the base unit of measure
SalesOrder/SalesOrderLine/OpenBaseUOMQuantity OOLINE.OBORQT, OBALQT, OBPLQT, OBIVQT; OIS100MI/LstLine	The field indicates the undelivered quantity
@unitCode MITMAS.MMUNMS; MMS200MI/GetItemBasic	The field indicates the base unit of measure

SalesOrder

SalesOrder/SalesOrderLine/ShippedQuantity

OOLINE.OBDLQT; OBIVQT; OIS100MI/LstLine

The field indicates the Delivered quantity

@unitCode

MITMAS.MMUNMS; MMS200MI/GetItmBasic

The field indicates the unit of measure

SalesOrder/SalesOrderLine/ShippedBaseUOMQuantity

OOLINE.OBDLQT; OBIVQT; OIS100MI/LstLine

The field indicates the Delivered quantity

@unitCode

MITMAS.MMUNMS; MMS200MI/GetItmBasic

The field indicates the base unit of measure

SalesOrder/SalesOrderLine/PricingAmount/UnitBaseAmount

OOLINE.OBSAPR; OIS100MI/LstLine

The field indicates the sales price for each sales price quantity.

@currencyID

OOLINE.OBCUCD; OIS100MI/LstLine

The field indicates the Currency

SalesOrder/SalesOrderLine/PricingAmount/UnitPretaxAmount

OOLINE.OBNEPR; OIS100MI/LstLine

The field indicates the net price.

@currencyID

OOLINE.OBCUCD; OIS100MI/LstLine

The field indicates the Currency

SalesOrder/SalesOrderLine/PricingAmount/UnitTotalAmount

OOLINE.OBNLAM; OIS100MI/LstLine

The field indicates the Net Line Amount (as well as currency)

@currencyID

OOLINE.OBCUCD; OIS100MI/LstLine

The field indicates the Currency

SalesOrder/SalesOrderLine/PricingAmount/UnitTotalBaseAmount

OOLINE.OBSAAM; OIS100MI/GetLine2

The field indicates the net line amount in local currency.

@currencyID

OOLINE.OBLOCD; OIS100MI/GetLine2

The field indicates the local currency.

ServiceOrder

ServiceOrder/ServiceOrderHeader/DocumentID/ID ACUORH.OHORNO; EQINFOMI/GetMaintCO	The Field indicates the key fields for the MCO-line
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location ACUORH.OLFACI; EQINFOMI/GetMaintCO	The field indicates the facility
ServiceOrder/ServiceOrderHeader/AlternateDocumentID/ID ACUORH.CUCUOR ; EQINFOMI/GetMaintCO	The field indicates the customers order reference
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
ServiceOrder/ServiceOrderHeader/DisplayID ACUORH.OHORNO; EQINFOMI/GetMaintCO	The MCO-order and line is the key field to MCO line and is set as the document id
ServiceOrder/ServiceOrderHeader/LastModificationDate/Time ACUORH.OHLMDDT+LMTS; EQINFOMI/GetMaintCO	The field indicates the last date and time when the MCO was changed.
ServiceOrder/ServiceOrderHeader/LastModificationPerson/IDs/ID ACUORH.OHCHID; EQINFOMI/GetMaintCO	The field indicates the user id who last changed the record
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
ServiceOrder/ServiceOrderHeader/DocumentDate/Time ACUORH.OLRGDT + OLRGTM; EQINFOMI/GetMaintCO	The field indicates the entry date and time when the record first was created
ServiceOrder/ServiceOrderHeader/Description MMOHED.QHTXT1; MOS100MI/Get	The field indicates the description on the work order header from first work order
@languageID ACUORH.OHLNCD; EQINFOMI/GetMaintCO	The field indicates the language code from MCO-header
ServiceOrder/ServiceOrderHeader/Note ACUORH.OHTXID; EQINFOMI / CRS980MI/GetMaintCO + LstTxtBlock + SltTxtBlock	The text associated with the MCO header
@languageID ACUORH.OHLNCD; EQINFOMI/GetMaintCO	The field indicates the language code from MCO-header
@noteID ACUORH.OHTXID; EQINFOMI /GetMaintCO	Text block ID
ServiceOrder/ServiceOrderHeader/PriorityCode ACUORH.OHOPRI; EQINFOMI/GetMaintCO	The field indicates the priority of the order
ServiceOrder/ServiceOrderHeader/Status/Code ACUORH.OHAOSL; EQINFOMI/GetMaintCO	The field indicates the lowest status on the MCO header, translate M3 statuses to standard bod statuses for service order.
ServiceOrder/ServiceOrderHeader/CustomerParty/PartyIDs/ID ACUORH.OHCUNO; EQINFOMI/GetMaintCO	The field indicates the customer number
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
ServiceOrder/ServiceOrderHeader/CustomerParty/Name OCUSMA.OKCUNM; EQINFOMI/GetBasic	The field indicates the customer name
ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Name OCUSMA.OKCUNM; CRS610MI/GetBasic	The field indicates the company location name for delivery address
ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address @type .OPCUA2, OPCUA3,OPCUA4; /	Indicate that address elements used - input-ORNO, ADRT,
ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/AttentionOfName OCUSMA.OKCUA1; CRS610MI/GetBasic	The field indicates the contact person for the customer.
ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/AddressLine @sequence OCUSMA.OKADID; CRS610MI/GetBasic	The field indicates the address id/seq of the the customer
ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/CitySubDivisionName OCUSMA.OKECAR; CRS610MI/GetBasic	The field is used for subdivision or state code, field ECAR in M3
ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/CityName OCUSMA.OKTOWN; CRS610MI/GetBasic	The field indicates the city of the the customer
ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/CountryCode OCUSMA.OKCSCD; CRS610MI/GetBasic	The field indicates the Country code for the the customer
ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/PostalCode OCUSMA.OKPONO; CRS610MI/GetBasic	The field indicates the postal code for the the customer
ServiceOrder/ServiceOrderHeader/CustomerParty/Contact/ID OCUSMA.OKYREF; CRS610MI/GetBasic	The field indicates the contact person on the the customer, M3 field YREF
@accountingEntity	

ServiceOrder

ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location ACUORH.OHFACI; EQINFOMI/GetMaintCO	The field indicates the facility.
ServiceOrder/ServiceOrderHeader/ShipToParty/PartyIDs/ID ACUORA.OHORNO; EQINFOMI/GetMcoAddress	The field indicates the delivery address for the material (if populated) Else take from WO header +
@accountingEntity ACUORA.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
ServiceOrder/ServiceOrderHeader/ShipToParty/Name ACUORA.OPCUNM; EQINFOMI/GetMcoAddress	The field indicates the company location name for delivery address
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address @type ACUORA. ; EQINFOMI/GetMcoAddress	The field indicates the format of the address.
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/AttentionOfName ACUORA.OPCUA1; EQINFOMI/GetMcoAddress	The field indicates the attention / contact name
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/AddressLine @sequence ACUORA.OPADID; EQINFOMI/GetMcoAddress	The field indicates the address id/seq of the delivery address
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/CityName ACUORA.OPTOWN; EQINFOMI/GetMcoAddress	The field indicates the city of the address
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/CountrySubDivisionCode ACUORA.OPECAR; EQINFOMI/GetMcoAddress	The field is used for subdivision or state code, field ECAR in M3
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/CountryCode ACUORA.OPCSCD; EQINFOMI/GetMcoAddress	The field indicates the country code of the address
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/PostalCode ACUORA.OPPONO; EQINFOMI/GetMcoAddress	The field indicates the postal code for the delivery address
ServiceOrder/ServiceOrderHeader/ConfiguredAsset/ID ACUORH.OLPRNO + OLBANO; EQINFOMI/GetMaintCO	The field indicates the equipment ID (PRNO + BANO)
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location ACUORH.FACI; EQINFOMI/GetMaintCO	The field indicates the facility
ServiceOrder/ServiceOrderHeader/ConfiguredAsset/Description MILOIN.LIALII; MMS240MI/GetBasic	The field indicates the Equipment description. Use OHPRNO and OHBANO from GetMaintCO to retrieve
ServiceOrder/ServiceOrderHeader/Classification @type ACUORH.OHFACI; EQINFOMI/GetMaintCO	The field indicates the facility
ServiceOrder/ServiceOrderHeader/Classification/Codes/Code ACUORL.OLPRNS; /LstByProduct	The field indicates a list of services Use COS100MI, LstMcoLine
ServiceOrder/ServiceOrderHeader/PlannedTimePeriod/StartDateTime MMOHED.QHSTDT + QHMSTI; MOS100MI/Get	The field indicates the planned start date and time
ServiceOrder/ServiceOrderHeader/PlannedTimePeriod/EndDateTime MMOHED.QHFIDT + QHMFTI; MOS100MI/Get	The field indicates the planned finish date and time.
ServiceOrder/ServiceOrderHeader/ActualTimePeriod/StartDateTime MMOHED.QHRSDT + QHRSTI ; MOS100MI/Get	The field indicates the actual start date and time
ServiceOrder/ServiceOrderHeader/ActualTimePeriod/EndDateTime MMOHED.QHREFD + QHRFTI; MOS100MI/Get	The field indicates the actual finish date and time.
ServiceOrder/ServiceOrderHeader/EstimatedDuration MMOHED.OHPRDY; MOS100MI/Get	The field indicates the number of production days
ServiceOrder/ServiceOrderHeader/PreventiveMaintenanceID ACUORL.OLSTRT + OLSUFI; EQINFOMI/LstMaintCOLine	The field indicates the service id for scheduled/preventive services (only populated if scheduled service)
ServiceOrder/ServiceOrderHeader/ProjectReference/ID ACUORH.OHAPRS + OHELNO; EQINFOMI/GetMaintCO	The field indicates the project reference id .
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location ACUORH.OHAPRS + OHELNO; EQINFOMI/GetMaintCO	The field indicates the project reference id .
ServiceOrder/ServiceOrderHeader/SalesPersonReference/IDs/ID ACUORH.OHSMCD; EQINFOMI/GetMaintCO	The field indicates the sales person.
ServiceOrder/ServiceOrderHeader/PreferredEngineerPerson/ID ACUORL.OLEMNO; EQINFOMI/LstMaintCOLine	The field indicates the preferred engineer.
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location ACUORL.OLFACI; EQINFOMI/LstMaintCOLine	The field indicates the location =facility

ServiceOrder

ServiceOrder/ServiceOrderHeader/EmergencyIndicator MMOHED.QHNSTP; EQINFOMI/LstWOServices	The field indicates the company / division number.
ServiceOrder/ServiceOrderHeader/SiteLocation/ID ACUORA.OAADID; EQINFOMI/GetMcoAddress	The field indicates the unique key to the equipment address
@accountingEntity ACUORH.OHCONO + OHDIVI; EQINFOMI/According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location ACUORL.OLFACI; EQINFOMI/LstMaintCOLine	The field indicates the location for equipment address, FACI in M3
ServiceOrder/ServiceOrderHeader/SiteLocation/Name ACUORA.OACUNM; EQINFOMI/GetMcoAddress	The field indicates the name of the equipment address
@languageID ACUORH.OHLNCD; EQINFOMI/GetMaintCO	The field indicates the language code from MCO-header
ServiceOrder/ServiceOrderHeader/SiteLocation/Address @type .; /	The field indicates the company / division number.
ServiceOrder/ServiceOrderHeader/SiteLocation/Address/AddressLine ACUORA.OACUA1, OACUA2, OACUA3, OACUA4; EQINFOMI/GetMcoAddress	The field indicates the address of the equipment.
@sequence ACUORA.OAADID; EQINFOMI/GetMcoAddress	The field indicates the company / division number.
ServiceOrder/ServiceOrderHeader/SiteLocation/Address/CitySubDivisionName ACUORA.OAECAR; EQINFOMI/GetMcoAddress	The field indicates the state code for the equipment address.
ServiceOrder/ServiceOrderHeader/SiteLocation/Address/CityName ACUORA.OAPONO; EQINFOMI/GetMcoAddress	The field indicates the city for the equipment address.
ServiceOrder/ServiceOrderHeader/SiteLocation/Address/CountrySubDivisionCode ACUORA.OAECAR; EQINFOMI/GetMcoAddress	The field indicates the state code for the equipment address.
ServiceOrder/ServiceOrderHeader/SiteLocation/Address/CountryCode ACUORA.OACSCD; EQINFOMI/GetMcoAddress	The field indicates the contry code for the equipment address.
ServiceOrder/ServiceOrderHeader/SiteLocation/Address/PostalCode	The field indicates the postal number for the equipment address.
ServiceOrder/ServiceOrderHeader/ServiceAreaCode MMOOPS.QQACTS; MOS104MI/LstOpElement	The field indicates the geographical area of the equipment based for employee allocation
ServiceOrder/ServiceOrderHeader/ServiceTypeCode MPDSCF.CASECL; EQINFOMI/LstMaintCOLine	The field indicates the service type code
ServiceOrder/ServiceOrderHeader/TravelDuration MMOOPS.QQSETI; MOS104MI/GetOpElement	The field indicates the travel duration.
ServiceOrder/ServiceOrderHeader/CustomerTimePeriod/StartDateTime ACUORL.OLAAP1 + OLAPTI; EQINFOMI/LstMaintCOLine	This field indicates the customer required start date-time
ServiceOrder/ServiceOrderHeader/CustomerTimePeriod/EndDateTime ACUORL.OLRLDT + ??; EQINFOMI/LstMaintCOLine	This field indicates the customer required end date-time
ServiceOrder/ServiceOrderHeader/PaymentTerm ACUORH.OHTEPY; EQINFOMI/GetMaintCO	This field indicates the payment term
@type CSYTAB.OLCONO + DIVI; CRS175MI/GetGeneralCode	The field indicates the company / division number.
ServiceOrder/ServiceOrderHeader/PaymentTerm/Description CSYTAB.OLCONO/DIVI; CRS175MI/GetGeneralCode	The field indicates the payment term description.
@languageID ACUORH.OHLNCD; EQINFOMI/GetMaintCO	The field indicates the language code from MCO-header
ServiceOrder/ServiceOrderLine/LineNumber ACUORL.OLPONR; EQINFOMI/LstMaintCOLine	The field indicates the line number.
ServiceOrder/ServiceOrderLine/Description MMOHED.QHTXT1 ; EQINFOMI/LstWOServices	The field indicates the service order line description.
@languageID ACUORH.OHLNCD; EQINFOMI/GetMaintCO	The field indicates the language code from MCO-header
ServiceOrder/ServiceOrderLine/Note ACUORL.OLTXID; EQINFOMI CRS980MI/GetMaintCOLine + LstTxtBlock + SlTtxtBlock	The field indicates the text associate with the TXID on MCO -line
@languageID ACUORH.OHLNCD; EQINFOMI/GetMaintCO	The field indicates the language code from MCO-header
ServiceOrder/ServiceOrderLine/DocumentReference @type ACUORH.OHAAGN; EQINFOMI/GetMaintCO	The field indicates the document redeference for the line, e.g. agreement.
ServiceOrder/ServiceOrderLine/DocumentReference/DocumentID/ID @accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location ACUORH.OHFACI; EQINFOMI/GetMaintCO	The field indicates the facility for the agreemet
ServiceOrder/ServiceOrderLine/OperationID/ID	

ServiceOrder

ACUORL.OLPRNS + OLSTRT + OLSUFI; EQINFOMI/LstMaintCOLine	The field indicates the service on the MCO-line
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location MMOOPE.QOFACI; MOS100MI/GetOp	The field indicates the facility for the operation
ServiceOrder/ServiceOrderLine/Failure/Problem/ID ACUORL.OLFCLA; EQINFOMI/LstMaintCOLine	The field indicates the Failure/Problem/ID.
ServiceOrder/ServiceOrderLine/Failure/Problem/Symptom/ID ACUORL.OLFCLA; EQINFOMI/LstMaintCOLine	The field indicates the Failure/Problem/Symptom/ID
ServiceOrder/ServiceOrderLine/Failure/Problem/Cause/ID ACUORL.OLFCL2; EQINFOMI/LstMaintCOLine	The field indicates the Failure/Problem/Cause/ID.
ServiceOrder/ServiceOrderLine/Failure/Problem/Remedy/ID ACUORL.OLFCL3; EQINFOMI/LstMaintCOLine	The field indicates the Failure/Problem/Remedy/ID
ServiceOrder/ServiceOrderLine/Status/Code ACUORL.OLAOST; EQINFOMI/LstMaintCOLine	The field indicates the Status/Code of the MCO-line
@listID .; /	The field indicates the list of Status/Code of the MCO line
ServiceOrder/ServiceOrderLine/ActivityTemplateCode ACUORL.OLSTRT + OLSUFI; EQINFOMI/LstMaintCOLine	The field indicates the service ID.
ServiceOrder/ServiceOrderLine/ServiceTypeCode MPDSCF.CASECL; EQINFOMI/LstMaintCOLine	The field indicates the Service type/classification
ServiceOrder/ServiceOrderLine/ConfiguredAsset/ID ACUORL.OLPRNO + OLBANO; EQINFOMI/LstMaintCOLine	The field indicates the equipment ID (PRNO + BANO)
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location ACUORL.FACI; EQINFOMI/LstMaintCOLine	The field indicates the facility
ServiceOrder/ServiceOrderLine/ConfiguredAsset/Description MILOIN.LIALII; MMS240MI/GetBasic	The field indicates the Equipment description.
ServiceOrder/ServiceOrderLine/CustomTimePeriod/StartDate/Time MMOHED.QHRRSD + QHRRST; EQINFOMI/LstWOServices	The field indicates the Customer Requested StartDate/Time
ServiceOrder/ServiceOrderLine/CustomTimePeriod/EndDate/Time MMOHED.QHRRFD + QHRRFT; EQINFOMI/LstWOServices	The field indicates the Customer Requested End Date/Time
ServiceOrder/ServiceOrderLine/PlannedTimePeriod/StartDate/Time MMOHED.QHSTDT + QHMSTI; EQINFOMI/LstWOServices	The field indicates the Planned Start Date/Time.
ServiceOrder/ServiceOrderLine/PlannedTimePeriod/EndDate/Time MMOHED.QHFIDT + QHMFTI; EQINFOMI/LstWOServices	The field indicates the Planned End Date/Time.
ServiceOrder/ServiceOrderLine/ActualTimePeriod/StartDate/Time MMOHED.QHRSDT + QHRSTI; EQINFOMI/LstWOServices	The field indicates the Actual Start Date/Time.
ServiceOrder/ServiceOrderLine/ActualTimePeriod/EndDate/Time MMOHED.QHRSDT + QHRFTI; EQINFOMI/LstWOServices	The field indicates the Actual End Date/Time.
ServiceOrder/ServiceOrderLine/SupplierParty/PartyIDs/ID MMOOPE.QOSUNO; MOS100MI/GetOp	The field indicates the supplier number but presently not mapped
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
ServiceOrder/ServiceOrderLine/SupplierParty/Name .; /	The field indicates the Supplier Name.
ServiceOrder/ServiceOrderLine/RequiredServiceSkills/Name ACUORL.OLPLGR; EQINFOMI/LstMaintCOLine	The field indicates the RequiredServiceSkills/Workcewnter from MCO-line
ServiceOrder/ServiceOrderLine/CustomerCallReference/DocumentID/ID ACUORH.OHYREF; EQINFOMI/GetMaintCO	The field indicates the customer ref
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location ACUORL.OLFACI; EQINFOMI/LstMaintCOLine	The field indicates the facility
ServiceOrder/ServiceOrderLine/AssignmentGroup/Line/Number MMOOPE.QOMWNO + QOOPNO ; MOS100MI/GetOp	The field indicates the operation element/assignment line
ServiceOrder/ServiceOrderLine/AssignmentGroup/ActivityEngineerPerson/IDs/ID MMOOPS.QQEMNO; MOS104MI/GetOpElement	The field indicates the employee number.
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
ServiceOrder/ServiceOrderLine/AssignmentGroup/ActivityEngineerPerson/Name CEAEMP.EAEMNM; CRS530MI/LstEmployee	The field indicates the employee name
ServiceOrder/ServiceOrderLine/AssignmentGroup/Status/Code MMOOPS.QQSTMB; MOS104MI/GetOpElement	The field indicates the mobility status
ServiceOrder/ServiceOrderLine/AssignmentGroup/AcceptedDate/Time	

ServiceOrder

MMOLOG.DMTRDT + DMTRTM; MOS102MI/Sel	The field indicates the date the status get updated
ServiceOrder/ServiceOrderLine/AssignmentGroup/RejectionDatetime	
MMOLOG.DMTRDT + DMTRTM; MOS102MI/Sel	The field indicates the date the status get updated
ServiceOrder/ServiceOrderLine/AssignmentGroup/PlannedTimePeriod/StartDateTime	
MMOOPE.QOSTDT + QOMSTI; MOS100MI/GetOp	The field indicates the the planned start date time
ServiceOrder/ServiceOrderLine/AssignmentGroup/PlannedTimePeriod/EndDateTime	
MMOOPE.QOFIDT + QOMFTI; MOS100MI/GetOp	The field indicates the planned finish date time
ServiceOrder/ServiceOrderLine/AssignmentGroup/ActualTimePeriod/StartDateTime	
MMOOPE.QORSDD + QORSTI; MOS100MI/GetOp	The field indicates the actual start date time
ServiceOrder/ServiceOrderLine/AssignmentGroup/ActualTimePeriod/EndDateTime	
MMOOPE.QORSFD + QORFTI; MOS100MI/GetOp	The field indicates the the actual finish date time.
ServiceOrder/ServiceOrderLine/AssignmentGroup/Note	
MMOOPE.QOTXID; MOS100MI + CRS980MI/GetOp + + LstTxtBlock + SltTxtBlock	The field indicates the text associated with the operation
@languageID	
ACUORH.OHLNCD; EQINFOMI/GetLine	The field indicates the language code from MCO-header
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/LineNumber	
MMOMAT.QMMSEC; MOS100MI/GetMtrl	The field indicates the material line sequence number
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/MaterialEngineerPerson/IDs/ID	
@accountingEntity	
ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/MaterialEngineerPerson/Name	
CEAEMP.EAEMNM; CRS530MI/LstEmployee	The field indicates the company / division number.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/Status/Code	
MMOMAT.QMWMST; MOS100MI/GetMtrl	The field indicates the material status code.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/CreationDateTime	
MMOMAT.QMRGDT + QMRGTM; MOS100MI/GetMtrl	The field indicates the entry date time.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/MaterialItem/ItemID/ID	
MMOMAT.QMMTNO; MOS100MI/GetMtrl	The field indicates the material id/item number.
@accountingEntity	
ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/MaterialItem/Description	
MITMAS.MMITDS; MMS200MI/Get	The field indicates the name of the material
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/PartyIDs/ID	
MMOMAT.QMADRR + QMADRT + QMADID; MOS100MI/GetWoAddress	The field indicates the delivery address for the material (if populated) Else take from WO header +
@accountingEntity	
ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Name	
OCUSAD.OPCUNM; MOS100MI/GetWoAddress	The field indicates the company location name for delivery address
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address	
@type	
; MOS100MI/GetWoAddress	The field indicates the format of the address.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/AttentionOfName	
OCUSAD.OPCUA1; MOS100MI/GetWoAddress	The field indicates the attention / contact name
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/AddressLine	
@sequence	
OCUSAD.OPADID; MOS100MI/GetWoAddress	The field indicates the address id/seq of the delivery address
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/CityName	
OCUSAD.OPTOWN; MOS100MI/GetWoAddress	The field indicates the city of the address
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/CountrySubDivisionCode	
OCUSAD.OPECAR; MOS100MI/GetWoAddress	The field is used for subdivision or state code, field ECAR in M3
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/CountryCode	
OCUSAD.OPCSCD; MOS100MI/GetWoAddress	The field indicates the country code of the address
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/PostalCode	
OCUSAD.OPPONO; MOS100MI/GetWoAddress	The field indicates the postal code for the delivery address
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedDeliveryTypeCode	
; /	The field indicates the delivery type code. If warehouse same as tech, then "VAN", else if item stocked "DEP" else PO
@accountingEntity	
ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location	
MMOMAT.QMWHSL; MOS100MI/GetMtrl	The field indicates the warehouse location for the material
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualDeliveryTypeCode	
	The field indicates the delivery type code. If warehouse same as tech, then "VAN", else if item stocked "DEP" else PO
@accountingEntity	
ACUORH.OHCONO + OHDIVI; /According to standard	

ServiceOrder

	The field indicates the accounting entity in M3 mapped to company number and division.
@location MMOMAT.QMWHSL; MOS100MI/GetMtrl	The field indicates the warehouse location for the material
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedQuantity MMOMAT.QMCNQT; MOS100MI/GetMtrl	The field indicates the estimated quantity
@unitCode MMOMAT.QMPEUN; MOS100MI/GetMtrl	The field indicates the estimated quantity Unit of measure.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualQuantity MMOMAT.QMRPQT; MOS100MI/GetMtrl	The field indicates the actual quantity/reported quantity
@unitCode MMOMAT.QMPEUN; MOS100MI/GetMtrl	The field indicates the estimated quantity Unit of measure.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/InvoiceQuantity ACUINV.ITTRQT; MOS100MI/GetMtrl	The field indicates the actual quantity/reported quantity on MCO line COS170
@unitCode MMOMAT.QMPEUN; MOS100MI/GetMtrl	The field indicates the estimated quantity Unit of measure.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualWarehouseLocation/ID MMOMAT.QMWHLO; MOS100MI/GetMtrl	The field indicates the warehouse
@accountingEntity ACUORH.OHCONO + OHDIVI; /According to standard	The field indicates the accounting entity in M3 mapped to company number and division.
@location MMOMAT.QMWHSL; MOS100MI/GetMtrl	The field indicates the warehouse location for the material
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedCostPriceAmount .; MOS100MI/GetMtrl	The field indicates the estimated cost
@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the currency for estimated cost
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedSalesPriceAmount .; MOS100MI/GetMtrl	The field indicates the EstimatedSalesPriceAmount (New field in MI)
@currencyID ACUORH.OHAMCU; EQINFOMI/GetMaintCO	The field indicates the material currency for sales price
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualSalesPriceAmount ACUINV.ITAWCO; MOS100MI/GetMtrl	The field indicates the ActualSalesPriceAmount from COS170
@currencyID ACUORH.OHAMCU; EQINFOMI/GetMaintCO	The field indicates the material currency for sales price
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedInvoicePriceAmount ACUINV.ITNEPR; MOS100MI/GetMtrl	The field indicates the EstimatedInvoicePriceAmount
@currencyID ACUORH.OHAMCU; EQINFOMI/GetMaintCO	The field indicates the material currency for sales price
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualInvoicePriceAmount ACUINV.ITNEPR; MOS100MI/GetMtrl	The field indicates the ActualInvoicePriceAmount
@currencyID ACUORH.OHAMCU; EQINFOMI/GetMaintCO	The field indicates the material currency for sales price
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/LineNumber MMOOPE.QOMWNO + QOOPNO ; MOS100MI/GetOp	The field indicates the operation.
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/CreationDateTime MMOOPE.QJRGDT + QJRGTM; MOS100MI/GetOp	The field indicates the entry date time.
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/Status/Code MMOOPE.QOWOST; MOS100MI/GetOp	The field indicates the status of the operation
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/LineCode MMOOEM.QQOEM0-9; MOS100MI/GetOp2	The field indicates the service/labor code.
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/EstimatedTimeDuration MMOOPE.QOPITI; MOS100MI/GetOp	The field indicates the estimated time.
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/ActualTimeDuration MMOOPE.QOUMAT; MOS100MI/GetOp	The field indicates the actual time.
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/EstimatedCostPriceAmount .; MOS100MI/GetOp	The field indicates the cost.
@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the currency for estimated cost
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/EstimatedSalesPriceAmount .; MOS100MI/GetOp	The field indicates the EstimatedSalesPriceAmount.
@currencyID ACUORH.OHAACU; EQINFOMI/GetMaintCO	The field indicates the currency for sales price
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/ActualCostPriceAmount ACUORL.ITAWCO; MOS100MI/GetOp	The field indicates the company / division number.
@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the currency for estimated cost
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/ActualSalesPriceAmount ACUINV.ITASP1; MOS100MI/GetOp	The field indicates the ActualSalesPriceAmount
@currencyID ACUORH.OHAACU; EQINFOMI/GetMaintCO	The field indicates the currency for sales price
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/EstimatedLaborRate	

ServiceOrder

ACULSR.AWALP1; MOS100MI/GetOp	The field indicates the estimated Labor rat. Estimated price divided w hourd
@currencyID ACUORH.OHAACU; EQINFOMI/GetMaintCO	The field indicates the currency for sales price
ServiceOrder/ServiceOrderLine/ServiceLaborGroup/ActualLaborRate ACUORL.OLNEPR / OLTRQT; /	The field indicates rate- calculate in mapping NEPR/TRQT
@currencyID ACUORH.OHAACU; EQINFOMI/GetMaintCO	The field indicates the currency for sales price
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/LineNumber MMOOPS.QQFACI + QQPRNO+ QQMWNO + QQOPNO +QQACTS; COS150MI/LstOperElement	The field indicates the key to the operation element line
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/CreationDateTime MMOOPS.QQRGDT + QQRGTM; COS150MI/LstOperElement	The field indicates the registration date and time
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Status/Code MMOOPS.QQSTAT; COS150MI/LstOperElement	The field indicates the status of the operation element. (10,20,30,90) Prel,waiting appr,processing ongoing, approved
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Description MMOOPS.QQACDS; COS150MI/LstOperElement	The field indicates the description
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/CostTypeCode MMOOPS.QQAMTY; COS150MI/LstOperElement	The field indicates the miscellaneous cost type
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/EstimatedCostPriceAmount ACUINV.ITAWCO; COS150MI/LstOperElement	The field indicates the estimated/ actual cost price amount depending of status of the line.
@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the currency for estimated cost
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/EstimatedSalesPriceAmount ACUINV.ITASP1; COS150MI/LstOperElement	The field indicates the estimated/actual sales price amount for the misc cost depending on status of the line
@currencyID ACUORH.OHAACU; EQINFOMI/GetMaintCO	The field indicates the currency for sales price
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/EstimatedInvoicePriceAmount ACUINV.ITASP1; COS150MI/LstOperElement	The field indicates the estimated/actual invoice price amount for the misc cost
@currencyID ACUORH.OHAACU; EQINFOMI/GetMaintCO	The field indicates the currency for estimated invoice amount
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualCostPriceAmount ACUINV.ITAWCO; COS150MI/LstOperElement	The field indicates the actual cost price amount.
@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the currency for actual cost
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualSalesPriceAmount ACUINV.ITASP1; COS150MI/LstOperElement	The field indicates the actual sales price amount
@currencyID ACUORH.OHAACU; EQINFOMI/GetMaintCO	The field indicates the currency for the the actual sales price amount
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualInvoicePriceAmount ACUINV.ITASP1; COS150MI/LstOperElement	The field indicates the the actual invoice price amount
@currencyID ACUORH.OHAACU; EQINFOMI/GetMaintCO	The field indicates the currency for the actual invoice price amount
ServiceOrder/ServiceOrderLine/ServiceOtherGroup/EstimatedQuantity ACUINV.ITTRQT; COS150MI/LstOperElement	The field indicates the estimated quantity
@unitCode ACUINV.ITUNIT; COS150MI/LstOperElement	The field indicates the estimated quantity unit of measure- Get unit of measurment from cost type - COS160/ saved in MOS104

ShipFromPartyMaster

ShipFromPartyMaster/PartyIDs CIDMAS.IDSUNO; CRS620MI/GetBasicData	SUTY = 0, 1, 2, 3, 6, 8 (exclude Forwarding agent => ShipCarrierPartyMaster)
ShipFromPartyMaster/PartyIDs/DisplayID CIDMAS.IDSUNO; CRS620MI/GetBasicData	The field indicates the unique identity of a supplier.
ShipFromPartyMaster/PartyIDs/TaxID @lid CIDMAS.IDCORG; CRS620MI/GetBasicData	The field indicates the supplier's organization number.
ShipFromPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC; CRS620MI/GetBasicData	The field indicates Standard Carrier Alpha Code (SCAC).
ShipFromPartyMaster/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicates supplier name.
ShipFromPartyMaster/Location/Address/AddressLine CIDADR.SAADR1 SAADR2 SAADR3 SAADR4; CRS620MI/LstAddresses	The field indicates an address line. Address line 3 and 4 may be concatenated from other address information. It is controlled in M3 BE whether the country is set up with a formatting rule or not.
ShipFromPartyMaster/Location/Address/CityName CIDADR.SATOWN; CRS620MI/LstAddresses	The field indicates the city in an address.
ShipFromPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; CRS620MI/LstAddresses @listID N/A.; MRS001MI/GetFieldInfo	The field indicates an area, province or state within a country. Code list ID = "State"
ShipFromPartyMaster/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses	The field indicates a country. Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
@listID N/A.; MRS001MI/GetFieldInfo	Code list ID = "Country"
ShipFromPartyMaster/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses	The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used.
ShipFromPartyMaster/Location/Status/EffectiveDateTime CIDADR.SASTDT; CRS620MI/LstAddresses	The field indicates the date from which this record is valid.
ShipFromPartyMaster/Contact/ID CIDREF.IRRFTY IRRFID; CRS620MI/LstSupplierRef	The field indicates the ID of the contact. It is concatenated from IRRFTY and IRRFID
ShipFromPartyMaster/Contact/Name CIDREF.IRYRE1; CRS620MI/LstSupplierRef	The field indicates the name of the contact.
ShipFromPartyMaster/Contact/Communication/ChannelCode @listID	M3 BE field Telephone number 1 has code "Phone" M3 BE field Telephone number 2 has code "Phone" M3 BE field Facsimile number has code "Fax" M3 BE field E-Mail address has code "EMail" ListID is set to "Communication Channels"
ShipFromPartyMaster/Contact/Communication/DialNumber CIDREF.IRPHNO/IRTFNO; CRS620MI/LstSupplierRef	The field indicates the telephone or facsimile number of the contact
ShipFromPartyMaster/Contact/Communication/URI CIDREF.IREMAL; CRS620MI/LstSupplierRef	The field indicates an e-mail address for the contact
ShipFromPartyMaster/Note MSYTXL.TLTX60; CRS980MI/	Need to create a MEC utility that retrieves all text blocks, text lines etc. Should be based on CRS980MI
ShipFromPartyMaster/BuyerContact/ID CIDVEN.IIBUYE; CRS620MI/GetBasicData	The field indicates the buyer.
ShipFromPartyMaster/BuyerContact/Name CMNUSR.JUTX40; MNS150MI/GetUserData	The field indicates the name of the buyer.
ShipFromPartyMaster/Status/Code CIDMAS.IDSTAT; CRS620MI/GetBasicData	The field indicates the supplier status. 10 = Pending 20 = Open 30 = Hold 90 = Deleted

ShipToPartyMaster

ShipToPartyMaster/PartyIDs/ID

OCUSMA.OKCUNO
OCUSAD.OPCUNO+OPADID.; CRS610MI/GetBasicData,
GetAddress

The field indicates the customer number

@accountingEntity

OCUSMA.OKCUNO+CMNDIV.CCDIVI
OCUSAD.OKCUNO+CMNDIV.CCDIVI.; N/A/

The field indicates the AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

@variationID

The field indicates the variationID

@lid

The logical ID of the system that is SOR for this noun instance.

ShipToPartyMaster/Name

OCUSMA.OKCUNM
OCUSAD.OPCUNM.; CRS610MI/GetBasicData,
GetAddress

The field indicates the customer name

ShipToPartyMaster/Location/Address

@type

Fixed value - "Text".; N/A/

The field indicates a fixed value "Text"

ShipToPartyMaster/Location/Address/AttentionOfName

OCUSMA.OKYREF
OCUSAD.OPYREF.; CRS610MI/GetBasicData,
GetAddress

The field indicates the customer's contact person

ShipToPartyMaster/Location/Address/AddressLine

OCUSMA.OKCUA1
OCUSMA.OKCUA2
OCUSMA.OKCUA3
OCUSMA.OKCUA4
OCUSAD.OPCUA1
OCUSAD.OPCUA2
OCUSAD.OPCUA3
OCUSAD.OPCUA4.; CRS610MI/GetBasicData,
GetAddress

The indicates the address lines for the customer address

@sequence

Incremental value starting with 1.; N/A/

The field indicates the Address Line sequence

ShipToPartyMaster/Location/Address/CityName

OCUSMA.OKTOWN
OCUSAD.OPTOWN.; CRS610MI/GetBasicData,
GetAddress

The field indicates the city

ShipToPartyMaster/Location/Address/CountrySubDivisionCode

OCUSMA.OKECAR
OCUSAD.OPECAR.; CRS610MI/GetBasicData,
GetAddress

The field indicates the state/region/countrysubdivision

@listID

M3 BE field State has different list ID depending on country:
- Canada has list ID "Canadian Provinces"
- France has list ID "France - Departements"
- United States has list ID "US States"
- Other countries have list ID "Country Sub-divisions"

ShipToPartyMaster/Location/Address/CountryCode

OCUSMA.OKCSCD
OCUSAD.OPCSCD.; CRS610MI/GetBasicData,
GetAddress

The field indicates the country code

@listID

M3 BE field Country has list ID "Countries"

ShipToPartyMaster/Location/Address/PostalCode

OCUSMA.OKPONO
OCUSAD.OPPONO.; CRS610MI/GetBasicData,
GetAddress

The field indicates the postal code

ShipToPartyMaster/Location/Address/Preference/Indicator

Fixed value = "True".; N/A/

The field is set to true

ShipToPartyMaster/Communication

@preferredIndicator

Fixed value = "False".; N/A/

The field is set to false

ShipToPartyMaster/Communication/ChannelCode

M3 BE field Telephone number 1 has code "Phone"
M3 BE field Telephone number 2 has code "Phone"
M3 BE field Facsimile number has code "Fax"
M3 BE field E-Mail address has code "EMail"

@listID

ListID is set to "Communication Channels"

ShipToPartyMaster/Communication/UseCode

ShipToPartyMaster

	Currently, M3 BE does not keep information about use code for different communication alternatives.
	We do though hardcode UseCodes according to: M3 BE field Telephone number 1 has UseCode "Office" M3 BE field Telephone number 2 has UseCode "Office" M3 BE field Facsimile number has UseCode "Fax" M3 BE field E-Mail address has UseCode "Office"
@listID	ListID is set to "Communication Use Codes"
ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO/OKPHN2/OKTFNO OCUSAD.OPPHNO/OPPHN2/OPTFNO.; CRS610MI/GetBasicData, GetAddress	The field indicates the telephone/telefax number of the customer. PHNO & PHN2 is phone numbers TFNO is fax number
ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData	The field indicates an e-mail address for the customer
ShipToPartyMaster/Communication/Preference/Indicator Fixed value = "False".; N/A/	The field is always set to false
ShipToPartyMaster/PaymentTermID OCUSMA.OKTEPY CCUDIV.OKTEPY .; CRS610MI/GetOrderInfo	The field indicates the payment terms id for the customer Data is retrieved from customer master, table OCUSMA, or, if applicable, from customer local exceptions, table CCUDIV.
ShipToPartyMaster/Status/Code OCUSMA .OKSTAT; CRS610MI/GetBasicData	The field indicates the status of the customer. If M3 status is 10, set element to "Pending" If M3 status is 20, set element to "Open" If M3 status is 90, set element to "Closed"
ShipToPartyMaster/Classification/Codes/Code 1) OCUSMA.OKCUTP;CRS610MI/GetBasicData 2) OCUSMA.OKTEDL/CCUDIV.OKTEDL; CRS610MI/GetOrderInfo 3) OCUSMA.OKSDST;CRS610MI/GetOrderInfo	The field indicates the Classification. 1) If Customer type field is filled, populate Code with this value 2) If Delivery terms field is filled, populate Code with this value Data is retrieved from customer master, table OCUSMA, or, if applicable, from customer local exceptions, table CCUDIV. 3) If District field is filled, populate Code with this value
@listID	The field indicates the Classification code listID. 1) If Customer type field is filled, set listID to "Customer Types" 2) If Delivery terms field is filled, set listID to "Incoterms" 3) If District field is filled, set listID to "District"
@sequence Incremental value starting with 1.; N/A/	The sequence attribute identifies the hierarchical position of the identifier in the case of multi-level codes
ShipToPartyMaster/CustomerParty/PartyIDs/ID OCUSMA .OKCUNO; CRS610MI/GetBasicData	In M3 BE customer master, ShipToParty is the same as CustomerParty.This element is set to same as the ShipToPartyMaster element
@accountingEntity	Customer records in M3 BE are managed on the tenant level, it does not belong to an accounting entity. To make sure the BODs are correctly received by ION, we populate the accountingEntity attribute with component.instance from the logicalID. E.g. m3be.orbit1412 330
ShipToPartyMaster/CustomerParty/Name OCUSMA .OKCUNM ; CRS610MI/GetBasicData	The field is the name of the customer record
ShipToPartyMaster/SalesPersonReference/IDs/ID OCUSMA .OKSMCD; CRS610MI/GetOrderInfo	The field indicates the person responsible for sales to a customer.
@accountingEntity CMNDIV.CCDIVI; N/A/	Accounting entity is equivalent with Division in M3. Note! This value can be translated using CRS881

Shipment

Shipment/ShipmentHeader/DocumentID/ID

MHPICH.PIDLIX/PIPLSX; /

The field indicates the delivery number and picking list suffix.

The field is taken from the event data instead of using an MI program.

@accountingEntity

MHPICH.PICONO+DIVI; /

The field indicates the accounting entity for the shipment.

The field is taken from the event data instead of using an MI program.

@location

MHPICH.PIWHLO; /

The field indicates the warehouse ID.

The field is taken from the event data instead of using an MI program.

Shipment/ShipmentHeader/Status/Code

MHDISH.OQPGRS; MWS410MI/GetHead

The field indicates the status of a delivery.

The field indicates the status of a delivery.

Open - 00 01
Hold - 02 03
Released - 50
Allocated - 05
Partially Shipped - 65
Shipped - 60
Received - 90 95

Shipment/ShipmentHeader/WarehouseLocation/Name

MITWHL.MWWHNM; MMS005MI/GetWarehouse

The field indicates the warehouse description.

Shipment/ShipmentHeader/CarrierRouteReference/DocumentID/ID

MHDISH.OQROUT; MWS410MI/GetHead

The field indicates the transportation route. A route is determined by a loading place with one or more unloading locations. The unloading locations can be located in a geographical area or region.

Routes are used to:

- Coordinate transportation to several customers along a road or within a specified area

- Distinguish orders needing special handling, such as special deliveries to be made with a company vehicle. In this case, the route can vary every time depending on where the order's destination.

Shipment/ShipmentHeader/CarrierRouteReference/RouteStop/ID

MHDISH.OQEDES; MWS410MI/GetHead

The field indicates the ID of a geographic location or a place, such as a city, town, or airport.

These IDs are used in the route management to define:

- Valid loading points, to be assigned to supplying warehouses

- Valid unloading points, to be assigned to consignees, that is, customers, warehouses, suppliers and subcontractors

In addition to the loading / unloading parameters above, the following must be defined in order to establish a route network and to assign consignees:

- Routes, with valid loading / starting points and eventually pre-defined unloading points, depending on the route type

- Route pre-selections, where consignees are assigned to relevant route options

Shipment/ShipmentHeader/TransportationMethodCode

CSYTAB.CTPARM; MWS410MI/GetHead

First check MODF, if blank check MODL.

MODF

The field indicates the final delivery method for a delivery number.

When a delivery number is created, the value is retrieved from the original order, but it can be changed manually.

The information is used when printing transportation documents.

MODL

The field indicates how the delivery is made.

Shipment/ShipmentHeader/ShipFromParty/PartyIDs/ID

MHDISH.OQWHLO; MWS410MI/GetHead

The field indicates the warehouse ID.

Shipment/ShipmentHeader/CarrierParty/PartyIDs/ID

MHDISH.OQFWNO; MWS410MI/GetHead

Shipment

	The field indicates the forwarding agent who can be used for the transport.
Shipment/ShipmentHeader/CarrierParty/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicates supplier name, most often the supplier's company name.
Shipment/ShipmentHeader/FreightTermCode MHDISH.OQTEDF or OQTEDL; MWS410MI/GetHead	First check TEDF, if blank check TEDL. TEDF The field indicates the final delivery terms for a delivery number. When a delivery number is created, the value is retrieved from the origin order, but it could be changed manually. The information is used when printing transportation documents. TEDL The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
Shipment/ShipmentHeader/ReturnToShipFromParty/Name MITWHL.MWVHNM; MMS005MI/GetWarehouse	The field indicates the warehouse description.
Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/AddressLine CIADDR.OAADR1 OAADR2 OAADR3 OAADR4; MMS005MI/GetWarehouse	The field indicates an address line. A maximum of 36 characters may be used.
Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CityName CIADDR.OATOWN; MMS005MI/GetWarehouse	The field indicates the city in an address.
Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CountrySubDivisionCode CIADDR.ECAR; MMS005MI/GetWarehouse	The field indicates an area, province or state within a country.
Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CountryCode CIADDR.CSCD; MMS005MI/GetWarehouse	The field indicates a country.
Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/PostalCode CIADDR.PONO; MMS005MI/GetWarehouse	The field indicates a postal code for a specific address.
Shipment/ShipmentHeader/ShipToParty/PartyIDs/ID MHDISH.OQCONA; MWS410MI/GetHead	The field indicates the consignee's ID. Do not populate for DO, use ShipToParty/Location/ID instead.
Shipment/ShipmentHeader/ShipToParty/Location/ID MHDISH.OQCONA; MWS410MI/GetHead	The field indicates the consignee's ID. Use this only for DO.
Shipment/ShipmentHeader/RequiredShipDateTime MHDISH.OQDTHM; MWS410MI/GetHead	The fields indicate the requested date and time (UTC).
Shipment/ShipmentHeader/PriorityCode MHDISH.OQPRI; MWS410MI/GetHead	The field indicates the order priority.
Shipment/ShipmentHeader/TransportationTerm/IncotermsCode MHDISH.OQTEDF or OQTEDL; MWS410MI/GetHead	First check TEDF, if blank check TEDL. TEDF The field indicates the final delivery terms for a delivery number. When a delivery number is created, the value is retrieved from the origin order, but it could be changed manually. The information is used when printing transportation documents. TEDL The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
Shipment/ShipmentHeader/TrackingID MHDISH.OQETRN; MWS410MI/GetHead	The field indicates the external identification, or the forwarder's identification, of a delivery note, bill of lading, or package.
Shipment/ShipmentItem/ItemID/ID MITALO.MQITNO; MWS422MI/LstPickDetail	This field pertains to the Item Numbers belonging to the Shipment.
@accountingEntity MITALO.MQCONO+DIVI; MWS422MI/LstPickDetail	The field indicates the accounting entity for the item.
Shipment/ShipmentItem/OrderQuantity MITALO.MQTRQT; MWS422MI/LstPickDetail	

Shipment

	The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.
@unitCode CSYTAB.CTPARM; MWS422MI/LstPickDetail	The field indicates the basic unit of measure assumed in TRQT.
Shipment/ShipmentItem/SalesOrderReference/DocumentID/ID MITALO.MQRIDN; MWS422MI/LstPickDetail	The field indicates an order number. Use for transaction type 31 (Sales order).
Shipment/ShipmentItem/SalesOrderReference/LineNumber MITALO.MQRIDL+MQRIDX; MWS422MI/LstPickDetail	The field indicates the order line number and sequence number within an order line.
Shipment/ShipmentItem/DocumentReference @type	Set to DO, RO, MO or Supplier return using Infor wording. DO - Transfer RO - SupplierRMA MO - Production Order
Shipment/ShipmentItem/DocumentReference/DocumentID MITALO.MQRIDN; MWS422MI/LstPickDetail	The field indicates an order number. Use for DO, RO, MO or Supplier return. DO - Transaction type 51 RO - Transaction type 41 MO - Transaction type 11 Supplier return - Transaction type
Shipment/ShipmentItem/DocumentReference/LineNumber MITALO.MQRIDL MWS422MI/LstPickDetail	The field indicates the order line number. Use RIDL for transaction type 11(MO), 41 (RO) and 51 (D)).
Shipment/ShipmentItem/SerializedLot/Lot/LotIDs/ID MITALO.MQBANO; MWS422MI/LstPickDetail	The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics. Use only if INDI = 1, 3.
Shipment/ShipmentItem/SerializedLot/Lot/SerialNumber MITALO.MQBANO; MWS422MI/LstPickDetail	The field indicates the serial number. Use only if INDI=2.
Shipment/ShipmentItem/LineNumber MITALO.MQRIDL; MWS422MI/LstPickDetail	This field contain the same value as in following references to order: RequisitionReference/LineNumber SalesOrderReference/LineNumber DocumentReference/LineNumber
Shipment/ShipmentUnit/TrackingID MHDISH.OQDLIX; DRS100MI/LstByDelivery	The field indicates the delivery number. This unique ID for the delivery is created or updated automatically during order line entry. Several order numbers can be attached to the same delivery number.
Shipment/ShipmentUnit/NetWeightMeasure MHDISH.OQNEW2; MWS410MI/GetHead	The field indicates the total weight of all items entered on the customer order. The information is based on the respective items' net weight in for outstanding and allocated quantities on the order lines.
@unitCode CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for all weights within a company.
Shipment/ShipmentUnit/GrossWeightMeasure MHDISH.OQGRW2; MWS410MI/GetHead	The field indicates the total weight for all items that have been entered on the order. The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity
@unitCode CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for all weights within a company.
Shipment/ShipmentUnit/TotalVolumeMeasure MHDISH.OQVM32; MWS410MI/GetHead	The field indicates the volume for each item in the item file or for undelivered order lines for a customer order.

Shipment

	The latter is calculated automatically by accumulating the remaining quantity of each order line with the volume of the item.
@unitCode CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for all volumes within a company.
Shipment/ShipmentUnit/ShipmentUnitContainer/ContainerID MPTRNS.ORMANR; MWS410MI/LstPackages	The field indicates the identity of a package. A package can be packed in another package.
Shipment/ShipmentUnit/ShipmentUnitContainer/ShippingMaterial/ID MPTRNS.ORMACT; MWS410MI/LstPackages	The field indicates the ID of the packaging.
Shipment/ShipmentUnit/ShipmentUnitItem/ItemID/ID MFTRNS.OSITNO; MWS423MI/LstContents	The field indicates the item number which is a unique ID for an individual item. Items are entered and maintained in Item Master. Item number can consist up to 15 alphanumeric characters.
Shipment/ShipmentUnit/ShipmentUnitItem/ShippedQuantity MFTRNS.OSDLQT; MWS423MI/LstContents	The field indicates the delivered quantity, expressed in the item's basic U/M.
Shipment/ShipmentUnit/ShipmentUnitItem/ShippedBaseUOMQuantity MITMAS.MMUNMS; MWS423MI/LstContents	The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
Shipment/ShipmentUnit/ShipmentUnitItem/LearningWeightMeasure MPTRNS.ORMRWE; MWS423MI/LstContents	The field indicates the total weight of the item. The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity
@unitCode CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for all weights within a company.
Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/DocumentID/ID MHDISH.OQRIDN; MWS423MI/LstContents	The field indicates an order number where item is connected to.
Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/LineNumber MHDISH.OQRIDL; MWS423MI/LstContents	The field indicates an order line where item is connected to.
Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/SubLineNumber MHDISH.OQRIDX; MWS423MI/LstContents	The field indicates an order line suffix where item is connected to.
Shipment/ShipmentHeader/DocumentID/ID For Shipment: DCONSI.DACONO; DRS100MI/LstShipment For Shipment Delivery: MHDISH.OQDLIX; MWS410MI/GetHead	For Shipment: This field indicates a shipment number, which is the unique identity used to identify a shipment. For Shipment Delivery: The field indicates the delivery number. This unique ID for the delivery is created or updated automatically during order line entry. Several order numbers can be attached to the same delivery number if allowed by the dispatch policy (MWS010)."
@accountingEntity For Shipment: DCONSI.DACONO DCONSI.DADIVI.; N/A For Shipment Delivery: MHDISH.OQCONO CMNDIV.CCDIVI .; /	For Shipment: This field indicates the company and division. For Shipment Delivery: The field indicates the company and division.
@variationID	For Shipment: This field indicates the number of the times the object has been published. For Shipment Delivery: The field indicates the number of times this BOD has been published.
@lid	For Shipment: This field indicates the logical ID of tge system. For Shipment Delivery: The field indicates the logical ID of the system.
Shipment/ShipmentHeader/LastModificationDateTime For Shipment Delivery: .; MWS410MI/GetServerTime	For Shipment Delivery: The field indicates the last modification date and time.
Shipment/ShipmentHeader/DocumentDateTime For Shipment Delivery: .; MWS410MI/GetServerTime	For Shipment Delivery: The field indicates the document date and time.
Shipment/ShipmentHeader/DocumentReference	

Shipment

@type

For Shipment Delivery:
Set to "Sales Order" for RORC = 3.

Shipment/ShipmentHeader/DocumentReference/DocumentID/ID

For Shipment Delivery:
MHDISH.OQRIDN; MWS410MI/GetHead

For Shipment Delivery:
The field indicates the document reference ID. This is only applicable for Sales Order.

Shipment/ShipmentHeader/Status/Code

For Shipment:
DCONSI.DACSTL; DRS100MI/LstShipment

For Shipment:
This field indicates the status of the Shipment.

For Shipment Delivery:
MHDISH.OQPGRS; MWS410MI/GetHead

00 - Open
10 - Open
20 - Allocated
30 - Allocated
40 - Staged
50 - Loaded
60 - Shipped
90 - Cancelled

For Shipment Delivery:
The field indicates the status of a delivery.

00 - Open
01 - Open
02 - Hold
03 - Hold
05 - Allocated
50 - Released
60 - Shipped
65 - Partly Shipped
90 - Received
95 - Received

Shipment/ShipmentHeader/ShipUnitQuantity

For Shipment Delivery:
; MWS410MI/GetHead

For Shipment Delivery:
The field indicates the ship unit quantity.

Shipment/ShipmentHeader/WarehouseLocation/ID

For Shipment:
DCONSI.DAWHLO; DRS100MI/LstShipment

For Shipment:
This field indicates the warehouse ID.

For Shipment Delivery:
MHDISH.OQWHLO; MW410MI/GetHead

Warehouse is a stock zone which is used to distinguish different geographical locations within a company. The warehouse is used as a planning level for material and production. Stock zones, stock locations and items are connected to the warehouse.

For Shipment Delivery:
The field indicates the location.

@accountingEntity

For Shipment Delivery:
MHDISH.OQCONO
CMNDIV.CCDIV1; /

For Shipment Delivery:
The field indicates the company and division.

Shipment/ShipmentHeader/WarehouseLocation/Name

MITWHL.MWWHNM; MMS005MI/GetWarehouse

For Shipment:
This field indicates the warehouse description.

For Shipment Delivery:
The field indicates the warehouse description.

Shipment/ShipmentHeader/WarehouseLocation/Address/AddressLine

For Shipment Delivery:
CIADDR.OAADR1
CIADDR.OAADR2
CIADDR.OAADR3
CIADDR.OAADR4; MMS005MI/GetWarehouse

For Shipment Delivery:
The field indicates the Address of the Location.

Shipment/ShipmentHeader/WarehouseLocation/Address/CityName

For Shipment Delivery:
CIADDR.OATOWN; MMS005MI/GetWarehouse

For Shipment Delivery:
The field indicates the city.

Shipment/ShipmentHeader/WarehouseLocation/Address/CountrySubDivisionCode

For Shipment Delivery:
CIADDR.OAECAR; MMS005MI/GetWarehouse

For Shipment Delivery:
The field indicates the state.

@listID

For Shipment Delivery:
; MRS001MI/GetFieldInfo

For Shipment Delivery:
The field indicates the list ID.

Shipment/ShipmentHeader/WarehouseLocation/Address/CountryCode

For Shipment Delivery:
CIADDR.OACSCD; MMS005MI/GetWarehouse

For Shipment Delivery:
The field indicates the country code.

@listID

Shipment

For Shipment Delivery: .; MRS001MI/GetFieldInfo	For Shipment Delivery: The field indicates the list ID.
Shipment/ShipmentHeader/WarehouseLocation/Address/PostalCode For Shipment Delivery: CIADDR.OAPONO; MMS005MI/GetWarehouse	For Shipment Delivery: The field indicates the Postal Code.
Shipment/ShipmentHeader/CarrierRouteReference/DocumentID/ID For Shipment: DCONSI.DAROUT; DRS100MI/LstShipment For Shipment Delivery: MHDISH.OQROUT; MWS410MI/GetHead	For Shipment: This field indicates the transportation route. A route is determined by a loading place with one or more unloading locations. The unloading locations can be located in a geographical area or region, such as southeast Germany Routes are used to: - Coordinate transportation to several customers along a road or within a specified area - Distinguish orders needing special handling, such as special deliveries to be made with a company vehicle. In this case, the route can vary every time depending on where the order's destination. For Shipment Delivery: The field indicates the transportation route. A route is determined by a loading place with one or more unloading locations. The unloading locations can be located in a geographical area or region, such as southeast Germany. Routes are used to: - Coordinate transportation to several customers along a road or within a specified area - Distinguish orders needing special handling, such as special deliveries to be made with a company vehicle. In this case, the route can vary every time depending on where the order's destination. For Shipment Delivery: The field indicates the company and division.
@accountingEntity For Shipment Delivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /	For Shipment Delivery: The field indicates the company and division.
Shipment/ShipmentHeader/CarrierRouteReference/RouteStop/RouteDay For Shipment Delivery: MHDISH.OQDEWD; MWS410MI/GetHead	For Shipment Delivery: The field indicates the day of the week when delivery is made to a customer. This information is specified in the order header for a standing order, but can be changed for each individual order line. Alternatives 1 = Mondays 2 = Tuesdays 3 = Wednesdays 4 = Thursdays 5 = Fridays 6 = Saturdays 7 = Sundays.
Shipment/ShipmentHeader/ActualShipDateTime For Shipment: DCONSI.DADSDT DADSHM; DRS100MI/LstShipment For Shipment Delivery: MHDISH.OQDSDT OQDSHM; MWS410MI/GetHead	For Shipment: This field indicates the planned departure date. For Shipment Delivery: The field indicates the actual departure date/time of the delivery.
Shipment/ShipmentHeader/ScheduledDeliveryDateTime For Shipment: DCONSI.DARDDT DARDTM; DRS100MI/LstShipment	For Shipment: This field indicates the Planned Route Departure Date/Time
Shipment/ShipmentHeader/ActualDeliveryDateTime For Shipment: DCONSI.DAARDT/DAARHM; DRS100MI/LstShipment For Shipment Delivery: MITTRA.MTRGDT MTRGTM; MWS070MI/LstTransByOrder	For Shipment: This field indicates when a transfer from the subsidiary company has arrived to the parent company. For Shipment Delivery: The field indicates the date/time the goods were delivered.
Shipment/ShipmentHeader/EstimatedWeightMeasure For Shipment: DCONSI.DAGWTE; DRS100MI/LstShipment	For Shipment: This field indicates the Estimated Gross Weight Packed
@unitCode For Shipment:	

Shipment

CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For Shipment: This field indicates the general unit of measure for all weights within a company.
Shipment/ShipmentHeader/LoadingWeightMeasure For Shipment: DCONSI.DAGR2; DRS100MI/LstShipment	For Shipment: This field indicates the Packed Gross Weight
@unitCode For Shipment: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For Shipment: This field indicates the general unit of measure for all weights within a company.
Shipment/ShipmentHeader/NetWeightMeasure For Shipment Delivery: MHDISH.OQNEWE; MWS410MI/GetHead	For Shipment Delivery: The field indicates the total weight of all items in the delivery.
Shipment/ShipmentHeader/GrossWeightMeasure For Shipment: DCONSI.DAGRWE; DRS100MI/LstShipment	For Shipment: This field indicates the Gross Weight
For Shipment Delivery: MHDISH.OQGRW2; MWS410MI/GetHead	For Shipment Delivery: The field indicates the gross weight of all items in the delivery.
@unitCode CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For Shipment: This field indicates the general unit of measure for all weights within a company.
	For Shipment Delivery: The field indicates the general unit of measure for all weights within a company.
Shipment/ShipmentHeader/TotalVolumeMeasure For Shipment: DCONSI.DAVLME; DRS100MI/LstShipment	For Shipment: This field indicates the Estimated Volume
For Shipment Delivery: MHDISH.OQVM32; MWS410MI/GetHead	For Shipment Delivery: The field indicates the volume of all items in the delivery.
@unitCode For Shipment: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For Shipment: This field indicates the general unit of measure for all volumes within a company.
Shipment/ShipmentHeader/TransportationMethodCode For Shipment: CSYTAB.CTPARM; CRS070MI/GetDelyMethod	For Shipment: The field indicates how the delivery is made.
For Shipment Delivery: MDDADV.OVTRCA; MWS410MI/GetHead	For Shipment Delivery: The field indicates transportation equipment which is the unique code identifying a specific mode of transportation.
	The code may for instance be the license number of a truck, the flight number of an aircraft etc.
Shipment/ShipmentHeader/ShipFromParty/PartyIDs For Shipment Delivery: MHDISH.OQFWNO; MWS410MI/LstShipment	For Shipment Delivery: The field indicates the forwarding agent who can be used for the transport.
Shipment/ShipmentHeader/CarrierParty/PartyIDs/ID For Shipment: DCONSI.DAFWNO; DRS100MI/LstShipment	The field indicates the forwarding agent who can be used for the transport.
For Shipment Delivery: MHDISH.OQFWNO; MWS410MI/GetHead	
@accountingEntity For Shipment Delivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /	For Shipment Delivery: The field indicates the company and division.
Shipment/ShipmentHeader/CarrierParty/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicates supplier name, most often the supplier's company name.
Shipment/ShipmentHeader/ReturnToShipFromParty/PartyIDs/ID For Shipment: DCONSI.DAWHLO; DRS100MI/LstShipment	The field indicates the warehouse ID.
For Shipment Delivery: DCONSI.DAWHLO; MWS410MI/GetHead	
Shipment/ShipmentHeader/ReturnToShipFromParty/Name MITWHL.MWVWHNM; MMS005MI/GetWarehouse	For Shipment: The field indicates the warehouse description.
	For Shipment Delivery: The field indicates the warehouse description.

Shipment

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/ID

For Shipment Delivery:
MHDISH.MWVHLO; MWS410MI/GetHead

For Shipment Delivery:
The field indicates the location ID.

@accountingEntity

For Shipment Delivery:
MHDISH.OQCONO
CMNDIV.CCDIV1.; /

For Shipment Delivery:
The field indicates the company and division.

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/AddressLine

For Shipment:
CIADDR.OAADR1
OAADR2
OAADR3
OAADR4; MMS005MI/GetWarehouse

The field indicates an address line. A maximum of 36 characters may be used.

For Shipment Delivery:
CIADDR.OAADR1
CIADDR.OAADR2
CIADDR.OAADR3
CIADDR.OAADR4.; MMS005MI/GetWarehouse

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CityName

CIADDR.OATOWN; MMS005MI/GetWarehouse

The field indicates the city in an address.

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CountrySubDivisionCode

CIADDR.ECAR; MMS005MI/GetWarehouse

The field indicates an area, province or state within a country.

@listID

For Shipment Delivery:
.; MRS001MI/GetFieldInfo

For Shipment Delivery:
The field indicates the list ID.

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CountryCode

CIADDR.CSCD; MMS005MI/GetWarehouse

The field indicates a country.

@listID

For Shipment Delivery:
.; MRS001MI/GetFieldInfo

For Shipment Delivery:
The field indicates the list ID.

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/PostalCode

CIADDR.PONO; MMS005MI/GetWarehouse

The field indicates a postal code for a specific address.

Shipment/ShipmentHeader/ShipToParty/PartyIDs/ID

For Shipment Delivery:
MHDISH.OQCONA
MWS410MI/GetHead

For Shipment Delivery:
The field indicates the consignee's ID, which depends on the delivery's order category. If Order category is 3 (Customer order) and order line Address ID (ADID) is blank, ShipToPartyID = CONA else ShipToPartyID = CONA+ADID. CONA and ADID will be concatenated without separator. CONA has exactly 10 characters while ADID can have maximum of 6.

OOLINE.OBADID
OIS100MI/GetLine.; /

@accountingEntity

For Shipment Delivery:
MHDISH.OQCONO
CMNDIV.CCDIV1.; /

For Shipment Delivery:
The field indicates the company and division.

Shipment/ShipmentHeader/ShipToParty/Location/Name

For Shipment Delivery:
CIADDR.OAWHNM
MMS005MI/GetWarehouse

For Shipment Delivery:
The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.

OOADRE.ODCUNM
OIS100MI/GetAddress.; /

Shipment/ShipmentHeader/ShipToParty/Location/Address/AddressLine

For Shipment Delivery:
CIADDR.OAADR1
CIADDR.OAADR2
CIADDR.OAADR3
CIADDR.OAADR4
MMS005MI/GetWarehouse

For Shipment Delivery:
The field indicates an address line. A maximum of 36 characters may be used.

OCUSAD.OPADR1
OCUSAD.OPADR2
OCUSAD.OPADR3
OCUSAD.OPADR4
CRS610MI/GetBasicData,GetAddress.; /

Shipment/ShipmentHeader/ShipToParty/Location/Address/CityName

For Shipment Delivery:
CIADDR.OATOWN
MMS005MI/GetWarehouse

For Shipment Delivery:
The field indicates the city in an address.

OCUSAD.OPTOWN
CRS610MI/GetBasicData,GetAddress.; /

Shipment/ShipmentHeader/ShipToParty/Location/Address/CountrySubDivisionCode

For Shipment Delivery:
CIADDR.OAECAR

For Shipment Delivery:
The field indicates an area, province or state within a country.

Shipment

MMS005MI/GetWarehouse	
OCUSAD.OPECAR CRS610MI/GetBasicData,GetAddress.; /	
@listID For Shipment Delivery: .; MRS001MI/GetFieldInfo	
For Shipment Delivery: The field indicates the list ID.	
Shipment/ShipmentHeader/ShipToParty/Location/Address/CountryCode For Shipment Delivery: CIADDR.OACSCD MMS005MI/GetWarehouse	
For Shipment Delivery: The field indicates a country.	
OCUSAD.OPCSCD CRS610MI/GetBasicData,GetAddress .; /	
@listID For Shipment Delivery: .; MRS001MI/GetFieldInfo	
For Shipment Delivery: The field indicates the list ID.	
Shipment/ShipmentHeader/ShipToParty/Location/Address/PostalCode For Shipment Delivery: CIADDR.OAPONO MMS005MI/GetWarehouse	
For Shipment Delivery: The field indicates a postal code for a specific address.	
OCUSAD.OPPONO CRS610MI/GetBasicData,GetAddress .; /	
Shipment/ShipmentHeader/ScheduledShipDateTime For Shipment: DCONSI.DARDDT DARDTM; DRS100MI/LstShipment	
For Shipment: This field indicate the date/time the order is to be shipped by the supplier.	
For Shipment Delivery: MHDISH.OQDSDT OQDSHM; MWS410MI/GetHead	
For Shipment Delivery: The field indicates the actual ship date. It is updated at stock issue.	
Shipment/ShipmentHeader/PlannedDeliveryDateTime For Shipment Delivery: MHDISH.OQDSTD OQDTHM; MWS410MI/GetHead	
For Shipment Delivery: The field indicates the Requested Delivery Date and Time	
Shipment/ShipmentHeader/PriorityCode For Shipment Delivery: MHDISH.OQPRIO; MWS410MI/GetHead	
For Shipment Delivery: The field indicates the priority of the delivery.	
Shipment/ShipmentHeader/DestinationCountryCode For Shipment Delivery: MHDISH.OQCSCD; MWS410MI/GetHead	
For Shipment Delivery: The field indicates the country.	
@listID For Shipment Delivery: .; MRS001Mi/GetFieldInfo	
For Shipment Delivery: The field indicates the list ID.	
Shipment/ShipmentHeader/TransportationTerm/IncotermsCode For Shipment Delivery: MHDISH.MQTEDL; MWS410MI/GetHead	
For Shipment Delivery: The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.	
@listID For Shipment Delivery: .; MRS001MI/GetFieldInfo	
For Shipment Delivery: The field indicates the list ID.	
Shipment/ShipmentHeader/TransportationTerm/PlaceOfOwnershipTransferLocation/Description For Shipment Delivery: CSYTAB.CTPARM; CRS065MI/GetDelyTerm	
For Shipment Delivery: The field indicates when the liability for a delivery is transferred from the supplier to the buyer.	
Shipment/ShipmentItem/ItemID/ID For Shipment: MFTRNS.MQITNO; MWS410MI/LstItem	
For Shipment: Use DRS100MI-LstByDelivery to retrieve deliveries connected to Shipment then retrieve item numbers connected to delivery	
For Shipment Delivery: MFTRNS.OSITNO; MWS423MI/LstContents	
This field pertains to the Item Numbers belonging to the Shipment.	
For Shipment Delivery: The field indicates the item number within the Shipment.	
@accountingEntity For Shipment Delivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /	
For Shipment Delivery: The field indicates the company and division.	
Shipment/ShipmentItem/Description For Shipment: MFTRNS.MQITDS; MWS410MI/LstItem	
For Shipment: This field indicates the description of the Item.	

Shipment

For Shipment Delivery: MITMAS.MMITDS; MWS423MI/LstContents	For Shipment Delivery: The field indicates the item description.
Shipment/ShipmentItem/OrderQuantity For Shipment Delivery: MGLINE.MRTRQT; MWS411MI/GetDeliveryLine	For Shipment Delivery: The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.
@unitCode For Shipment Delivery: MITMAS.MMUNMS; MWS423MI/LstContents	For Shipment Delivery: This field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
Shipment/ShipmentItem/ShippedQuantity For Shipment: MFTRNS.MQTRQT; MWS410MI/LstItem For Shipment Delivery: MFTRNS.OSDLQT; MWS423MI/LstContents	For Shipment: This field indicates the Delivered Quantity. For Shipment Delivery: The field indicates the delivered quantity, expressed in the item's basic U/M.
@unitCode For Shipment: MITMAS.MMUNMS; MMS410MI/LstItem For Shipment Delivery: MITMAS.MMUNMS; MWS423MI/LstContents	For Shipment: This field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit. For Shipment Delivery: The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
Shipment/ShipmentItem/ShippedBaseUOMQuantity For Shipment Delivery: MFTRNS.OSDLQT; MWS423MI/LstContents	For Shipment Delivery: The field indicates the delivered quantity, expressed in the item's basic U/M.
@unitCode For Shipment Delivery: MITMAS.MMUNMS; MWS423MI/LstContents	For Shipment Delivery: The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
Shipment/ShipmentItem/SalesOrderReference/DocumentID/ID For Shipment: MHDISH.MQRIDN; MWS410MI/GetHead For Shipment Delivery: MFTRNS.OSRIDN; MWS423MI/LstContents	For Shipment: This field indicates an order number. For Shipment Delivery: The field indicates an order number.
@accountingEntity For Shipment Delivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /	For Shipment Delivery: The field indicates the company and division.
Shipment/ShipmentItem/SalesOrderReference/LineNumber For Shipment Delivery: MFTRNS.OSRIDL; MWS410MI/LstContents	For Shipment Delivery: The field indicates the order line number.
Shipment/ShipmentItem/SerializedLot/ItemQuantity For Shipment Delivery: MFTRNS.OSDLQT; MWS410MI/LstContents	For Shipment Delivery: This field indicates the delivered quantity, expressed in the item's basic U/M.
@unitCode For Shipment Delivery: MITMAS.MMUNMS; MWS423MI/LstContents	For Shipment Delivery: The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
Shipment/ShipmentItem/LineNumber	For Shipment Delivery: Incrementing counter starting from 1.
Shipment/ShipmentUnit/TrackingID For Shipment: MHDISH.OQDLIX; DRS100MI/LstByDelivery For Shipment Delivery: MPTRNS.ORPANR; MWS410MI/LstPackageLine	For Shipment: This field indicates the delivery number. This unique ID for the delivery is created or updated automatically during order line entry. Several order numbers can be attached to the same delivery number. For Shipment Delivery: The field indicates the identity of a package.
Shipment/ShipmentUnit/ContainerID For Shipment Delivery: MPTRNS.ORCAMU; MWS410MI/LstPackageLine	For Shipment Delivery: The field indicates the ID of the packaging, and is defined in (MMS050).
Shipment/ShipmentUnit/NetWeightMeasure	

Shipment

For Shipment:
MHDISH.OQNEW2; MWS410MI/GetHead

For Shipment Delivery:
MFTRNS.OSNEWE; MWS410MI/LstPackageLine

For Shipment:
This field indicates the total weight of all items entered on the customer order.

The information is based on the respective items' net weight in for outstanding and allocated quantities on the order lines.

For Shipment Delivery:
The field indicates the total weight of all items entered on the customer order.

The information is based on the respective items' net weight in (MMS001/F) for outstanding and allocated quantities on the order lines.

@unitCode

For Shipment:
CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds

For Shipment:
This field indicates the general unit of measure for all weights within a company.

Shipment/ShipmentUnit/GrossWeightMeasure

For Shipment:
MHDISH.OQGRW2; MWS410MI/GetHead

For Shipment:
This field indicates the total weight for all items that have been entered on the order.

The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity

For Shipment Delivery:
The field indicates the total weight for all items that have been entered on the order.

The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity

@unitCode

CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds

For Shipment:
This field indicates the general unit of measure for all weights within a company.

For Shipment Delivery:
The field indicates the unit code.

Shipment/ShipmentUnit/TotalVolumeMeasure

For Shipment:
MHDISH.OQVM32; MWS410MI/GetHead

For Shipment:
This field indicates the volume for each item in the item file or for undelivered order lines for a customer order.

The latter is calculated automatically by accumulating the remaining quantity of each order line with the volume of the item.

For Shipment Delivery:
The field indicates the volume for each item in the item file or for undelivered order lines for a customer order.

The latter is calculated automatically by accumulating the remaining quantity of each order line with the volume of the item.

@unitCode

CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds

For Shipment:
This field indicates the general unit of measure for all volumes within a company.

For Shipment Delivery:
The field indicates the unit code.

Shipment/ShipmentUnit/ShipmentUnitContainer/ContainerID

For Shipment:
MPTRNS.ORPANR; MWS410MI/LstPackages

For Shipment:
This field indicates the identity of a package. A package can be packed in another package.

Shipment/ShipmentUnit/ShipmentUnitContainer/ShippingMaterial/ID

For Shipment:
MPTRNS.ORPACT; MWS410MI/LstPackages

For Shipment:
This field indicates the ID of the packaging.

Shipment/ShipmentUnit/ShipmentUnitItem/ItemID/ID

MFTRNS.OSITNO; MWS423MI/LstContents

For Shipment:
This field indicates the item number which is a unique ID for an individual item. Items are entered and maintained in Item Master. Item number can consist up to 15 alphanumeric characters.

For Shipment Delivery:
The field indicates the item number.

Shipment/ShipmentUnit/ShipmentUnitItem/ItemID/RevisionID

For Shipment Delivery:

Shipment

MHDISH.OQCONO CMNDIV.CCDIVI.; /	For Shipment Delivery: 0
Shipment/ShipmentUnit/ShipmentUnitItem/ShippedQuantity MFTRNS.OSDLQT; MWS423MI/LstContents	For Shipment: This field indicates the delivered quantity, expressed in the item's basic U/M. For Shipment Delivery: The field indicates quantity delivered expressed in an alternate U/M.
@unitCode For Shipment Delivery: MITMAS.MMUNMS; MWS423MI/LstContents	For Shipment Delivery: Basic U/M The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
Shipment/ShipmentUnit/ShipmentUnitItem/ShippedBaseUOMQuantity For Shipment: MITMAS.MMUNMS; MWS423MI/LstContents	For Shipment: This field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
Shipment/ShipmentUnit/ShipmentUnitItem/EstimatedWeightMeasure For Shipment Delivery: MFTRNS.OSNEWE; MWS423MI/LstContents	For Shipment Delivery: The field indicates the total weight of all items entered on the customer order. The information is based on the respective items' net weight in (MMS001/F) for outstanding and allocated quantities on the order lines.
Shipment/ShipmentUnit/ShipmentUnitItem/LoadingWeightMeasure For Shipment: MPTRNS.ORGRWE; MWS423MI/LstContents For Shipment Delivery: MFTRNS.OSGRWE; MWS423MI/LstContents	For Shipment: This field indicates the total weight of the item. The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity For Shipment Delivery: The field indicates the total weight for all items that have been entered on the order. The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity
@unitCode CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For Shipment: This field indicates the general unit of measure for all weights within a company. For Shipment Delivery: The field indicates the unit code.
Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/DocumentID/ID For Shipment: MHDISH.OQRIDN; MWS423MI/LstContents For Shipment Delivery: MITALO.MQRIDN; MWS423MI/LstContents	For Shipment: This field indicates an order number where item is connected to. For Shipment Delivery: The field indicates the order number.
@accountingEntity For Shipment Delivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /	For Shipment Delivery: 0
Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/LineNumber For Shipment: MHDISH.OQRIDL; MWS423MI/LstContents For Shipment Delivery: MITALO.MQRIDL; MWS423MI/LstContents	For Shipment: This field indicates an order line where item is connected to. For Shipment Delivery: The field indicates the order line number.
Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/SubLineNumber For Shipment: MHDISH.OQRIDX; MWS423MI/LstContents For Shipment Delivery: MITALO.MQRIDX; MWS423MI/LstContents	For Shipment: This field indicates an order line suffix where item is connected to. For Shipment Delivery: The field indicates the line suffix.

SourceSystemGLMovement

SourceSystemGLMovement/IDs/ID

For Actuals:
FBAVAL.YEA4+PERI+BIT1->BIT7; GLS215MI/GetBitFromPtid

For Budgets:
FBUDET.BUPE+AIT1+AIT2+AIT3+AIT4+AIT5+AIT6+AIT7+CUCD
+BUNO+BVER; BUS100MI/IstBudPerVal

For Actuals:
If BAKY = 8, display the fields: YEA4+PERI+Accounting string.
Spaces will be underscores (_). Delimiter will be dot (.) If BAKY = 8,
display the fields:

For Budgets:
Taken from the event; Budget period + Accounting dimension 1 to 7 +
Currency + Budget number + Budget version

@accountingEntity

For Actuals:
FBAVAL.DIVI; GLS215MI/GetBitFromPtid

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to
translate.

SourceSystemGLMovement/Status/Code

@listID

For Actuals:
Status is either Open or Closed

SourceSystemGLMovement/GLMovementRow/LedgerSetupReference/BookInstanceID

For Budgets:
FBUDET.BCBVER+BCBUNO; BUS100MI/IstBudPerVal

For Budgets:
Taken from the event; Combination of budget version and budget
number.

SourceSystemGLMovement/GLMovementRow/AccountingBookTypeCode

Constant; /

For Actuals:
Constant = 'Actual'

For Budgets:
Constant = 'Budget'

SourceSystemGLMovement/GLMovementRow/PostingKey

For Actuals:
FBAVAL.YEA4+PERI+BIT1->BIT7; GLS215MI/GetBitFromPtid

For Actuals:
YEA4+PERI+Accounting string. Spaces will be underscores (_).
Delimiter will be dot (.)

For Budgets:
FBUDET.BCBUPE
+BCAIT1+BCAIT2+BCAIT3+BCAIT4+BCAIT5+BCAIT6+BCAIT7+BCCUC
+BCBUNO+BCBVER; BUS100MI/IstBudPerVal

For Budgets:
Taken from the event; Budget period + Accounting dimension 1 to 7 +
Currency + Budget number + Budget version

SourceSystemGLMovement/GLMovementRow/GLAccount/GLNominalAccount

For Actuals:
FBAVAL.BIT1; GLS215MI/GetBitFromPtid

For Actuals:
The field indicates a balance identity in a balance dimension.

For Budgets:
FBUDET.BCAIT1; BUS100MI/IstBudPerVal

A selection may be entered for each of the seven levels. The contents
of these levels are determined by the heading that is linked to each
field.

For Budgets:
Taken from the event; Accounting dimension 1

SourceSystemGLMovement/GLMovementRow/GLAccount/GLNominalAccountName

For Actuals:
FCHACC.TX40; CRS630MI/getAccountID

For Actuals:
The field indicates a description of the current identity.

For Budgets:
FCHACC.EATX40; CRS630MI/getAccountID

For Budgets:
GL account name description

SourceSystemGLMovement/GLMovementRow/AccountType

FCHACC.AT01, AT02; CRS630MI/getAccountID

If AT01 = 1 then 'BalanceSheet'. If AT02 = 1 then 'ProfitAndLoss'

SourceSystemGLMovement/GLMovementRow/DimensionCodes/DimensionCode

For Actuals:
FBAVAL.BIT2-7; GLS215MI/GetBitFromPtid

For Actuals:
The field indicates a balance identity in a balance dimension.

For Budgets:
FBUDET.BCAIT2-BCAIT7; BUS100MI/IstBudPerVal

A selection may be entered for each of the seven levels. The contents
of these levels are determined by the heading that is linked to each
field.

For Budgets:
Taken from the event; Accounting dimension 2 to 7.

@listID

CSYTAB.PARM; CRS185MI/getGeneralCode

Names from CRS012

@sequence

For Actuals:
FBAVAL.BIT2-7; GLS215MI/GetBitFromPtid

For Actuals:
BIT2 = 2, BIT3 = 3 etc.

For Budgets:
FBUDET.BCAIT2-BCAIT7; BUS100MI/IstBudPerVal

For Budgets:
Taken from the event; Accounting dimension 2 to 7.

SourceSystemGLMovement/GLMovementRow/AccountingDate/PeriodID

For Actuals:
FBAKEY.YEA4+PERI; GLS215MI/getPeriodBalance

For Actuals:
Period year

SourceSystemGLMovement

For Budgets: FBUDET.BUPE; BUS100MI/IstBudPerVal	For Budgets: Position 4-6 of budget period
SourceSystemGLMovement/GLMovementRow/AccountingDate/Year	
For Actuals: FBAKEY.YEA4; GLS215MI/getPeriodBalance	For Actuals: The field indicates the year. It is entered using four positions, for example, 2002.
For Budgets: FBUDET.BUPE; BUS100MI/IstBudPerVal	For Budgets: Position 0-3 of budget period
SourceSystemGLMovement/GLMovementRow/DebitMovement/FunctionalAmount	
For Actuals: FBAVAL.ACAD; GLS215MI/getPeriodBalance	For Actuals: Local currency amount
For Budgets: FBUDET.BLAM; BUS100MI/IstBudPerVal	For Budgets: If BLAM >= 0; Local currency amount - budget
@currencyID	
For Actuals: CMNDIV.CUCD; MNS100MI/getBasicData	For Actuals: Currency code from MNS100
For Budgets: CMNDIV.LOCD; MNS100MI/getBasicData	For Budgets: Currency code taken from the company/division setup
SourceSystemGLMovement/GLMovementRow/DebitMovement/Amount	
For Actuals: FBAVAL.CUAD; GLS215MI/getPeriodBalance	For Actuals: Foreign currency amount. Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting
For Budgets: FBUDET.BCUA; BUS100MI/IstBudPerVal	For Budgets: Foreign currency amount - budget
@currencyID	
For Actuals: FCHACC.CUCD; CRS630MI/getAccountID	For Actuals: Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting
For Budgets: FBUDET.CUCD; BUS100MI/IstBudPerVal	For Budgets: Currency code
SourceSystemGLMovement/GLMovementRow/DebitMovement/ReportingCurrencyAmount	
For Actuals: FBAVAL.TCAD; GLS215MI/getPeriodBalance	For Actuals: Third currency amount. Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting
@currencyID	
For Actuals: CSYPAR.PARM; GLS215MI/getPeriodBalance	For Actuals: Third currency
SourceSystemGLMovement/GLMovementRow/CreditMovement/FunctionalAmount	
For Actuals: FBAVAL.ACAC; GLS215MI/getPeriodBalance	For Actuals: Local currency amount
For Budgets: FBUDET.BLAM; BUS100MI/IstBudPerVal	For Budgets: If BLAM < 0
@currencyID	
For Actuals: CMNDIV.CUCD; MNS100MI/getBasicData	For Actuals: Currency code from MNS100
For Budgets: CMNDIV.LOCD; MNS100MI/getBasicData	
SourceSystemGLMovement/GLMovementRow/CreditMovement/Amount	
For Actuals: FBAVAL.CUAC; GLS215MI/getPeriodBalance	For Actuals: Foreign currency amount. Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting
For Budgets: FBUDET.BCUA; BUS100MI/IstBudPerVal	For Budgets: if BCUA < 0; Foreign currency amount - budget
@currencyID	
For Actuals: FCHACC.CUCD; CRS630MI/getAccountID	For Actuals: Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting
For Budgets: FBUDET.CUCD; BUS100MI/IstBudPerVal	For Budgets: Currency code
SourceSystemGLMovement/GLMovementRow/CreditMovement/ReportingCurrencyAmount	
For Actuals: FBAVAL.TCAC; GLS215MI/getPeriodBalance	For Actuals: Third currency amount. Only included if currency connection = 2 on

SourceSystemGLMovement

@currencyID

For Actuals:
CSYPAR.PARM; GLS215MI/getPeriodBalance

account (currency connection =2= only the currency code of the account can be used for posting

For Actuals:
Third currency

SourceSystemGLMovement/GLMovementRow/NetMovement/FunctionalAmount

For Actuals:
FBAVAL.ACAD+ACAC; GLS215MI/getPeriodBalance

Local currency amount

For Budgets:
FBUDET.BLAM; BUS100MI/IstBudPerVal

@currencyID

For Actuals:
CMNDIV.CUCD; MNS100MI/getBasicData

Currency code from MNS100

For Budgets:
CMNDIV.LOCD; MNS100MI/getBasicData

SourceSystemGLMovement/GLMovementRow/NetMovement/Amount

For Actuals:
FBAVAL.CUCD+CUCC; GLS215MI/getPeriodBalance

For Actuals:
Foreign currency amount. Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting

For Budgets:
FBUDET.BCUA; BUS100MI/IstBudPerVal

For Budgets:
Foreign currency amount

@currencyID

For Actuals:
FCHACC.CUCD; CRS630MI/getAccountID

For Actuals:
Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting

For Budgets:
FBUDET.CUCD; BUS100MI/IstBudPerVal

For Budgets:
Currency code

SourceSystemGLMovement/GLMovementRow/GLFullAccount

For Actuals:
FBAKEY.BIT1; GLS215MI/GetBitFromPtid

For Actuals:
Account

For Budgets:
FBUDET.AIT1; BUS100MI/IstBudPerVal

For Budgets:
Taken from the event; Accounting dimension 1

SourceSystemJournalEntry

SourceSystemJournalEntry/JournalEntryHeader/JournalID

FGLEDG.YEA4;VSER,VONO; GLS200MI/LstVoucherLine

Concatenated Year, Voucher series number and Voucher number

@accountingEntity

; GLS200MI/LstVoucherLine

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.
E.g. 780_AAA
It is possible to translate using CRS881, but we recommend NOT to translate.

@variationID

Populated according to standard

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/DocumentDateTime

System date time

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/PeriodID

FGLEDG.CYP6; GLS200MI/LstVoucherLine

Financial period

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/PostDateTime

FGLEDG.ACDT; GLS200MI/LstVoucherLine

Accounting Date of first line of voucher

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/Year

FGLEDG.YEA4; GLS200MI/LstVoucherLine

Year for first line of voucher

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/EffectiveTimePeriod/StartDateTime

CSYPER.FDAT; CRS910MI/Select

First Datetime of period

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/EffectiveTimePeriod/EndDateTime

CSYPER.TDAT; CRS910MI/Select

Last Datetime of period

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/Amount

FGLEDG.CUAM; GLS200MI/GetVoucherHead

The field indicates the currency amount, that is, the recorded amount in the appropriate currency.

There are three key currency types in M3 BE:

1. Local currency - the base, domestic currency used by the company and to which all transactions are converted in the general ledger. A value expressed in this currency is called local amount.

2. Foreign currency - any other currency used. A value expressed in such a currency is called currency amount.

3. Third currency - a currency with special status, such as the euro within the Monetary Union (EMU), or the U.S. dollar. A third currency may be useful for reporting and comparison purposes, for example when you wish to present your figures in a stable currency.

@currencyID

FGLEDG.CUCD; GLS200MI/GetVoucherHead

Foreign currency code

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/FunctionalAmount

FGLEDG.ACAM; GLS200MI/GetVoucherHead

Sum of accounted amount

@currencyID

CMNDIV.CUCD; MNS100MI/GetBasicData

Local currency currency code

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/Description

CSYTAB.TX40; CRS175MI/GetGeneralCode

Description of FAM function in CRS405/E. STCO = FEID

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/LedgerType

Constant.; /

Constant = 'Actual'

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingJournalReference/ID

FGLEDG.FEID; GLS200MI/GetVoucherHead

Reference to accounting journal BOD, FAM Entry ID on transaction is used

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/LedgerSetupReference/DocumentID/ID

FGLEDG.DIVI; GLS200MI/GetVoucherHead

Division

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/JournalStatus/Code

Constant.; /

Constant = 'Final'

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/SourceSystemJournalCode

Constant.; /

Constant = 'SourceLedger'

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/EnteredAudit/PersonReference/IDs/ID

FGLEDG.CHID; GLS200MI/LstVoucherLine

Change ID

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/EnteredAudit/PersonReference/Name

CMNUSR.TX40; MNS150MI/GetUserData

Full Name from User master

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/EnteredAudit/DateTime

FGLEDG.RGDT, RGTM; GLS200MI/LstVoucherLine

Registration date time

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ModifiedAudit/PersonReference/IDs/ID

FGLEDG.CHID; GLS200MI/LstVoucherLine

Change ID

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ModifiedAudit/PersonReference/Name

CMNUSR.TX40; MNS150MI/GetUserData

Full Name from User master

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ModifiedAudit/DateTime

FGLEDG.LMDT; GLS200MI/LstVoucherLine

Last modified date

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/PostedAudit/PersonReference/IDs/ID

FGLEDG.CHID; GLS200MI/LstVoucherLine

Change ID

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/PostedAudit/PersonReference/Name

SourceSystemJournalEntry

CMNUSR.TX40; MNS150MI/GetUserData	Full Name from User master
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/PostedAudit/DateTime FGLEDG.LMDT; GLS200MI/LstVoucherLine	Last modified date
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ExchangeRateDateTime FGLEDG.ACDT; GLS200MI/LstVoucherLine	Accounting date
SourceSystemJournalEntry/JournalEntryLine/Amount FGLEDG.CUAM; GLS200MI/LstVoucherLine	Foreign currency amount
@currencyID FGLEDG.CUCD; GLS200MI/LstVoucherLine	Four foreign currency code
SourceSystemJournalEntry/JournalEntryLine/FunctionalAmount FGLEDG.ACAM; GLS200MI/LstVoucherLine	Local currency amount
@currencyID CMNDIV.CUCD; MNS100MI/GetBasicData	Local currency code
SourceSystemJournalEntry/JournalEntryLine/AmountToFunctionalExchangeRate/RateNumeric FGLEDG.ARAT; GLS200MI/LstVoucherLine	Exchange rate
SourceSystemJournalEntry/JournalEntryLine/AmountToFunctionalExchangeRate/SourceUnitBaseNumeric CSYTAB.RAFA; CRS175MI/GetGeneralCode	Rate factor for transaction currency code
SourceSystemJournalEntry/JournalEntryLine/AmountToFunctionalExchangeRate/TargetUnitBaseNumeric CSYTAB.RAFA; CRS175MI/GetGeneralCode	Rate factor for local currency code
SourceSystemJournalEntry/JournalEntryLine/AmountToFunctionalExchangeRate/DivisionIndicator CMNDIV.DMCU; MNS100MI/GetBasicData	If DMCU equals 1 then DivisionIndicator is 'false'; if DMCU equals 2 then DivisionIndicator is 'true'
SourceSystemJournalEntry/JournalEntryLine/AmountToFunctionalExchangeRate/CurrencyRateTypeReference/DocumentID/ID FGLEDG.CRTP; GLS200MI/LstVoucherLine	Rate type
SourceSystemJournalEntry/JournalEntryLine/AlternativeCurrencyAmount FGLEDG.TCAM; GLS200MI/LstVoucherLine	Third currency amount
@currencyID FGLEDG.THCC; GLS200MI/LstVoucherLine	Currency code from CRS750
SourceSystemJournalEntry/JournalEntryLine/GLAccount/GLNominalAccount FGLEDG.AIT1; GLS200MI/LstVoucherLine	Account
SourceSystemJournalEntry/JournalEntryLine/GLAccount/GLNominalAccountName FCHACC.TX40; CRS630MI/GetAccountID	Account description
@languageID FCHIDL.LNCD; CRS630MI/LstAccountLng	The field indicates the language in which external documents are to be printed. Note that invoices in the order system are printed in the language indicated for the invoice recipient.
SourceSystemJournalEntry/JournalEntryLine/GLAccount/AccountingChartReference/ID Constant.; /	Constant 'AccountingChartStandard'
SourceSystemJournalEntry/JournalEntryLine/DimensionCodes/DimensionCode FGLEDG.AIT2-AIT7; GLS200MI/LstVoucherLine	Loop through AIT2->AIT7
@listID CSYTAB.multiple; CRS175MI/GetGeneralCode	YGAI52, YGAI53, YGAI54, YGAI55, YGAI56, YGAI57
@sequence Constant.; /	Values '1' -> '6'
SourceSystemJournalEntry/JournalEntryLine/SourceLine FGLEDG.JSNO; GLS200MI/LstVoucherLine	Journal sequence number
SourceSystemJournalEntry/JournalEntryLine/DebitCreditFlag FGLEDG.DBCR; GLS200MI/LstVoucherLine	"DEBIT" or "CREDIT"
SourceSystemJournalEntry/JournalEntryLine/SourceAccountingDate/PeriodID .; GLS200MI/LstVoucherLine	Period
SourceSystemJournalEntry/JournalEntryLine/SourceAccountingDate/PostDateTime FGLEDG.ACDT; GLS200MI/LstVoucherLine	Accounting Date
SourceSystemJournalEntry/JournalEntryLine/SourceAccountingDate/Year FGLEDG.YEA4; GLS200MI/LstVoucherLine	Year
SourceSystemJournalEntry/JournalEntryLine/Description FGLEDG.VTXT; GLS200MI/LstVoucherLine	Voucher text
SourceSystemJournalEntry/JournalEntryLine/GLFullAccount FGLEDG.AIT1; GLS200MI/LstVoucherLine	Accounting dimension 1 = Account

SupplierPartyMaster

SupplierPartyMaster/PartyIDs/ID CIDMAS.IDSUNO; CRS620MI/GetBasicData	SUTY = 0, 1, 2, 3, 6, 8 (exclude Forwarding agent => CarrierPartyMaster)
@variationID	A sequence number.
@lid	The logical ID of the system that is this SOR for this noun instance.
SupplierPartyMaster/PartyIDs/DisplayID CIDMAS.IDSUNO; CRS620MI/GetBasicData	The field indicates the unique identity of a supplier.
SupplierPartyMaster/PartyIDs/TaxID CIDMAS.IDCORG; CRS620MI/GetBasicData	The field indicates the supplier's organization number.
@schemeName CIDMAS.IDFWSC; CRS620MI/GetBasicData	The field indicates Standard Carrier Alpha Code (SCAC).
SupplierPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC; CRS620MI/GetBasicData	The field indicates Standard Carrier Alpha Code (SCAC).
SupplierPartyMaster/LastModificationDateTime CIDMAS CIDVEN.IDLMDT IILMDT; CRS620MI/GetUserData	0
SupplierPartyMaster/LastModificationPerson/IDs/ID	LastModificationPerson/IDs/ID is mapped to CHID. CHID is retrieved from EventData.
@accountingEntity CIDMAS.IDCONO.; /	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 780_AAA It is possible to translate using CRS881, but we recommend NOT to translate.
SupplierPartyMaster/LastModificationPerson/Name CSYUSR.CRRENM; MNS150MI/GetUserData	LastModificationPerson/Name is retrieved from LastmodificationPerson/IDs/ID: CHID (ChangedBy) is retrieved from EventData.
SupplierPartyMaster/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicates supplier name.
SupplierPartyMaster/Location/Address/AddressLine CIDADR.SAADR1/CIDADR.SAADR2/CIDADR.SAADR3/ CIDADR.SAADR4; CRS620MI/LstAddresses	The field indicates an address line. Address line 3 and 4 may be concatenated from other address information. It is controlled in M3 BE whether the country is set up with a formatting rule or not.
@sequence	The field indicates the Address Line sequence
SupplierPartyMaster/Location/Address/CityName CIDADR.SATOWN; CRS620MI/LstAddresses	The field indicates the city in an address
SupplierPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; CRS620MI/LstAddresses	The field indicates an area, province or state within a country.
SupplierPartyMaster/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses	The field indicates a country.
@listID N/A.; MRS001MI/GetFieldInfo	Code list ID = "Countries"
SupplierPartyMaster/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses	The field indicates a postal code for a specific address.
SupplierPartyMaster/Location/Status/EffectiveDateTime CIDADR.SASTDT; CRS620MI/LstAddresses	The field indicates the date from which this record is valid.
SupplierPartyMaster/Communication @sequence	Communication@sequence 1 =' PHNO' Communication@sequence 2 = 'PHN2' Communication@sequence 3 ='TFNO'
SupplierPartyMaster/Communication/ChannelCode	Phone: PHNO Email: EMAL
SupplierPartyMaster/Communication/UseCode	Use code: Office: PHNO and EMAL Fax: TFNO
SupplierPartyMaster/Contact/ID CIDREF.IRRFTY IRRFID; CRS620MI/LstSupplierRef	The field indicates the ID of the contact. It is concatenated from IRRFTY and IRRFID
SupplierPartyMaster/Contact/Name CIDREF.IRYRE1; CRS620MI/GetSupplierRef	Name of contact
SupplierPartyMaster/Contact/Communication/ChannelCode	Channel codes: Phone, Email, Fax are used to decide what API field is to be used.

SupplierPartyMaster

	Phone: CRS620MI/UpdSupplierRef/PHNO Fax: CRS620MI/UpdSupplierRef/TFNO
@listID	Set to "Communication Channels"
SupplierPartyMaster/Contact/Communication/DialNumber CIDREF.IRPHNO IRTFNO; CRS620MI/AddSupplierRef UpdSupplierRef	Depending on channel code add DialNumber directly after CountryDialing+Area Dialing element value as part of phone or fax number if element exists
SupplierPartyMaster/Contact/Communication/URI CIDREF.IREMAI; CRS620MI/LstSupplierRef	The field indicates an e-mail address for the contact
SupplierPartyMaster/PaymentTermID CIDVEN.IITEPY; CRS620MI/GetBasicData	0
SupplierPartyMaster/PaymentMethodCode CIDVEN.IIPYME; CRS620MI/GetBasicData	0
@listID	Set listID = "Payment Methods"
SupplierPartyMaster/FinancialParty/PartyIDs/ID CBANAC.BCBKNO; CRS692MI/GetBasicData	Supplier bank. Bank party master interface in M3 is CRS690MI
SupplierPartyMaster/FinancialParty/Location/Address/AddressLine CIDADR.SAADR1 SAADR2 SAADR3 SAADR4; CRS620MI/GetAddress	TODO: how do we know if the FinancialParty is a bank or insurance company? Are there any indicator for that in the inbound ProcessSupplierPartyMaster BOD? Bank address can be added to CIDADR, address type to use: 10 = Bank address
SupplierPartyMaster/FinancialParty/Location/Address/CityName CIDADR.SATOWN; CRS620MI/GetAddress	City name
SupplierPartyMaster/FinancialParty/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; CRS620MI/GetAddress	Area/state
SupplierPartyMaster/FinancialParty/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/GetAddress	Country code
SupplierPartyMaster/FinancialParty/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/GetAddress	Postal number
SupplierPartyMaster/FinancialParty/BranchParty/PartyIDs/TaxID CBANAC.BCBRNO; CRS692MI/GetBasicData	Branch number? VAT Registration number
SupplierPartyMaster/FinancialParty/FinancialAccount/ID CBANAC.BCBKID; CRS692MI/GetBasicData	Bank account identity. CRS692MI/AddBankAccount/BKTP should be equal to 3 = Supplier bank account. ACHO should be equal to SUNO. Status STAT = ? Bank priority CBPY = ? and Language LNCD.
SupplierPartyMaster/FinancialParty/FinancialAccount/IBANID CBANAC.BCIBAN; CRS692MI/GetBasicData	International bank account number
SupplierPartyMaster/FinancialParty/FinancialAccount/CurrencyCode CBANAC.BCCUCD; CRS692MI/GetBasicData	Currency code
SupplierPartyMaster/FinancialParty/FinancialAccount/Name CBANAC.BCBANA; CRS692MI/GetBasicData	Bank account name.
@languageID CBANAC.BCBANA; CRS692MI/GetBasicData	Bank account name.
SupplierPartyMaster/FinancialParty/FinancialAccount/Status/ArchiveIndicator	When this indicator is true do not add the account(?)
SupplierPartyMaster/SalesContact/ID CIDREF.IRRFID; CRS620MI/GetBasicData	In M3 BE supplier contacts are created using reference types (mandatory). Add this contact with CRS620MI/AddSupplierRef/RFTY equal to 10 = Purchase, (15 = Repair or subcontract, 20 = Delivery receipt, 25 = Claim, 30 = Financial, 35 = Agreement)
@accountingEntity CIDMAS.IDCONO.; /	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 780_AAA It is possible to translate using CRS881, but we recommend NOT to translate.
SupplierPartyMaster/SalesContact/Name CIDREF.IRYRE1; CRS620MI/GetSupplierRef	Name of contact
SupplierPartyMaster/SalesContact/Communication/ChannelCode	Phone: PHNO Email: EMAL
SupplierPartyMaster/SalesContact/Communication/UseCode	Use code: Office: PHNO and EMAL Fax: TFNO
SupplierPartyMaster/SalesContact/Communication/CountryDialing CIDREF.IRPHNO IRTFNO; CRS620MI/GetSupplierRef	Depending on channel code add CountryDialing element value as part of phone or fax number if element exists
SupplierPartyMaster/SalesContact/Communication/AreaDialing CIDREF.IRPHNO	

SupplierPartyMaster

IRTFNO; CRS620MI/GetSupplierRef	Depending on channel code add AreaDialing directly after CountryDialing element value as part of phone or fax number if element exists
SupplierPartyMaster/SalesContact/Communication/DialNumber CIDREF.IRPHNO IRTFNO; CRS620MI/GetSupplierRef	Depending on channel code add DialNumber directly after CountryDialing+Area Dialing element value as part of phone or fax number if element exists
SupplierPartyMaster/SalesContact/Communication/URI CIDREF.IREMAL ; CRS620MI/GetSupplierRef	0
SupplierPartyMaster/ShippingContact/ID CIDREF.IRRFID; CRS620MI/GetSupplierRef	In M3 BE supplier contacts are created using reference types (mandatory). Add this contact with CRS620MI/AddSupplierRef/RFTY equal to 20 = Delivery receipt (10 = Purchase, 15 = Repair or subcontract, 25 = Claim, 30 = Financial, 35 = Agreement)
@accountingEntity CIDMAS.IDCONO.; /	AccountingEntity for M3 is defaulted as a combination of CONO DIVI.
SupplierPartyMaster/ShippingContact/Name CIDREF.IRYRE1; CRS620MI/GetSupplierRef	E.g. 780 AAA
SupplierPartyMaster/ShippingContact/Communication/ChannelCode	Channel codes: Phone, Email. Phone: CRS620MI/GetSupplierRef/PHNO Email: CRS620MI/GetSupplierRef/EMAL
SupplierPartyMaster/ShippingContact/Communication/UseCode	Use code: Office: PHNO and EMAL Fax: TFNO
SupplierPartyMaster/ShippingContact/Communication/URI CIDREF.IREMAL ; CRS620MI/GetSupplierRef	E-mail address of the contact
SupplierPartyMaster/CustomerServiceContact/ID CIDREF.IRRFID; CRS620MI/GetSupplierRef	In M3 BE supplier contacts are created using reference types (mandatory). Add this contact with CRS620MI/AddSupplierRef/RFTY equal to 15 = Repair or subcontract (10 = Purchase, 20 = Delivery receipt, 25 = Claim, 30 = Financial, 35 = Agreement)
@accountingEntity CIDMAS.IDCONO.; /	AccountingEntity for M3 is defaulted as a combination of CONO DIVI.
SupplierPartyMaster/CustomerServiceContact/Name CIDREF.IRYRE1; CRS620MI/GetSupplierRef	E.g. 780 AAA
SupplierPartyMaster/CustomerServiceContact/Communication/ChannelCode	Channel codes: Phone, Email, Fax are used to decide what API field is to be used. Phone: CRS620MI/AddSupplierRef/PHNO Fax: CRS620MI/AddSupplierRef/TFNO
SupplierPartyMaster/CustomerServiceContact/Communication/UseCode	Use code: Office: PHNO and EMAL Fax: TFNO
SupplierPartyMaster/CustomerServiceContact/Communication/CountryDialing CIDREF.IRPHNO IRTFNO; CRS620MI/GetSupplierRef	Depending on channel code add CountryDialing element value as part of phone or fax number if element exists
SupplierPartyMaster/CustomerServiceContact/Communication/AreaDialing CIDREF.IRPHNO IRTFNO; CRS620MI/GetSupplierRef	Depending on channel code add AreaDialing directly after CountryDialing element value as part of phone or fax number if element exists
SupplierPartyMaster/CustomerServiceContact/Communication/DialNumber CIDREF.IRPHNO IRTFNO; CRS620MI/GetSupplierRef	Depending on channel code add DialNumber directly after CountryDialing+Area Dialing element value as part of phone or fax number if element exists
SupplierPartyMaster/CustomerServiceContact/Communication/URI CIDREF.IREMAL ; CRS620MI/GetSupplierRef	E-mail address of the contact
SupplierPartyMaster/Status/Code CIDMAS.IDSTAT; CRS620MI/GetBasicData	The field indicates the supplier status. M3 BE status is translated according to: 10 = Pending 20 = Open 30 = Hold 90 = Deleted
SupplierPartyMaster/CurrencyCode CIDVEN.IICUCD; CRS620MI/GetBasicData	0
@listID	Set to listID = "Currency"

SupplierPartyMaster

SupplierPartyMaster/Classification/Codes/Code	
CIDMAS	0 = Supplier - default when no code is available (istID = "Supplier Categories")
CIDVEN.IDSUTY	1 = Agent
IITDCD; CRS620MI/GetBasicData	2 = Only payee
	3 = Supplier group
	(5 = Forwarding agent -> another BOD noun)
	6 = Insurance company
	8 = Miscellaneous suppliers
@listID	
Supplier Categories: (M3 BE supplier types are)	
SupplierPartyMaster/BuyerPersonReference/IDs/ID	
CIDVEN.IIBUYE; CRS620MI/GetBasicData	The field indicates the buyer.
@accountingEntity	
0	
SupplierPartyMaster/BuyerPersonReference/Name	
CMNUSR.CRRENM; MNS150MI/GetUserData	The field indicates the name of the buyer. This is retrieved from MNS150MI field NAME. Use BUYE as key to API transaction.