



Cross BOD Mapping and Descriptions

Infor M3 Business Engine with Infor Business Vault

Copyright © 2013 Infor

All rights reserved.

Important Notices

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement, the terms of which separate agreement shall govern your use of this material and all supplemental related materials ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above. Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Without limitation, U.S. export control laws and other applicable export and import laws govern your use of this material and you will neither export or re-export, directly or indirectly, this material nor any related materials or supplemental information in violation of such laws, or use such materials for any purpose prohibited by such laws.

Trademark Acknowledgements

The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or related affiliates and subsidiaries. All rights reserved. All other company, product, trade or service names referenced may be registered trademarks or trademarks of their respective owners.

Publication Information

Release: Infor M3 Business Engine with Infor Business Vault

Publication Date: June 19, 2013

Version: 1.0

Introduction

This document contains end-to-end documentation of the integration. It is organized by elements in the BOD, according to the BOD schema definition.

The two integrated applications are on the left and the right side of the document. The arrows define the direction of the BOD and there is separate documentation for each direction.

For each application, the involved table/column information and additional notes are provided per BOD element. In the additional notes, it is explained how exactly the BOD element is published or processed.

This document lists only the BOD elements that are used in the integration. Full BOD mapping documentation is provided with the individual applications.

AccountingChart

Infor M3 Business Engine - Infor Business Vault

AccountingChart/IDs/ID		▶▶▶	
Constant = 'AccountingChartStandard'			ACNTING_CHART.ID_ID
AccountingChart/Status/Code		▶▶▶	
Constant = 'Open'			ACNTING_CHART.S_CD
AccountingChart/DimensionSequence/SequencedDimension		▶▶▶	
@sequence			
Constant from '1' to '6' (Dimension numbers)			ACNTING_CHART.DS_SQNCD DIM_01
			[@sequence='1']/ListID

AdvanceShipNotice

Infor M3 Business Engine - Infor Business Vault

AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentID/ID

MHEXRH.RIDN; Partner + Warehouse + Transaction type + Order number + Receiving
MHS800MI/LstExpRec number



ASN.ASNH_DID_ID

AdvanceShipNotice/AdvanceShipNoticeHeader/DisplayID

MHEXRH.TTYP + RIDN; Order number
MHS800MI/LstExpRec



ASN.ASNH_DISPLAY_ID

AdvanceShipNotice/AdvanceShipNoticeHeader/LastModificationDateTime

MHEXRH.LMDT; The field indicates the date the record was last changed.
MHS800MI/LstExpRec Note: Time zone conversion is therefore not done.



ASN.ASNH_LAST_MODIFICA
TION_DATE

AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentDateTime

MHEXRH.RGDT + Date and time created expressed in UTC
RGTM; MHS800MI/
LstExpRec



ASN.ASNH_DCMNT_DATE

AdvanceShipNotice/AdvanceShipNoticeHeader/Note

MHEXRH.USD1+USD2+LThe five user-defined fields concatenated. Each field is 15 positions
USD4+USD5; alphanumeric. Those fields will typically be blank but can be used for
MHS800MI/LstExpRec customer-specific functionality



ASN_NT_LC.ASNH_NOTE

AdvanceShipNotice/AdvanceShipNoticeHeader/Status/Code

MHEXRH.CMND; // If CMND="*ADD" , "*CHG" then set Status Code="Open" // If
MHS800MI/LstExpRec CMND= "DLT" then set Status Code = "Canceled" // If CMND =
"*PRC" then status will NOT trigger a BOD to be sent // If
CMND="*CLS" then set Status Code="Closed"



ASN.ASNH_S_CD

AdvanceShipNotice/AdvanceShipNoticeHeader/GrossWeightMeasure

MHEXRH.GRWE; The field indicates the total weight for all items that have been entered
MHS800MI/LstExpRec on the order.



ASN.ASNH_GROSS_WGHT

The basis for this calculation is the gross weight of each item in the
item file multiplied by the quantity.

AdvanceShipNotice/AdvanceShipNoticeHeader/CountryOfOriginCode

MHEXRH.CSCD; Taken from the suppliers country or the country where the shipment is
MHS800MI/LstExpRec sent from. TTYP = 10 (Manufacturing Order); 20 (Purchase Order); 30
(Customer Order Returns); 40 (Requisition Order); 50 (Distribution
Order)



ASN.ASNH_CNTRY_OF_ORGN
_CD

AdvanceShipNotice/AdvanceShipNoticeHeader/TransportationMethodCode

MHEXRH.MODL; Delivery method. Can be translated using CRS881 if required.
MHS800MI/LstExpRec



ASN.ASNH_TRANSPORTATIO
N MTHD_CD

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/PartyIDs/ID

MHEXRH.SUNO; If Transaction Type = 10 (Manufacturing Order), 20 (Purchase Order),
MHS800MI /LstExpRec 40 (Requisition Order), 50 (Distribution Order) then display the Supplier
number.



ASN.ASNH_SFP_PID_ID

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Contact/Name

MHEXRH.YREF; The field indicates the customer's contact person.
MHS800MI/LstExpRec



ASN_LC.ASNH_SFP_C_PRI_
NAME

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/PartyIDs/ID

MHEXRH.SUNO; If TTYP = 30 (Customer Order Returns), this will indicate the customer
MHS800MI/LstExpRec whi is sending back goods as return.



ASN.ASNH_RTSFP_PID_ID

AdvanceShipNotice

Infor M3 Business Engine - Infor Business Vault

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipToParty/Location/ID

MHEXRH.WHLO; The field indicates the warehouse ID.
MHS800MI/LstExpRec

►►►
ASN.ASNH_ST_L_ID

AdvanceShipNotice/AdvanceShipNoticeHeader/TransportationTerm/IncotermsCode

MHEXRH.TEDL; Delivery Terms. It's recommended to set up the delivery terms in M3 to
MHS800MI/LstExpRec correspond to standardized Incoterms. If this isn't done, the values can
be translated into Incoterms using CRS881. The field indicates delivery
terms, which define when the responsibility for a delivery is transferred
from the supplier to the customer.
The following codes are recommended according to Incoterms: N.B.
The text within parentheses indicates the delivery term's text on line 2.
EXW Ex Works (Manufacturing location)
FCA Free Carrier (Transport ID)
FAS Free Alongside Ship (Loading port)
FOB Free On Board (Loading port)
CFR Cost & Freight (Destination)
CIF Cost Insurance & Freight (Destination)
CPT Carriage Paid To (Destination)
CIP Carriage & Insurance Paid to (Destination)
DAF Delivered At Frontier (Customs location)
DES Delivered Ex Ship (Destination)
DEQ Delivered Ex Quay (Customs port)
DDU Delivered Duty Unpaid (Import location country)
DDP Delivered Duty Paid (Destination country)
XXX Other (Name)
Example:
Code Delivery text line1 Delivery text line 2
CIF Cost, Insurance & Freight Rotterdam
DDP Delivered duty unpaid Milan, Italy
Both the code and the text can be changed during order entry.
For freight documents created from the transportation planning
routines, the delivery terms are retrieved from the selected route, and
managed by the shipment regardless of this value.

►►►
ASN.ASNH_TT_INCOTERMS_
CD

AdvanceShipNotice/AdvanceShipNoticeItem/Note

MHEXRD.USD1+USD2+L5 used-defined fields concatenated. Each field is 15 characters
USD4+USD5; alphanumeric. Those fields are typically blank but can be used for
MHS800MI/LstExpRec customer-specific modifications. Note: Add "-" between each field to
separate them.

►►►
ASN_ITEM_NT_LC.ASNI_NO
TE

AdvanceShipNotice/AdvanceShipNoticeItem/ShippedQuantity

@unitCode

MHEXRD.ALUN; The field indicates an alternate unit of measure (U/M) for the basic U/M
MHS800MI/ for an item.
LstExpRecDetail

►►►
ASN_ITEM.ASNI_SHIPPED_
QTY_TXN_ID

AdvanceShipNotice/AdvanceShipNoticeItem/ShippedBaseUOMQuantity

@unitCode

MHEXRD.UNMS; The field indicates the basic unit of measure in which each item is
MHS800MI/ recorded in inventory.
LstExpRecDetail

►►►
ASN_ITEM.ASNI_SHIPPED_
QTY_BC_UNIT

AdvanceShipNotice/AdvanceShipNoticeItem/ShippedBaseUOMQuantity

MHEXRD.TRQT; The field indicates the quantity, in the basic unit of measure, for the

►►►
ASN_ITEM.ASNI_SHIPPED_

AdvanceShipNotice

Infor M3 Business Engine - Infor Business Vault

MHS800MI/ LstExpRecDetail	planned or actual transaction.	QTY_BC_UOM
<hr/>		
AdvanceShipNotice/AdvanceShipNoticeltem/RequisitionReference/DocumentID/ID		
MHEXRD.TTYP + RIDN + RIDX; MHS800MI/ LstExpRecDetail	If Transaction Type = 40 (Requisition Order) then display Transaction type plus Order number plus Line suffix.	▶▶▶ ASN_ITEM.ASNI_RR_DID_I D
<hr/>		
AdvanceShipNotice/AdvanceShipNoticeltem/RequisitionReference/LineNumber		
MHEXRD.RIDL; MHS800MI/ LstExpRecDetail	The field indicates the order line number.	▶▶▶ ASN_ITEM.ASNI_RR_LINE_ NMBR
<hr/>		
AdvanceShipNotice/AdvanceShipNoticeltem/PurchaseOrderReference/DocumentID/ID		
MHEXRD.TTYP + RIDN + RIDX; MHS800MI/ LstExpRecDetail	If Transaction Type = 25 (Purchase Order) then display Transaction type plus Order number plus Line suffix.	▶▶▶ ASN_ITEM.ASNI_POR_DID_ ID
<hr/>		
AdvanceShipNotice/AdvanceShipNoticeltem/PurchaseOrderReference/LineNumber		
MHEXRD.RIDL + PNLS; MHS800MI/ LstExpRecDetail	The field indicates the order line number and purchase order line subnumber.	▶▶▶ ASN_ITEM.ASNI_POR_LINE_ _NMBR
<hr/>		
AdvanceShipNotice/AdvanceShipNoticeltem/SerializedLot/Lot/LotIDs/ID		
MHEXRD.BANO; MHS800MI/ LstExpRecDetail	If item is lot-controlled. The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics.	▶▶▶ ASN_ITEM_LOT.ASNI_SL_L _LID_ID
<hr/>		
Serial numbers can be used for lot numbering.		
<hr/>		
AdvanceShipNotice/AdvanceShipNoticeltem/SerializedLot/Lot/SerialNumber		
MHEXRD.BANO; MHS800MI/ LstExpRecDetail	If item is serial number controlled. The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item. All units included in a lot have the same characteristics.	▶▶▶ ASN_ITEM_LOT.ASNI_SL_L _SERIAL_NMBR
<hr/>		
Serial numbers can be used for lot numbering.		
<hr/>		
AdvanceShipNotice/AdvanceShipNoticeltem/LineNumber		
MHEXRD.RELI; MHS800MI/ LstExpRecDetail	If TTYP = 30 (Customer Order) then display RELI. Note: Line number is only existing when transaction type is customer order.	▶▶▶ ASN_ITEM.ASNI_LINE_NMB R
<hr/>		

AssetMaster/IDs/ID

FFASMA.ASID SBNO;
FAS001MI/GetAsset

The field indicates the unique alpha-numeric ID of a fixed asset.

▶▶▶
ASSET.ID_ID

A fixed asset can be identified either by the ID or the subnumber. The subnumber is a serial number for identification of one or several fixed assets under a specific fixed asset number.

When you enter a supplier invoice and select an account defined as a fixed asset account, FA program is activated. There you can either add costs to an existing asset by selecting its ID, or create a new, preliminary asset by entering some basic data.

In the latter case, the asset automatically receives status 5 (Preliminary) and a preliminary asset ID in the form of a sequence number. When you change the status of the asset to definite, you can select a new ID. The preliminary number is then saved in the fixed asset master file, which enables you to use it for inquiries.

AssetMaster/Description

FFASMA.TXT1, TXT2;
FAS001MI/GetAsset

The field indicates an optional text that can be printed on different order documents together with the current material line.

▶▶▶
ASSET_LC.DSC

AssetMaster/Status/Code

FFASMA.FAST;
FAS001MI/GetAsset

If status = 1, 5, 7, 8 is OPEN ; 9 = CLOSED

▶▶▶
ASSET.S_CD

AssetMaster/Status/EffectiveDateTime

FFASMA.RGDT +
RGTM; FAS001MI/
GetAsset

Entry date and entry time.

▶▶▶
ASSET.S_EFF_DATE

BillToPartyMaster

Infor M3 Business Engine - Infor Business Vault

BillToPartyMaster/PartyIDs/ID OCUSMA.OKCUNO; The field indicates the Customer number CRS610MI/GetBasicData	▶▶▶ BILL_TO_PARTY.PID_ID
BillToPartyMaster/Name OCUSMA.OKCUNM; This field indicates the customer name CRS610MI/GetBasicData	▶▶▶ BILL_TO_PARTY_LC.NAME
BillToPartyMaster/Location/Address/AttentionOfName OCUSMA.OKYREF; The field indicates the customer's contact person CRS610MI/GetBasicData	▶▶▶ BILL_TO_PARTY_LC.L_A_P RI_ATT_NAME
BillToPartyMaster/Location/Address/AddressLine @sequence The field indicates the Address Line sequence	▶▶▶ BILL_TO_PARTY_LC.L_A_P RI_AL_ADDL_01 [@sequence='1']
BillToPartyMaster/Location/Address/CityName OCUSMA.OKTOWN; The field indicates the city CRS610MI/GetBasicData	▶▶▶ BILL_TO_PARTY.L_A_PRI_ CITY_NAME
BillToPartyMaster/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; The field indicates the state/region/countrysubdivision CRS610MI/GetBasicData	▶▶▶ BILL_TO_PARTY.L_A_PRI_ C_SBDVSN
BillToPartyMaster/Location/Address/CountryCode OCUSMA.OKCSCD; The field indicates the country code CRS610MI/GetBasicData	▶▶▶ BILL_TO_PARTY.L_A_PRI_ CNTRY_CD
BillToPartyMaster/Location/Address/PostalCode OCUSMA.OKPONO; The field indicates the postal code CRS610MI/GetBasicData	▶▶▶ BILL_TO_PARTY.L_A_PRI_ POSTAL_CD
BillToPartyMaster/PaymentTermID OCUSMA.OKTEPY/ The field indicates the payment terms id for the customer CCUDIV.O Data is retrieved from customer master, table OCUSMA, or, if KTEPY.; CRS610MI/ applicable, from customer local exceptions, table CCUDIV. GetOrderInfo	▶▶▶ BILL_TO_PARTY.PMT_TERM _ID
BillToPartyMaster/Status/Code OCUSMA.OKSTAT; The field indicates the status of the customer. CRS610MI/GetBasicData If M3 status is 10, set element to "Pending" If M3 status is 20, set element to "Open" If M3 status is 90, set element to "Closed"	▶▶▶ BILL_TO_PARTY.S_CD
BillToPartyMaster/Classification/Codes/Code @listID The field indicates the Classification code listID. 1) If Customer type field is filled, set listID to "Customer Types" 2) If Delivery terms field is filled, set listID to "Incoterms" 3) If District field is filled, set listID to "District"	▶▶▶ BILL_TO_PARTY.C_C_CD_B ILL_TO_PARTY_TYPS [@listID='Customer Types']
BillToPartyMaster/Classification/Codes/Code @sequence The sequence attribute identifies the hierarchical position of the identifier in the case of multi-level codes	▶▶▶ BILL_TO_PARTY.C_C_CD_0 1 [@sequence='1']

BillToPartyMaster

BillToPartyMaster/CustomerParty/PartyIDs/ID		▶▶▶
OCUSMA.OKCUNO;	This is a list of customers that uses BillToParty as the invoice recipient.	BILL_TO_PARTY.CP_PID_I
CRS610MI/	(The BillToParty itself is also included in the list)	D
LstByInvoiceRec		
BillToPartyMaster/ShipToParty/PartyIDs/ID		▶▶▶
OCUSMA.OKCUNO;	This is a list of ShipToParties for the BillToParty id.	BILL_TO_PARTY.STP_PID_
CRS610MI/	It reflects the same data as CustomerParty	ID
LstByInvoiceRec	(The BillToParty itself is also included in the list)	

CodeDefinition

Infor M3 Business Engine - Infor Business Vault

CodeDefinition/DocumentID/ID

For Delivery Terms: This indicates the code id
CSYTAB.CTSTKY; N/A/

►►►
CODE.DID_ID

For General Code:
CSYTAB.CTSTKY; /

For Payment Terms:
CSYTAB.CTSTKY; N/A/

For Purchase Order
Types:
MPORDT.OTORTY; N/A/

CodeDefinition/EffectiveTimePeriod/StartDateTime

For Accounting For Accounting Dimension:
Dimension: Valid From Date from CRS630
FCHACC.EAVFDT;
CRS630MI/GetAccountID

►►►
CODE.ETP_START_DATE

CodeDefinition/EffectiveTimePeriod/EndDateTime

For Accounting For Accounting Dimension:
Dimension: Valid To Date from CRS630
FCHACC.EAVTDT;
CRS630MI/GetAccountID

►►►
CODE.ETP_END_DATE

CodeDefinition/Status/Code

For Accounting For Accounting Dimension:
Dimension: Blocked from CRS630
FCHACC.EALCCD;
CRS630MI/GetAccountID

For Delivery Terms:
This indicates the Status of the code id.
It is hardcoded to "Open"

For General Code:
This indicates the Status of the code id.
It is hardcoded to "Open"

For Payment Terms:
This indicates the Status of the code id.
It is hardcoded to "Open"

For Purchase Order Types:
This indicates the Status of the code id.
It is always set to "Open"

►►►
CODE.S_CD

CodeDefinition/ReadOnlyIndicator

This indicates that this instance is ReadOnly, but if this instance is for a
Dimension Type instance it is not inherited by the children. Default
value is false

►►►
CODE.READ_INDCTR

CodeDefinition/ListID

CSYTAB.CTPARM;
CRS175MI/
GetGeneralCode

For Accounting Dimension:
Loop through fields YGAI51, YGAI52, YGAI53, YGAI54, YGAI55,
YGAI56, YGAI57

►►►
CODE.LIST_ID

For Delivery Terms:

This indicates the list id for Delivery term.

M3 BE field Delivery term has list ID "Incoterms"

For Dynamic Dimension:

Loop through fields YGAI51, YGAI52, YGAI53, YGAI54, YGAI55, YGAI56, YGAI57

For General Code:

This indicates the list id for the General code.

Currently we support following list id's:

M3 BE field Item group has list ID "Item Groups"

M3 BE field Product group has list ID "Product Groups"

M3 BE field Business area has list ID "Business Sectors"

M3 BE field Procurement group has list ID "Buying Groups"

M3 BE field Country has list ID "Countries"

M3 BE field State has different list ID depending on country:

- Canada has list ID "Canadian Provinces"

- France has list ID "France - Departements"

- United States has list ID "US States"

- Other countries have list ID "Country Sub-divisions"

M3 BE field District has list ID "District"

For Payment Terms:

This indicates the list id for Payment terms.

M3 BE field Payment terms has list ID "PaymentTerm"

For Purchase Order Types:

This indicates the list id for the General code.

This is set to "Purchase Order Types"

CodeDefinition/CodeValue

For Accounting

Dimension:

FCHACC.EAAITM;

CRS630MI /

GetAccountID

For Accounting Dimension:

Accounting ID from CRS630

For Delivery Terms:

This indicates the code value.

For Delivery Terms:

CSYTAB.CTSTKY; /

For Dynamic Dimension:

Accounting ID from CRS630

For Dynamic Dimension:

FCHACC.EAAITM;

CRS630MI /

GetAccountID

For General Code:

This indicates the code value.

For Payment Terms:

This indicates the code value.

For General Code:

CSYTAB.CTSTKY; N/A/

For Purchase Order Types:

This indicates the code value.



CODE_LC.CD_VL

CodeDefinition

Infor M3 Business Engine - Infor Business Vault

For Payment Terms:
CSYTAB.CTSTKY; /

For Purchase Order
Types:
MPORDT.OTORTY; N/A/

CodeDefinition/Name

For Accounting
Dimension:
FCHACC,
FCAIDL.EATX40,
ELTX40; CRS630MI/
GetAccountID,
LstAccountIDLng
For Delivery Terms:
CSYTAB.CTTX15;
CRS175MI/
GetGeneralCode
For Dynamic Dimension:
FCHACC.EAAITM;
CRS630MI /
GetAccountID
For General Code:
CSYTAB.CTTX15;
CRS175MI/
LstCodesByLng
For Payment Terms:
CSYTAB.CTTX15;
CRS175MI/
GetGeneralCode
For Purchase Order
Types:
MPORDT.OTTX15; N/A/

►►►
CODE_LC.NAME

CodeDefinition/Description

For Delivery Terms:
CSYTAB.CTPARM;
CRS175MI/
GetGeneralCode
For Dynamic Dimension:
FCHACC.EAAITM;
CRS630MI /
GetAccountID
For General Code:
CSYTAB.CTTX40;

►►►
CODE_LC.DSC

CodeDefinition

CRS175MI/ LstCodesByLng	It is a substring of the first 72 characters of field PARM.
For Payment Terms: CSYTAB.CTPARM; CRS175MI/ GetGeneralCode	For Purchase Order Types: The field indicates the code description.
For Purchase Order Types: MPORDT.OTTX40; N/A/	

CurrencyExchangeRateMaster

Infor M3 Business Engine - Infor Business Vault

CurrencyExchangeRateMaster/IDs/ID

CCURRA.CONCATENATThe field indicates an ID. The ID is a concatenation of the fields
UCD+CULOCD currency, local currency and validity date.
+CUCUTD); CRS055MI/
SelExchangeRate



CURR_EXCHANGE_RATE.ID_
ID

CurrencyExchangeRateMaster/CurrencyExchangeRate/SourceCurrencyCode

CCURRA.CUCUCD; The field indicates the abbreviation for the currency. The abbreviation
CRS055MI/ should follow ISO standards.
SelExchangeRate



CURR_EXCHANGE_RATE.LC.
CER_SRCE_CURR_CD

CurrencyExchangeRateMaster/CurrencyExchangeRate/TargetCurrencyCode

CCURRA.CULOCD; The field indicates the currency relative to which the currency rate is
CRS055MI/ given. Normally this is the local currency for the division.
SelExchangeRate

However, in an EMU installation in status 2, the rate is always stated
towards the Monetary Union currency.



CURR_EXCHANGE_RATE.LC.
CER_TARGET_CURR_CD

CurrencyExchangeRateMaster/CurrencyExchangeRate/RateNumeric

CCURRA.CUARAT; The field indicates the exchange rate for the chosen currency.
CRS055MI/
SelExchangeRate

The rate may be entered with up to six decimal places. The result,
however, will be displayed with two decimal places.



CURR_EXCHANGE_RATE.CER
_RATE_NMRC

CurrencyExchangeRateMaster/CurrencyExchangeRate/EffectiveTimePeriod/ StartDateTime

CCURRA.CUCUTD; The field indicates the date from which the registered data becomes
CRS055MI/ valid.
SelExchangeRate



CURR_EXCHANGE_RATE.CER
_ETP_START_DATE

CurrencyExchangeRateMaster/CurrencyRateTypeReference/DocumentID/ID

CCURRA.CUCRTP; The field indicates the exchange rate type, such as variable rate,
CRS055MI/ budget exchange rate, or rate used for group consolidation.
SelExchangeRate

Exchange rate types are used for budgeting and annual financial
statements and can be connected to customers, suppliers, and price
lists.



CURR_EXCHANGE_RATE.CRT
R_DID_ID

CurrencyRateType

Infor M3 Business Engine - Infor Business Vault

CurrencyRateType/DocumentID/ID

CSYTAB.CTSTKY; The field indicates the exchange rate type, such as variable rate,
CRS175MI/ budget exchange rate, or rate used for group consolidation.
GetGeneralCode



CURR_RATE_TYP.DID_ID

CurrencyRateType/Description

CSYTAB.CTPARM; The field indicates optional text for the currency rate type
CRS175MI/
GetGeneralCode



CURR_RATE_TYP_LC.DSC

CurrencyRateType/Status/Code

Always set to "Open"



CURR_RATE_TYP.S_CD

CurrencyRateType/Name

CSYTAB.CTTX40; The field indicates optional text for the currency rate type
CRS175MI/
GetGeneralCode



CURR_RATE_TYP_LC.NAME

CurrencyRateType/ShortName

CSYTAB.CTTX15; The field indicates a name for currency rate type
CRS175MI/
GetGeneralCode



CURR_RATE_TYP_LC.SHORT
_NAME

CustomerPartyMaster

Infor M3 Business Engine - Infor Business Vault

CustomerPartyMaster/PartyIDs/ID		▶▶▶	
OCUSMA.OKCUNO;	This field indicates the customer number	CUSTOMER.PID_ID	
CRS610MI/GetBasicData			
CustomerPartyMaster/Name		▶▶▶	
OCUSMA.OKCUNM;	This field indicates the customer name	CUSTOMER_LC.NAME	
CRS610MI/GetBasicData			
CustomerPartyMaster/Location/Address/AttentionOfName		▶▶▶	
OCUSMA.OKYREF;	This field indicates the customer's contact person	CUSTOMER_LC.L_A_PRI_AT	
CRS610MI/GetBasicData		TN_NAME	
CustomerPartyMaster/Location/Address/AddressLine @sequence		▶▶▶	
	The field indicates the Address Line sequence	CUSTOMER_LC.L_A_PRI_AL	[@sequence='1']
		ADDL_01	
CustomerPartyMaster/Location/Address/CityName		▶▶▶	
OCUSMA.OKTOWN;	This field indicates the city	CUSTOMER.L_A_PRI_CITY_	
CRS610MI/GetBasicData		NAME	
CustomerPartyMaster/Location/Address/CountrySubDivisionCode		▶▶▶	
OCUSMA.OKECAR;	This field indicates the state/region/countrysubdivision	CUSTOMER.L_A_PRI_C_SBD	
CRS610MI/GetBasicData		VSN	
CustomerPartyMaster/Location/Address/CountryCode		▶▶▶	
OCUSMA.OKCSCD;	This field indicates the country code	CUSTOMER.L_A_PRI_CNTRY	
CRS610MI/GetBasicData		_CD	
CustomerPartyMaster/Location/Address/PostalCode		▶▶▶	
OCUSMA.OKPONO;	This field indicates the postal code	CUSTOMER.L_A_PRI_POSTA	
CRS610MI/GetBasicData		L_CD	
CustomerPartyMaster/PaymentTermID		▶▶▶	
OCUSMA.OKTEPY/	This field indicates the payment terms id for the customer	CUSTOMER.PMT_TERM_ID	
CCUDIV.O	Data is retrieved from customer master, table OCUSMA, or, if		
KTEPY.;	applicable, from customer local exceptions, table CCUDIV.		
CRS610MI/			
GetOrderInfo			
CustomerPartyMaster/Status/Code		▶▶▶	
OCUSMA.OKSTAT;	This field indicates the status of the customer.	CUSTOMER.S_CD	
CRS610MI/GetBasicData			
	If M3 status is 10, set element to "Pending"		
	If M3 status is 20, set element to "Open"		
	If M3 status is 90, set element to "Closed"		
CustomerPartyMaster/Classification/Codes/Code @listID		▶▶▶	
	The field indicates the Classification code listID.	CUSTOMER.C_C_CD_CSTM_	[@listID='Customer Types']
	1) If Customer type field is filled, set listID to "Customer Types"	TYP	
	2) If Delivery terms field is filled, set listID to "Incoterms"		
	3) If District field is filled, set listID to "District"		
CustomerPartyMaster/Classification/Codes/Code @sequence		▶▶▶	
	The sequence attribute identifies the hierarchical position of the identifier in the case of multi-level codes	CUSTOMER.C_C_CD_01	[@sequence='1']

CustomerPartyMaster

Infor M3 Business Engine - Infor Business Vault

CustomerPartyMaster/CustomerAccount/TotalCreditLimitAmount



@currencyID

OCUSMA.OKCUCD The field indicates the currency code for the credit limit.
CCUDIV.OKCUCD.; Data is by retrieved from customer master, table OCUSMA, or, if
CRS610MI/GetFinancial applicable, from customer local exceptions, table CCUDIV.

CUSTOMER_ACNT.CA_TOTAL
_CRDT_LMT_AMT_TXN_ID

CustomerPartyMaster/CustomerAccount/TotalCreditLimitAmount



OCUSMA.OKCRL3/ The field indicates the highest credit limit for the customer. It is
OKCRL2/O retrieved, in priority order, from, Credit limit 3, Credit limit 2 or Credit
KCRLM; CRS610MI/ limit field.
GetFinancial

CUSTOMER_ACNT.CA_TOTAL
_CRDT_LMT_AMT_TXN

CustomerReturn

Infor M3 Business Engine - Infor Business Vault

CustomerReturn/CustomerReturnHeader/DocumentID/ID

OCHEAD.OCREPN; This field indicates the receiving number which identifies a customer return.
OIS390MI/GetHead



CUSTOMER_RETURN.CRH_DI
D ID

CustomerReturn/CustomerReturnHeader/AlternateDocumentID/ID

OCHEAD.OCORNO; The field indicates the customer order number
OIS390MI/GetHead



CUSTOMER_RETURN.CRH_AD
ID ID

CustomerReturn/CustomerReturnHeader/Status/Code

OCHEAD.OCRESH; The field indicates the lowest status of a line in a customer return.
OIS390MI/GetHead
5=Open
11=Open
12=Partially Received
13=Partially Received
2=Credited
22=Received
23=Received
33=Received
99=Canceled



CUSTOMER_RETURN.CRH_S_
CD

CustomerReturn/CustomerReturnHeader/CustomerParty/PartyIDs/ID

OCHEAD.OCUNO; The field indicates the customer number.
OIS390MI/GetHead



CUSTOMER_RETURN.CRH_CP
PID ID

CustomerReturn/CustomerReturnHeader/BillToParty/PartyIDs/ID

OCHEAD.OCPYNO; The field indicates the customer ID who receives the invoice.
OIS390MI/GetHead



CUSTOMER_RETURN.CRH_BT
P PID ID

CustomerReturn/CustomerReturnHeader/TransportationTerm/IncotermsCode

OOHEAD.OATEDL; The field indicates delivery terms, which control when transport responsibility shifts from supplier to customer.
OIS100MI/GetHead



CUSTOMER_RETURN.CRH_TT
INCOTERMS CD

CustomerReturn/CustomerReturnHeader/PaymentMethodCode

OOHEAD.OATEPY; The field indicates how the due date is to be calculated.
OIS100MI/GetHead



CUSTOMER_RETURN.CRH_PM
T_MTHD_CD

CustomerReturn/CustomerReturnHeader/PromisedReturnDateTime

OCHEAD.OCEPDT; The field indicates the date of a customer return to stock, either when it arrives or when it is expected to arrive.
OIS390MI/GetHead



CUSTOMER_RETURN.CRH_PR
MSD_RETURN_DATE

CustomerReturn/CustomerReturnHeader/RequiredReturnDateTime

OCHEAD.OCEPDT; The field indicates the date of a customer return to stock, either when it arrives or when it is expected to arrive.
OIS390MI/GetHead



CUSTOMER_RETURN.CRH_RQ
RD_RETURN_DATE

CustomerReturn/CustomerReturnLine/LineNumber

OCLINE.ODREL; The field indicates a line number, which is a sequence number that identifies each line of a customer return.
OIS390MI/LstLine



CUSTOMER_RETURN_LINE.C
RL_LINE_NMBR

CustomerReturn/CustomerReturnLine/Status/Code

OCLINE.ODREST; The field indicates the status of a line in a customer return.
OIS390MI/GetLine
Alternatives:
2 - Credited
5, 11 - Open
12, 13 - Partially Received
22, 23, 33 - Received
99 - Cancelled



CUSTOMER_RETURN_LINE.C
RL_S_CD

CustomerReturn/CustomerReturnLine/Item/ItemID/ID



CustomerReturn

Infor M3 Business Engine - Infor Business Vault

OCLINE.ODITNO; OIS390MI/LstLine	The field indicates the item number	CUSTOMER_RETURN_LINE.C RL_I_ID_ID
CustomerReturn/CustomerReturnLine/Item/Description		
MITMAS.MMFUDS; MMS200MI/GetItemBasic	The field indicates the description of the item.	CUSTOMER_RETURN_LINE_L C.CRL_I_DSC
CustomerReturn/CustomerReturnLine/Item/SerializedLot/Lot/LotIDs/ID		
OCLINE.ODBANO; OIS390MI/LstLine	The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item.	CUSTOMER_RETURN_LINE.C RL_I_SL_L_ID_ID
CustomerReturn/CustomerReturnLine/Item/SerializedLot/SerialNumber		
OCLINE.ODBANO; OIS390MI/LstLine	The field indicates the unique serial number assigned by the manufacturer.	CUSTOMER_RETURN_LINE.C RL_I_SL_SERIAL_NMBR
CustomerReturn/CustomerReturnLine/Quantity		
@unitCode		
.; OIS390MI/GetLine	The field indicates the unit of measure.	CUSTOMER_RETURN_LINE.C RL_QTY_TXN_ID
CustomerReturn/CustomerReturnLine/Quantity		
OCLINE.ODREQ1; OIS390MI/GetLine	The field indicates the returned quantity.	CUSTOMER_RETURN_LINE.C RL_QTY_TXN
CustomerReturn/CustomerReturnLine/BaseUOMQuantity		
@unitCode		
.; OIS390MI/GetLine	The field indicates the basic unit of measure.	CUSTOMER_RETURN_LINE.C RL_QTY_BC_UNIT
CustomerReturn/CustomerReturnLine/BaseUOMQuantity		
OCLINE.ODREQ1; OIS390MI/GetLine	The field indicates the quantity in basic unit of measure.	CUSTOMER_RETURN_LINE.C RL_QTY_BC_UOM
CustomerReturn/CustomerReturnLine/UnitPrice/Amount		
@currencyID		
OCHEAD.OCCUCD; OIS390MI/GetHead	The field indicates the currency.	CUSTOMER_RETURN_LINE.C RL_UP_AMT_TXN_ID
CustomerReturn/CustomerReturnLine/UnitPrice/Amount		
OCLINE.ODSAPR; OIS390MI/GetLine	The field indicates the sales price.	CUSTOMER_RETURN_LINE.C RL_UP_AMT_TXN
CustomerReturn/CustomerReturnLine/UnitPrice/PerQuantity		
@unitCode		
OCHEAD.OCCUCD; OIS390MI/GetHead	The field indicates the currency.	CUSTOMER_RETURN_LINE.C RL_UP_PER_QTY_TXN_ID
CustomerReturn/CustomerReturnLine/UnitPrice/PerQuantity		
OCLINE.ODSAPR; OIS390MI/GetLine	The field indicates the unit price.	CUSTOMER_RETURN_LINE.C RL_UP_PER_QTY_TXN
CustomerReturn/CustomerReturnLine/ExtendedAmount		
@currencyID		
OCHEAD.OCCUCD; OIS390MI/GetHead	The field indicates the currency.	CUSTOMER_RETURN_LINE.C RL_EXTND_AMT_TXN_ID
CustomerReturn/CustomerReturnLine/ExtendedAmount		
OCLINE.ODSAPR * ODREQ1; OIS390MI/	The field indicates the extended amount.	CUSTOMER_RETURN_LINE.C RL_EXTND_AMT_TXN

CustomerReturn

GetLine	
<hr/>	
CustomerReturn/CustomerReturnLine/ExtendedBaseAmount	▶▶▶
@currencyID	
OCHEAD.; OIS390MI/ The field indicates the local currency.	CUSTOMER_RETURN_LINE.C
GetLine	RL_EXTND_AMT_BC_ID
<hr/>	
CustomerReturn/CustomerReturnLine/ExtendedBaseAmount	▶▶▶
OCLINE.; OIS390MI/ The field indicates the extended base amount.	CUSTOMER_RETURN_LINE.C
GetLine	RL_EXTND_AMT_BASE
<hr/>	

FinancialCalendar

Infor M3 Business Engine - Infor Business Vault

FinancialCalendar/FinancialCalendarID/ID	▶▶▶
Constant.; / Constant = 'Financial Calendar'	FNCL_CLNDR.FCID_ID
FinancialCalendar/Name	▶▶▶
Constant.; / Constant = 'Financial Calendar'	FNCL_CLNDR.LC.NAME
FinancialCalendar/Status/Code	▶▶▶
Constant.; / Constant = 'Open'	FNCL_CLNDR.S_CD
FinancialCalendar/CalendarYear/Year	▶▶▶
CSYPER.CPYEA4; The field indicates the year. It is entered using four positions, for CRS910MI/Select example, 2002.	FNCL_CLNDR_PRD.CY_P_YE AR
FinancialCalendar/CalendarYear/Period/PeriodID	▶▶▶
CSYPER.CPPERI; The field indicates the period within the calendar year. CRS910MI/Select	FNCL_CLNDR_PRD.CY_P_PR D_ID
FinancialCalendar/CalendarYear/Period/Name	▶▶▶
CSYPER.CPNAME; This field indicates the name of the period. CRS910MI/Select	FNCL_CLNDR_PRD_LC.CY_P NAME
FinancialCalendar/CalendarYear/Period/ShortName	▶▶▶
CSYPER.CPNAME; This field indicates the name of the period. CRS910MI/Select	FNCL_CLNDR_PRD_LC.CY_P SHORT_NAME
FinancialCalendar/CalendarYear/Period/EffectiveTimePeriod/StartDateTime	▶▶▶
CSYPER.CPFDAT; The field indicates the start date for the system period. CRS910MI/Select	FNCL_CLNDR_PRD.CY_P_ET P_START_DATE
<p>The date must be later than the start date of the previous period, but need not be within the current calendar year. This allows handling split financial years, for example.</p> <p>The date must be earlier than the start date of the next period, even if the next period is in another year. Validation is performed to be sure that these two conditions are met.</p> <p>The end date is always entered automatically as the day before the start date of the next period, except for the last period. The end date for the last period must be entered manually.</p>	
FinancialCalendar/CalendarYear/Period/EffectiveTimePeriod/EndDateTime	▶▶▶
CSYPER.CPTDAT; The field indicates the date when the system period ends. CRS910MI/Select	FNCL_CLNDR_PRD.CY_P_ET P_END_DATE
<p>This date is calculated as the date before the start date of the next period, except for the last period where the end date must be entered.</p>	

InventoryAdjustment

Infor M3 Business Engine - Infor Business Vault

InventoryAdjustment/InventoryAdjustmentHeader/LastModificationDateTime

; MWS070MI/
GetServerTime

Current date/time.

►►►
INVNTRY_ADJ.IAH_LAST_M
ODIFICATION DATE

InventoryAdjustment/InventoryAdjustmentHeader/DocumentDateTime

; MWS070MI/
GetServerTime

Current date/time.

►►►
INVNTRY_ADJ.IAH_DCMNT_
DATE

InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/ID

MITTRA.MLWHLO; The field indicates the warehouse ID.
MWS070MI/
GetStockTrans

►►►
INVNTRY_ADJ_LINE.IAL_W
L_ID

InventoryAdjustment/InventoryAdjustmentLine/Item/ItemID/ID

MITTRA.MTITNO; The field indicates the item number.
MWS070MI/
GetStockTrans

►►►
INVNTRY_ADJ_LINE.IAL_I
_IID_ID

InventoryAdjustment/InventoryAdjustmentLine/Quantity @unitCode

MITMAS.MMUNMS; The field indicates the quantity, in the basic unit of measure, for the
MMS200MI/GetItmBasic planned or actual transaction.

►►►
INVNTRY_ADJ_LINE.IAL_Q
TY_TXN_ID

InventoryAdjustment/InventoryAdjustmentLine/Quantity

MITTRA.MTTRQT; The field indicates the quantity, in the basic unit of measure, for the
MWS070MI/
GetStockTrans planned or actual transaction.

►►►
INVNTRY_ADJ_LINE.IAL_Q
TY_TXN

InventoryAdjustment/InventoryAdjustmentLine/TransactionDateTime

.MTTRDT; MWS070MI/
GetStockTrans

The field indicates the transaction date which may be entered manually during entry of certain transactions. When this is possible, the current date is always proposed by default for the transaction date.

►►►
INVNTRY_ADJ_LINE.IAL_T
XN_DATE

InventoryCount

Infor M3 Business Engine - Infor Business Vault

InventoryCount/InventoryCountHeader/DocumentDateTime

MITTKV.; MMS307MI/ Current date/time.
GetServerTime



INVNTRY_COUNT.ICH_DCMN
T_DATE

InventoryCount/InventoryCountHeader/WarehouseLocation/ID

MITTKV.SVWHLO; The field indicates the warehouse ID.
MMS307MI/
GetPhysInvVar



INVNTRY_BALANCE.IB_WL_
NID Custom Mapping: NID

InventoryCount/InventoryCountLine/LineNumber

MITTKV.SVSTRN; Value set to sequence number; Set constant '00001'
MMS307MI/
GetPhysInvVar



INVNTRY_COUNT_LINE.ICL
_LINE_NMBR

InventoryCount/InventoryCountLine/Item/ItemID/ID

MITTKV.SVITNO; The field indicates the item number.
MMS307MI/
GetPhysInvVar



INVNTRY_BALANCE.IB_I_I
ID_NID Custom Mapping: NID

InventoryCount/InventoryCountLine/Quantity

@unitCode

MITMAS.MMUNMS; The field indicates the unit in which each item is recorded in inventory,
MMS200MI/GetItmBasic even if alternate inventory units of measure are used. All balance
information for the current item is always stored in this unit.



INVNTRY_BALANCE.IB_CCE
Q_UNTICD

InventoryCount/InventoryCountLine/Quantity

MITTKV.SVSTQI; The field indicates physical counted quantity in the basic U/M of the
MMS307MI/
GetPhysInvVar item.



INVNTRY_BALANCE.IB_CCE
Q_QTY

InventoryCount/InventoryCountLine/AdjustmentQuantity

MITTKV.SVDFQT; The field indicates the delta between previous and current quantity.
MMS307MI/
GetPhysInvVar



INVNTRY_COUNT_LINE.ICL
_ADJ_QTY_TXN

InventoryHold

Infor M3 Business Engine - Infor Business Vault

InventoryHold/LastModificationDateTime

; MWS070MI/
GetServerTime

Current date/time



INVNTRY_HOLD.LAST_MODI
FICATION_DATE

InventoryHold/DocumentDateTime

; MWS070MI/
GetServerTime

Current date/time



INVNTRY_HOLD.DCMNT_DAT
E

InventoryHold/ItemInstance/ItemID/ID

MITTRA.MTITNO;
MWS070MI/
GetStockTrans

The field indicates the item number.



INVNTRY_HOLD.II_IID_ID

InventoryHold/ItemInstance/Description

MITMAS.MMITDS;
MWS070MI/
GetStockTrans

The field indicates a supplementary description of the item.



INVNTRY_HOLD_LC.II_DSC

InventoryHold/TransactionDateTime

MITTRA.MTTRDT;
MWS070MI/
GetStockTrans

The field indicates the transaction date which may be entered manually during entry of certain transactions. When this is possible, the current date is always proposed by default for the transaction date.



INVNTRY_HOLD.TXN_DATE

InventoryHold/HoldQuantity

MITTRA.MTTRQT;
MWS070MI/
GetStockTrans

The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.



INVNTRY_HOLD.HOLD_QTY_
TXN

InventoryHold/HoldBaseUOMQuantity

MITMAS.MMUNMS;
MWS070MI/
GetStockTrans

The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.



INVNTRY_HOLD.HOLD_QTY_
BC_UOM

Invoice

Infor M3 Business Engine - Infor Business Vault

Invoice/InvoiceHeader/DocumentID/ID

OINVOH.UHEXIN; This contains Invoice prefix and Invoice number.
OIS350MI/GetInvHead

►►►
INVOICE.IH_DID_ID

Invoice/InvoiceHeader/Note

OINVOH.UHIDAT; This field indicates year the invoice was created.
OIS350MI/GetInvHead

►►►
INVOICE_NT_LC.IH_NOTE

Invoice/InvoiceHeader/ExtendedAmount

@currencyID

OINVOH.UHCUCD; The field indicates the abbreviation for the currency. The abbreviation
OIS350MI/GetInvHead should follow ISO standards.

►►►
INVOICE.IH_EXTND_AMT_T
XN_ID

Example:
GBP British pounds
USD United States dollars
SEK Swedish kronor.

Invoice/InvoiceHeader/ExtendedAmount

OINVOL.UHIVAM; Total AMT2 of all IVTP = 30
OIS350MI/LstInvLine

►►►
INVOICE.IH_EXTND_AMT_T
XN

Invoice/InvoiceHeader/ExtendedBaseAmount

@currencyID

CMNDIV.CCLOCD; The field indicates the abbreviation for the currency. The abbreviation
OIS350MI/GetInvHead should follow ISO standards.

►►►
INVOICE.IH_EXTND_AMT_B
C_ID

Example:
GBP British pounds
USD United States dollars
SEK Swedish kronor.

Invoice/InvoiceHeader/ExtendedBaseAmount

OINVOL.UHIVLA; Total AMT1 of all IVTP = 30
OIS350MI/LstInvLine

►►►
INVOICE.IH_EXTND_AMT_B
ASE

Invoice/InvoiceHeader/TotalAmount

@currencyID

OINVOH.UHCUCD; The field indicates the abbreviation for the currency. The abbreviation
OIS350MI/GetInvHead should follow ISO standards.

►►►
INVOICE.IH_TOTAL_AMT_T
XN_ID

Example:
GBP British pounds
USD United States dollars
SEK Swedish kronor.

Invoice/InvoiceHeader/TotalAmount

OINVOH.UHAMT2; The field indicates the amount including taxes, charges and allowances
OIS350MI/GetInvHead in foreign currency

►►►
INVOICE.IH_TOTAL_AMT_T
XN

Invoice/InvoiceHeader/TotalBaseAmount

@currencyID

CMNDIV.CCLOCD; The field indicates the abbreviation for the currency. The abbreviation
OIS350MI/GetInvHead should follow ISO standards.

►►►
INVOICE.IH_TOTAL_AMT_B
C_ID

Example:

Invoice

Infor M3 Business Engine - Infor Business Vault

GBP British pounds
USD United States dollars
SEK Swedish kronor.

Invoice/InvoiceHeader/TotalBaseAmount



OINVOH.UHAMT1; The field indicates the amount including taxes, charges and allowances
OIS350MI/GetInvHead in local currency

INVOICE.IH_TOTAL_AMT_B
ASE

Invoice/InvoiceHeader/CustomerParty/PartyIDs/ID



OINVOH.UHCUNO; The field indicates the unique identification of a customer. It can contain
OIS350MI/GetInvHead up to ten positions, and is alphanumeric.

INVOICE.IH_CP_PID_ID

Invoice/InvoiceHeader/PaymentTerm/Term/ID



ODHEAD.UHTEPY; The field indicates how the due date is to be calculated.
OIS350MI/
LstInvHeadByCo

INVOICE_PMT_TERM.IH_PT
_T_ID

Invoice/InvoiceHeader/PaymentTerm/Term/DueDateTime



OINVOH.UHDUOT; The field indicates the date the invoice is due for payment.
OIS350MI/
LstInvHeadByCo

INVOICE_PMT_TERM.IH_PT
_T_DUE_DATE

Invoice/InvoiceHeader/Tax/ID



OINVOL.ONVTCD; The field indicates the VAT Code. Read LstInvLineByType by getting
OIS350MI/ all IVTP = 40 records.
LstInvLineByTyp

INVOICE_TX.IH_T_ID

Invoice/InvoiceHeader/Tax/Amount



@currencyID

OINVOH.UHCUCD; The field indicates the currency
OIS350MI/GetInvHead

INVOICE_TX.IH_T_AMT_TX
N ID

Invoice/InvoiceHeader/Tax/Amount



OINVOL.ONIVAM; The field indicates the Tax Amount
OIS350MI/
LstInvLineByTyp

INVOICE_TX.IH_T_AMT_TX
N

Invoice/InvoiceHeader/Tax/BaseAmount



@currencyID

CMNDIV.CCLOCD; The field indicates the abbreviation for the currency. The abbreviation
OIS350MI/GetInvHead should follow ISO standards.

INVOICE_TX.IH_T_AMT_BC
_ID

Example:
GBP British pounds
USD United States dollars
SEK Swedish kronor.

Invoice/InvoiceHeader/Tax/BaseAmount



OINVOL.ONIVLA; The field indicates the Tax Amount
OIS350MI/
LstInvLineByTyp

INVOICE_TX.IH_T_AMT_BA
SE

Invoice/InvoiceHeader/Charge/ID



OINVOL.ONIVTP; Get all Records with IVTP = 67, 60, 65, If IVTP = 65 set ID to "Service
OIS350MI/LstInvLine Charge" else "Order Charge"

INVOICE_CHRG.IH_C_ID

Invoice/InvoiceHeader/Charge/Amount



@currencyID

Invoice

Infor M3 Business Engine - Infor Business Vault

OINVOH.UHCUCD; OIS350MI/GetInvHead	The field indicates the currency	INVOICE_CHRG.IH_C_AMT_ TXN_ID
Invoice/InvoiceHeader/Charge/Amount		
OINVOL.ONIVAM; OIS350MI/LstInvLine	The fields indicates the Charge Amount	INVOICE_CHRG.IH_C_AMT_ TXN
Invoice/InvoiceHeader/Charge/BaseAmount		
@currencyID		
CMNDIV.CCLOCD; OIS350MI/GetInvHead	The field indicates the currency	INVOICE_CHRG.IH_C_AMT_ BC_ID
Invoice/InvoiceHeader/Charge/BaseAmount		
OINVOL.ONIVLA; OIS350MI/LstInvLine	The fields indicates the Charge Base Amount	INVOICE_CHRG.IH_C_AMT_ BASE
Invoice/InvoiceHeader/Status/Code		
OINVOH.UHINST; OIS350MI/GetInvHead	The field indicates how far an invoice has progressed in the invoicing flow.	INVOICE.IH_S_CD
INST >= 80 = "Open"		
Invoice/InvoiceHeader/BillToParty/PartyIDs/ID		
OINVOH.UNPYNO; OIS350MI/GetInvHead	The field indicates the person/business who has paid or will pay the invoice.	INVOICE.IH_BTP_PID_ID
Invoice/InvoiceLine/Note		
OINVOL.CONO + DIVI + YEA4, INPX, IVNO, IVTP, ORNO, DLIX, WHLO , IVRF; OIS350MI/ LstInvLineByTyp	This contains concatenated values of the following: company, division, year, invoice prefix, invoice number, information type, order number, delivery number, warehouse, invoice reference.	INVOICE_LINE_NT_LC.IL_ NOTE
Invoice/InvoiceLine/Item/ItemID/ID		
ODLINE.UBITNO; OIS350MI/GetDelLine	The field indicates the item number (for Maintenance, the item number or equipment number), which is a unique ID for an individual	INVOICE_LINE.IL_I_IID_ ID
Invoice/InvoiceLine/Item/Description		
OOLINE.OBITDS; OIS350MI/GetDelLine	The field indicates the name for each item.	INVOICE_LINE_LC.IL_I_D SC
Invoice/InvoiceLine/Quantity		
@unitCode		
MITMAS.MMUNMS; OIS350MI/GetDelLine	The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.	INVOICE_LINE.IL_QTY_TX N_ID
Invoice/InvoiceLine/Quantity		
ODLINE.UBIVQA; OIS350MI/GetDelLine	The field indicates the invoiced quantity in a basic U/M for the delivery line. Invoiced quantity is updated at invoicing. During invoice updating, delivered quantity on the delivery line is transferred to the invoiced quantity on the order line and to the invoiced quantity on the delivery line. Delivered quantity on the order line is reduced by the transferred delivered quantity on the delivery line.	INVOICE_LINE.IL_QTY_TX N
Invoice/InvoiceLine/BaseUOMQuantity		

Invoice

Infor M3 Business Engine - Infor Business Vault

@unitCode

MITMAS.MMUNMS; The field indicates the unit in which each item is recorded in inventory, INVOICE_LINE.IL_QTY_BC
OIS350MI/GetDelLine even if alternate inventory units of measure are used. All balance _UNIT
information for the current item is always stored in this unit.

Invoice/InvoiceLine/BaseUOMQuantity

ODLINE.UBIVQT; Quantity of an invoice line ►►► INVOICE_LINE.IL_QTY_BC
OIS350MI/GetDelLine UOM

Invoice/InvoiceLine/UnitPrice/Amount

@currencyID

OINVOH.UHCUCD; The field indicates the currency ►►► INVOICE_LINE.IL_UP_AMT
OIS350MI/GetInvHead TXN_ID

Invoice/InvoiceLine/UnitPrice/Amount

ODLINE.UBSAPR; The field indicates the invoice amount in the local currency. ►►► INVOICE_LINE.IL_UP_AMT
OIS350MI/GetDelLine _TXN

Invoice/InvoiceLine/UnitPrice/PerQuantity

@unitCode

ODLINE.UBSPUN; The field indicates the sales price U/M ►►► INVOICE_LINE.IL_UP_PER
OIS350MI/GetDelLine QTY_TXN_ID

Invoice/InvoiceLine/UnitPrice/PerQuantity

ODLINE.UBSACD; The field indicates the quantity to which the sales price applies. Sales ►►► INVOICE_LINE.IL_UP_PER
OIS350MI/GetDelLine price quantity is defined for each item and is expressed in the item unit _QTY_TXN
of measure.

Invoice/InvoiceLine/ExtendedAmount

@currencyID

OINVOH.UHCUCD; The field indicates the abbreviation for the currency. The abbreviation ►►► INVOICE_LINE.IL_EXTND_
OIS350MI/GetInvHead should follow ISO standards. AMT_TXN_ID

Example:
GBP British pounds
USD United States dollars
SEK Swedish kronor.

Invoice/InvoiceLine/ExtendedAmount

OINVOL.ONIVAM; The field indicates the requested claimable amount. ►►► INVOICE_LINE.IL_EXTND_
OIS350MI/ AMT_TXN
LstInvLineByTyp It is the amount of each item on a service claim that is requested for payment.

Invoice/InvoiceLine/ExtendedBaseAmount

@currencyID

CMNDIV.CCLOCD; The field indicates the abbreviation for the currency. The abbreviation ►►► INVOICE_LINE.IL_EXTND_
OIS350MI/GetInvHead should follow ISO standards. AMT_BC_ID

Example:
GBP British pounds
USD United States dollars
SEK Swedish kronor.

Invoice/InvoiceLine/ExtendedBaseAmount

OINVOL.ONIVLA; The field indicates the requested claimable amount. ►►► INVOICE_LINE.IL_EXTND_
OIS350MI/ AMT_BASE

Invoice

Infor M3 Business Engine - Infor Business Vault

LstInvLineByTyp	It is the amount of each item on a service claim that is requested for payment.	
<hr/>		
Invoice/InvoiceLine/TotalAmount		▶▶▶
@currencyID		
OINVOH.UHCUCD; OIS350MI/GetInvHead	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.	INVOICE_LINE.IL_TOTAL_ AMT_TXN_ID
	Example: GBP British pounds USD United States dollars SEK Swedish kronor.	
<hr/>		
Invoice/InvoiceLine/TotalAmount		▶▶▶
OINVOL.ONIVAM; OIS350MI/ LstInvLineByTyp	The field indicates the requested claimable amount. It is the amount of each item on a service claim that is requested for payment.	INVOICE_LINE.IL_TOTAL_ AMT_TXN
<hr/>		
Invoice/InvoiceLine/TotalBaseAmount		▶▶▶
@currencyID		
CMNDIV.CCLOCD; OIS350MI/GetInvHead	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.	INVOICE_LINE.IL_TOTAL_ AMT_BC_ID
	Example: GBP British pounds USD United States dollars SEK Swedish kronor.	
<hr/>		
Invoice/InvoiceLine/TotalBaseAmount		▶▶▶
OINVOL.ONIVLA; OIS350MI/ LstInvLineByTyp	The field indicates the requested claimable amount. It is the amount of each item on a service claim that is requested for payment.	INVOICE_LINE.IL_TOTAL_ AMT_BASE
<hr/>		
Invoice/InvoiceLine/InvoiceCharge/ID		▶▶▶
OINVOL.ONIVTP; OIS350MI/LstInvLine	Get only IVTP = 67 Records. Constant = "Order Charge"	INVOICE_LINE_INVOICE_C HRG.IL_IC_ID
<hr/>		
Invoice/InvoiceLine/InvoiceCharge/Amount		▶▶▶
@currencyID		
OINVOH.UHCUCD; OIS350MI/GetInvHead	The field indicates the currency	INVOICE_LINE_INVOICE_C HRG.IL_IC_AMT_TXN_ID
<hr/>		
Invoice/InvoiceLine/InvoiceCharge/Amount		▶▶▶
OINVOL.ONIVAM; OIS350MI/LstInvLine	The fields indicates the Charge Amount	INVOICE_LINE_INVOICE_C HRG.IL_IC_AMT_TXN
<hr/>		
Invoice/InvoiceLine/InvoiceCharge/BaseAmount		▶▶▶
@currencyID		
CMNDIV.CCLOCD; OIS350MI/GetInvHead	The field indicates the currency	INVOICE_LINE_INVOICE_C HRG.IL_IC_AMT_BC_ID
<hr/>		
Invoice/InvoiceLine/InvoiceCharge/BaseAmount		▶▶▶
OINVOL.ONIVLA; OIS350MI/LstInvLine	The fields indicates the Charge Base Amount	INVOICE_LINE_INVOICE_C HRG.IL_IC_AMT_BASE

Invoice

Infor M3 Business Engine - Infor Business Vault

Invoice/InvoiceLine/InvoiceAllowance/Amount

►►►

@currencyID

OINVOH.UHCUCD; The field indicates the currency
OIS350MI/GetInvHead

INVOICE_LINE_INVOICE_A
LLWNC.IL_IA_AMT_TXN_ID

Invoice/InvoiceLine/InvoiceAllowance/Amount

►►►

OINVOL.ONIVAM; The fields indicates the Allowance Amount
OIS350MI/
LstInvLineByTyp

INVOICE_LINE_INVOICE_A
LLWNC.IL_IA_AMT_TXN

Invoice/InvoiceLine/InvoiceAllowance/BaseAmount

►►►

@currencyID

CMNDIV.CCLOCID; The field indicates the currency
OIS350MI/GetInvHead

INVOICE_LINE_INVOICE_A
LLWNC.IL_IA_AMT_BC_ID

Invoice/InvoiceLine/InvoiceAllowance/BaseAmount

►►►

OINVOL.ONIVLA; The fields indicates the Allowance Base Amount
OIS350MI/
LstInvLineByTyp

INVOICE_LINE_INVOICE_A
LLWNC.IL_IA_AMT_BASE

Invoice/InvoiceLine/SalesOrderReference/DocumentID/ID

►►►

ODLINE.UBORNO; The field indicates a unique identity for a customer order.
OIS350MI/GetDelLine

INVOICE_LINE.IL_SOR_DI
D_ID

Different order number series can be used, which are controlled by an assigned order type. Number series are connected to an order type

Invoice/InvoiceLine/SalesOrderReference/LineNumber

►►►

ODLINE.UBPONR; This field indicates the line number
OIS350MI/GetDelLine

INVOICE_LINE.IL_SOR_LI
NE_NMBR

Invoice/InvoiceLine/ExtendedCost/Amount

►►►

@currencyID

OINVOH.UHCUCD; The field indicates the currency
OIS350MI/GetInvHead

INVOICE_LINE.IL_EXTND_
COST_AMT_TXN_ID

Invoice/InvoiceLine/ExtendedCost/Amount

►►►

ODLINE.UBDCOS; This field indicates the Extended Cost
OIS350MI/GetDelLine

INVOICE_LINE.IL_EXTND_
COST_AMT_TXN

Invoice/InvoiceLine/ExtendedCost/BaseAmount

►►►

ODLINE.UBDCOS; This field indicates the Extended Cost Converted to local currency
OIS350MI/GetDelLine

INVOICE_LINE.IL_EXTND_
COST_AMT_BASE

Invoice/InvoiceLine/ShipToParty/PartyIDs/ID

►►►

ODHEAD.UACUNO; The field indicates the unique identification of a customer. It can contain
OIS350MI/GetDelLine up to ten positions, and is alphanumeric.

INVOICE_LINE.IL_STP_PI
D_ID

ItemMaster

Infor M3 Business Engine - Infor Business Vault

ItemMaster/ItemMasterHeader/ItemID/ID

MITMAS.MMITNO; The field indicates the item number which, is a unique ID for an individual item. Item number can consist up to 15 alphanumeric characters.
MMS200MI/GetItemBasic

▶ ▶ ▶
ITEM.IMH_IID_ID

ItemMaster/ItemMasterHeader/ItemID/RevisionID

MITMAS.MMECVE; The field indicates the revision number (edition) for an item or document.
MMS200MI/GetItemTech

▶ ▶ ▶
ITEM.IMH_IID_RVSN_ID

ItemMaster/ItemMasterHeader/UPCID

MITPOP.MPPOPN; Correspond to GTIN-12 and UCC-12. This is a 12-digit number used for identifying goods.
MMS025MI/LstAlias

▶ ▶ ▶
ITEM.IMH_UPCID

Alias qualifier = UPC

ItemMaster/ItemMasterHeader/GTIN

MITPOP.MPPOPN; The Global Trade Item Number is a 14-digit number which includes various EAN/UCC numbering structures.
MMS025MI/LstAlias

▶ ▶ ▶
ITEM.IMH_GTIN

Alias qualifier = GTIN

ItemMaster/ItemMasterHeader/ServiceIndicator

Set to false for all items

▶ ▶ ▶
ITEM.IMH_SRVC_INDCTR

ItemMaster/ItemMasterHeader/Description

MITMAS.MMFUDS and General item description.
MITLAD.MDFUDS; If description also exists in specific languages, this is provided together
MMS200MI/ with the language ID
LstItemDescLang

▶ ▶ ▶
ITEM_LC.IMH_DSC

ItemMaster/ItemMasterHeader/Classification/Codes/Code

@listID

- 1) M3 BE field Item group has list ID "Item Groups"
- 2) M3 BE field Product group has list ID "Product Groups"
- 3) M3 BE field Business area has list ID "Business Sectors"
- 4) M3 BE field Procurement group has list ID "Buying Groups"
- 5) M3 BE field Item type has list ID "Item Types"
- 6) M3 BE field Item category group has list ID "Item Classes"

▶ ▶ ▶
ITEM.IMH_C_C_CD_ABCCDS [@listID='ABC Codes']

ItemMaster/ItemMasterHeader/Classification/Codes/Code

@sequence

The sequence attribute is used for the ordering of elements within a document. It identifies the hierarchical position of the identifier in the case of multi-level codes.

▶ ▶ ▶
ITEM.IMH_C_C_CD_01 [@sequence='1']

ItemMaster/ItemMasterHeader/TrackingIndicator

MITMAS.MMSTCD; Inventory Accounting
MMS200MI/GetItemBasic The field indicates whether the stock kept for the item is accounted in inventory.
1 = true; 0, 2, 3 = false

▶ ▶ ▶
ITEM.IMH_TRACKING_INDC
TR

- 0 = No.
1 = Yes, the item is inventory accounted.
2 = No, the item is not inventory accounted, but it is planned as demand in the material planning process in (MMS080 - Material Plan. Open).

ItemMaster

Infor M3 Business Engine - Infor Business Vault

3 = No, the item is not inventory accounted, but it is planned as a function number. A function number is a dummy number for items that can replace each other. So material planning for the item is done on the function number level instead of the item level.

ItemMaster/ItemMasterHeader/ItemStatus/Code



MITMAS.MMSTAT; The field indicates the item's status.
MMS200MI/GetItmBasic M3 BE status is translated according to :
10 = Pending
15 = Pending
20 = Open
30 = Open
40 = Open
50 = DoNotReorder
80 = Obsolete
90 = Obsolete
99 = Deleted

ITEM.IMH_IS_CD

ItemMaster/ItemMasterHeader/ItemStatus/Description



MITMAS.MMSTAT; Item status description
MMS200MI/GetItmBasic M3 BE status description is translated according to:
10 = Preliminary Item
15 = Replacement Item
20 = Released Item
30 = Alternate Items Available
40 = Low Turnover Item
50 = Discontinued Item
80 = Not Carried
90 = No Longer Stocked
99 = Item Number Changed

ITEM_LC.IMH_IS_DSC

ItemMaster/ItemMasterHeader/BaseUOMCode



MITMAS.MMUNMS; The field indicates the unit in which each item is recorded in inventory,
MMS200MI/GetItmBasic even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.

ITEM.IMH_BASE_UOMCD

ItemMaster/ItemMasterHeader/StorageUOMCode



MITMAS.MMUNMS; The field indicates the unit in which each item is recorded in inventory,
MMS200MI/GetItmBasic even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.

ITEM.IMH_STORAGE_UOMCD

In M3BE, the StorageUOMCode is the same as Base UOM Code

ItemMaster/ItemMasterHeader/SerialControlIndicator



MITMAS.MMINDI; The field indicates if and how serial control is to be applied for each
MMS200MI/GetItmBasic item.
0,1,3 = false; 2,5 = true

ITEM.IMH_SERIAL_CNTRL_INDCTR

ItemMaster/ItemMasterHeader/LotControlIndicator



MITMAS.MMINDI; The field indicates if and how lot control is to be applied for each item.
MMS200MI/GetItmBasic 0 = false 1,2,3,5 = true

ITEM.IMH_LOT_CNTRL_INDCTR

ItemMaster/ItemMasterHeader/ConfiguredItemIndicator



MITMAS.MMCHCD; The field indicates if the item is configured when ordered or configured
MMS200MI/GetItmBasic as a maintenance item.

ITEM.IMH_CONFIGURED_ITEM_INDCTR

ItemMaster

Infor M3 Business Engine - Infor Business Vault

0, 3 = false
1, 2 = true
4, 5 = omitted, i.e. the element is not included in the BOD

ItemMaster/ItemMasterHeader/CatchWeightIndicator

MITMAS.MMACTI; The field indicates whether this is a catch weight item.
MMS200MI/GetItemBasic

▶▶▶

ITEM.IMH_CATCH_WGHT_IN
DCTR

0, 1 = false
2, 3, 4 = true

ItemMaster/ItemMasterHeader/SellableIndicator

MITMAS.MMSALE; The field indicates if the item is a sales item.
MMS200MI/GetItemBasic 0 = false 1,2 = true

▶▶▶

ITEM.IMH_SELLABLE_INDC
TR

ItemMaster/ItemMasterHeader/PackagingUnit/GrossWeightMeasure

@unitCode

CSYPAR.CPPARM; The field indicates the general unit of measure for weights.
CRS175MI/ It is stored in M3 BE, program CRS703 General Units of Measure.
GetItemFreeFlds

▶▶▶

ITEM.IMH_PU_GWM_UNIT

ItemMaster/ItemMasterHeader/PackagingUnit/GrossWeightMeasure

MITMAS.MMGRWE; The field indicates the item's weight per basic U/M including the weight
MHS001MI/ChgIntItm of any product packaging material.
The information is used when creating packages for transportation
purposes, and should not include the transportation packaging material
such as transportation boxes, pallets, containers etc.

▶▶▶

ITEM.IMH_PU_GROSS_WGHT

ItemMaster/ItemMasterHeader/PackagingUnit/TotalVolumeMeasure

@unitCode

CSYPAR.CPPARM; The field indicates the general unit of measure for volumes .
CRS175MI/ It is stored in M3 BE, program CRS703 General Units of Measure.
GetItemFreeFlds

▶▶▶

ITEM.IMH_PU_TVM_UNIT

ItemMaster/ItemMasterHeader/PackagingUnit/TotalVolumeMeasure

MITMAS.MMVOL3; The field indicates the item volume per basic U/M including any product
MHS001MI/ChgIntItm packaging material

▶▶▶

ITEM.IMH_PU_TOTAL_VLM

ItemMaster/ItemMasterHeader/ProcurementParameters/ProcurementMethodCode

MITMAS.MMMABU; The field indicates whether the item is manufactured in-house or
MMS200MI/GetItemBasic purchased.
1 = Manufacture
2 = Purchase

▶▶▶

ITEM.IMH_PP_PROCUREMENT
T_MTHD_CD

Location

Infor M3 Business Engine - Infor Business Vault

Location/ID

MITWHL.MWWHLO; The field indicates the warehouse ID.
MMS005MI/
LstWarehouses

▶▶▶
LOCATION.ID

Location/Name

MITWHL.MWWHNM; The field indicates optional text
MMS005MI/
LstWarehouses

▶▶▶
LOCATION_LC.NAME

Location/Address/CityName

CIADDR.OATOWN; The field indicates the city in an address.
MMS005MI/
LstWarehouses

▶▶▶
LOCATION.A_PRI_CITY_NA
ME

Location/Address/CountrySubDivisionCode

CIADDR.OAECAR; The field indicates an area, province or state within a country.
MMS005MI/
LstWarehouses

▶▶▶
LOCATION.A_PRI_C_SBDVS
N

Location/Address/CountryCode

CIADDR.OACSCD; The field indicates a country.
MMS005MI/
LstWarehouses

▶▶▶
LOCATION.A_PRI_CNTRY_C
D

Location/Address/PostalCode

CIADDR.OAPONO; The field indicates a postal code for a specific address.
MMS005MI/
LstWarehouses

▶▶▶
LOCATION.A_PRI_POSTAL_
CD

Location/TimeZone/TimeZoneOffset

CITZON.TZTGMT; The field indicates the number of hours and minutes by which the
MMS005MI/Select current time zone deviates from UTC (Universal Time Coordinated).
Note that UTC replaces Greenwich Mean Time (GMT).
You should enter any time zone that is earlier than UTC with a minus
sign after the number of hours.

▶▶▶
LOCATION.TZ_TZ_OFFSET

Location/TimeZone/Description

CITZON.TZTX40; The field indicates a description of the current identity.
MMS005MI/Select

▶▶▶
LOCATION_LC.TZ_DSC

PayFromPartyMaster

Infor M3 Business Engine - Infor Business Vault

PayFromPartyMaster/PartyIDs/ID		▶▶▶
OCUSMA.OKCUNO; This field indicates the customer number	PAY_FROM_PARTY.PID_ID	
CRS610MI/GetBasicData		
PayFromPartyMaster/Name		▶▶▶
OCUSMA.OKCUNM; This field indicates the customer name	PAY_FROM_PARTY_LC.NAME	
CRS610MI/GetBasicData		
PayFromPartyMaster/Location/Address/AttentionOfName		▶▶▶
OCUSMA.OKYREF; This field indicates the customer's contact person	PAY_FROM_PARTY_LC.L_A_	
CRS610MI/GetBasicData	PRI_ATTN_NAME	
PayFromPartyMaster/Location/Address/AddressLine		▶▶▶
@sequence	The field indicates the Address Line sequence	
	PAY_FROM_PARTY_LC.L_A_	[@sequence='1']
	PRI_AL_ADDL_01	
PayFromPartyMaster/Location/Address/CityName		▶▶▶
OCUSMA.OKTOWN; This field indicates the city	PAY_FROM_PARTY.L_A_PRI	
CRS610MI/GetBasicData	CITY_NAME	
PayFromPartyMaster/Location/Address/CountrySubDivisionCode		▶▶▶
The field indicates the state/region/countrysubdivision	PAY_FROM_PARTY.L_A_PRI	
	C_SBDVSN	
PayFromPartyMaster/Location/Address/CountryCode		▶▶▶
OCUSMA.OKCSCD; This field indicates the country code	PAY_FROM_PARTY.L_A_PRI	
CRS610MI/GetBasicData	_CNTRY_CD	
PayFromPartyMaster/Location/Address/PostalCode		▶▶▶
OCUSMA.OKPONO; This field indicates the postal code	PAY_FROM_PARTY.L_A_PRI	
CRS610MI/GetBasicData	POSTAL_CD	
PayFromPartyMaster/PaymentTermID		▶▶▶
OCUSMA.OKTEPY/ This field indicates the payment terms id for the customer	PAY_FROM_PARTY.PMT_TER	
CCUDIV.O Data is retrieved from customer master, table OCUSMA, or, if	M_ID	
KTEPY.; CRS610MI/ applicable, from customer local exceptions, table CCUDIV.		
GetOrderInfo		
PayFromPartyMaster/Status/Code		▶▶▶
OCUSMA.OKSTAT; This field indicates the status of the customer.	PAY_FROM_PARTY.S_CD	
CRS610MI/GetBasicData		
If M3 status is 10, set element to "Pending"		
If M3 status is 20, set element to "Open"		
If M3 status is 90, set element to "Closed"		
PayFromPartyMaster/Classification/Codes/Code		▶▶▶
@listID	The field indicates the Classification code listID.	
	1) If Customer type field is filled, set listID to "Customer Types"	
	2) If Delivery terms field is filled, set listID to "Incoterms"	
	3) If District field is filled, set listID to "District"	
	PAY_FROM_PARTY.C_C_CD_	[@listID='Departments']
	OFC	
PayFromPartyMaster/Classification/Codes/Code		▶▶▶
@sequence	The sequence attribute identifies the hierarchical position of the identifier in the case of multi-level codes	
	PAY_FROM_PARTY.C_C_CD_	[@sequence='1']
	01	

PayFromPartyMaster

PayFromPartyMaster/BillToParty/PartyIDs/ID



OCUSMA.OKCUNO; This is a list of customer records from M3 BE that is the invoice
BODCSSMI/ recipient for the PayFromPartyMaster.
LstBillToParty It is retrived in two steps using BODCSSMI/LstBillToParty:
1) All customer records (OKCUNO) that uses the PayFromPartyMaster
id as Payer (OKPYNO)
2) For each customer record (OKCUNO), retrieve the invoice recipient
(OKINRC) if it is populated, otherwise retrieve the payer (OKPYNO)

PAY_FROM_PARTY.BTP_PID
_ID

PayableTransaction

Infor M3 Business Engine - Infor Business Vault

PayableTransaction/PayableTransactionHeader/DocumentID/ID

FPLEDG.CONO + DIVI + Transaction code = 40; Unique key in FPLEDG; Company + Division + YEA4 + JRNO + JSNO; Year + Journal Number + Journal Sequence Number
APS200MI/GetInvoice

►►►
PYBL_TXN.PTH_DID_ID

PayableTransaction/PayableTransactionHeader/AlternateDocumentID/ID

FPLEDG.SUNO + SPYN Transaction code = 40; Alternate key in FPLEDG; Supplier number + + SINO + INYR; Payee number + Supplier Invoice number + Invoice year
APS200MI/GetInvoice

►►►
PYBL_TXN.PTH_ADID_ID

PayableTransaction/PayableTransactionHeader/DocumentDateTime

FPLEDG.IVDT; The field indicates the date from which the invoice is valid.
APS200MI/GetInvoice

►►►
PYBL_TXN.PTH_DCMNT_DATE

PayableTransaction/PayableTransactionHeader/Description

FPLEDG.TDSC; The field indicates the transaction description from the user-defined accounting options for manual payments.
APS200MI/GetInvoice

►►►
PYBL_TXN.LC.PTH_DSC

The description allows for a more detailed voucher description.

PayableTransaction/PayableTransactionHeader/Status/Code

FPLEDG.Various; PAID --> Reconciliation code = 9 and Invoice Amount less Paid Amount = 0 and Transaction Code = 50; PARTIAL PAID --> Reconciliation code <> 9 and Paid amount less than Invoice Amount and Transaction Code = 50; VOID --> Reconciliation code = 9 and Payment status = 4 (blocked) and Transaction Code = 40; DISPUTE --> Payment Stop > 0; PREPAID --> Paid amount greater than Invoice Amount or Transaction Code = 40 and Information type = AP; OPEN --> Reconciliation code = 0 and Payment status = 0 and Payment stop = 0
APS200MI/GetInvoice

►►►
PYBL_TXN.PTH_S_CD

PayableTransaction/PayableTransactionHeader/SupplierParty/PartyIDs/ID

FPLEDG.SUNO; The field indicates the unique identity of a supplier.
APS200MI/GetInvoice

►►►
PYBL_TXN.PTH_SP_PID_ID

PayableTransaction/PayableTransactionHeader/SupplierParty/Contact/Communication/DialNumber

CIDMAS.PHNO or The field indicates the telephone number of the customer or supplier.
PHN2; CRS620MI/
GetBasicData

►►►
PYBL_TXN.PTH_SP_C_PRI_C_PHONEOFC

PayableTransaction/PayableTransactionHeader/PayableStyle

If invoice amount is negative then "Credit Memo". If the transaction is applied on On-Account then "Prepaid". If the two conditions are not met, it is "Invoice".

►►►
PYBL_TXN.LC.PTH_PYBL_STYLE

PayableTransaction/PayableTransactionHeader/InvoiceReference/DocumentID/ID

FPLEDX.PEXI; If MI returns any record from FPLEDX, information category = 416 then use PEXI (original invoice number) else invoice number = SINO; 416 is "splitted AP invoice"
APS251MI/LstInvInfo

►►►
PYBL_TXN.PTH_SIR_DID_ID

PayableTransaction/PayableTransactionHeader/ExtendedAmount@currencyID

FGLEDG.CUCD; The field indicates the abbreviation for the invoice currency. The abbreviation should follow ISO standards.
APS200MI/GetInvTotlInfo

►►►
PYBL_TXN.PTH_EXTND_AMT_TXN_ID

PayableTransaction/PayableTransactionHeader/ExtendedAmount

FGLEDG.CUAM - TXCU; Invoice current amount less tax currency amount

►►►
PYBL_TXN.PTH_EXTND_AMT

PayableTransaction

Infor M3 Business Engine - Infor Business Vault

APS200MI/GetInvTotInfo	_TXN
PayableTransaction/PayableTransactionHeader/TotalAmount @currencyID FGLEDG.CUCD; The field indicates the abbreviation for the invoice foreign currency. The APS200MI/GetInvTotInfo abbreviation should follow ISO standards.	▶▶▶ PYBL_TXN.PTH_TOTAL_AMT TXN_ID
PayableTransaction/PayableTransactionHeader/TotalAmount FGLEDG.CUAM; Invoice amount for TRCD = 40 APS200MI/GetInvTotInfo	▶▶▶ PYBL_TXN.PTH_TOTAL_AMT TXN
PayableTransaction/PayableTransactionHeader/Tax/BasisAmount @currencyID FGLEDG.CUCD; The field indicates the abbreviation for the invoice currency. The APS200MI/GetInvTotInfo abbreviation should follow ISO standards.	▶▶▶ PYBL_TXN_TX.PTH_T_BASI S_AMT_TXN_ID
PayableTransaction/PayableTransactionHeader/Tax/BasisAmount FGLEDG.TBCU; Sum of FGLEDG transaction with transaction code = 41 and AT04 > 2 APS200MI/GetInvTotInfo	▶▶▶ PYBL_TXN_TX.PTH_T_BASI S_AMT_TXN
PayableTransaction/PayableTransactionHeader/Tax/Amount @currencyID FGLEDG.CUCD; The field indicates the abbreviation for the currency. The abbreviation APS200MI/GetInvTotInfo should follow ISO standards.	▶▶▶ PYBL_TXN_TX.PTH_T_AMT_ TXN_ID
PayableTransaction/PayableTransactionHeader/Tax/Amount FGLEDG.TXCU; Summary of FGLEDG transactions with TRCD = 41 and AT04 = 1 or 2 APS200MI/GetInvTotInfo	▶▶▶ PYBL_TXN_TX.PTH_T_AMT_ TXN
PayableTransaction/PayableTransactionHeader/DiscountStatus/DiscountTakenAmount @currencyID FPLEDG.CUCD; The field indicates the abbreviation for the foreign invoice currency. The APS200MI/GetInvTotInfo abbreviation should follow ISO standards.	▶▶▶ PYBL_TXN.PTH_DS_DISC_T AKEN_AMT_TXN_ID
PayableTransaction/PayableTransactionHeader/DiscountStatus/DiscountTakenAmount FGLEDG.CDCU; Cash discount for an invoice payment. Cash discount taken is in foreign APS200MI/GetInvTotInfo currency.	▶▶▶ PYBL_TXN.PTH_DS_DISC_T AKEN_AMT_TXN
PayableTransaction/PayableTransactionHeader/PayableAmount @currencyID FGLEDG.CUCD; The field indicates the abbreviation for the invoice currency. The APS200MI/GetInvTotInfo abbreviation should follow ISO standards.	▶▶▶ PYBL_TXN.PTH_PYBL_AMT_ TXN_ID
PayableTransaction/PayableTransactionHeader/PayableAmount FGLEDG.CUAM; Outstanding foreign amount. This is the amount of an invoice less APS200MI/GetInvTotInfo payments.	▶▶▶ PYBL_TXN.PTH_PYBL_AMT_ TXN
PayableTransaction/PayableTransactionHeader/PaidAmount @currencyID FGLEDG.CUCD; The field indicates the abbreviation for the foreign currency. The APS200MI/GetInvTotInfo abbreviation should follow ISO standards.	▶▶▶ PYBL_TXN.PTH_PAID_AMT_ TXN_ID
PayableTransaction/PayableTransactionHeader/PaidAmount FGLEDG.PCUA; Paid foreign amount APS200MI/GetInvTotInfo	▶▶▶ PYBL_TXN.PTH_PAID_AMT_ TXN
PayableTransaction/PayableTransactionHeader/PaymentMethodCode CSYTAB.PARM; First payment method AP is read (PYME), then payment type CRS175MI/ connected to the method (PYTP) is read. If payment class (PYCL) in	▶▶▶ PYBL_TXN.PTH_PMT_MTHD_ CD

PayableTransaction

Infor M3 Business Engine - Infor Business Vault

GetGeneralCode payment type is: 0 = "Cash"; 1 = "Cheque"; 2 = "Cheque"; 3 = "GIRO";
4 = "BankDraft"; 5 = "Credit Transfer"; everything else "Cash".

PayableTransaction/PayableTransactionHeader/PaymentTerm/Term/ID

FPLEDG.TEPY; The field indicates how the due date is to be calculated.
APS200MI/GetInvoice



PYBL_TXN_PMT_TERMS.PTH
PT_T_ID

PayableTransaction/PayableTransactionHeader/PaymentTerm/Term/Description

CSYTAB.TX40; The field indicates a description of the current identity.
CRS175MI/
GetGeneralCode



PYBL_TXN_PMT_TERMS.LC.
PTH_PT_T_DSC

PayableTransaction/PayableTransactionHeader/PaymentTerm/Term/DueDateTime

FPLEDG.DUDT; The field indicates the date the invoice is due for payment according to
APS200MI/GetInvoice payment or cash discount terms.



PYBL_TXN_PMT_TERMS.PTH
PT_T_DUE_DATE

PayableTransaction/PayableTransactionHeader/RemitToParty/PartyIDs/ID

FPLEDG.SPYN; Payee is used.
APS200MI/GetInvoice



PYBL_TXN.PTH_RTP_PID_I
D

Person

Person/ID		▶▶▶
CMNUSR.JUUSID;	The field indicates a unique identity of a user in the M3 system.	PERSON.ID
MNS150MI/GetUserData	A new user is created automatically in the operating system as well. If the user is already entered in the operating system, the existing name is used.	
	This ID must be used when reporting work performed. It is also used as a basis for the Payroll Administration and Time and Attendance modules.	
Person/Name		▶▶▶
CMNUSR.JUTX40;	The field indicates the name of the user.	PERSON_LC.NAME
MNS150MI/GetUserData		

ProductionOrder

Infor M3 Business Engine - Infor Business Vault

ProductionOrder/ProductionOrderHeader/DocumentID/ID

MWOHED.VHFACI The unique keys are combination of FACI + PRNO + MFNO
MWOHED.VHPRNO
MWOHED.VHMFNO.;
PMS100MI/Get



PRD_ORD.POH_DID_ID

ProductionOrder/ProductionOrderHeader/DisplayID

MWOHED.MFNO; 0
PMS100MI/Get



PRD_ORD.POH_DISPLAY_ID

ProductionOrder/ProductionOrderHeader/Status/Code

MWOHED.WHST; MWOHED.WHST values is mapped to Infor Status as follow:
PMS100MI/Get
Planned = 10
Firm = (N/A)
Released = 20
Active = 40, 50, 60
Stopped = 25, 26, 45, 46, 55, 56, 65, 66
Cancelled = (N/A)
Completed = 80
History = (N/A)
Closed = 90



PRD_ORD.POH_S_CD

Note: (N/A) = not available

ProductionOrder/ProductionOrderHeader/OrderBaseUOMQuantity

@unitCode

MWOHED.UNMS; 0
MMS200MI/GetltnBasic



PRD_ORD.POH_ORDER_QTY_
BC_UNIT

ProductionOrder/ProductionOrderHeader/OrderBaseUOMQuantity

MWOHED.ORQT; 0
PMS100MI/Get



PRD_ORD.POH_ORDER_QTY_
BC_UOM

ProductionOrder/ProductionOrderHeader/RequiredQuantity

@unitCode

MWOHED.MAUN; Additional for BI
PMS100MI/Get



PRD_ORD.POH_RQRD_QTY_T
XN_ID

ProductionOrder/ProductionOrderHeader/RequiredQuantity

MWOHED.ORQA; Additional for BI
PMS100MI/Get



PRD_ORD.POH_RQRD_QTY_T
XN

ProductionOrder/ProductionOrderHeader/ExecutionTimePeriod/StartDateTime

MWOHED.RSDT; Note that time does not exist in M3 BE.
PMS100MI/Get



PRD_ORD.POH_ETP_START_
DATE

ProductionOrder/ProductionOrderHeader/ExecutionTimePeriod/EndDateTime

MWOHED.REFD; Note that time does not exist in M3 BE.
PMS100MI/Get



PRD_ORD.POH_ETP_END_DA
TE

ProductionOrder/ProductionOrderHeader/ForecastedTimePeriod/StartDateTime

MWOHED.STDT 0
MWOHED.MSTI.;
PMS100MI/Get



PRD_ORD.POH_FTP_START_
DATE

ProductionOrder/ProductionOrderHeader/ForecastedTimePeriod/EndDateTime

MWOHED.FIDT 0



PRD_ORD.POH_FTP_END_DA

ProductionOrder

Infor M3 Business Engine - Infor Business Vault

MWOHED.MFTI; PMS100MI/Get	TE
ProductionOrder/ProductionOrderDetail/Sequence MWOHED.SCHN; 0 PMS100MI/Get	►►► PRD_ORD_OPR.O_ORDER_DT L_SEQNC
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/ItemID/ID MWOHED.PRNO; Output item does not exist in M3, thus use the product no from the PMS100MI/Get Production header.	►►► PRD_ORD_OPR_OUT_ITM.O_ OI_IID_NID Custom Mapping: NID
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/ProducedBaseUOMQuantity @unitCode MITMAS.UNMS; 0 MMS200MI/GetItmBasic	►►► PRD_ORD_OPR_OUT_ITM.O_ OI_PRDCD_QTY_BC_UNIT
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/ProducedBaseUOMQuantity MWOOPE.MAQT; 0 PMS100MI/ SelOperations	►►► PRD_ORD_OPR_OUT_ITM.O_ OI_PRDCD_QTY_BC_UOM
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/OrderBaseUOMQuantity @unitCode MITMAS.UNMS; 0 MMS200MI/GetItmBasic	►►► PRD_ORD_OPR_OUT_ITM.O_ OI_ORDER_QTY_BC_UNIT
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/OrderBaseUOMQuantity MWOOPE.ORQT; 0 PMS100MI/ SelOperations	►►► PRD_ORD_OPR_OUT_ITM.O_ OI_ORDER_QTY_BC_UOM
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/Rejection/RejectBaseUOMQuantity @unitCode MITMAS.UNMS; 0 MMS200MI/GetItmBasic	►►► PRD_ORD_OPR_OUT_ITM.O_ OI_R_REJECT_QTY_BC_UNIT
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/Rejection/RejectBaseUOMQuantity MWOOPE.SCQT; 0 PMS100MI/ SelOperations	►►► PRD_ORD_OPR_OUT_ITM.O_ OI_R_REJECT_QTY_BC_UOM

PurchaseOrder

Infor M3 Business Engine - Infor Business Vault

PurchaseOrder/PurchaseOrderHeader/DocumentID/ID	▶▶▶
MPHEAD.IAPUNO; The field indicates the unique number that is assigned to a purchase order when it is created.	PUR_ORDER.POH_DID_ID
PurchaseOrder/PurchaseOrderHeader/DocumentID/RevisionID	▶▶▶
MPLINE.IBREVN; The field indicates a revision. PPS200MI/GetHead By using the revision number, it is possible to ascertain which purchase order lines are connected to a certain revision by updating them with the revision number.	PUR_ORDER.POH_DID_RVSN_ID
PurchaseOrder/PurchaseOrderHeader/DocumentDateTime	▶▶▶
MPHEAD.IAPUDT; The field indicates when the purchase order was placed. PPS200MI/GetHead	PUR_ORDER.POH_DCMNT_DATE
PurchaseOrder/PurchaseOrderHeader/Note	▶▶▶
MSYTXH.THTX40; The field indicates the notes or remarks. PPS200MI/LstHeadTxt	PUR_ORDER_ANTS_LC.POH_NOTES
PurchaseOrder/PurchaseOrderHeader/Status/Code	▶▶▶
MPHEAD.IAPUSL; / The field indicates the lowest or highest status.	PUR_ORDER.POH_STATUS_CD
PurchaseOrder/PurchaseOrderHeader/SupplierParty/PartyIDs/ID	▶▶▶
MPHEAD.IASUNO; The field indicates the unique identity of a supplier. PPS200MI/GetHead	PUR_ORDER.POH_SUPP_PID_ID
PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/ID	▶▶▶
MPPOAD.ADADK2; The field indicates the address type. PPS200MI/GetAddresses	PUR_ORDER.POH_STP_LOC_ID
PurchaseOrder/PurchaseOrderHeader/ShipFromParty/PartyIDs/ID	▶▶▶
MPHEAD.IASUNO; The field indicates the unique identity of a supplier. PPS200MI/GetHead	PUR_ORDER.POH_SFP_PID_ID
PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Contact/Communication/URI	▶▶▶
CIDREF.IREMAL; The field indicates an e-mail address for the contact CRS620MI/LstSupplierRef	PUR_ORDER.POH_SFP_CONTACT_URI_EMAIL
PurchaseOrder/PurchaseOrderHeader/ExtendedAmount @currencyID	▶▶▶
MPHEAD.IACUCD; The field indicates currency used. PPS200MI/GetHead	PUR_ORDER.POH_EXTND_AMOUNT_TXN_ID
PurchaseOrder/PurchaseOrderHeader/ExtendedAmount	▶▶▶
MPHEAD.IACOAM; The field indicates Net amount PPS200MI/GetHead	PUR_ORDER.POH_EXTND_AMOUNT_TXN
PurchaseOrder/PurchaseOrderHeader/ExtendedBaseAmount @currencyID	▶▶▶
MPHEAD.IACUCD; The field indicates local currency used. PPS200MI/LstLine	PUR_ORDER.POH_EXTND_AMOUNT_BC_ID
PurchaseOrder/PurchaseOrderHeader/ExtendedBaseAmount	▶▶▶
; PPS200MI/LstLine The field indicates base amount	PUR_ORDER.POH_EXTND_AMOUNT_BASE
PurchaseOrder/PurchaseOrderHeader/TransportationTerm/IncotermsCode	▶▶▶
MPHEAD.IATEDL; The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer. PPS200MI/GetHead	PUR_ORDER.POH_TRANSPORTATION_TERM_INCOTERMS_CD

PurchaseOrder

Infor M3 Business Engine - Infor Business Vault

PurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/ID	▶▶▶
MPHEAD.IATEPY; The field indicates how the due date is to be calculated.	PUR_ORDER.POH_PT_T_ID
PPS200MI/GetHead	
PurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/Description	▶▶▶
CSYTAB.CTPARM; The field indicates the description of the payment term.	PUR_ORDER_LC.POH_PT_T_
PPS200MI/GetHead	DSC
PurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/Amount	▶▶▶
@currencyID	
MPHEAD.IACUCD; The field indicates the currency.	PUR_ORDER.POH_PT_T_AMT
PPS200MI/GetHead	TXN_ID
PurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/Amount	▶▶▶
MPHEAD.IACOAM; The field indicates the total order cost for the purchase order.	PUR_ORDER.POH_PT_T_AMT
PPS200MI/GetHead	TXN
PurchaseOrder/PurchaseOrderHeader/RequestedShipDateTime	▶▶▶
MPHEAD.IADWDT; The field indicates requested delivery date.	PUR_ORDER.POH_RQSTD_SH
PPS200MI/GetHead	IP_DATE
PurchaseOrder/PurchaseOrderHeader/OrderDateTime	▶▶▶
MPHEAD.IAPUDT; The field indicates when the purchase order was placed.	PUR_ORDER.POH_ORDER_DA
PPS200MI/GetHead	TE
PurchaseOrder/PurchaseOrderLine/LineNumber	▶▶▶
MPLINE.IBPNLI; The field indicates the sequence number assigned to the purchase	PUR_ORDER_LINE.POL_LIN
PPS200MI/LstLine order line.	E_NMBR
PurchaseOrder/PurchaseOrderLine/Note	▶▶▶
MSYTXL.TLTX60; The field indicates the notes or remarks.	PUR_ORDER_LINE_NT_LC.P
PPS200MI/LstLineTxt	OL_NOTE
PurchaseOrder/PurchaseOrderLine/Status/Code	▶▶▶
MPLINE.IBPUST; The field indicates the following status of the Purchase Order line:	PUR_ORDER_LINE.POL_S_C
PPS200MI/LstLine	D
15-Open	
20-Open	
25-Open	
31-Open	
32-Open	
33-Unconfirmed	
35-Open	
40-Open	
45-Open	
50-Receivied	
51-Received	
60-Received	
64-Received	
65-Received	
69-Received	
70-Partially Received	
75-Received	
80-Invoiced	
85-Invoiced	
90-Invoiced	
99-Cancelled	

PurchaseOrder

Infor M3 Business Engine - Infor Business Vault

PurchaseOrder/PurchaseOrderLine/Item/ItemID/ID	▶▶▶
MPLINE.IBITNO; The field indicates the item number. PPS200MI/LstLine	PUR_ORDER_LINE.POL_I_I ID ID
PurchaseOrder/PurchaseOrderLine/Item/Description	▶▶▶
MPLINE.IBPITT; The field indicates the description of an item in a purchase order. PPS200MI/LstLine	PUR_ORDER_LINE_LC.POL_ I_DSC
PurchaseOrder/PurchaseOrderLine/Quantity	▶▶▶
@unitCode MPLINE.IBPUUN; The field indicates the unit of measure (U/M) in which the purchase PPS200MI/LstLine price is expressed.	PUR_ORDER_LINE.POL_QTY TXN ID
PurchaseOrder/PurchaseOrderLine/Quantity	▶▶▶
MPLINE.IBORQA; The field indicates the ordered quantity . PPS200MI/LstLine	PUR_ORDER_LINE.POL_QTY TXN
PurchaseOrder/PurchaseOrderLine/BaseUOMQuantity	▶▶▶
@unitCode ; PPS200MI/LstLine The field indicates the unit of measure (U/M) in which the purchase price is expressed.	PUR_ORDER_LINE.POL_QTY BC_UNIT
PurchaseOrder/PurchaseOrderLine/BaseUOMQuantity	▶▶▶
; PPS200MI/LstLine The field indicates the quantity.	PUR_ORDER_LINE.POL_QTY BC_UOM
PurchaseOrder/PurchaseOrderLine/UnitPrice/Amount	▶▶▶
@currencyID MPHEAD.IACUCD; The field indicates the currency. PPS200MI/GetHead	PUR_ORDER_LINE.POL_UP_ AMT_TXN_ID
PurchaseOrder/PurchaseOrderLine/UnitPrice/Amount	▶▶▶
MPLINE.IBPUPR; The field indicates the purchase price. PPS200MI/LstLine	PUR_ORDER_LINE.POL_UP_ AMT_TXN
PurchaseOrder/PurchaseOrderLine/UnitPrice/BaseAmount	▶▶▶
@currencyID MPHEAD.; PPS200MI/ The field indicates the local currency. GetHead	PUR_ORDER_LINE.POL_UP_ AMT_BC_ID
PurchaseOrder/PurchaseOrderLine/UnitPrice/BaseAmount	▶▶▶
MPLINE.; PPS200MI/ The field indicates the purchase price in local currency LstLine	PUR_ORDER_LINE.POL_UP_ AMT_BASE
PurchaseOrder/PurchaseOrderLine/UnitPrice/PerQuantity	▶▶▶
@unitCode MPLINE.IBPUUN; The field indicates the unit of measure (U/M) in which the purchase PPS200MI/LstLine price is expressed.	PUR_ORDER_LINE.POL_UP_ PER_QTY_TXN_ID
PurchaseOrder/PurchaseOrderLine/UnitPrice/PerQuantity	▶▶▶
MPLINE.IBPUCD; The field indicates the purchase price quantity. This is specified per PPS200MI/LstLine item and is the quantity expressed in the purchase price U/M that the purchase price refers to.	PUR_ORDER_LINE.POL_UP_ PER_QTY_TXN
PurchaseOrder/PurchaseOrderLine/ExtendedAmount	▶▶▶
@currencyID MPHEAD.IACUCD; The field indicates the currency. PPS200MI/GetHead	PUR_ORDER_LINE.POL_EXT ND_AMT_TXN_ID

PurchaseOrder

Infor M3 Business Engine - Infor Business Vault

PurchaseOrder/PurchaseOrderLine/ExtendedAmount MPLINE.IBLNAM; The field indicates the order value for the purchase order line. PPS200MI/LstLine	▶▶▶ PUR_ORDER_LINE.POL_EXT ND_AMT_TXN
PurchaseOrder/PurchaseOrderLine/ExtendedBaseAmount @currencyID .; PPS200MI/LstLine The field indicates the currency.	▶▶▶ PUR_ORDER_LINE.POL_EXT ND_AMT_BC_ID
PurchaseOrder/PurchaseOrderLine/ExtendedBaseAmount .; PPS200MI/LstLine The field indicates the order value for the purchase order line.	▶▶▶ PUR_ORDER_LINE.POL_EXT ND_AMT_BASE
PurchaseOrder/PurchaseOrderLine/RequiredDeliveryDateTime MPLINE.IBDWDT The field indicates the delivery date that is to be specified for the +IBTIHM; PPS200MI/ supplier on the purchase order document. LstLine	▶▶▶ PUR_ORDER_LINE.POL_RQR D_DLVR_DATE
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/ID MPPOAD.ADADK2; The field indicates the address type. PPS200MI/ GetDelAddress	▶▶▶ PUR_ORDER_LINE.POL_ST_ L_ID
PurchaseOrder/PurchaseOrderLine/TransportationTerm/IncotermsCode MPLINE.IBTEDL; The field indicates delivery terms, which define when the responsibility PPS200MI/ListLine for a delivery is transferred from the supplier to the customer.	▶▶▶ PUR_ORDER_LINE.POL_TT_ INCOTERMS_CD
PurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT The field indicates the confirmed delivery date and time +IBTIHM; PPS200MI/ LstLine	▶▶▶ PUR_ORDER_LINE.POL_PRM SD_DLVR_DATE
PurchaseOrder/PurchaseOrderLine/ReceivedQuantity @unitCode MPLINE.IBPUUN; The field indicates the unit of measure of the received quantity PPS200MI/LstLine	▶▶▶ PUR_ORDER_LINE.POL_RCV D_QTY_TXN_ID
PurchaseOrder/PurchaseOrderLine/ReceivedQuantity MPLINE.IBRVQA; The field indicates the received quantity PPS200MI/LstLine	▶▶▶ PUR_ORDER_LINE.POL_RCV D_QTY_TXN
PurchaseOrder/PurchaseOrderLine/ReceivedBaseUOMQuantity @unitCode .; PPS200MI/LstLine The field indicates the received quantity basic unit of measure.	▶▶▶ PUR_ORDER_LINE.POL_RCV D_QTY_BC_UNIT
PurchaseOrder/PurchaseOrderLine/ReceivedBaseUOMQuantity .; PPS200MI/LstLine The field indicates the received quantity in basic unit of measure	▶▶▶ PUR_ORDER_LINE.POL_RCV D_QTY_BC_UOM
PurchaseOrder/PurchaseOrderLine/OpenQuantity @unitCode MPLINE.IBPUUN; The field indicates the pending quantity unit of measure.. PPS200MI/LstLine	▶▶▶ PUR_ORDER_LINE.POL_OPE N_QTY_TXN_ID
PurchaseOrder/PurchaseOrderLine/OpenQuantity MPLINE.IBORQA - The field indicates the pending quantity. IBRVQA; PPS200MI/	▶▶▶ PUR_ORDER_LINE.POL_OPE N_QTY_TXN

PurchaseOrder

Infor M3 Business Engine - Infor Business Vault

LstLine		
PurchaseOrder/PurchaseOrderLine/OpenBaseUOMQuantity @unitCode		►►►
; PPS200MI/LstLine	The field indicates the pending quantity basic unit of measure.	PUR_ORDER_LINE.POL_OPEN_QTY_BC_UNIT
PurchaseOrder/PurchaseOrderLine/OpenBaseUOMQuantity ;	PPS200MI/LstLine The field indicates the pending quantity in basic unit of measure	►►►
		PUR_ORDER_LINE.POL_OPEN_QTY_BC_UOM
PurchaseOrder/PurchaseOrderLine/SalesOrderReference/DocumentID/ID MPLINE.IBRORN;	The field indicates the sales order number.	►►►
PPS200MI/LstLine		PUR_ORDER_LINE.POL_SOR_DID_ID
PurchaseOrder/PurchaseOrderLine/SalesOrderReference/LineNumber MPLINE.IBRORL;	The field indicates a sales order line.	►►►
PPS200MI/LstLine		PUR_ORDER_LINE.POL_SOR_LINE_NMBR
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/LineNumber MPLINE.IBPNLS;	The field indicates the number of the subline.	►►►
PPS200MI/LstLine		PUR_ORDER_SUB_LINE.POSL_SUB_LINE_NMBR
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Item/ItemID/ID MPLINE.IBITNO;	The field indicates the item number.	►►►
PPS200MI/LstLine		PUR_ORDER_SUB_LINE.POSL_I_ID_ID
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Item/Description MPLINE.IBPITT;	The field indicates the description of an item in a purchase order.	►►►
PPS200MI/LstLine		PUR_ORDER_SUB_LINE.LC.POL_POSL_I_DSC
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Quantity @unitCode		►►►
MPLINE.IBPUUN;	The field indicates the unit of measure (U/M) in which the quantity on the purchase order is expressed.	PUR_ORDER_SUB_LINE.POSL_QTY_TXN_ID
PPS200MI/LstLine		
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Quantity MPLINE.IBORQA;	The field indicates the ordered quantity.	►►►
PPS200MI/LstLine		PUR_ORDER_SUB_LINE.POSL_QTY_TXN
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/BaseUOMQuantity @unitCode		►►►
; PPS200MI/LstLine	The field indicates the basic unit of measure	PUR_ORDER_SUB_LINE.POSL_QTY_BC_UNIT
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/BaseUOMQuantity ;	PPS200MI/LstLine The field indicates the ordered quantity in basic unit of measure	►►►
		PUR_ORDER_SUB_LINE.POSL_QTY_BC_UOM
PurchaseOrder/PurchaseOrderLine/ShipFromParty/PartyIDs/ID MPLINE.IBSUNO;	The field indicates the unique identity of a supplier.	►►►
PPS200MI/LstLine		PUR_ORDER_LINE.POL_SFP_PID_ID
PurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID MPHEAD.IAPRSU;	The field indicates a valid supplier number for the supplier that should receive the payment. Payee is entered only if the supplier and the payee are not the same legal entity.	►►►
PPS200MI/GetHead		PUR_ORDER.POH_RTP_PID_ID
PurchaseOrder/PurchaseOrderHeader/ShipToParty/PartyIDs/ID MPPOAD.ADADK2;	The field indicates the address type.	►►►
		PUR_ORDER.POH_STP_PID_

PurchaseOrder

Infor M3 Business Engine - Infor Business Vault

PPS200MI/GetAddresses	ID
PurchaseOrder/PurchaseOrderLine/ContractReference/DocumentID/ID MPLINE.IBOURR; The field indicates the agreement number. PPS200MI/LstLine	▶▶▶ PUR_ORDER_LINE.POL_CR_ DID_ID
PurchaseOrder/PurchaseOrderLine/ProductionOrderReference/DocumentID/ID MPLINE.IBRORN; The field indicates the manufacturing order number. PPS200MI/LstLine	▶▶▶ PUR_ORDER_LINE.POL_POR DID_ID
PurchaseOrder/PurchaseOrderLine/ShipToParty/PartyIDs/ID MPPOAD.ADADK2; The field indicates the address type. PPS200MI/ GetDelAddress	▶▶▶ PUR_ORDER_LINE.POL_STP _PID_ID

Quote

Infor M3 Business Engine - Infor Business Vault

Quote/QuoteHeader/Status/Code

►►►

OOQUOH.QFSTAT; The field indicates the status of the record.
OIS100MI/GetQuot

QUOTE.QH_S_CD

10 - Open
20 - Open
30 - Lost
40 - Open
50 - Open
60 - Awarded
90 - Deleted

Quote/QuoteHeader/CustomerParty/PartyIDs/ID

►►►

OOHEAD.OACUNO; The field indicates the unique identification of a customer. It can contain
OIS100MI/GetHead up to ten positions, and is alphanumeric.

QUOTE.QH_CP_PID_ID

Quote/QuoteHeader/ShipToParty/PartyIDs/ID

►►►

OOHEAD.OACUNO; The field indicates the unique identification of a customer. It can contain
OIS100MI/GetHead up to ten positions, and is alphanumeric.

QUOTE.QH_STP_PID_ID

Quote/QuoteHeader/ExtendedAmount

►►►

@currencyID

OOHEAD.OACUCD; The field indicates the abbreviation for the currency. The abbreviation
OIS100MI/GetHead should follow ISO standards.

QUOTE.QH_EXTND_AMT_TXN
ID

Quote/QuoteHeader/ExtendedAmount

►►►

OOHEAD.OANTAM; The field indicates the net order value, including any discounts,
OIS100MI/GetHead expressed in the domestic currency.

QUOTE.QH_EXTND_AMT_TXN

No charges is included in the amount.

Quote/QuoteHeader/TotalAmount

►►►

@currencyID

OOHEAD.OACUCD; The field indicates the abbreviation for the currency. The abbreviation
OIS100MI/GetHead should follow ISO standards.

QUOTE.QH_TOTAL_AMT_TXN
ID

Quote/QuoteHeader/PayFromParty/PartyIDs/ID

►►►

OOHEAD.OAPYNO; The field indicates the person/business who has paid or will pay the
OIS100MI/GetHead invoice.

QUOTE.QH_PFP_PID_ID

The payer is specified when an invoice should be sent somewhere
other than to the customer placing the order.

For order and sales statistics, the payer is used as a statistic ID. For
total statistics, the payer is one of the key IDs.

Quote/QuoteHeader/TransportationTerm/IncotermsCode

►►►

OOHEAD.OATEDL; The field indicates delivery terms, which define when the responsibility
OIS100MI/GetHead for a delivery is transferred from the supplier to the customer.

QUOTE.QH_TT_INCOTERMS_
CD

Quote/QuoteHeader/RFQReference/DocumentID/ID

►►►

OOHEAD.OAOFNO; The field indicates a reference to the quotation number belonging to a
OIS100MI/GetHead customer order, service order or agreement.

QUOTE.QH_RFQR_DID_ID

Quote/QuoteHeader/EffectiveTimePeriod/EndDateTime

►►►

OOQUOH.QFGIDT; The field indicates how long a quotation is valid.
OIS100MI/GetQuot

QUOTE.QH_ETP_END_DATE

Quote

Infor M3 Business Engine - Infor Business Vault

Quote/QuoteHeader/ExpectedDeliveryDate

OOHEAD.OARLDZ; The field indicates the date the customer wants the delivery to arrive at
OIS100MI/GetHead the final destination.

The information is expressed in the time zone of the unloading location at the final destination.

If the loading and unloading locations are in different time zones, this date can be different from what applies for the local time zone.



QUOTE.QH_EXPCTD_DLVRY_ DATE

Quote/QuoteHeader/SalesPersonReference/IDs/ID

OOHEAD.OASMCD; The field indicates the person responsible for sales to a customer.
OIS100MI/GetHead

The salesperson can be used as a statistical category in order entry and for sales statistics.

During customer order entry, the salesperson from the customer file is defaulted but can be changed.



QUOTE.QH_SPR_ID_ID_01

Quote/QuoteLine/LineNumber

OOHEAD.OAPONR; The field indicates the line number, defining each line in a customer
OIS100MI/LstLine order. A line number is assigned automatically when entering order lines.



QUOTE_LINE.QL_LINE_NMB R

Quote/QuoteLine/Status/Code

OOQUOH.QFSTAT; The field indicates the highest line status among the customer order
OIS100MI/GetQuot lines.

The lowest status in the order header shows the lowest line status among the order lines.

10 - Open
20 - Open
30 - Lost
40 - Open
50 - Open
60 - Awarded
90 - Deleted



QUOTE_LINE.QL_S_CD

Quote/QuoteLine/Item/ItemID/ID

OOLINE.OBITNO; The field indicates the item number (for Maintenance, the item number
OIS100MI/LstLine or equipment number), which is a unique ID for an individual item.



QUOTE_LINE.QL_I_ID_ID

Quote/QuoteLine/Item/Description

OOLINE.OBITDS; The field indicates the name for each item.
OIS100MI/LstLine



QUOTE_LINE_LC.QL_I_DSC

Quote/QuoteLine/Quantity

@unitCode

OOLINE.OBALUN; The field indicates an alternate unit of measure (U/M) for the basic U/M
OIS100MI/LstLine for an item. An unlimited number of alternate U/Ms may be defined for each item.



QUOTE_LINE.QL_QTY_TXN_ ID

Quote/QuoteLine/Quantity

OOLINE.OBORQA; The field indicates the ordered quantity in an alternate unit of measure.
OIS100MI/LstLine



QUOTE_LINE.QL_QTY_TXN

Quote

Infor M3 Business Engine - Infor Business Vault

Quote/QuoteLine/UnitPrice/Amount



@currencyID

OOLINE.OBCUCD; The field indicates the abbreviation for the currency.
OIS100MI/LstLine

QUOTE_LINE.QL_UP_AMT_T
XN_ID

Quote/QuoteLine/UnitPrice/Amount



OOLINE.OBSAPR; The field indicates the sales price for each sales price quantity.
OIS100MI/LstLine

QUOTE_LINE.QL_UP_AMT_T
XN

If no value is specified in the sales price quantity, the sales price per unit applies.

The sales price per unit is calculated as: Price per unit= Sales price/
Sales price quantity.

Quote/QuoteLine/UnitPrice/PerQuantity



@unitCode

OOLINE.OBSPUN; The field indicates the sales price U/M. This is the U/M on which the
OIS100MI/LstLine item's price is based. Every item has a standard sales price U/M
specified. However, order lines can be entered using a different U/M.

QUOTE_LINE.QL_UP_PER_Q
TY_TXN_ID

Quote/QuoteLine/UnitPrice/PerQuantity



OOLINE.OBSACD; The field indicates the quantity to which the sales price applies. Sales
OIS100MI/LstLine price quantity is defined for each item and is expressed in the item unit
of measure.

QUOTE_LINE.QL_UP_PER_Q
TY_TXN

Quote/QuoteLine/ExtendedAmount



@currencyID

OOLINE.OBCUCD; The field indicates the abbreviation for the currency.
OIS100MI/LstLine

QUOTE_LINE.QL_EXTND_AM
T_TXN_ID

Quote/QuoteLine/ExtendedAmount



OOLINE.OBNLAM; The field indicates the net amount for an invoice line.
OIS100MI/LstLine

QUOTE_LINE.QL_EXTND_AM
T_TXN

Quote/QuoteLine/PromisedDeliveryDate/Time



OOLINE.OBCODT The field indicates the confirmed delivery date.
OBOHMI; OIS100MI/ The confirmed delivery date is entered manually and is normally agreed
LstLine upon with the customer.

QUOTE_LINE.QL_PRMSD_DL
VRY_DATE

The field indicates the time when the shipment is confirmed to be
delivered to the customer.

ReceivableTransaction

Infor M3 Business Engine - Infor Business Vault

ReceivableTransaction/ReceivableTransactionHeader/DocumentID/ID

FSLEDG.YEA4+JRNO Unique key in FSLEDG
+JSNO;
ARS200MI/GetInvTotInfo



RVBL_TXN.RTH_DID_ID

ReceivableTransaction/ReceivableTransactionHeader/AlternateDocumentID/ID

FSLEDG.CUNO+PYNO Alternate key in FSLEDG
+CINO+
INYN; ARS200MI/
GetInvTotInfo



RVBL_TXN.RTH_ADID_ID

ReceivableTransaction/ReceivableTransactionHeader/DocumentDateTime

FSLEDG.RGDT + The field indicates the date and time that the object was created. This
RGTM; ARS200MI/ date and time is set automatically.
GetInvTotInfo



RVBL_TXN.RTH_DCMNT_DAT
E

ReceivableTransaction/ReceivableTransactionHeader/Description

FSLEDG.TDSC; Transaction description from the invoice record in FSLEDG
ARS200MI/GetInvTotInfo



RVBL_TXN.LC.RTH_DSC

ReceivableTransaction/ReceivableTransactionHeader/Status/Code

FSLEDG.Various; If reconciliation code = 9 then status is set to "Paid". If paid amount >
ARS200MI/GetInvTotInfo invoice amount then status is set to "UnappliedCash". If paid amount <
invoice amount and reconciliation code <> 9 then status is set to
"PartialPay". If all amounts is 0 then status is set to "Void". If a stop
date (BLDT) is set then status = "Dispute". For all other conditions
status is set to "Open".



RVBL_TXN.RTH_S_CD

ReceivableTransaction/ReceivableTransactionHeader/CustomerParty/PartyIDs/ID

FSLEDG.CUNO; The field indicates the unique identification of a customer. It can contain
ARS200MI/GetInvTotInfo up to ten positions, and is alphanumeric.



RVBL_TXN.RTH_CP_PID_ID

For temporary customers (customer type 9), the customer number must
be within a defined range where only customers with customer type 9
can be entered.

ReceivableTransaction/ReceivableTransactionHeader/BillToParty/PartyIDs/ID

FSLEDG.PYNO; BillTo is not available in Accounts Receivable, Payer is used
ARS200MI/GetInvTotInfo



RVBL_TXN.RTH_BTP_PID_I
D

ReceivableTransaction/ReceivableTransactionHeader/BillToParty/Location/Address/ AttentionOfName

OCUSMA.CUNM; The field indicates the customer name, which is used as
CRS610MI/GetBasicData complementary information to the customer number on panels and
documents.



RVBL_TXN.LC.RTH_BTP_L_
A_ATTIN_NAME

ReceivableTransaction/ReceivableTransactionHeader/PayFromParty/PartyIDs/ID

FSLEDG.PYNO; The field indicates the person/business who has paid or will pay the
ARS200MI/GetInvTotInfo invoice.



RVBL_TXN.RTH_PFP_PID_I
D

The payer is specified when an invoice should be sent somewhere
other than to the customer placing the order.

For order and sales statistics, the payer is used as a statistic ID. For
total statistics, the payer is one of the key IDs.

ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Term/ID



ReceivableTransaction

Infor M3 Business Engine - Infor Business Vault

CSYTAB.STKY; CRS175MI/ GetGeneralCode	The field indicates a key value, which is a value included in the group of items displayed in this panel.	RVBL_TXN_PMT_TERMS.RTH_PT_T_ID
The type of value entered is determined by what is entered in the 'Key type' field.		
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Term/Description		▶▶▶
CSYTAB.PARM; CRS175MI/ GetGeneralCode	First 72 characters of PARM	RVBL_TXN_PMT_TERMS.LC.RTH_PT_T_DSC
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm/Term/DueDateTime		▶▶▶
FSLEDG.DUDT; ARS200MI/GetInvTotInfo	The field indicates the date the invoice is due for payment according to payment or cash discount terms.	RVBL_TXN_PMT_TERMS.RTH_PT_T_DUE_DATE
ReceivableTransaction/ReceivableTransactionHeader/ReceivableStyle		▶▶▶
FSLEDG.SLOP; ARS200MI/GetInvTotInfo	If SLOP = 12 then ReceivableStyle = "CreditMemeo" If SLOP = 16 then ReceivableStyle = "DebitMemo" If SLOP > 18 > 99 then ReceivableStyle = "Miscellaneous" For all other SLOP ReceivableStyle = "Invoice"	RVBL_TXN.LC.RTH_RCVBL_STYLE
ReceivableTransaction/ReceivableTransactionHeader/ReceivableStyleCategory		▶▶▶
FSLEDG.TRCD; ARS200MI/GetInvoice	If TRCD = 10 then ReceivableStyleCategory = "I" If TRCD = 20 then ReceivableStyleCategory = "P"	RVBL_TXN.RTH_RCVBL_STY LE_CTGRY
ReceivableTransaction/ReceivableTransactionHeader/InvoiceReference/DocumentID/ID		▶▶▶
FSLEDX.SEXI; ARS251MI/LstInvInfo	If the MI returns any records from FSLEDX, infor category = 228 then use SEXI (original invoice number) else invoice number = CINO	RVBL_TXN.RTH_IR_DID_ID
ReceivableTransaction/ReceivableTransactionHeader/ExtendedAmount@currencyID		▶▶▶
FSLEDG.CUCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.	RVBL_TXN.RTH_EXTND_AMT_TXN_ID
ReceivableTransaction/ReceivableTransactionHeader/ExtendedAmount		▶▶▶
FSLEDG/ FGLEDG.CUAM; ARS200MI/GetInvTotInfo	Invoice currency amount minus tax currency amount	RVBL_TXN.RTH_EXTND_AMT_TXN
ReceivableTransaction/ReceivableTransactionHeader/TotalAmount@currencyID		▶▶▶
FSLEDG.CUCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the invoice foreign currency. The abbreviation should follow ISO standards.	RVBL_TXN.RTH_TOTAL_AMT_TXN_ID
ReceivableTransaction/ReceivableTransactionHeader/TotalAmount		▶▶▶
FSLEDG.CUAM; ARS200MI/GetInvTotInfo	Invoice foreign amount	RVBL_TXN.RTH_TOTAL_AMT_TXN
ReceivableTransaction/ReceivableTransactionHeader/TotalBaseAmount@currencyID		▶▶▶
FSLEDG.LOCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the invoice local currency. The abbreviation should follow ISO standards.	RVBL_TXN.RTH_TOTAL_AMT_BC_ID
ReceivableTransaction/ReceivableTransactionHeader/TotalBaseAmount		▶▶▶
FSLEDG.ACAM; ARS200MI/GetInvTotInfo	Invoice local amount.	RVBL_TXN.RTH_TOTAL_AMT_BASE

ReceivableTransaction

Infor M3 Business Engine - Infor Business Vault

ReceivableTransaction/ReceivableTransactionHeader/Tax/BasisAmount @currencyID FSLEDG.CUCD; The field indicates the abbreviation for the invoice foreign currency. The ARS200MI/GetInvTotInfo abbreviation should follow ISO standards.	RVBL_TXN_TX.RTH_T_BASI S_AMT_TXN_ID
ReceivableTransaction/ReceivableTransactionHeader/Tax/BasisAmount FGLEDG.CUAM; Sum of FGLEDG transactions with TRCD = 11 and AT04 > 2 ARS200MI/GetInvTotInfo	RVBL_TXN_TX.RTH_T_BASI S_AMT_TXN
ReceivableTransaction/ReceivableTransactionHeader/Tax/Amount @currencyID FSLEDG.CUCD; The field indicates the abbreviation for the currency. The abbreviation ARS200MI/GetInvTotInfo should follow ISO standards.	RVBL_TXN_TX.RTH_T_AMT_ TXN_ID
ReceivableTransaction/ReceivableTransactionHeader/Tax/Amount FGLEDG.CUAM; Sum of FGLEDG transactions with TRCD = 11 and AT04 = 1 or 2 ARS200MI/GetInvTotInfo	RVBL_TXN_TX.RTH_T_AMT_ TXN
ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountAllowedAmount @currencyID FSLEDG.CUCD; The field indicates the abbreviation for the invoice foreign currency. The ARS200MI/GetInvTotInfo abbreviation should follow ISO standards.	RVBL_TXN.RTH_DS_DISC_A LWD_AMT_TXN_ID
ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountAllowedAmount FGLEDG.CDCU; Cash discount for an invoice payment. Cash discount taken is in foreign ARS200MI/GetInvTotInfo currency.	RVBL_TXN.RTH_DS_DISC_A LWD_AMT_TXN
ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountAllowedBaseAmount @currencyID FSLEDG.LOCD; The field indicates the abbreviation for the invoice local currency. The ARS200MI/GetInvTotInfo abbreviation should follow ISO standards.	RVBL_TXN.RTH_DS_DISC_A LWD_AMT_BC_ID
ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountAllowedBaseAmount FGLEDG.CDAM; The field indicates the amount that is the cash discount in the specified ARS200MI/GetInvTotInfo currency. Cash discount means that a customer has been granted a certain discount from the invoiced amount if the payment is received within a specified number of days, calculated from the accounting date of the invoice.	RVBL_TXN.RTH_DS_DISC_A LWD_AMT_BASE
ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountTakenAmount @currencyID FSLEDG.CUCD; The split payment parameter on the payment FAM function (AR30) ARS200MI/GetInvTotInfo needs to be set to "several AR payments" or else cash discounts cannot be detected	RVBL_TXN.RTH_DS_DISC_T AKEN_AMT_TXN_ID
ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountTakenAmount FSLEDG.CDCU; The split payment parameter on the payment FAM function (AR30) ARS200MI/GetInvTotInfo needs to be set to "several AR payments" (WWSPAR = 1) or else cash discounts cannot be detected. Sum of FSLEDG record with TRCD = 20	RVBL_TXN.RTH_DS_DISC_T AKEN_AMT_TXN

ReceivableTransaction

Infor M3 Business Engine - Infor Business Vault

and SLOP = 18

ReceivableTransaction/ReceivableTransactionHeader/ReceivableAmount @currencyID FSLEDG.CUCD; The field indicates the abbreviation for the foreign currency. The ARS200MI/GetInvTotInfo abbreviation should follow ISO standards.	RVBL_TXN.RTH_RCVBL_AMT TXN_ID
ReceivableTransaction/ReceivableTransactionHeader/ReceivableAmount FSLEDG.CUAM; Outstanding foreign currency amount. ARS200MI/GetInvTotInfo	RVBL_TXN.RTH_RCVBL_AMT TXN
ReceivableTransaction/ReceivableTransactionHeader/ReceivableBaseAmount @currencyID FSLEDG.LOCD; The field indicates the abbreviation for the invoice local currency. The ARS200MI/GetInvTotInfo abbreviation should follow ISO standards.	RVBL_TXN.RTH_RCVBL_AMT BC_ID
ReceivableTransaction/ReceivableTransactionHeader/ReceivableBaseAmount FSLEDG.ACAM; The field indicates the amount in the local currency. It is the local ARS200MI/GetInvTotInfo currency used by the company to which all transactions are converted in the General Ledger.	RVBL_TXN.RTH_RCVBL_AMT _BASE
ReceivableTransaction/ReceivableTransactionHeader/ReceivedAmount @currencyID FSLEDG.CUCD; The field indicates the abbreviation for the currency. The abbreviation ARS200MI/GetInvTotInfo should follow ISO standards.	RVBL_TXN.RTH_RCVD_AMT_ TXN_ID
ReceivableTransaction/ReceivableTransactionHeader/ReceivedAmount FGLEDG.CUAM; Paid amount ARS200MI/GetInvTotInfo	RVBL_TXN.RTH_RCVD_AMT_ TXN
ReceivableTransaction/ReceivableTransactionHeader/PaymentMethodCode CSYTAB.PARM; First Payment method AR is read (STKY = PYCD), then the payment CRS175MI/ type connected to the method is read. If Payment class in payment type GetGeneralCode is: 0 - "Cash" 1 - "Cheque" 2 - "Cheque" 3 - If the credit card flag is set on the payment method then "CreditCard" else "ElectronicFundsTransfer" 4 - "BankDraft" 5 - "CreditTransfer" everything else "Cash"	RVBL_TXN.RTH_PMT_MTHD_ CD
ReceivableTransaction/ReceivableTransactionHeader/WriteOff/Amount @currencyID FSLEDG.CUCD; The field indicates the abbreviation for the currency. The abbreviation ARS200MI/GetInvTotInfo should follow ISO standards.	RVBL_TXN.RTH_WRITE_OFF AMT_TXN_ID
ReceivableTransaction/ReceivableTransactionHeader/WriteOff/Amount FGLEDG.CUAM; Payment transactions with 98 > SLOP > 18 ARS200MI/GetInvTotInfo	RVBL_TXN.RTH_WRITE_OFF AMT_TXN
ReceivableTransaction/ReceivableTransactionHeader/WriteOff/BaseAmount @currencyID FGLEDG.LOCD; The field indicates the abbreviation for the invoice local currency. The ARS200MI/GetInvTotInfo abbreviation should follow ISO standards.	RVBL_TXN.RTH_WRITE_OFF AMT_BC_ID
ReceivableTransaction/ReceivableTransactionHeader/WriteOff/BaseAmount	

ReceivableTransaction

Infor M3 Business Engine - Infor Business Vault

FGLEDG.WRAM; ARS200MI/GetInvTotInfo	WriteOff accounted amount in local currency.	RVBL_TXN.RTH_WRITE_OFF _AMT_BASE
ReceivableTransaction/ReceivableTransactionHeader/WriteOff/ReasonCode		▶▶▶
FSLEDG.TDSC; ARS200MI/GetInvTotInfo	The field indicates the transaction description from the user-defined accounting options for manual payments.	RVBL_TXN.RTH_WO_RSN_CD
	The description allows for a more detailed voucher description.	

RemitToPartyMaster

Infor M3 Business Engine - Infor Business Vault

RemitToPartyMaster/PartyIDs/DisplayID CIDMAS.IDSUNO; The field indicates the unique identity of a supplier. CRS620MI/GetBasicData	▶▶▶ REMIT_TO_PARTY.PID_DISPLAY_ID
RemitToPartyMaster/PartyIDs/TaxID @schemeAgencyName CIDMAS.IDCORG; The field indicates the supplier's organization number. CRS620MI/GetBasicData	▶▶▶ REMIT_TO_PARTY.PID_TID_SCHEMEAGENCYNAME_01
RemitToPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC; The field indicates Standard Carrier Alpha Code (SCAC). CRS620MI/GetBasicData	▶▶▶ REMIT_TO_PARTY.PID_SCACID
RemitToPartyMaster/Name CIDMAS.IDSUNM; The field indicates supplier name. CRS620MI/GetBasicData	▶▶▶ REMIT_TO_PARTY_LC.NAME
RemitToPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; The field indicates an area, province or state within a country. CRS620MI/LstAddresses	▶▶▶ REMIT_TO_PARTY.L_A_PRIORITY_SBDVSN
RemitToPartyMaster/Location/Address/CountryCode CIDADR.SACSCD; The field indicates a country. CRS620MI/LstAddresses	▶▶▶ REMIT_TO_PARTY.L_A_PRIORITY_CNTRY_CD
RemitToPartyMaster/Location/Address/PostalCode CIDADR.SAPONO; The field indicates a postal code for a specific address. CRS620MI/LstAddresses	▶▶▶ REMIT_TO_PARTY.L_A_PRIORITY_POSTAL_CD
RemitToPartyMaster/Contact/Name CIDREF.IRYRE1; The field indicates the name of the contact. CRS620MI/ LstSupplierRef	▶▶▶ REMIT_TO_PARTY_LC.C_PRIORITY_NAME
RemitToPartyMaster/Contact/Communication/DialNumber CIDREF.IRPHNO/ The field indicates the telephone or facsimile number of the contact IRTFNO; CRS620MI/ LstSupplierRef	▶▶▶ REMIT_TO_PARTY.C_PRIORITY_CONTACT_PHONEOFC
RemitToPartyMaster/Note MSYTXL.TLTX60; Need to create a MEC utility that retrieves all text blocks, text lines etc. CRS980MI/ Should be based on CRS980MI	▶▶▶ REMIT_TO_PARTY_NT_LC.NOTE
RemitToPartyMaster/Status/Code CIDMAS.IDSTAT; The field indicates the supplier status. CRS620MI/GetBasicData 10 = Pending 20 = Open 30 = Hold 90 = Deleted	▶▶▶ REMIT_TO_PARTY.S_CD
RemitToPartyMaster/FinancialParty/Contact/Communication/URI CIDREF.IREMAL; The field indicates an e-mail address for the contact CRS620MI/ LstSupplierRef	▶▶▶ REMIT_TO_PARTY.FP_C_PRIORITY_URI_EMAIL

Requisition

Infor M3 Business Engine - Infor Business Vault

Requisition/RequisitionHeader/DocumentID/ID

MPOPLP.POPLPN PO Proposal number = PLPN, Subnumber Proposal=PLPS
POPLPS; PPS170MI/
GetPlannedPO This fields indicates an internal number on the planned order and a subnumber which is set automatically when the planned order is created.

►►►
REQUISITION.RH_DID_ID

Requisition/RequisitionHeader/DocumentDateTime

MPOPLP.PORGDT This field indicates the date and time the document was created.
PORGTM; PPS170MI/ These are set automatically and transformed to UTC timezone.
GetPlannedPO

►►►
REQUISITION.RH_DCMNT_D
ATE

Requisition/RequisitionLine/LineNumber

MPOPLP.POPLPS; This field indicates a subnumber which is set automatically when the
PPS170MI/ planned order is created. The subnumber is used internally by the
GetPlannedPO system.

►►►
REQUISITION_LINE.RL_LI
NE_NMBR

Requisition/RequisitionLine/Status/Code

MPOPLP.POPSTS; This field indicates the status of the planned order.
PPS170MI/
GetPlannedPO 00 - Pending
05 - Pending
10 - Open
15 - Open
20 - Open
30 - Open
40 - Open
50 - Open
55 - Open
60 - Approved

►►►
REQUISITION_LINE.RL_S_
CD

Requisition/RequisitionLine/Quantity

@unitCode

MPOPLP.POPUUN; This field indicates the unit of measure (U/M) in which the quantity on
PPS170MI/ the purchase order is expressed.
GetPlannedPO

The purchase order U/M can be the alternate U/M or the item's
standard purchase U/M, if an alternate does exist. If there is no
standard purchase U/M, the item's basic U/M is used.

►►►
REQUISITION_LINE.RL_QT
Y_TXN_ID

Requisition/RequisitionLine/Quantity

MPOPLP.POPPQT; This field indicates the quantity that has been calculated to cover a
PPS170MI/ future requirement. The quantity is expressed in purchase order unit of
GetPlannedPO measure

►►►
REQUISITION_LINE.RL_QT
Y_TXN

Requisition/RequisitionLine/BaseUOMQuantity

@unitCode

MPOPLP.POUNMS; This field indicates the unit in which each item is recorded in inventory.
PPS170MI/
GetPlannedPO

►►►
REQUISITION_LINE.RL_QT
Y_BC_UNIT

Requisition/RequisitionLine/BaseUOMQuantity

MPOPLP.POTRQT; This field indicates the quantity in the basic unit of measure for the
PPS170MI/ planned or actual transaction.
GetPlannedPO

►►►
REQUISITION_LINE.RL_QT
Y_BC_UOM

Requisition

Infor M3 Business Engine - Infor Business Vault

Requisition/RequisitionLine/ExtendedBaseAmount



@currencyID

CMNDIV.CCLOCD;
PPS170MI/
GetPlannedPO

This field indicates the local currency, that is, the basic currency used by the division.

REQUISITION_LINE.RL_EX
TND_AMT_BC_ID

Requisition/RequisitionLine/ExtendedBaseAmount



MPOPLP.POCUPR;
PPS170MI/
GetPlannedPO

The field indicates the sales price expressed in the service order's currency or the agreement price in the agreement's currency.

REQUISITION_LINE.RL_EX
TND_AMT_BASE

SalesOrder

Infor M3 Business Engine - Infor Business Vault

SalesOrder/SalesOrderHeader/DocumentID/ID OOHEAD.ORNO; Customer Order Number OIS100MI/GetHead	▶▶▶ SALES_ORDER.SOH_DID_ID
SalesOrder/SalesOrderHeader/AlternateDocumentID/ID 0	▶▶▶ SALES_ORDER.SOH_ADID_ID
SalesOrder/SalesOrderHeader/DocumentDateTime OOHEAD.OARGDT This is the date and time the sales order header was created in M3 BE. OARGTM; N/A/ It is retrieved via the event, and is concatenated from M3 BE fields RGDT and RGTM	▶▶▶ SALES_ORDER.SOH_DCMNT_DATE
SalesOrder/SalesOrderHeader/Status/Code OOHEAD.ORSL; The field indicates the customer orders lowest status, M3 BE field OIS100MI/GetHead ORSL. It is translated according to: 5 = Pending 10 = Hold 20 = Open 22, 23, 24, 29, 33, 39, 44 or 49 = Approved 26, 27, 36, 37, 46 or 47 = PartiallyShipped 66, 67 or 69 = Shipped 77 or 79 = Invoiced 90 = Canceled	▶▶▶ SALES_ORDER.SOH_S_CD
SalesOrder/SalesOrderHeader/CustomerParty/PartyIDs/ID OOHEAD.CUNO; Customer identity OIS100MI/GetHead	▶▶▶ SALES_ORDER.SOH_CP_PID_ID
SalesOrder/SalesOrderHeader/CustomerParty/Contact/Name OCUSMA.YREF-YRE1; Our reference person number 1 and number 2 CRS610MI/GetBasicData	▶▶▶ SALES_ORDER.LC.SOH_CP_C_PRI_NAME
SalesOrder/SalesOrderHeader/CustomerParty/Contact/Communication/DialNumber OCUSMA.PHNO-PHN1; Phone number to reference persons CRS610MI/GetBasicData	▶▶▶ SALES_ORDER.SOH_CP_C_PRI_C_PHONEOFC
SalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID OCUSMA.CUNM; Customer name CRS610MI/GetBasicData	▶▶▶ SALES_ORDER.SOH_STP_PID_ID
SalesOrder/SalesOrderHeader/ExtendedAmount@currencyID OOHEAD.CUCD; Currency NetOrderValue OIS100MI/Gethead	▶▶▶ SALES_ORDER.SOH_EXTND_AMT_TXN_ID
SalesOrder/SalesOrderHeader/ExtendedAmount OOHEAD.NTAM; Net Order Value OIS100MI/Gethead	▶▶▶ SALES_ORDER.SOH_EXTND_AMT_TXN
SalesOrder/SalesOrderHeader/TotalAmount@currencyID OOHEAD.CUCD; Currency Total value OIS100MI/Gethead	▶▶▶ SALES_ORDER.SOH_TOTAL_AMT_TXN_ID
SalesOrder/SalesOrderHeader/TotalAmount OOHEAD.TOPY; Total value	▶▶▶ SALES_ORDER.SOH_TOTAL_

SalesOrder

Infor M3 Business Engine - Infor Business Vault

OIS100MI/Gethead	AMT_TXN
SalesOrder/SalesOrderHeader/BillToParty/PartyIDs/ID OOHEAD.INRC; Invoice Recipient OIS100MI/Gethead	▶▶▶ SALES_ORDER.SOH_BTP_PI D_ID
SalesOrder/SalesOrderHeader/BillToParty/Contact/Name OCUSMA.YREF-YRE1; Our reference person number 1 and number 2 (Invoice recipient) CRS610MI/GetBasicData	▶▶▶ SALES_ORDER_LC.SOH_BTP C_PRI_NAME
SalesOrder/SalesOrderHeader/BillToParty/Contact/Communication/DialNumber OCUSMA.PHNO-PHN1; Phone number to reference persons (Invoice recipient) CRS610MI/GetBasicData	▶▶▶ SALES_ORDER.SOH_BTP_C_ PRI_C_PHONEOFC
SalesOrder/SalesOrderHeader/PayFromParty/Contact/Name OCUSMA.YREF-YRE1; Our reference person number 1 and number 2 (Payer) CRS610MI/GetBasicData	▶▶▶ SALES_ORDER_LC.SOH_PFP C_PRI_NAME
SalesOrder/SalesOrderHeader/TransportationTerm/IncotermsCode OOHEAD.TEDL; 0 OIS100MI/GetHead	▶▶▶ SALES_ORDER.SOH_TT_INC OTERMS_CD
SalesOrder/SalesOrderHeader/PaymentTerm/Discount/Amount @currencyID .; OIS100MI/GetHead Currency	▶▶▶ SALES_ORDER_PMT_TERM.S OH_PT_D_AMT_TXN_ID
SalesOrder/SalesOrderHeader/PaymentTerm/Discount/Amount .; OIS100MI/ VAT GetOrderValue	▶▶▶ SALES_ORDER_PMT_TERM.S OH_PT_D_AMT_TXN
SalesOrder/SalesOrderHeader/PaymentTerm/Discount/BaseAmount @currencyID .; OIS100MI/GetHead Currency	▶▶▶ SALES_ORDER_PMT_TERM.S OH_PT_D_AMT_BC_ID
SalesOrder/SalesOrderHeader/PaymentTerm/Discount/BaseAmount .; OIS100MI/ VAT GetOrderValue	▶▶▶ SALES_ORDER_PMT_TERM.S OH_PT_D_AMT_BASE
SalesOrder/SalesOrderHeader/PaymentTerm/Discount/ReportAmount @currencyID .; OIS100MI/GetHead Currency	▶▶▶ SALES_ORDER_PMT_TERM.S OH_PT_D_AMT_RPRTG_ID
SalesOrder/SalesOrderHeader/PaymentTerm/Discount/ReportAmount .; OIS100MI/ VAT GetOrderValue	▶▶▶ SALES_ORDER_PMT_TERM.S OH_PT_D_AMT_RPRTG
SalesOrder/SalesOrderHeader/DistributedCharge/Amount @currencyID .; OIS100MI/GetHead Currency	▶▶▶ SALES_ORDER_DTRBT_CHRG .SOH_DC_AMT_TXN_ID
SalesOrder/SalesOrderHeader/DistributedCharge/Amount OOHEAD.EFAM and Charge EXAM; OIS100MI/ GetOrderValue	▶▶▶ SALES_ORDER_DTRBT_CHRG .SOH_DC_AMT_TXN
SalesOrder/SalesOrderHeader/EarliestDeliveryDateTime	▶▶▶

SalesOrder

Infor M3 Business Engine - Infor Business Vault

OOHEAD.FFDT; OIS100MI/GetHead	Earliest Delivery Date	SALES_ORDER.SOH_ERLST_ DLVRY_DATE
<hr/>		
SalesOrder/SalesOrderHeader/RequestedShipDateTime		▶▶▶
OOHEAD.RLDT & RLHM; OIS100MI/ GetHead	Requested Delivery Date and Time	SALES_ORDER.SOH_RQSTD_ SHIP_DATE
<hr/>		
SalesOrder/SalesOrderHeader/ExtendedPretaxAmount		▶▶▶
OOHEAD.ORVA; OIS100MI/ GetOrderValue	0	SALES_ORDER.SOH_EXTND_ PRTX_AMT_TXN
<hr/>		
SalesOrder/SalesOrderLine/LineNumber		▶▶▶
OOLINE.PONR; OIS100MI/LstLine	Order Line number	SALES_ORDER_LINE.SOL_L INE_NMBR
<hr/>		
SalesOrder/SalesOrderLine/Status/Code		▶▶▶
OOLINE.ORST; OIS100MI/LstLine	The field indicates the customer order lines status, M3 BE field ORST. It is translated according to: 5 = Pending 10 = Hold 20 = Open 22, 23, 24, 29, 33, 34, 39, 44 or 49 = Approved 26, 27, 36, 37, 46 or 47 = PartiallyShipped 66, 67 or 69 = Shipped 77 or 79 = Invoiced 90 = Canceled"	SALES_ORDER_LINE.SOL_S _CD
<hr/>		
SalesOrder/SalesOrderLine/Item/ItemID/ID		▶▶▶
OOLINE.ITNO; OIS100MI/LstLine	Item Number	SALES_ORDER_LINE.SOL_I IID_ID
<hr/>		
SalesOrder/SalesOrderLine/Item/Description		▶▶▶
MITMAS.ITDS; MMS200MI/GetitmBasic	Item description	SALES_ORDER_LINE_LC.SO L_I_DSC
<hr/>		
SalesOrder/SalesOrderLine/Quantity @unitCode		▶▶▶
OOLINE.UNMS; OIS100MI/LstLine	Unit of Measure	SALES_ORDER_LINE.SOL_Q TY_TXN_ID
<hr/>		
SalesOrder/SalesOrderLine/Quantity		▶▶▶
OOLINE.ORQT; OIS100MI/LstLine	Quantity for Orderline (in Basic Unit of Measure)	SALES_ORDER_LINE.SOL_Q TY_TXN
<hr/>		
SalesOrder/SalesOrderLine/BaseUOMQuantity @unitCode		▶▶▶
OOLINE.UNMS; OIS100MI/LstLine	Unit of Measure	SALES_ORDER_LINE.SOL_Q TY_BC_UNIT
<hr/>		
SalesOrder/SalesOrderLine/BaseUOMQuantity		▶▶▶
OOLINE.ORQT; OIS100MI/LstLine	Quantity for Orderline (in Basic Unit of Measure)	SALES_ORDER_LINE.SOL_Q TY_BC_UOM
<hr/>		
SalesOrder/SalesOrderLine/ExtendedAmount @currencyID		▶▶▶
.; OIS100MI/LstLine	Currency	SALES_ORDER_LINE.SOL_E

SalesOrder

Infor M3 Business Engine - Infor Business Vault

	XTND_AMT_TXN_ID
SalesOrder/SalesOrderLine/ExtendedAmount OOLINE. ; OIS100MI/ Net Line Amount (as well as currency) LstLine	▶▶▶ SALES_ORDER_LINE.SOL_E XTND_AMT_TXN
SalesOrder/SalesOrderLine/RequestedShipDateTime OOLINE.DWDT+DWHM; Requested Delivery date for Orderline OIS100MI/LstLine	▶▶▶ SALES_ORDER_LINE.SOL_R QSTD_SHIP_DATE
SalesOrder/SalesOrderLine/RequiredDeliveryDateTime OOLINE.DWDZ+DWHZ; 0 OIS100MI/GetLine	▶▶▶ SALES_ORDER_LINE.SOL_R QRD_DLVR_DATE
SalesOrder/SalesOrderLine/PromisedShipDateTime OOLINE.DWDT+DWHM; Confirmed deliverydate + time OIS100MI/LstLine	▶▶▶ SALES_ORDER_LINE.SOL_P RMSD_SHIP_DATE
SalesOrder/SalesOrderLine/PromisedDeliveryDateTime OO:LINE.DWDT Confirmed deliverydate + time +DWHM; OIS100MI/ LstLine	▶▶▶ SALES_ORDER_LINE.SOL_P RMSD_DLVR_DATE
SalesOrder/SalesOrderLine/AllocatedQuantity @unitCode OOLINE.ALUN; Unit of Measure for allocated quantity OIS100MI/LstLine	▶▶▶ SALES_ORDER_LINE.SOL_A LLOCATED_QTY_TXN_ID
SalesOrder/SalesOrderLine/AllocatedQuantity OOLINE.ALQT; Allocated quantity for line OIS100MI/LstLine	▶▶▶ SALES_ORDER_LINE.SOL_A LLOCATED_QTY_TXN
SalesOrder/SalesOrderLine/ShippedQuantity OOLINE.DLQT; Delivered quantity for line OIS100MI/LstLine	▶▶▶ SALES_ORDER_LINE.SOL_S HIPPED_QTY_TXN
SalesOrder/SalesOrderHeader/PayFromParty/Contact/Communication/DialNumber OCUSMA.PHNO-PHN1; Phone number to reference persons (Payer) CRS610MI/GetBasicData	▶▶▶ SALES_ORDER.SOH_PFP_C_ PRI_C_PHONEOFC
SalesOrder/SalesOrderHeader/PayFromParty/PartyIDs/ID OCUSMA.PYNO; Payer OIS100MI/Gethead	▶▶▶ SALES_ORDER.SOH_PFP_PI D ID
SalesOrder/SalesOrderLine/ShipToParty/PartyIDs/ID OOHEAD.CUNO; Customer OIS100MI/GetHead	▶▶▶ SALES_ORDER_LINE.SOL_S TP_PID_ID

ShipFromPartyMaster

Infor M3 Business Engine - Infor Business Vault

ShipFromPartyMaster/PartyIDs/DisplayID CIDMAS.IDSUNO; The field indicates the unique identity of a supplier. CRS620MI/GetBasicData	►►► SHIP_FROM_PARTY.PID_DI SPLAY_ID
ShipFromPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC; The field indicates Standard Carrier Alpha Code (SCAC). CRS620MI/GetBasicData	►►► SHIP_FROM_PARTY.PID_SC ACID
ShipFromPartyMaster/Name CIDMAS.IDSUNM; The field indicates supplier name. CRS620MI/GetBasicData	►►► SHIP_FROM_PARTY_LC.NAM E
ShipFromPartyMaster/Location/Address/CityName CIDADR.SATOWN; The field indicates the city in an address. CRS620MI/LstAddresses	►►► SHIP_FROM_PARTY.L_A_PR I_CITY_NAME
ShipFromPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; The field indicates an area, province or state within a country. CRS620MI/LstAddresses	►►► SHIP_FROM_PARTY.L_A_PR I_C_SBDVSN
ShipFromPartyMaster/Location/Address/CountryCode CIDADR.SACSCD; The field indicates a country. CRS620MI/LstAddresses Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.	►►► SHIP_FROM_PARTY.L_A_PR I_CNTRY_CD
ShipFromPartyMaster/Location/Address/PostalCode CIDADR.SAPONO; The field indicates a postal code for a specific address. CRS620MI/LstAddresses The postal code is an address element that can be part of an address line if address formatting rules are used.	►►► SHIP_FROM_PARTY.L_A_PR I_POSTAL_CD
ShipFromPartyMaster/Contact/Name CIDREF.IRYRE1; The field indicates the name of the contact. CRS620MI/ LstSupplierRef	►►► SHIP_FROM_PARTY_LC.C_P RI_NAME
ShipFromPartyMaster/Contact/Communication/DialNumber CIDREF.IRPHNO; The field indicates the telephone or facsimile number of the contact IRTFNO; CRS620MI/ LstSupplierRef	►►► SHIP_FROM_PARTY.C_PRI_ C_PHONEOFC
ShipFromPartyMaster/Contact/Communication/URI CIDREF.IREMAL; The field indicates an e-mail address for the contact CRS620MI/ LstSupplierRef	►►► SHIP_FROM_PARTY.C_PRI_ C_URI_EMAIL
ShipFromPartyMaster/Note MSYTXL.TLTX60; Need to create a MEC utility that retrieves all text blocks, text lines etc. CRS980MI/ Should be based on CRS980MI	►►► SHIP_FROM_PARTY_NT_LC. NOTE
ShipFromPartyMaster/BuyerContact/Name CMNUSR.JUTX40; The field indicates the name of the buyer. MNS150MI/GetUserData	►►► SHIP_FROM_PARTY_LC.BC_ PRI_NAME
ShipFromPartyMaster/Status/Code CIDMAS.IDSTAT; The field indicates the supplier status. CRS620MI/GetBasicData 10 = Pending	►►► SHIP_FROM_PARTY.S_CD

ShipFromPartyMaster

20 = Open
30 = Hold
90 = Deleted

ShipToPartyMaster

Infor M3 Business Engine - Infor Business Vault

ShipToPartyMaster/PartyIDs/ID		►►►
OCUSMA.OKCUNO; This field indicates the customer number	SHIP_TO_PARTY.PID_ID	
CRS610MI/GetBasicData		
ShipToPartyMaster/Name		►►►
OCUSMA.OKCUNM; This field indicates the customer name	SHIP_TO_PARTY_LC.NAME	
CRS610MI/GetBasicData		
ShipToPartyMaster/Location/Address/AttentionOfName		►►►
OCUSMA.OKYREF; The field indicates the customer's contact person	SHIP_TO_PARTY_LC.L_A_P	
CRS610MI/GetBasicData	RI_ATTN_NAME	
ShipToPartyMaster/Location/Address/AddressLine @sequence		►►►
The field indicates the Address Line sequence	SHIP_TO_PARTY_LC.L_A_P	[@sequence='1']
	RI_AL_ADDL_01	
ShipToPartyMaster/Location/Address/CityName		►►►
OCUSMA.OKTOWN; This field indicates the city	SHIP_TO_PARTY.L_A_PRI	
CRS610MI/GetBasicData	CITY_NAME	
ShipToPartyMaster/Location/Address/CountrySubDivisionCode		►►►
OCUSMA.OKECAR; The field indicates the state/region/countrysubdivision	SHIP_TO_PARTY.L_A_PRI	
CRS610MI/GetBasicData	C_SBDVSN	
ShipToPartyMaster/Location/Address/CountryCode		►►►
OCUSMA.OKCSCD; The field indicates the country code	SHIP_TO_PARTY.L_A_PRI	
CRS610MI/GetBasicData	CNTRY_CD	
ShipToPartyMaster/Location/Address/PostalCode		►►►
OCUSMA.OKPONO; This field indicates the postal code	SHIP_TO_PARTY.L_A_PRI	
CRS610MI/GetBasicData	POSTAL_CD	
ShipToPartyMaster/PaymentTermID		►►►
OCUSMA.OKTEPY/ The field indicates the payment terms id for the customer	SHIP_TO_PARTY.PMT_TERM	
CCUDIV.O Data is retrieved from customer master, table OCUSMA, or, if	_ID	
KTEPY.; CRS610MI/ applicable, from customer local exceptions, table CCUDIV.		
GetOrderInfo		
ShipToPartyMaster/Status/Code		►►►
OCUSMA.OKSTAT; The field indicates the status of the customer.	SHIP_TO_PARTY.S_CD	
CRS610MI/GetBasicData		
If M3 status is 10, set element to "Pending"		
If M3 status is 20, set element to "Open"		
If M3 status is 90, set element to "Closed"		
ShipToPartyMaster/Classification/Codes/Code @listID		►►►
The field indicates the Classification code listID.	SHIP_TO_PARTY.C_C_CD_S	[@listID='Customer Types']
1) If Customer type field is filled, set listID to "Customer Types"	HIPTO_PARTY_TYPS	
2) If Delivery terms field is filled, set listID to "Incoterms"		
3) If District field is filled, set listID to "District"		
ShipToPartyMaster/Classification/Codes/Code @sequence		►►►
The sequence attribute identifies the hierarchical position of the identifier in the case of multi-level codes	SHIP_TO_PARTY.C_C_CD_0	[@sequence='1']
	1	

ShipToPartyMaster

ShipToPartyMaster/CustomerParty/PartyIDs/ID



OCUSMA.OKCUNO; In M3 BE customer master, ShipToParty is the same as
CRS610MI/GetBasicData CustomerParty. This element is set to same as the ShipToPartyMaster
element

SHIP_TO_PARTY.CP_PID_I
D

Shipment

Infor M3 Business Engine - Infor Business Vault

Shipment/ShipmentHeader/DocumentID/ID



SHIPMENT.SH_DID_ID

For Shipments: For Shipments:
DCONSI.DACONO; The field indicates a shipment number, which is the unique identity
DRS100MI/LstShipment used to identify a shipment.

For Shipment Deliveries: For Shipment Deliveries:
MHDISH.OQDLIX; "The field indicates the delivery number. This unique ID for the delivery
MWS410MI/GetHead is created or updated automatically during order line entry.

Several order numbers can be attached to the same delivery number if
allowed by the dispatch policy (MWS010)."

Shipment/ShipmentHeader/Status/Code



SHIPMENT.SH_S_CD

For Shipments: For Shipments:
DCONSI.DACSTL; Status of the Shipment.
DRS100MI/LstShipment

For Shipment Deliveries: 00 - Open
MHDISH.OQPGRS; 10 - Open
MWS410MI/GetHead 20 - Allocated
30 - Allocated
40 - Staged
50 - Loaded
60 - Shipped
90 - Cancelled

For Shipment Deliveries:
Delivery Status

The field indicates the status of a delivery.

00 - Open
01 - Open
02 - Hold
03 - Hold
05 - Allocated
50 - Released
60 - Shipped
65 - Partly Shipped
90 - Received
95 - Received

Shipment/ShipmentHeader/WarehouseLocation/ID



SHIPMENT.SH_WL_ID

For Shipments: For Shipments:
DCONSI.DAWHLO; The field indicates the warehouse ID.
DRS100MI/LstShipment

For Shipment Deliveries: Warehouse is a stock zone which is used to distinguish different
MHDISH.OQWHLO; geographical locations within a company. The warehouse is used as a
MW410MI/GetHead planning level for material and production. Stock zones, stock locations
and items are connected to the warehouse.

For Shipment Deliveries:
Location

Shipment

Infor M3 Business Engine - Infor Business Vault

Shipment/ShipmentHeader/CarrierRouteReference/DocumentID/ID



SHIPMENT.SH_CRR_DID_ID

For Shipments:
DCONSI.DAROUT;
DRS100MI/LstShipment

For Shipments:
The field indicates the transportation route. A route is determined by a loading place with one or more unloading locations. The unloading locations can be located in a geographical area or region, such as southeast Germany

Routes are used to:

- Coordinate transportation to several customers along a road or within a specified area

- Distinguish orders needing special handling, such as special deliveries to be made with a company vehicle. In this case, the route can vary every time depending on where the order's destination.

Shipment/ShipmentHeader/ActualShipDateTime



SHIPMENT.SH_ACTL_SHIP_ DATE

For Shipments:
DCONSI.DADSDT
DADSHM; DRS100MI/
LstShipment

For Shipments:
The field indicates the planned departure date.

Shipment/ShipmentHeader/ScheduledDeliveryDateTime



SHIPMENT.SH_SCHDD_DLVR_ Y_ DATE

For Shipments:
DCONSI.DARDDT
DARDTM; DRS100MI/
LstShipment

For Shipments:
The field indicates the Planned Route Departure Date/Time

For Shipment Deliveries:
The field indicates the date/time the most recent goods receipt was reported.

For Shipment Deliveries:
MHDISH.OQRCDT
OQRCTM; MWS410MI/
GetHead

Shipment/ShipmentHeader/ActualDeliveryDateTime



SHIPMENT.SH_ACTL_DLVRY_ DATE

For Shipments:
DCONSI.DAARDT/
DAARHM; DRS100MI/
LstShipment

For Shipments:
The field indicates when a transfer from the subsidiary company has arrived to the parent company.

Shipment/ShipmentHeader/EstimatedWeightMeasure @unitCode



SHIPMENT.SH_EWM_UNIT

For Shipments:
CSYTAB.CTPARM;
CRS175MI/
GetItemFreeFlds

For Shipments:
The field indicates the general unit of measure for all weights within a company.

Shipment/ShipmentHeader/EstimatedWeightMeasure



SHIPMENT.SH_ESTD_WGHT

For Shipments:
DCONSI.DAGWTE;
DRS100MI/LstShipment

For Shipments:
The field indicates the Estimated Gross Weight Packed

Shipment/ShipmentHeader/LoadingWeightMeasure @unitCode



SHIPMENT.SH_LWM_UNIT

For Shipments:
CSYTAB.CTPARM;

For Shipments:
The field indicates the general unit of measure for all weights within a

Shipment

Infor M3 Business Engine - Infor Business Vault

CRS175MI/ GetItemFreeFlds	company.	
<hr/>		
Shipment/ShipmentHeader/LoadingWeightMeasure		▶▶▶
For Shipments: DCONSI.DAGR2; DRS100MI/LstShipment	For Shipments: The field indicates the Packed Gross Weight	SHIPMENT.SH_LOADING_WG HT
<hr/>		
Shipment/ShipmentHeader/GrossWeightMeasure		▶▶▶
@unitCode		
CSYTAB.CTPARM; CRS175MI/ GetItemFreeFlds	For Shipments: The field indicates the general unit of measure for all weights within a company.	SHIPMENT.SH_GWM_UNIT
	For Shipment Deliveries: The field indicates the general unit of measure for all weights within a company.	
<hr/>		
Shipment/ShipmentHeader/GrossWeightMeasure		▶▶▶
For Shipments: DCONSI.DAGRWE; DRS100MI/LstShipment	For Shipments: This field indicates the Gross Weight	SHIPMENT.SH_GROSS_WGHT
	For Shipment Deliveries: The field indicates the gross weight of all items in the delivery.	
MHDISH.OQGRW2; MWS410MI/GetHead		
<hr/>		
Shipment/ShipmentHeader/TotalVolumeMeasure		▶▶▶
@unitCode		
For Shipments: CSYTAB.CTPARM; CRS175MI/ GetItemFreeFlds	For Shipments: The field indicates the general unit of measure for all volumes within a company.	SHIPMENT.SH_TVM_UNIT
<hr/>		
Shipment/ShipmentHeader/TotalVolumeMeasure		▶▶▶
For Shipments: DCONSI.DAVLME; DRS100MI/LstShipment	For Shipments: This field indicates the Estimated Volume	SHIPMENT.SH_TOTAL_VLM
<hr/>		
Shipment/ShipmentHeader/TransportationMethodCode		▶▶▶
For Shipments: CSYTAB.CTPARM; CRS070MI/ GetDelyMethod	For Shipments: The field indicates how the delivery is made.	SHIPMENT.SH_TRANSPORTA TION_MTHD_CD
	For Shipment Deliveries: Transportation Equipment	
For Shipment Deliveries: MDDADV.OVTRCA; MWS410MI/GetHead	The field indicates transportation equipment which is the unique code identifying a specific mode of transportation.	
	The code may for instance be the license number of a truck, the flight number of an aircraft etc.	
<hr/>		
Shipment/ShipmentHeader/CarrierParty/PartyIDs/ID		▶▶▶
For Shipments: DCONSI.DAFWNO; DRS100MI/LstShipment	The field indicates the forwarding agent who can be used for the transport.	SHIPMENT.SH_CRP_PID_ID

Shipment

Infor M3 Business Engine - Infor Business Vault

For Shipment Deliveries:
MHDISH.OQFWNO;
MWS410MI/GetHead

Shipment/ShipmentHeader/ReturnToShipFromParty/PartyIDs/ID

For Shipments: The field indicates the warehouse ID.
DCONSI.DAWHLO;
DRS100MI/LstShipment



SHIPMENT.SH_RTSFP_PID_
ID

For Shipment Deliveries:
DCONSI.DAWHLO;
MWS410MI/GetHead

Shipment/ShipmentHeader/ScheduledShipDateTime

For Shipments: For Shipments:
DCONSI.DARDDT This field indicate the date/time the order is to be shipped by the
DARDTM; DRS100MI/ supplier.
LstShipment



SHIPMENT.SH_SCHDD_SHIP
_DATE

For Shipment Deliveries: The field indicates the actual ship date. It is updated at stock issue.
MHDISH.OQSDT The field indicates the actual ship time. It is updated at stock issue.
OQDSHM; MWS410MI/
GetHead

Shipment/ShipmentHeader/TransportationTerm/IncotermsCode

For Shipment Deliveries: For Shipment Deliveries:
MHDISH.MQTEDL; The field indicates delivery terms, which define when the responsibility
MWS410MI/GetHead for a delivery is transferred from the supplier to the customer.



SHIPMENT.SH_TT_INCOTER
MS_CD

Shipment/ShipmentHeader/TransportationTerm/PlaceOfOwnershipTransferLocation/Description

For Shipment Deliveries: For Shipment Deliveries:
CSYTAB.CTPARM; The field indicates when the liability for a delivery is transferred from the
CRS065MI/GetDelyTerm supplier to the buyer.



SHIPMENT_LC.SH_TT_POOT
L_DSC

Shipment/ShipmentItem/ItemID/ID

MFTRNS.MQITNO; For Shipments:
MWS410MI/LstItem Use DRS100MI-LstByDelivery to retrieve deliveries connected to
Shipment then retrieve item numbers connected to delivery



SHIPMENT_LINE.SI_IID_I
D

This field pertains to the Item Numbers belonging to the Shipment.

For Shipment Deliveries:
This field indicates the item number within the Shipment.

Shipment/ShipmentItem/Description

For Shipments: For Shipments:
MFTRNS.MQITDS; This field indicates the description of the Item.
MWS410MI/LstItem



SHIPMENT_LINE_LC.SI_DS
C

For Shipment Deliveries:
For Shipment Deliveries: This field indicates the item description.
MITMAS.MMITDS;
MWS410MI/LstItem

Shipment/ShipmentItem/OrderQuantity @unitCode



Shipment

Infor M3 Business Engine - Infor Business Vault

For Shipment Deliveries: MITMAS.MMUNMS; MWS410MI/LstItem	For Shipment Deliveries: Basic U/M The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.	SHIPMENT_LINE.SI_RQSTD _SHIP_QTY_TXN_ID
<hr/>		
Shipment/ShipmentItem/OrderQuantity		
For Shipment Deliveries: MGLINE.MRTRQT; MWS410MI/LstItem	For Shipment Deliveries: Transaction Quantity - Base U/M The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.	SHIPMENT_LINE.SI_RQSTD _SHIP_QTY_TXN
<hr/>		
Shipment/ShipmentItem/ShippedQuantity @unitCode		
For Shipments: MITMAS.MMUNMS; MMS410MI/LstItem	For Shipments: The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.	SHIPMENT_LINE.SI_SHIPP ED_QTY_TXN_ID
For Shipment Deliveries: MITMAS.MMUNMS; MWS410MI/LstItem	For Shipment Deliveries: Basic U/M The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.	
<hr/>		
Shipment/ShipmentItem/ShippedQuantity		
For Shipments: MFTRNS.MQTRQT; MWS410MI/LstItem	For Shipments: This field indicates the Delivered Quantity.	SHIPMENT_LINE.SI_SHIPP ED_QTY_TXN
For Shipment Deliveries: MGLINE.MRPAQT; MWS410MI/LstItem	For Shipment Deliveries: The field indicates the delivered quantity, expressed in the item's basic U/M.	
<hr/>		
Shipment/ShipmentItem/SalesOrderReference/DocumentID/ID		
MHDISH.MQRIDN; MWS410MI/GetHead	The field indicates an order number.	SHIPMENT_LINE.SI_SOR_D ID_ID
<hr/>		
Shipment/ShipmentHeader/ShipToParty/PartyIDs/ID		
For Shipment Deliveries: MHDISH.OQCONA; MWS410MI/GetHead	For Shipment Deliveries: The field indicates the consignee's ID, which depends on the delivery's order category.	SHIPMENT.SH_STP_PID_ID

SourceSystemGLMovement

Infor M3 Business Engine - Infor Business Vault

SourceSystemGLMovement/IDs/ID

For Actual:
FBAVAL +
FBAKEY.YEA4+PERI
+BIT1->BIT7; GLS215MI/
getPeriodBalance
For Budget:
FBUDET.BUPE
+AIT1+AIT2+AIT3+AIT4+
+BUNO+BVER;
BUS100MI/IstBudPerVal

For Actual:
YEA4+PERI+Accounting string. Spaces will be underscores (_).
Delimiter will be dot (.)
For Budget:
Taken from the event; Budget period + Accounting dimension 1 to 7 +
Currency + Budget number + Budget version

►►►
GL_BALANCE.ID_ID

SourceSystemGLMovement/GLMovementRow/LedgerSetupReference/BookInstanceID

For Budget:
FBUDET.BCBVER
+BCBUNO; BUS100MI/
IstBudPerVal

For Budget:
Taken from the event; Combination of budget version and budget
number.

►►►
GL_BALANCE.GLMR_LSR_BK
INSTNCID

SourceSystemGLMovement/GLMovementRow/AccountingBookTypeCode

Constant.; /
For Actual:
Constant = 'Actual'
For Budget:
Constant = 'Budget'

►►►
GL_BALANCE.GLMR_ACNTNG
_BOOK_TYP_CD

SourceSystemGLMovement/GLMovementRow/PostingKey

For Actual:
FBAVAL +
FBAKEY.YEA4+PERI
+BIT1->BIT7; GLS215MI/
getPeriodBalance
For Budget:
FBUDET.BCBUPE
+BCAIT1+BCAIT2+BCAIT
+BCBUNO+BCBVER;
BUS100MI/IstBudPerVal

For Actual:
YEA4+PERI+Accounting string. Spaces will be underscores (_).
Delimiter will be dot (.)
For Budget:
Taken from the event; Budget period + Accounting dimension 1 to 7 +
Currency + Budget number + Budget version

►►►
GL_BALANCE.GLMR_POSTIN
G_KEY

SourceSystemGLMovement/GLMovementRow/GLAccount/GLNominalAccount

For Actual:
FBAKEY.BIT1;
GLS215MI/
getPeriodBalance
For Budget:
FBUDET.BCAIT1;
BUS100MI/IstBudPerVal

For Actual:
The field indicates a balance identity in a balance dimension.
A selection may be entered for each of the seven levels. The contents
of these levels are determined by the heading that is linked to each field.
For Budget:
Taken from the event; Accounting dimension 1

►►►
GL_BALANCE.GLMR_GLA_GL
N_ACNT

SourceSystemGLMovement/GLMovementRow/GLAccount/GLNominalAccountName

For Actual:
FCHACC.TX40;
CRS630MI/getAccountID
For Budget:
GL account name description

For Actual:
The field indicates a description of the current identity.

►►►
GL_BALANCE_LC.GLMR_GLA
_GLN_ACNT_NAME

SourceSystemGLMovement

Infor M3 Business Engine - Infor Business Vault

FCHACC.EATX40;
CRS630MI/getAccountID

SourceSystemGLMovement/GLMovementRow/AccountType

FCHACC.AT01, AT02; If AT01 = 1 then 'BalanceSheet'. If AT02 = 1 then 'ProfitAndLoss'
CRS630MI/getAccountID

►►►

GL_BALANCE.GLMR_ACNT_T
YP

SourceSystemGLMovement/GLMovementRow/DimensionCodes/DimensionCode

►►►

@sequence

For Actual:
FBAVAL.BIT2-7;
GLS215MI/
getPeriodBalance

For Actual:
BIT2 = 2, BIT3 = 3 etc.

For Budget:
Taken from the event; Accounting dimension 2 to 7.

GL_BALANCE.GLMR_DC_DC_
LIST_ID_01

[@sequence='1']/@listID

For Budget:
FBUDET.BCAIT2-
BCAIT7; BUS100MI/
IstBudPerVal

SourceSystemGLMovement/GLMovementRow/AccountingDate/PeriodID

►►►

For Actual:
FBAKEY.YEA4+PERI;
GLS215MI/
getPeriodBalance

For Actual:
Period year

For Budget:
Position 4-6 of budget period

GL_BALANCE.GLMR_AD_PRD
_ID

For Budget:
FBUDET.BUPE;
BUS100MI/IstBudPerVal

SourceSystemGLMovement/GLMovementRow/AccountingDate/Year

►►►

For Actual:
FBAKEY.YEA4;
GLS215MI/
getPeriodBalance

For Actual:
The field indicates the year. It is entered using four positions, for
example, 2002.

For Budget:
Position 0-3 of budget period

GL_BALANCE.GLMR_AD_YEA
R

For Budget:
FBUDET.BUPE;
BUS100MI/IstBudPerVal

SourceSystemGLMovement/GLMovementRow/DebitMovement/FunctionalAmount

►►►

@currencyID

For Actual:
CMNDIV.CUCD;
MNS100MI/getBasicData

For Actual:
Currency code from MNS100

For Budget:
CMNDIV.LOCD;
MNS100MI/getBasicData

For Budget:
Currency code taken from the company/division setup

GL_BALANCE.GLMR_DM_DEB
IT_AMT_BC_ID

SourceSystemGLMovement/GLMovementRow/DebitMovement/FunctionalAmount

►►►

For Actual:
FBAVAL.ACAD;
GLS215MI/
getPeriodBalance

For Actual:
Local currency amount

For Budget:
If BLAM >= 0; Local currency amount - budget

GL_BALANCE.GLMR_DM_DEB
IT_AMT_BASE

SourceSystemGLMovement

Infor M3 Business Engine - Infor Business Vault

For Budget:
FBUDET.BLAM;
BUS100MI/IstBudPerVal

SourceSystemGLMovement/GLMovementRow/DebitMovement/Amount

►►►

@currencyID

For Actual: FCHACC.CUCD;
CRS630MI/getAccountID
For Actual: Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting)

GL_BALANCE.GLMR_DM_DEB
IT_AMT_TXN_ID

For Budget: FBUDET.CUCD;
BUS100MI/IstBudPerVal
For Budget: Currency code

SourceSystemGLMovement/GLMovementRow/DebitMovement/Amount

►►►

For Actual: FBAVAL.CUAD;
GLS215MI/
getPeriodBalance
For Actual: Foreign currency amount. Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting)

GL_BALANCE.GLMR_DM_DEB
IT_AMT_TXN

For Budget: FBUDET.BCUA;
BUS100MI/IstBudPerVal
For Budget: Foreign currency amount - budget

SourceSystemGLMovement/GLMovementRow/DebitMovement/ ReportingCurrencyAmount

►►►

@currencyID

For Actual: CSYPAR.PARM;
GLS215MI/
getPeriodBalance
For Actual: Third currency

GL_BALANCE.GLMR_DM_DEB
IT_AMT_RPRTG_ID

SourceSystemGLMovement/GLMovementRow/DebitMovement/ ReportingCurrencyAmount

►►►

For Actual: FBAVAL.TCAD;
GLS215MI/
getPeriodBalance
For Actual: Third currency amount. Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting)

GL_BALANCE.GLMR_DM_DEB
IT_AMT_RPRTG

SourceSystemGLMovement/GLMovementRow/CreditMovement/FunctionalAmount @currencyID

►►►

For Actual: CMNDIV.CUCD;
MNS100MI/getBasicData
Currency code from MNS100

GL_BALANCE.GLMR_CM_CRD
T_AMT_BC_ID

For Budget: CMNDIV.LOCD;
MNS100MI/getBasicData

SourceSystemGLMovement/GLMovementRow/CreditMovement/FunctionalAmount

►►►

For Actual: FBAVAL.ACAC;
GLS215MI/
getPeriodBalance
For Actual: Local currency amount
For Budget: If BLAM < 0

GL_BALANCE.GLMR_CM_CRD
T_AMT_BASE

SourceSystemGLMovement

Infor M3 Business Engine - Infor Business Vault

For Budget:
FBUDET.BLAM;
BUS100MI/IstBudPerVal

SourceSystemGLMovement/GLMovementRow/CreditMovement/Amount



@currencyID

For Actual: FCHACC.CUCD;
CRS630MI/getAccountID
For Actual: Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting)

GL_BALANCE.GLMR_CM_CRD
T_AMT_TXN_ID

For Budget: FBUDET.CUCD;
BUS100MI/IstBudPerVal
For Budget: Currency code

SourceSystemGLMovement/GLMovementRow/CreditMovement/Amount



For Actual: FBAVAL.CUAC;
GLS215MI/
getPeriodBalance
For Actual: Foreign currency amount. Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting)

GL_BALANCE.GLMR_CM_CRD
T_AMT_TXN

For Budget: FBUDET.BCUA;
BUS100MI/IstBudPerVal
For Budget: if BCUA < 0; Foreign currency amount - budget

SourceSystemGLMovement/GLMovementRow/CreditMovement/ ReportingCurrencyAmount



@currencyID

For Actual: CSYPAR.PARM;
GLS215MI/
getPeriodBalance
For Actual: Third currency

GL_BALANCE.GLMR_CM_CRD
T_AMT_RPRTG_ID

SourceSystemGLMovement/GLMovementRow/CreditMovement/ ReportingCurrencyAmount



For Actual: FBAVAL.TCAC;
GLS215MI/
getPeriodBalance
For Actual: Third currency amount. Only included if currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting)

GL_BALANCE.GLMR_CM_CRD
T_AMT_RPRTG

SourceSystemGLMovement/GLMovementRow/NetMovement/FunctionalAmount @currencyID



For Actual: CMNDIV.CUCD;
MNS100MI/getBasicData
Currency code from MNS100

GL_BALANCE.GLMR_NM_NET
_AMT_BC_ID

For Budget: CMNDIV.LOCD;
MNS100MI/getBasicData

SourceSystemGLMovement/GLMovementRow/NetMovement/FunctionalAmount



For Actual: FBAVAL.ACAD+ACAC;
GLS215MI/
getPeriodBalance
Local currency amount

GL_BALANCE.GLMR_NM_NET
_AMT_BASE

SourceSystemGLMovement

Infor M3 Business Engine - Infor Business Vault

For Budget:
FBUDET.BLAM;
BUS100MI/IstBudPerVal

SourceSystemGLMovement/GLMovementRow/NetMovement/Amount



@currencyID

For Actual: For Actual:
FCHACC.CUCD; Only included if currency connection = 2 on account (currency
CRS630MI/getAccountID connection =2= only the currency code of the account can be used for
posting

GL_BALANCE.GLMR_NM_NET
_AMT_TXN_ID

For Budget:
FBUDET.CUCD; For Budget:
BUS100MI/IstBudPerVal Currency code

SourceSystemGLMovement/GLMovementRow/NetMovement/Amount



For Actual: For Actual:
FBAVAL.CUCD+CUC; Foreign currency amount. Only included if currency connection = 2 on
GLS215MI/ account (currency connection =2= only the currency code of the
getPeriodBalance account can be used for posting

GL_BALANCE.GLMR_NM_NET
_AMT_TXN

For Budget: For Budget:
FBUDET.BCUA; Foreign currency amount
BUS100MI/IstBudPerVal

SourceSystemJournalEntry

Infor M3 Business Engine - Infor Business Vault

SourceSystemJournalEntry/JournalEntryHeader/JournalID

FGLEDG.YEA4,VSER,VCCConcatenated Year, Voucher series number and Voucher number
GLS200MI/
LstVoucherLine



GL_JOURNAL.SSJEH_JRNL_
ID

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/PeriodID

FGLEDG.CYP6; Financial period
GLS200MI/
LstVoucherLine



GL_JOURNAL.SSJEH_BJEH_
AD_PRD_ID

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/PostDateTime

FGLEDG.ACDT; Accounting Date of first line of voucher
GLS200MI/
LstVoucherLine



GL_JOURNAL.SSJEH_BJEH_
AD_POST_DATE

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/Year

FGLEDG.YEA4; Year for first line of voucher
GLS200MI/
LstVoucherLine



GL_JOURNAL.SSJEH_BJEH_
AD_YEAR

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/Amount@currencyID

FGLEDG.CUCD; Foreign currency code
GLS200MI/
GetVoucherHead



GL_JOURNAL.SSJEH_BJEH_
CNTR_TOTAMT_TXN_ID

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/Amount

FGLEDG.CUAM; The field indicates the currency amount, that is, the recorded amount in the appropriate currency.
GLS200MI/
GetVoucherHead



GL_JOURNAL.SSJEH_BJEH_
CNTRL_TOTAL_AMT_TXN

There are three key currency types in M3 BE:

1. Local currency - the base, domestic currency used by the company and to which all transactions are converted in the general ledger. A value expressed in this currency is called local amount.
2. Foreign currency - any other currency used. A value expressed in such a currency is called currency amount.
3. Third currency - a currency with special status, such as the euro within the Monetary Union (EMU), or the U.S. dollar. A third currency may be useful for reporting and comparison purposes, for example when you wish to present your figures in a stable currency.

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/FunctionalAmount@currencyID

CMNDIV.CUCD; Local currency currency code
MNS100MI/GetBasicData



GL_JOURNAL.SSJEH_BJEH_
CNTR_TOTAMT_BC_ID

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/FunctionalAmount

FGLEDG.ACAM; Sum of accounted amount



GL_JOURNAL.SSJEH_BJEH_

SourceSystemJournalEntry

Infor M3 Business Engine - Infor Business Vault

GLS200MI/ GetVoucherHead		CNTR_TOTAMT_BASE
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/Description	▶▶▶	
CSYTAB.TX40; Description of FAM function in CRS405/E. STCO = FEID CRS175MI/ GetGeneralCode		GL_JOURNAL_LC.SSJEH_BJ EH_DSC
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/LedgerType	▶▶▶	
Constant.; / Constant = 'Actual'		GL_JOURNAL.SSJEH_BJEH_ LEDGER_TYP
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ AccountingJournalReference/ID	▶▶▶	
FGLEDG.FEID; Reference to accounting journal BOD, FAM Entry ID on transaction is GLS200MI/ used GetVoucherHead		GL_JOURNAL.SSJEH_BJEH_ AJR_ID
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ JournalStatus/Code	▶▶▶	
Constant.; / Constant = 'Final'		GL_JOURNAL.SSJEH_BJEH_ JS_CD
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ EnteredAudit/PersonReference/IDs/ID	▶▶▶	
FGLEDG.CHID; Change ID GLS200MI/ LstVoucherLine		GL_JOURNAL.SSJEH_BJEH_ EA_PR_ID_ID
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ EnteredAudit/PersonReference/Name	▶▶▶	
CMNUSR.TX40; Full Name from User master MNS150MI/GetUserData		GL_JOURNAL_LC.SSJEH_BJ EH_EA_PR_NAME
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ EnteredAudit/DateTime	▶▶▶	
FGLEDG.RGDT,RGTM; Registration date time GLS200MI/ LstVoucherLine		GL_JOURNAL.SSJEH_BJEH_ EA_DATE
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ ModifiedAudit/PersonReference/IDs/ID	▶▶▶	
FGLEDG.CHID; Change ID GLS200MI/ LstVoucherLine		GL_JOURNAL.SSJEH_BJEH_ MA_PR_ID_ID
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ ModifiedAudit/PersonReference/Name	▶▶▶	
CMNUSR.TX40; Full Name from User master MNS150MI/GetUserData		GL_JOURNAL_LC.SSJEH_BJ EH_MA_PR_NAME
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/ ModifiedAudit/DateTime	▶▶▶	
FGLEDG.LMDT; Last modified date GLS200MI/ LstVoucherLine		GL_JOURNAL.SSJEH_BJEH_ MA_DATE

SourceSystemJournalEntry

Infor M3 Business Engine - Infor Business Vault

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/PostedAudit/PersonReference/IDs/ID	▶▶▶
FGLEDG.CHID; Change ID GLS200MI/ LstVoucherLine	GL_JOURNAL.SSJEH_BJEH_ PA_PR_ID_ID
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/PostedAudit/PersonReference/Name	▶▶▶
CMNUSR.TX40; Full Name from User master MNS150MI/GetUserData	GL_JOURNAL_LC.SSJEH_BJ EH_PA_PR_NAME
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/PostedAudit/DateTime	▶▶▶
FGLEDG.LMDT; Last modified date GLS200MI/ LstVoucherLine	GL_JOURNAL.SSJEH_BJEH_ PA_DATE
SourceSystemJournalEntry/JournalEntryLine/Amount@currencyID	▶▶▶
FGLEDG.CUCD; Foureign currency curfency code GLS200MI/ LstVoucherLine	GL_JOURNAL_LINE.SSJEL_ AMT_TXN_ID
SourceSystemJournalEntry/JournalEntryLine/Amount	▶▶▶
FGLEDG.CUAM; Foreign currency amount GLS200MI/ LstVoucherLine	GL_JOURNAL_LINE.SSJEL_ AMT_TXN
SourceSystemJournalEntry/JournalEntryLine/FunctionalAmount@currencyID	▶▶▶
CMNDIV.CUCD; Local currency curfency code MNS100MI/GetBasicData	GL_JOURNAL_LINE.SSJEL_ AMT_BC_ID
SourceSystemJournalEntry/JournalEntryLine/FunctionalAmount	▶▶▶
FGLEDG.ACAM; Local currency amount GLS200MI/ LstVoucherLine	GL_JOURNAL_LINE.SSJEL_ AMT_BASE
SourceSystemJournalEntry/JournalEntryLine/AlternativeCurrencyAmount@currencyID	▶▶▶
FGLEDG.THCC; Currency code from CRS750 GLS200MI/ LstVoucherLine	GL_JOURNAL_LINE.SSJEL_ AMT_SECONDARY_ID
SourceSystemJournalEntry/JournalEntryLine/AlternativeCurrencyAmount	▶▶▶
FGLEDG.TCAM; Third currency amount GLS200MI/ LstVoucherLine	GL_JOURNAL_LINE.SSJEL_ AMT_SECONDARY
SourceSystemJournalEntry/JournalEntryLine/GLAccount/GLNominalAccount	▶▶▶
FGLEDG.AIT1; Account GLS200MI/ LstVoucherLine	GL_JOURNAL_LINE.SSJEL_ GLA_GLN_ACNT
SourceSystemJournalEntry/JournalEntryLine/GLAccount/GLNominalAccountName	▶▶▶
FCHACC.TX40; Account description CRS630MI/GetAccountID	GL_JOURNAL_LINE_LC.SSJ EL_GLA_GLN_ACNT_NAME

SourceSystemJournalEntry

Infor M3 Business Engine - Infor Business Vault

**SourceSystemJournalEntry/JournalEntryLine/GLAccount/AccountingChartReference/
ID**



Constant.; / Constant 'AccountingChartStandard'

GL_JOURNAL_LINE.SSJEL_
GLA_ACR_ID

**SourceSystemJournalEntry/JournalEntryLine/DimensionCodes/DimensionCode
@sequence**



Constant.; / Values '1' -> '6'

GL_JOURNAL_LINE.SSJEL_
DC_DC_LIST_ID_01 [@sequence='1']/@listID

SourceSystemJournalEntry/JournalEntryLine/SourceLine



FGLEDG.JSNO; Journal sequence number
GLS200MI/
LstVoucherLine

GL_JOURNAL_LINE.SSJEL_
SRCE_LINE

SourceSystemJournalEntry/JournalEntryLine/DebitCreditFlag



FGLEDG.DBCR; "DEBIT" or "CREDIT"
GLS200MI/
LstVoucherLine

GL_JOURNAL_LINE.SSJEL_
DEBIT_CRDT_FLAG

SourceSystemJournalEntry/JournalEntryLine/SourceAccountingDate/PeriodID



.; GLS200MI/ Period
LstVoucherLine

GL_JOURNAL_LINE.SSJEH_
BJEH_AD_PRD_ID

SourceSystemJournalEntry/JournalEntryLine/SourceAccountingDate/PostDateTime



FGLEDG.ACDT; Accounting Date
GLS200MI/
LstVoucherLine

GL_JOURNAL_LINE.SSJEH_
BJEH_AD_POST_DATE

SourceSystemJournalEntry/JournalEntryLine/SourceAccountingDate/Year



FGLEDG.YEA4; Year
GLS200MI/
LstVoucherLine

GL_JOURNAL_LINE.SSJEH_
BJEH_AD_YEAR

SourceSystemJournalEntry/JournalEntryLine/Description



FGLEDG.VTXT; Voucher text
GLS200MI/
LstVoucherLine

GL_JOURNAL_LINE_LC.SSJ
EL_DSC

SourceSystemJournalEntry/JournalEntryLine/GLFullAccount



FGLEDG.AIT1; Accounting dimension 1 = Account
GLS200MI/
LstVoucherLine

GL_JOURNAL_LINE.SSJEL_
GLF_ACNT

SupplierPartyMaster

Infor M3 Business Engine - Infor Business Vault

SupplierPartyMaster/PartyIDs/ID CIDMAS.IDSUNO; SUTY = 0, 1, 2, 3, 6, 8 (exclude Forwarding agent => CRS620MI/GetBasicData ShipCarrierPartyMaster)	▶▶▶ SUPPLIER.PID_ID
SupplierPartyMaster/PartyIDs/DisplayID CIDMAS.IDSUNO; The field indicates the unique identity of a supplier. CRS620MI/GetBasicData	▶▶▶ SUPPLIER.PID_DISPLAY_I D
SupplierPartyMaster/PartyIDs/TaxID CIDMAS.IDCORG; The field indicates the supplier's organization number. CRS620MI/GetBasicData	▶▶▶ SUPPLIER.PID_TX_ID_01
SupplierPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC; The field indicates Standard Carrier Alpha Code (SCAC). CRS620MI/GetBasicData	▶▶▶ SUPPLIER.PID_SCACID
SupplierPartyMaster/Name CIDMAS.IDSUNM; The field indicates supplier name. CRS620MI/GetBasicData	▶▶▶ SUPPLIER_LC.NAME
SupplierPartyMaster/Location/Address/AddressLine @sequence The field indicates the Address Line sequence	▶▶▶ SUPPLIER_LC.L_A_PRI_AL ADDL_01 [@sequence='1']
SupplierPartyMaster/Location/Address/CityName CIDADR.SATOWN; The field indicates the city in an address CRS620MI/LstAddresses	▶▶▶ SUPPLIER.L_A_PRI_CITY_ NAME
SupplierPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; The field indicates an area, province or state within a country. CRS620MI/LstAddresses	▶▶▶ SUPPLIER.L_A_PRI_C_SBD VSN
SupplierPartyMaster/Location/Address/CountryCode CIDADR.SACSCD; The field indicates a country. CRS620MI/LstAddresses	▶▶▶ SUPPLIER.L_A_PRI_CNTRY _CD
SupplierPartyMaster/Location/Address/PostalCode CIDADR.SAPONO; The field indicates a postal code for a specific address. CRS620MI/LstAddresses	▶▶▶ SUPPLIER.L_A_PRI_POSTA L_CD
SupplierPartyMaster/Contact/Name CIDREF.IRYRE1; The field indicates the name of the contact. CRS620MI/ LstSupplierRef	▶▶▶ SUPPLIER_LC.C_PRI_NAME
SupplierPartyMaster/Status/Code CIDMAS.IDSTAT; The field indicates the supplier status. CRS620MI/GetBasicData M3 BE status is translated according to: 10 = Pending 20 = Open 30 = Hold 90 = Deleted	▶▶▶ SUPPLIER.S_CD
SupplierPartyMaster/BuyerPersonReference/IDs/ID CIDVEN.IIBUYE; The field indicates the buyer. CRS620MI/GetBasicData	▶▶▶ SUPPLIER.BPR_ID_ID
SupplierPartyMaster/Contact/Communication/DialNumber	▶▶▶

SupplierPartyMaster

Infor M3 Business Engine - Infor Business Vault

CIDREF.IRPHNO/ IRTFNO; CRS620MI/ LstSupplierRef	The field indicates the telephone or facsimile number of the contact	SUPPLIER.C_PRI_C_PHONE OFC
<hr/>		
SupplierPartyMaster/Contact/Communication/URI CIDREF.IREMAL; CRS620MI/ LstSupplierRef	The field indicates an e-mail address for the contact	▶▶▶ SUPPLIER.C_PRI_C_URI_E MAIL
<hr/>		