

## 2. 配置网络

笔记本： 优秀笔记

创建时间： 2018/12/20 13:12

更新时间： 2018/12/20 13:44

作者： 306798658@qq.com

### 1. 查看网卡信息

- 命令1: ip addr

```
[root@localhost ~]# ip addr1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN
link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00 #能够看到还回口的相关信息
inet 127.0.0.1/8 scope host lo
    valid_lft forever preferred_lft forever
inet6 ::1/128 scope host
    valid_lft forever preferred_lft forever
2: eno16777736: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP qlen 1000
link/ether 00:0c:29:53:5c:6a brd ff:ff:ff:ff:ff:ff #能够看到 MAC 地址
inet 172.16.166.254/24 brd 172.16.166.255 scope global eno16777736 #能够看到 IP 地址
    valid_lft forever preferred_lft forever
inet6 fe80::20c:29ff:fe53:5c6a/64 scope link
    valid_lft forever preferred_lft forever
```

- 命令2: ifconfig

该命令包含于 net-tools 软件包中，默认是不能正确执行的，等你配置好网络后，可以使用yum install -y net-tools命令安装该指令

```
[root@localhost ~]# ifconfig
eno16777736: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 172.16.166.254 netmask 255.255.255.0 broadcast 172.16.166.255
    inet6 fe80::20c:29ff:fe53:5c6a prefixlen 64 scopeid 0x20<link>
    ether 00:0c:29:53:5c:6a txqueuelen 1000 (Ethernet)
    RX packets 192 bytes 19043 (18.5 KiB)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 141 bytes 18501 (18.0 KiB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

lo: flags=73<UP,LOOPBACK,RUNNING> mtu 65536
    inet 127.0.0.1 netmask 255.0.0.0
    inet6 ::1 prefixlen 128 scopeid 0x10<host>
    loop txqueuelen 0 (Local Loopback)
    RX packets 0 bytes 0 (0.0 B)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 0 bytes 0 (0.0 B)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

### 2. 查看路由信息

- 命令: route -n #n参数表示使用纯数字来显示 IP 地址

```
[root@localhost ~]# route -n
Kernel IP routing table
Destination Gateway Genmask Flags Metric Ref Use Iface
0.0.0.0 172.16.166.2 0.0.0.0 UG 1024 0 0 eno16777736
172.16.166.0 0.0.0.0 255.255.255.0 U 0 0 0 eno16777736
```

这里的172.16.166.2就是网关，一会要用到这个IP。

### 3. 通过 DHCP 服务获取 IP

- 命令: dhclient

说明：无法重复运行 dhclient，在第二次运行前需要使用dhclient -r来释放。

#### 4. 直接修改网卡的配置文件（推荐）

配置文件：/etc/sysconfig/network-scripts/ifcfg-xxx(文件名可能有所不同)

```
[root@localhost ~]# vi /etc/sysconfig/network-scripts/ifcfg-eno16777736
HWADDR=00:0C:29:53:5C:6A
TYPE=Ethernet
BOOTPROTO=static          #分 static 与 dhcp 两种
DEFROUTE=yes
PEERDNS=yes
PEERROUTES=yes
IPV4_FAILURE_FATAL=no
IPV6INIT=yes
IPV6_AUTOCONF=yes
IPV6_DEFROUTE=yes
IPV6_PEERDNS=yes
IPV6_PEERROUTES=yes
IPV6_FAILURE_FATAL=no
NAME=eno16777736
UUID=c56b15e6-2ca7-4c8f-886e-dc80dabbf8d7
ONBOOT=yes                #是否开机启动
IPADDR=172.16.166.254      #IP 地址
NETMASK=255.255.255.0      #子网掩码
GATEWAY=172.16.166.2       #网关
DNS1=223.5.5.5             #DNS 服务器
```

#### 5. 重启网络服务

```
# systemctl restart network.service
```

#### 6. 检测

```
# ping www.qq.com        #看是否能ping通
```