

# Connecting to your Linux or Unix instance in Amazon Lightsail using SFTP

---


*Last updated: July 2, 2019*

You can transfer files between your local computer and your Linux or Unix instance in Amazon Lightsail by connecting to your instance using SFTP (SSH File Transfer Protocol). To do this, you must get the private key for your instance, and then use it to configure the FTP client. This tutorial shows you how to configure the FileZilla FTP client to connect to your instance. These steps may also apply to other FTP clients.

## Prerequisites

Complete the following prerequisites if you haven't already:

- Download and install FileZilla on your local computer. For more information, see the following download options:
  - [Download FileZilla Client for Windows](#)
  - [Download FileZilla Client for Mac OS X](#)
  - [Download FileZilla Client for Linux](#)
- Get the public IP address of your instance. Sign in to the [Lightsail console](#), and then copy the public IP address that is displayed next to your instance, as shown in the following example:



## Get the SSH key for your instance


Complete the following steps to get the default private key for the AWS Region of your instance, which is required to connect to your instance using FileZilla.

### Note

If you're using your own key pair, or you created a key pair using the Lightsail console, locate your own private key and use it to connect to your instance. Lightsail does not store your private key when you upload your own key or create a key pair using the Lightsail console. You cannot connect to your instance using SFTP without your private key.

1. Sign in to the [Lightsail console](#).
2. Choose **Account** on the top navigation bar, and then choose **Account** from the drop-down.
3. Choose the **SSH Keys** tab.

4. Choose **Download** next to the default private key for the region where your instance is located.




5. Save your private key in a secured location on your local drive.

## Configure FileZilla and connect to your instance

Complete the following steps to configure FileZilla to connect to your instance.

1. Open FileZilla.
2. Choose **File, Site Manager**.
3. In the **Protocol** dropdown, choose **SFTP – SSH File Transfer Protocol**.
4. In the **Host** text box, enter or paste your instance's public IP address.
5. In the **Logon Type** dropdown, choose **Key File**.
6. In the **User** text box, enter one of the following default user names depending on your instance operating system:
  - Amazon Linux, openSUSE, and FreeBSD: **ec2-user**
  - CentOS: **centos**
  - Debian: **admin**
  - Ubuntu: **ubuntu**
  - Powered by Bitnami instances: **bitnami**
  - Plesk instances: **ubuntu**
7. Next to the **Key File** text box, choose **Browse**.

8. Locate the private key file that you downloaded from the Lightsail console earlier in this procedure, and then choose **Open**.



9. Choose **Connect**.

You are successfully connected if you see status messages similar to the following example:

```
Status:    Connecting to 192.0.2.0...
Status:    Connected to 192.0.2.0
Status:    Retrieving directory listing...
Status:    Listing directory /home/ec2-user
Status:    Directory listing of "/home/ec2-user" successful
```

For more information about using FileZilla, including how to transfer files between your local computer and your instance, see the [FileZilla Wiki page](#).