

Configure Passive Authentication for VMS


 For supported software information, click [here](#).

Versa Messaging Service (VMS) is a services platform that enhances the scalability of Versa services and applications. VMS is built by leveraging state-of-the-art open source technologies such as Kubernetes and Docker.

The following are some of the main features of VMS:

- Handles data such as critical network performance information, security updates, and passive authentication data such as user-to-IP address mapping
- Manages highly dynamic data that is streamed to each Versa Operating System™ (VOS™) device to keep it updated
- Processes a high volume and a large scale of data

VMS is a component of the Versa headend as shown in the following figure.



VOS devices use VMS to support passive authentication, using it to check and confirm user identity without requiring any specific action to authenticate users. For passive authentication, VMS handles high volumes of streamed data and disseminates this data to VOS devices deployed across a network.

VMS circulates user–IP address mappings to VOS devices over two channels:

- Real-time channel—Streams data in near real-time from VMS servers to VOS devices that are configured to receive the user–IP address mappings.
- Bulk update channel—Creates a snapshot of the current user–IP address mappings available to VOS devices at a configurable interval. VOS devices use the bulk update channel to synchronize the user–IP mappings when the real-time channel is not available.




VMS includes the following components:


- Database—The database receives the user–IP address bindings from the Microsoft Active Directory (AD) server using a Windows Management Instrumentation (WMI) agent. If the full set of user–IP address mappings is requested, the response is received as a bulk update. The WMI Agent subscribes only to certain AD events.
- Messaging server—Publishes real-time user–IP address mappings to devices that subscribe to receive incremental updates for the version installed on the device. Incremental updates are published only if the incremental update is greater than the full update version.
- Package builder—Provisions the update for devices and informs Versa Director about the availability of a new full update of the user–IP address mappings database.
- WMI agent—Receives and passes on notifications from AD to VMS to update VMS entries, and learns about new events. The WMI agent publishes incremental updates to the real-time messaging server. For more information, see [Install and Configure the WMI Agent](#).
- VOS devices—Search for user–IP address mapping in the local VOS database. If a VOS device receives the traffic from a user whose IP address is present in its user–IP address mapping, the configured user or group policies are evaluated and policies are applied. To authenticate users who are not authenticated using passive authentication (for example, WiFi users and guest users), you must configure VOS with active authentication using SAML or Kerberos. VMS supports user–IP address mappings for IPv6 addresses. Currently, however, Versa Networks does not support IPv6 as a transport from VMS to VOS devices.

Configure a Messaging Server

To configure a messaging server, you add a messaging server and then associate it with an authentication profile whose authentication type is set to "passive."

Add a Messaging Server

1. In Director view:
 - a. Select the Administration tab in the top menu bar.
 - b. Select the Appliances in the left menu bar.
 - c. Select a device name in the main panel. The view changes to Appliance view.
2. Select the Configuration tab in the top menu bar.
3. Select Others  > Organization  > Messaging Service  in the left menu bar.



- Click the Add icon. In the Add Messaging Service Server popup window, enter information for the following fields.

The screenshot shows the 'Add Messaging Service Server' popup window. The window has a title bar with a close button (X). The form contains the following fields:

- Name ***: A text input field.
- Description**: A text input field.
- Routing Instance**: A dropdown menu with the value '---Please Select---'.
- CA Chain**: A dropdown menu with the value '---Please Select---'.
- Port**: A text input field with the value '3074'.
- Address**: A section header for a text input field.
- FQDN**: A text input field.





At the bottom right of the window, there are two buttons: 'OK' (green) and 'Cancel' (dark blue).

Field	Description
Name (Required)	Enter a name for the messaging server. <i>Value:</i> Text string from 1 through 127 characters <i>Default:</i> None
Description	Enter a text description for the VMS messaging server.
Routing Instance	Select the routing instance through which the VMS messaging server is reachable.
CA Chain	Select the certificate authority (CA) chain to use for the server.
Port	Enter the port number for the VMS messaging server. <i>Default:</i> 3074
Address	
◦ FQDN	Enter the fully qualified domain name of the messaging server.

- Click OK.

Associate an Authentication Profile with a VMS Server

To associate a user or group authentication profile with a VMS messaging server:

- In Director view:
 - Select the Administration tab in the top menu bar.
 - Select Appliances in the left menu bar.
 - Select a device name in the main panel. The view changes to Appliance view.
- Select the Configuration tab in the top menu bar.
- Select Object and Connectors  > Connectors  > Users/Groups  > Authentication > Profiles in the left menu bar.
- Click the  Add icon. The Add Authentication Profile popup window displays. For more information, see [Configure an Authentication Profile](#) in the Configure User and Group Policy article.

Add Authentication Profile [X]

Name*

Description

Tags

Authentication Type: **Passive** (dropdown arrow)

VMS Profile: **VMS1** (dropdown arrow)

Kerberos Profile: --Select-- (+ Create Kerberos Profile)

LDAP Profile: --Select-- (+ Create LDAP Profile)

SAML Profile: --Select-- (+ Create SAML Profile)

Caching Mode: IP Based

Cache Expiration (mins): 10

Cookie Name:

Concurrent Login: 1

Routing Instance: --Select--

Expiration Mode: --Select-- (dropdown arrow)

Authenticator Profiles: --Select-- (dropdown arrow)

LEF Profile: --Select-- (dropdown arrow)

☒ Default Profile

Certificate Auth Profile: --Select-- (+ Create Cert Auth Profile)

OK Cancel

5. In the Authentication Type field, select Passive.
6. In the VMS Profile field, select the messaging server you configured in [Configure a Messaging Server](#), above.
7. Click OK.

Supported Software Information

VOS Releases 22.1.3 and earlier support all content described in this article when used with the initial release of VMS (unnumbered).

Additional Information

[Configure User and Group Policy](#)

[Install and Configure the WMI Agent](#)

https://docs.versa-networks.com/Management_and_Orchestration/Versa_Messaging_Service/Passive_Authentication/04_Co...

Updated: Wed, 23 Oct 2024 08:49:54 GMT

Copyright © 2024, Versa Networks, Inc.

[Install the Versa Messaging Service](#)