

FILE: EDITCARD

Compliments of FRESS

A File Retrieval and Editing SyStem

Release 9.1     2 MAY 79

GRID ALTER code

Format is !+GRID<subgrid>,...,<subgrid>+

where a subgrid is

<vert iter>(<horiz iter><symbol><horiz expan>)<vert expan>

Summary of the vertical and horizontal expansion characters.

Meaning of column headings:

S -- symbol

C -- grid characters

H -- horizontal expansion character

V -- vertical expansion character

S	C	H	V
A	┌	—	
B	┐	—	
C	└	∅	
D	┘	—	
E	├	—	
F	┤	∅	
G	┴	—	∅
H	┬	—	∅
I	┴	∅	∅
J	┬	∅	∅
K	┴	—	∅
L	┬	—	∅

## SPECIAL CHARACTERS

!! literal exclamation point (!)

!~ literal "not" character (~)

!/ literal percent (%)

The following is a list of other FRESS control characters and their form code representations:

!74	¢	!123	#
!80	&	!124	@
!108	%	!126	=
!109	underscore	!127	"
!111	?		

The following is a list of special characters available on the 1403 li printer with TN print chain but not represented on a standard 2741 or Dat terminal:

!96	-	minus	!175	•	
!139	{	left brace	!176	°	superscripts
!140	≤		!177	1	
!141	ˆ	superscript (	!178	1	
!142	+	superscript +	!179	3	
!143	+	line intersection	!180	4	
!155	}	right brace	!181	5	
!156	◊	lozenge	!182	6	
!157	ˆ	superscript )	!183	7	
!158	±		!184	8	
!159	■	box	!185	9	
!160	-	superscript -	!187	┘	lower right corner
!161	°	degree sign	!188	┐	upper right corner
!171	└	lower left corner	!189	]	right bracket
!172	┌	upper left corner	!190	≠	
!173	[	left bracket	!191	—	horizontal line
!174	≥				

# EDIT and ALTER Codes

In the following definitions, n means n characters; m means m lines; x is a t index number; L R C means left or right justified or centered. < > means optional parameter, choices are separated by blanks.

## -EDIT CODES-

Bn<,m>	Draw box n by m		before
C	Center line	In	Begin new line and indent spaces
E	End heading		
F<i>	Begin footnote; footnote counter is i; Next F ends the footnote	Jn	Hanging indent of n spaces
		K<m>	Conditional page
Hi	Begin heading; i is 1 Caps, underscored, new page 2 Caps, underscored 3 Caps 4 Underscored 5 Caps, underscored, skip one line before 6 Underscored, skip one line	N<i><C R>	New page or new column (C reset page counter is i; R means roman numeral page numbers
		P	New paragraph
		R	Revision bar until next R
		S<m>	Skip m lines
		T<*n x><L R C><,fill,fillnum>	Tab
		U<*n x>	Justified tab

## +ALTER CODES+

B<H L U>	Underscoring blank mode H heading blanks only; default L do not underscore blanks U underscore all blanks	MARGIN<ln><,<rn><,<tm><,<bm>>>>	ragged left margin Left, right, top and bottom margins of a full page column; default is 0,0,9,6
COLUMNi	i is the number of columns; default is 1	OFFSETn	leave n space offset inside margin; default is 0
DATE<1 2>	Print the date 1 is numeric; 2 is alphabetic.	PAGE<n><,m>	Reset output buffer; default is 110,66
DEPTHm	number of lines per page; default is 66	PARA<n><,m>	Indent n spaces and skip m lines for each -P default is 5,1
DIn	Set decimal label level increment; default 3	SETTABx=n<L R C>...<;x=n<L R C>>	Reset default tab setting default is every 10 spaces
GUTTERn	spacing between columns; default is 3	SPACEm	m is 1, 2, or 3 for single, double, or triple spacing; default is 1
HEAD<A B>	Select heading table; default is B For headings 2, 3 and 4, table A skips fewer lines	TABLE<x=n,nn><L R C>...<;x=n,nn<L R C>>	n and nn are the left and right boundaries of an entry; default is !+TABLE+
HEADi=a,m,mm...<;i=a,m,mm>	reset heading table B; a can be the sum of: 32 underscored, 4 caps, 1 new page, 0 none m lines are skipped before and mm lines are skipped after the heading	TITLEa<=m<L R C>>+<title string>	title string is printed every page a is character indicating title string
JUSTCi;Li or JUST<Ci Li>	Column and line justification; default C0,L0 C0 widow elimination, padding and balancing C1 no column padding C2 no widow elimination C3 no column balancing L0 fully justified lines L1 bell justification L2 text set flush left with ragged right margin L3 text set flush right with	TOFC<i<=n>>...<;i<=n>>	i is the heading level to be included in the table contents; n is the indentation level; default all levels
		WIDOWm	Lines allowed to stand alone at the top and bottom of column; default is twice the current spacing value
		WIDTHn	n is the page width; default is 65