

ACTIVE DIRECTORY


Active Directory (AD), Microsoft'un geliřtirdiđi Windows tabanlı ađlarda alıřan bir dizin hizmetidir. ađda bulunan kullanıcılar, bilgisayarlar, yazıcılar ve diđer kaynaklar gibi nesnelerin bilgilerini merkezi bir veritabanında saklar. Bu nesneleri yönetmek ve erişim izinlerini düzenlemek için kullanılır. Active Directory kimlik yönetimi, oturum açma ve yetkilendirme gibi işlevleri sağlar.

Active Directory Windows server üzerine kurulabilen bir makine olduđu için sanallařtırma ortamına Windows server makinemi kuruyorum.

Windows Server Kurulumu

Windows Server, Microsoft'un işletim sistemi ailesinin bir parçasıdır ve özellikle sunucu ortamları için tasarlanmış bir işletim sistemidir. Windows Server, kurumsal ađlarda ve büyük ölçekli işletmelerde yaygın olarak kullanılır. eřitli sürümleri bulunur ve işletim sistemi özellikleri sürüme göre farklılık gösterebilir.


Bende 2016 datacenter sürümünün iso dosyası yer alıyor. Öncelikle kurulum için sanallařtırma ortamına ihtiyacımız var, ben VMware kullanıyorum. Yeni bir sanal makine oluştur diyorum ve iso dosyamı seçiyorum. Gerekli depolama, ram ve işlemci kullanımını seçiyorum.




Daha sonra yükleme işleminin bitmesini bekliyorum. Ardından Windows server makinemiz açılıyor. Makinemi daha sonra makineler ile bağlantı kurabilmesi için VLAN ađına alıyorum. Makinemizin ip adresini statik olarak ayarlamak çok önemli. Makinemin karışmaması için ismini anlayacađım şekilde deđiřtiriyorum.

STATİK IP VERME


İlk olarak Kontrol Paneli açıyorum. Network ve Internet ayarlarından “Network and Sharing Center” seçeneğine tıklıyorum. “Ethernet0” seçeneğini seçiyorum.




“Properties” seçeneğine tıklıyorum.



“Internet Protocol Version 4 (TCP/IPv4)” seçeneğini seçiyorum.




Burada kullanmak istediğim ip adresini giriyorum ve OK ile çıkıyorum.




Active Directory Kurulumu

İlk olarak “Add rules and features” seçeneğine tıklayarak Active Directory rolünü bu Sunucuya yükleyerek bu sunucuyu Domain Controller seviyesine yükselteceğim.



“Skip this page by default” seçeneğini işaretleyerek devam ediyorum.



İlk seçenek olan “rol tabanlı veya özellik tabanlı kurulum” seçeneğini seçiyorum.

The screenshot shows the 'Add Roles and Features Wizard' window. The title bar says 'Add Roles and Features Wizard'. The main heading is 'Select installation type'. On the right, it says 'DESTINATION SERVER WIN-0B46R3AN6U4'. On the left, there is a navigation pane with the following items: 'Before You Begin', 'Installation Type' (selected), 'Server Selection', 'Server Roles', 'Features', 'Confirmation', and 'Results'. The main area contains the text: 'Select the installation type. You can install roles and features on a running physical computer or virtual machine, or on an offline virtual hard disk (VHD)'. There are two radio button options:
1. **Role-based or feature-based installation** (selected): 'Configure a single server by adding roles, role services, and features.'
2. **Remote Desktop Services installation**: 'Install required role services for Virtual Desktop Infrastructure (VDI) to create a virtual machine-based or session-based desktop deployment.'
At the bottom, there are four buttons: '< Previous', 'Next >', 'Install', and 'Cancel'.



Tek bir server'ım olduğu için onu seçip devam ediyorum.

The screenshot shows the 'Add Roles and Features Wizard' window. The title bar says 'Add Roles and Features Wizard'. The main heading is 'Select destination server'. On the right, it says 'DESTINATION SERVER WIN-0B46R3AN6U4'. On the left, there is a navigation pane with the following items: 'Before You Begin', 'Installation Type', 'Server Selection' (selected), 'Server Roles', 'Features', 'Confirmation', and 'Results'. The main area contains the text: 'Select a server or a virtual hard disk on which to install roles and features.' There are two radio button options:
1. **Select a server from the server pool** (selected)
2. **Select a virtual hard disk**
Below the options, there is a section titled 'Server Pool'. It contains a 'Filter:' text box. Below the filter is a table with the following data:


Name	IP Address	Operating System
WIN-0B46R3AN6U4	192.168.18.132	Microsoft Windows Server 2016 Datacenter

Below the table, it says '1 Computer(s) found'. At the bottom, there is a note: 'This page shows servers that are running Windows Server 2012 or a newer release of Windows Server, and that have been added by using the Add Servers command in Server Manager. Offline servers and newly-added servers from which data collection is still incomplete are not shown.'
At the bottom, there are four buttons: '< Previous', 'Next >', 'Install', and 'Cancel'.


“Active Directory Domain Services” seçeneğini seçiyoruz ve “Add Features” diyerek devam ediyorum.




Gerekli olan .Net ve Group Policy Management özellikleri eklendiği için başka bir özellik seçmeden devam ediyorum.




Tekrar "Next" diyerek devam ediyorum.



Rol kurulumundan sonra gerekli görürse restart etmesi için ilk seçeneği seçiyorum ve “Install” seçeneğini seçiyorum.



İlk defa bir Domain kuracağım için “Add a new forest” seçeneğini işaretliyorum. Domain ismimizi veriyorum. Burası da iki kısımdan oluşur “domain adı” ve “uzantısı”. Ben localde çalışacağım için “efekanacar.local” ismini veriyorum.



“DNS Server” ve “Global Catalog” seçeneklerini seçiyorum. Bir şifre belirliyorum ve devam ediyorum.

The screenshot shows the 'Domain Controller Options' page of the Active Directory Domain Services Configuration Wizard. The left sidebar lists the steps: Deployment Configuration, Domain Controller Options (selected), DNS Options, Additional Options, Paths, Review Options, Prerequisites Check, Installation, and Results. The main area is titled 'Domain Controller Options' and includes the following sections:

- Deployment Configuration:** Select functional level of the new forest and root domain.
- Forest functional level:** Windows Server Technical Preview (dropdown).
- Domain functional level:** Windows Server Technical Preview (dropdown).
- Specify domain controller capabilities:**
 - ☒ Domain Name System (DNS) server
 - ☒ Global Catalog (GC)
 - ☐ Read only domain controller (RODC)
- Type the Directory Services Restore Mode (DSRM) password:**
 - Password: [masked]
 - Confirm password: [masked]

At the bottom, there are buttons for '< Previous', 'Next >', 'Install', and 'Cancel'. A link 'More about domain controller options' is also present.

Burada DNS sunucumuz kurulu olmadığı için bir hata mesajı alıyorum. Domain Controller kurulumu sırasında bir DNS kurulacağı için bu kısmı default olarak bırakıyorum.

The screenshot shows the 'DNS Options' page of the Active Directory Domain Services Configuration Wizard. The left sidebar lists the steps: Deployment Configuration, Domain Controller Options, DNS Options (selected), Additional Options, Paths, Review Options, Prerequisites Check, Installation, and Results. The main area is titled 'DNS Options' and includes the following sections:

- Deployment Configuration:** Specify DNS delegation options.
- Specify DNS delegation options:**
 - ☐ Create DNS delegation

A yellow warning box at the top states: 'A delegation for this DNS server cannot be created because the authoritative parent zone cannot be found o... Show more X'. At the bottom, there are buttons for '< Previous', 'Next >', 'Install', and 'Cancel'. A link 'More about DNS delegation' is also present.


“NetBIOS domain name” ekranını da default bir şekilde bırakıp devam ediyorum.

The screenshot shows the 'Additional Options' screen of the Active Directory Domain Services Configuration Wizard. The window title is 'Active Directory Domain Services Configuration Wizard'. On the left, a navigation pane lists the steps: Deployment Configuration, Domain Controller Options, DNS Options, Additional Options (selected), Paths, Review Options, Prerequisites Check, Installation, and Results. The main area is titled 'Additional Options' and contains the text 'Verify the NetBIOS name assigned to the domain and change it if necessary'. Below this, it says 'The NetBIOS domain name:' followed by a text box containing 'EFEKANACAR'. In the top right corner, it says 'TARGET SERVER WIN-0B46R3AN6U4'. At the bottom, there are four buttons: '< Previous', 'Next >', 'Install', and 'Cancel'. A link 'More about additional options' is also present.


Bu kısımda bahsettiği dizinlerin nerede oluşturulacağından bahsediyor. Devam ediyorum.

The screenshot shows the 'Paths' screen of the Active Directory Domain Services Configuration Wizard. The window title is 'Active Directory Domain Services Configuration Wizard'. On the left, a navigation pane lists the steps: Deployment Configuration, Domain Controller Options, DNS Options, Additional Options, Paths (selected), Review Options, Prerequisites Check, Installation, and Results. The main area is titled 'Paths' and contains the text 'Specify the location of the AD DS database, log files, and SYSVOL'. Below this, there are three rows of text boxes with folder paths and browse buttons (...): 'Database folder: C:\Windows\NTDS', 'Log files folder: C:\Windows\NTDS', and 'SYSVOL folder: C:\Windows\SYSVOL'. In the top right corner, it says 'TARGET SERVER WIN-0B46R3AN6U4'. At the bottom, there are four buttons: '< Previous', 'Next >', 'Install', and 'Cancel'. A link 'More about Active Directory paths' is also present.


Bu kısımda yaptığımız bütün işlemlerin scriptini gösteriyor. Devam ediyorum.




Bu kısımda indirme işlemi için hazır olup olmadığını test etmek için bir ön değerlendirme testi yapılıyor. Bu testte ilk başta "Administrator" kullanıcısına güçlü bir parola kurmam hakkında bir hata almıştım. Hatayı düzelttikten sonra "Rerun Prerequisites Check" seçeneğine tıklayarak testi tekrarlandırıyorum. Artık indirme işlemine hazırım.



İndirme işlemi tamamlandıktan sonra makine yeniden başlatılıyor.




Makine açıldığında "Active Directory Domain Services" kurulu olduğunu görüyorum.




DHCP KURULUMU


Active Directory kurulumuna çok benzeyen DHCP kurulumunda yine “Add rules and features” seçeneğine tıklayarak başlıyoruz, ana ekranda bu seçenek gözüküyor ise “Manage” menüsündende ulaşabilirsiniz.




“Server Roles” kısmına kadar devam ettikten sonra, bu kısımda Active Directory kurulumundan farklı olarak “DHCP Server” seçeneğini seçiyorum.



“Add Features” seçeneği ile devam ediyorum. Aynı şekilde ilerledikten sonra indirme işlemini başlatıyorum.



İndirme işlemi bittikten sonra ünlem işaretine tıklayarak “Complete DHCP Configuration” seçeneğini seçiyorum.



DHCP konfigürasyonunu bitirmek için devam ediyorum.

The screenshot shows the 'Description' step of the DHCP Post-Install configuration wizard. The window title is 'DHCP Post-Install configuration wizard'. On the left, there is a sidebar with three tabs: 'Description' (selected), 'Authorization', and 'Summary'. The main content area has the heading 'Description' and contains the following text: 'The following steps will be performed to complete the configuration of the DHCP Server on the target computer:'. Below this, it lists two steps: 'Create the following security groups for delegation of DHCP Server Administration.' followed by a bulleted list: '- DHCP Administrators' and '- DHCP Users'. The final step listed is 'Authorize DHCP server on target computer (if domain joined)'. At the bottom of the window, there are four buttons: '< Previous', 'Next >' (highlighted with a dashed border), 'Commit', and 'Cancel'.


Yetkili bir hesap ile giriş yapmamı istiyor, "Commit" diyerek devam ediyorum.

The screenshot shows the 'Authorization' step of the DHCP Post-Install configuration wizard. The window title is 'DHCP Post-Install configuration wizard'. On the left, there is a sidebar with three tabs: 'Description', 'Authorization' (selected), and 'Summary'. The main content area has the heading 'Authorization' and contains the text: 'Specify the credentials to be used to authorize this DHCP server in AD DS.'. Below this, there are three radio button options: 'Use the following user's credentials' (selected), 'Use alternate credentials', and 'Skip AD authorization'. Under the first option, there is a text box for 'User Name' containing the text 'EFEKANACAR\Efekan'. Under the second option, there is a text box for 'UserName' and a 'Specify...' button. At the bottom of the window, there are four buttons: '< Previous', 'Next >', 'Commit' (highlighted with a blue background), and 'Cancel'.


DHCP ile Scope Oluřturma

DHCP (Dynamic Host Configuration Protocol), ađdaki cihazlara otomatik olarak IP adresi, alt ađ maskesi, varsayılan ađ geđidi ve DNS sunucusu gibi ađ konfigürasyon bilgilerini sađlayan bir iletiřim protokolüdür. DHCP, ađ yöneticilerinin bu bilgileri manuel olarak her cihaza atamak yerine otomatik olarak dađıtarak ađ yönetimini kolaylařtırır.


Sađ üřtte yer alan “Tools” sekmesinden “DHCP” seğıeneđini seğıyorum.



Açılan sekmede makine altında yer alan IPv4 seğıeneđine sađ tıklayarak “New Scope” seğıeneđini seğıyorum.



Yeni oluşturacak olduğum scope'a bir isim veriyorum ve Description kısmına tanımlama ifadesini yani vereceğim IP aralığını yazıyorum.



New Scope Wizard

Scope Name
You have to provide an identifying scope name. You also have the option of providing a description.

Type a name and description for this scope. This information helps you quickly identify how the scope is to be used on your network.

Name:


Description:

< Back Next > Cancel

Vermek istediğim IP aralığını giriyorum.

192.168.10.1 – 192.168.10.99

Subnet Mask otomatik olarak girilecektir, devam ediyorum.



New Scope Wizard

IP Address Range
You define the scope address range by identifying a set of consecutive IP addresses.

Configuration settings for DHCP Server

Enter the range of addresses that the scope distributes.

Start IP address:

End IP address:

Configuration settings that propagate to DHCP Client

Length:

Subnet mask:

< Back Next > Cancel

Burada dahil olmasını istemediğim IP aralığı var ise belirtmemi istiyor. Ben buraya boş bırakarak devam edeceğim.

New Scope Wizard

Add Exclusions and Delay

Exclusions are addresses or a range of addresses that are not distributed by the server. A delay is the time duration by which the server will delay the transmission of a DHCP OFFER message.



Type the IP address range that you want to exclude. If you want to exclude a single address, type an address in Start IP address only.

Start IP address:

1 . . .

End IP address:

. . .

Add

Excluded address range:

Remove

Subnet delay in milli second:

0

< Back

Next >

Cancel

Burada IP atamasının ne kadar süreli olacağını ayarlıyabiliyorum, Default yani 8 gün olarak devam edeceğim.

New Scope Wizard

Lease Duration

The lease duration specifies how long a client can use an IP address from this scope.



Lease durations should typically be equal to the average time the computer is connected to the same physical network. For mobile networks that consist mainly of portable computers or dial-up clients, shorter lease durations can be useful. Likewise, for a stable network that consists mainly of desktop computers at fixed locations, longer lease durations are more appropriate.

Set the duration for scope leases when distributed by this server.

Limited to:

Days:

8

Hours:

0

Minutes:

0

< Back

Next >

Cancel

DHCP'yi yapılandırmak için ilk seçeneği seçerek devam ediyorum.

New Scope Wizard

Configure DHCP Options

You have to configure the most common DHCP options before clients can use the scope.

When clients obtain an address, they are given DHCP options such as the IP addresses of routers (default gateways), DNS servers, and WINS settings for that scope.

The settings you select here are for this scope and override settings configured in the Server Options folder for this server.

Do you want to configure the DHCP options for this scope now?

☒ Yes, I want to configure these options now

☐ No, I will configure these options later

< Back Next > Cancel

Burada kullanıcılar tarafından kullanılan router'a Ip adresi ekleyebiliyorum. Bu kısmı şimdilik geçeceğim, daha sonra ekleme işlemini gerçekleştirebilirim.

New Scope Wizard

Router (Default Gateway)

You can specify the routers, or default gateways, to be distributed by this scope.

To add an IP address for a router used by clients, enter the address below.

IP address:

< Back Next > Cancel

DNS servisin adını girmemi isteyen bu sayfada DNS server adı otomatik olarak çıktığı için devam ediyorum.

New Scope Wizard

Domain Name and DNS Servers

The Domain Name System (DNS) maps and translates domain names used by clients on your network.

You can specify the parent domain you want the client computers on your network to use for DNS name resolution.

Parent domain:

To configure scope clients to use DNS servers on your network, enter the IP addresses for those servers.

Server name:	IP address:	
<input type="text"/>	<input type="text" value="192.168.18.172"/>	<input type="button" value="Add"/>
<input type="button" value="Resolve"/>		<input type="button" value="Remove"/>
		<input type="button" value="Up"/>
		<input type="button" value="Down"/>

< Back Next > Cancel

Wins server kısmında bir şey yapmadan devam ediyorum.

New Scope Wizard

WINS Servers

Computers running Windows can use WINS servers to convert NetBIOS computer names to IP addresses.

Entering server IP addresses here enables Windows clients to query WINS before they use broadcasts to register and resolve NetBIOS names.

Server name:	IP address:	
<input type="text"/>	<input type="text" value="192.168.18.2"/>	<input type="button" value="Add"/>
<input type="button" value="Resolve"/>		<input type="button" value="Remove"/>
		<input type="button" value="Up"/>
		<input type="button" value="Down"/>

To change this behavior for Windows DHCP clients modify option 046, WINS/NBT Node Type, in Scope Options.

< Back Next > Cancel

Scope'u şu an aktifleştirmek için ilk seçeneği seçerek devam ediyorum.

New Scope Wizard

Activate Scope
Clients can obtain address leases only if a scope is activated.

Do you want to activate this scope now?

☒ Yes, I want to activate this scope now

☐ No, I will activate this scope later

< Back Next > Cancel

Başarılı bir şekilde Scope oluşturdum.

New Scope Wizard

Completing the New Scope Wizard
You have successfully completed the New Scope wizard.

To provide high availability for this scope, configure failover for the newly added scope by right clicking on the scope and clicking on configure failover.

To close this wizard, click Finish.

< Back Finish Cancel

Client Makineyi Active Directory Yapısına Almak

Öncelikle Aynı ortam üzerine yeni bir Windows makine oluşturun. Makinemi Active Directory gibi VLAN ağına alıyorum. Aynı ağda olduklarını kontrol etmek için Active Directory Sunucuma ping atıyorum.


```
C:\Windows\system32>ping 192.168.18.172

Pinging 192.168.18.172 with 32 bytes of data:
Reply from 192.168.18.172: bytes=32 time<1ms TTL=128
Reply from 192.168.18.172: bytes=32 time<1ms TTL=128
Reply from 192.168.18.172: bytes=32 time<1ms TTL=128
Reply from 192.168.18.172: bytes=32 time<1ms TTL=128


Ping statistics for 192.168.18.172:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\Windows\system32>
```


Bilgisayar'a sağ tıklayarak "Properties" seçeneğini seçiyorum.




Burada "Advanced system settings" seçeneğini seçiyorum.




Computer Name bölümünden etki alanını ve çalışma alanını değiştirmek için kullanılan “Change” kısmına tıklıyorum.




Bu kısımda member of > Domain 'i seçiyorum. Buraya Active Directory domain ismimi yazıyorum.



Bu kısımda hata yaşadığım için makineleri tekrar kurdum kaldığım yerden devam ediyorum. Active Directory Makinemde kullanıcı adını ve şifresini girdikten sonra domain aktif hale geliyor.




Active Directory makinemde “Tools” kısmında “Active Directory Users and Computers” seçeneğine tıklıyorum. Computers altında Domain’e ekli olan bilgisayarları görebilirsiniz.



Organizational Unit Oluřturma

Domain adına (EFEKANACAR.COM) sađ tıklayarak New > Organizational Unit ifadesini seğıyorum. Adını “GUVENLIK YONETIMI” olarak ayarlıyorum ve OK ile kaydediyorum.



New Object - Organizational Unit

Create in: EFEKANACAR.COM/


Name: GUVENLIK YONETIMI

☒ Protect container from accidental deletion

OK Cancel Help

Kullanıcı Oluřturma

Oluřturmuş olduđu Organizational Unit’in ierisine girerek sađ tıklıyorum, New > User seğıeneđini seğıyorum. Burada oluřturmak istediđim kullanıcıya isim ve logon ismi veriyorum.



New Object - User

Create in: EFEKANACAR.COM/GUVENLIK YONETIMI

First name: ali Initials:

Last name: demir

Full name: ali demir

User logon name: alidemir @EFEKANACAR.COM

User logon name (pre-Windows 2000): EFEKANACAR\alidemir

< Back Next > Cancel

Daha sonra kullanıcıya bir şifre veriyorum.

Active Directory Users and Computers

New Object - User

Create in: EFEKANACAR.COM/GUVENLIK YONETIMI

Password:

Confirm password:

☐ User must change password at next logon

☐ User cannot change password

☐ Password never expires

☐ Account is disabled

< Back Next > Cancel

Finish diyerek işlemi tamamlıyorum.

New Object - User

Create in: EFEKANACAR.COM/GUVENLIK YONETIMI

When you click Finish, the following object will be created:


Full name: ali demir

User logon name: alidemir@EFEKANACAR.COM

< Back Finish Cancel

Grup oluřturma

Grup oluřturmak iin Organizational Unit'in ierisine girerek saė tıklıyorum, New > Group seeneėini seiyorum. Grup ismini yazdıktan sonra OK ile kaydediyorum.



New Object - Group

Create in: EFEKANACAR.COM/GUVENLIK YONETIMI

Group name:
FINANS GRUBU

Group name (pre-Windows 2000):
FINANS GRUBU


Group scope:
☐ Domain local
☒ Global
☐ Universal

Group type:
☒ Security
☐ Distribution

OK Cancel

Gruba Kullanıcı Ekleme

Gruba eklemek istediėim kullanıcıya saė tıklayarak Properties seeneėini seiyorum. Burada kullanıcı hakkındaki btn ayarları yapabilirsiniz. Member of kısmından "Add.." seeneėini seiyorum.



ali demir Properties

Remote control Remote Desktop Services Profile COM+
General Address Account Profile Telephones Organization
Member Of Dial-in Environment Sessions

Member of:

Name	Active Directory Domain Services Folder
Domain Users	EFEKANACAR.COM/Users

Add... Remove

Primary group: Domain Users

Set Primary Group

There is no need to change Primary group unless you have Macintosh clients or POSIX-compliant applications.

OK Cancel Apply Help

Buradan grupları görüntülemek için “Advanced...” seçeneğini seçiyorum.

Select Groups

Select this object type:
Groups or Built-in security principals

From this location:
EFEKANACAR.COM

Enter the object names to select (examples):

Advanced...

OK Cancel

Find Now diyorum ve eklemek istediğim gruba çift tıklıyorum.

Select Groups

Select this object type:
Groups or Built-in security principals

From this location:
EFEKANACAR.COM

Common Queries

Name: Starts with

Description: Starts with

☐ Disabled accounts

☐ Non expiring password

Days since last logon:


Find Now

Stop


Search results:

Name	Description	In Folder
Domain Contr...	All domain contr...	EFEKANACAR....
Domain Guests	All domain guests	EFEKANACAR....
Domain Users	All domain users	EFEKANACAR....
Enterprise Ad...	Designated admi...	EFEKANACAR....
Enterprise Ke...	Members of this ...	EFEKANACAR....
Enterprise Re...	Members of this ...	EFEKANACAR....
Event Log Re...		EFEKANACAR....
FINANS GRUBU		EFEKANACAR....
Group Policy ...	Members in this ...	EFEKANACAR....
Guests		EFEKANACAR....


Apply diyerek kaydediyorum ve OK ile çıkıyorum.



İsimleri "FINANS GRUBU", "İNSAN KAYNAKLARI" VE "İT GRUBU" olan 3 adet grup oluşturdum, bu 3 gruba 5'er adet kullanıcı ekledim.



Bu kullanıcılardan herhangi birine Domaine bağı Client makineyi kullanarak girebilirim. Girmek için logon adı ve vermiş olduğum şifreyi girmem yeterlidir.



Efekan ACAR