



**TECNOLÓGICO  
NACIONAL DE MÉXICO**



Ingeniería en Sistemas Computacionales

**Conmutación y enrutamiento de redes 14:00 – 15:00**

**Unidad 1**

**Evidencia 5: Práctica de sumarización**


Docente: M.C. Angélica Salazar Ramírez

Alumno: Escobar Sánchez José Alejandro


Control: 19170573

Correo: [19170573@culiacan.tecnm.mx](mailto:19170573@culiacan.tecnm.mx)

## Captura de topología de red



## Captura de la configuración de enrutamiento del router TRES



The screenshot shows a window titled 'TRES' with a blue header bar. Below the header are four tabs: 'Physical', 'Config', 'CLI' (selected), and 'Attributes'. The main content area is titled 'IOS Command Line Interface' and displays the output of the 'show ip route' command. The output includes status messages for interfaces Serial0/1 and Serial0/2, a warning about authorized personnel, and a detailed list of routes and their codes. At the bottom of the window, there are 'Copy' and 'Paste' buttons, and a 'Top' button with a checkbox.

```
TRES>ena
Password:
TRES#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

S    200.35.65.0/24 is directly connected, Serial0/0
     200.35.67.0/25 is subnetted, 1 subnets
S      200.35.67.0 is directly connected, Serial0/1
     200.35.68.0/25 is subnetted, 1 subnets
S      200.35.68.128 is directly connected, Serial0/2
     200.35.71.0/30 is subnetted, 3 subnets
C      200.35.71.0 is directly connected, Serial0/1
C      200.35.71.4 is directly connected, Serial0/2
C      200.35.71.8 is directly connected, Serial0/0

TRES#
```

☐ Top

## Script de configuración y ejercicio de sumarización de rutas

## EJERCICIO DE SUMARIZACION DE RUTAS

Router UNO

200.35.65.0/25

200.35.65.128/25

200.35.65.00000000

200.35.65.10000000

Nueva mascara de red

11111111.11111111.11111111.00000000

/24

Super red 1:

200.35.65.0/24

Router DOS

200.35.67.0/26

200.35.67.64/26

200.35.67.00000000

200.35.67.01000000

Nueva mascara de red

11111111.11111111.11111111.10000000

/25

Super red 2:

200.35.67.0/25

Router CUATRO

200.35.68.128/26

200.35.68.192/26

200.35.68.10000000

200.35.68.11000000

Nueva mascara de red

11111111.11111111.11111111.10000000

/25

Super red 3:

200.35.68.128/25

## SCRIPT DE CONFIGURACION

# config router UNO

enable

configure terminal

hostname UNO

no ip domain-lookup

enable secret cisco

```
line console 0
login
line vty 0 15
password cisco
login
banner motd #!!! WARNING: Authorized personnel only. !!!#
interface Se0/0
description Enlace al router TRES
ip address 200.35.71.9 255.255.255.252
clock rate 128000
no shut
interface L01
ip address 200.35.65.1 255.255.255.128
interface L02
ip address 200.35.65.129 255.255.255.128
exit
ip route 0.0.0.0 0.0.0.0 Se0/0
```


```
# config router DOS
enable
configure terminal
hostname DOS
no ip domain-lookup
enable secret cisco
line console 0
login
line vty 0 15
password cisco
login
banner motd #!!! WARNING: Authorized personnel only. !!!#
interface Se0/0
description Enlace al router TRES
ip address 200.35.71.2 255.255.255.252
clock rate 128000
no shut
interface L01
ip address 200.35.67.1 255.255.255.192
interface L02
ip address 200.35.67.65 255.255.255.192
exit
ip route 0.0.0.0 0.0.0.0 Se0/0
```

```
# config router CUATRO
enable
configure terminal
hostname CUATRO
no ip domain-lookup
enable secret cisco
line console 0
login
line vty 0 15
```

```
password cisco
login
banner motd #!!! WARNING: Authorized personnel only. !!!#
interface Se0/0
description Enlace al router TRES
ip address 200.35.71.6 255.255.255.252
no shut
interface L01
ip address 200.35.68.129 255.255.255.192
interface L02
ip address 200.35.68.193 255.255.255.192
exit
ip route 0.0.0.0 0.0.0.0 Se0/0

# config router TRES
enable
configure terminal
hostname TRES
no ip domain-lookup
enable secret cisco
line console 0
login
line vty 0 15
password cisco
login
banner motd #!!! WARNING: Authorized personnel only. !!!#
interface Se0/0
description Enlace al router UNO
ip address 200.35.71.10 255.255.255.252
no shut
interface Se0/1
description Enlace al router DOS
ip address 200.35.71.1 255.255.255.252
no shut
interface Se0/2
description Enlace al router CUATRO
ip address 200.35.71.5 255.255.255.252
no shut
exit
ip route 200.35.65.0 255.255.255.0 Se0/0
ip route 200.35.67.0 255.255.255.128 Se0/1
ip route 200.35.68.128 255.255.255.128 Se0/2
```

## Captura de la práctica en laboratorio



```

a - application route
+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

192.168.1.0/30 is subnetted, 1 subnets
S   192.168.1.0 is directly connected, Serial0/1/0
192.168.30.0/24 is variably subnetted, 2 subnets, 2 masks
C   192.168.30.0/30 is directly connected, GigabitEthernet0/0
L   192.168.30.2/32 is directly connected, GigabitEthernet0/0
S   200.35.65.0/24 is directly connected, Serial0/1/1
S   200.35.67.0/25 is subnetted, 1 subnets
    200.35.67.0 is directly connected, Serial0/1/0
C   200.35.71.0/24 is variably subnetted, 4 subnets, 2 masks
L   200.35.71.0/30 is directly connected, Serial0/1/0
C   200.35.71.1/32 is directly connected, Serial0/1/0
C   200.35.71.8/30 is directly connected, Serial0/1/1
L   200.35.71.10/32 is directly connected, Serial0/1/1
Router(config)#
Router(config)#
*Sep 29 19:57:16.579: %LINK-3-UPDOWN: Interface Serial0/1/0, changed state to do
wn
*Sep 29 19:57:17.579: %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/
0, changed state to down

```