



Cyber Defence Operation Centre

NEC Africa

Installing ArcSight ESM 6.11 on CentOS 7

Document Information

Author:	Armand Kruger
Title:	Cyber Defence Analyst
Version:	1.0
Department:	Cyber Defence Operations Centre

Table of Content

Chapter 1

ArcSight ESM 6.11 Prerequisites	1
---------------------------------------	---

Chapter 2

Installing ArcSight ESM 6.11	3
------------------------------------	---

Chapter 3

Preparing The System	3
----------------------------	---

ArcSight ESM 6.11 Prerequisites

Note: Please make sure that the base OS (CentOS 7) is already preconfigured with the below settings before attempting to follow the below ArcSight ESM 6.11 Installation Guide!

Base OS Pre-Configured Settings:

- Valid Hostname (Not Localhost)
- Static IP
- Subnet Mask
- DNS Name Server
- Default Gateway
- Stable Internet Connection

Refer to – “Installing & Maintaining an CentOS 7 Minimal Server Environment Fact Sheet” for guidelines regarding the above pre-configured settings

CentOS 7 OS Packages to Install after CentOS 7 Installation:

- Java
- Net-Tools
- Tcpdump

Ports to be Allowed Through the Firewall

- TCP 8443
- TCP 9000
- UDP 694
- TCP 7789
- UDP 22

Preparing the System for ArcSight ESM 6.11

Log in a Root User

```
Username: root
Password: *****
```

Create a New Folder in the Following Directory

```
mkdir /opt/arcsight
```

Give the Directory Read & Write Permissions

```
chmod 755 /opt/arcsight
```

Untar the ArcSight Installer File

```
tar xvf <ESMInstallerName>.tar
```

Note: Replace <ESMInstaller> with your ESM Installer File

After the file is untarred, it creates a script called “**prepare_system.sh**” in the “**Tools**” Sub-Directory. Run the “**prepare_system.sh**” & change ownership off all the files and folders that were extracted from the tar file to be owned by the arcsight user account

Navigate to the Sub-Directory “Tools”

```
cd /tools
```

Run the “prepare_system.sh script

```
./prepare_system.sh
```

Change Ownership of all Files & Directories to user arcsight

```
chown -R arcsight MainDirectory/
```

Reboot the System

```
reboot
```

After Bootup & Logon, Type the following Command

```
ulimit -a
```

Verify the Following Values

```
open files 65536
```

```
max user processes 10240
```

Install the Time Package

```
rpm -Uvh tzdata-2017g-1.e17.noarch.rpm
```

Set the Correct Time-Zone

```
timectl set-timezone Africa/Johannesburg
```

Restart the Logind Service

```
systemctl restart system-logind.service
```

Reboot the System

```
reboot
```

Login as the arcsight user

```
Username: arcsight
```

```
Password: *****
```

Note: Make sure that you have the appropriate Read & Write Permissions to the /opt/arcsight folder & the folder that contains the license file before starting the ESMSuite Installer!

Starting the ArcSight ESM 6.11 Installer

Make the File Executable

```
chmod +x ArcSightESMSuite.bin
```

Run the Installation File (.bin)

```
./ArcSightESMSuite.bin -i console
```

Type the Following Command after the Suite Installer Stops (To continue with the ESM Installer)

```
/opt/arcsight/manager/bin/arcsight firstbootsetup -boxster -soft -i console
```

Follow the Installation Steps and Make sure that you specify the following information during the Installation Procedure

- Accept the License Agreement
- Installation Directory: /opt/arcsight
- Location of the License File (Full Path Included License File)
- CORR Password
- System Storage Space: (Depends on Available Storage)
- Event Storage Space: (Depends on Available Storage)
- Retention Period: 14 Days
- Email Notifications
- Product Mode: Default Mode
- Event Broker: No
- ArcSight Investigate: No
- Extra Packages: None (Continue)
- Review Summary & Continue

Enter the Below Command immediately after the ESM Configuration Has Completed

```
/opt/arcsight/manager/bin/setup_services.sh
```

The ESM Installation should now be successfully completed, you should now be able to login from The Console (Windows-based or Linux-based).

Note: If the ESM Installation was unsuccessful, Uninstall the ESM Following the Below Steps and Commands and reinstall the ESM. Before Re-Installation, make sure that you have met all required prerequisites & system prepare requirements.

Uninstalling The ESM

Login as Root

```
Username: Root
```

```
Password: *****
```

Run the Following Command

```
/opt/arcsight/manager/bin/remove_services.sh
```

Reboot

```
reboot
```

Login as user arcsight

```
Username: arcsight
```

```
Password: *****
```

Verify if any ArcSight Processes are Running

```
ps -elf | grep /opt/arcsight
```

Shut Down Remaining ArcSight Processes (If there is Present)

```
kill -9 <process_id_number>
```

Navigate to the Following Directory

```
cd /opt/arcsight/suite/UninstallerData
```

Run the Following Script

```
./Uninstall_ArcSight_ESM_Suite_6.11.0
```

Note: After the script has completed, navigate to /tmp & /opt and make sure that there is no ArcSight related files present. If there is any ArcSight related files present, deleted all of them and reboot the system.