

UF_CGM_export_error_f_t [\(view source\)](#)

Defined in: `uf_cgm_types.h`

Overview

UF_CGM_export_error_f_t

An `export_error` callback of type `UF_CGM_export_error_f_t` is invoked if some error occurs while generating the CGM file. In this callback, the application can restore the state of application objects/geometry and can free resources allocated for the operation.

The `export_error` callback is invoked only if the `pre_export` callback returned `TRUE` for the same export operation.

If the `export_error` callback is invoked, then the `post_export` callback is not invoked for the same export operation.

```
void UF_CGM_export_error_f_t
(
    UF_CGM_export_reason_t reason,
    UF_CGM_export_source_t source,
    tag_t drawing_sheet,
    void * appl_data
)
```

UF_CGM_export_reason_t	reason	Input	The reason that CGM export is in progress
UF_CGM_export_source_t	source	Input	The source for the CGM export
tag_t	drawing_sheet	Input	The tag of the drawing sheet being exported, or <code>NULL_TAG</code> if the export is the current display.
<code>void *</code>	appl_data	Input	The application data passed to the registration of the function. This is always <code>NULL</code> .

UF_CGM_post_export_f_t [\(view source\)](#)

Defined in: `uf_cgm_types.h`

Overview

UF_CGM_post_export_f_t

A `post_export` callback of type `UF_CGM_post_export_f_t` is invoked after geometry is successfully recorded in a CGM file. In this callback, the application can restore the state of application objects/geometry and can free resources allocated for the operation.

The `post_export` callback is invoked only if the `pre_export` callback returned `TRUE` for the same export operation.

The `post_export` callback is not invoked if an error occurs during the export operation. The `export_error` callback is invoked instead.

```
void UF_CGM_post_export_f_t
(
    UF_CGM_export_reason_t reason,
    UF_CGM_export_source_t source,
    tag_t drawing_sheet,
    void * appl_data
)
```

UF_CGM_export_reason_t	reason	Input	The reason that CGM export is in progress
UF_CGM_export_source_t	source	Input	The source for the CGM export
tag_t	drawing_sheet	Input	The tag of the drawing sheet being exported, or NULL_TAG if the export is the current display.
void *	appl_data	Input	The application data passed to the registration of the function. This is always NULL.

UF_CGM_pre_export_f_t (view source)

Defined in: uf_cgm_types.h

Overview

```
UF_CGM_pre_export_f_t
```

A pre_export callback of type UF_CGM_pre_export_f_t is invoked before geometry is recorded in a CGM file during a CGM export operation. In this function, the application might enable or disable display of application objects, as appropriate.

If the application decides to take some action in response to the export operation, then the application can return a (void) pointer to arbitrary application data in the appl_data parameter. This pointer will later be passed as the appl_data parameter to the post_export and export_error callback functions.

The application returns TRUE from the pre_export callback if the operation is of interest, and FALSE otherwise. The post_export and export_error callback functions are not invoked unless the pre_export callback returns TRUE.

```
logical UF_CGM_pre_export_f_t
(
    UF_CGM_export_reason_t reason,
    UF_CGM_export_source_t source,
    tag_t drawing_sheet,
    void ** appl_data
)
```

UF_CGM_export_reason_t	reason	Input	The reason that CGM export is in progress
UF_CGM_export_source_t	source	Input	The source for the CGM export
tag_t	drawing_sheet	Input	The tag of the drawing sheet being exported, or NULL_TAG if the export is the current display.

void * *	appl_data	Input	The application data passed to the registration of the function.
----------	------------------	-------	--