

# tsm licenses

You can use the `tsm licenses` commands to manage server license tasks like activating or deactivating a [Tableau Server] product key on- or off-line, and getting associated files for offline activation or deactivation.

- [tsm licenses activate](#){MCXref .xref}
- [tsm licenses deactivate](#){MCXref .xref}
- [tsm licenses get-offline-activation-file](#){MCXref .xref}
- [tsm licenses get-offline-deactivation-file](#){MCXref .xref}
- [tsm licenses list](#){MCXref .xref}
- [tsm licenses refresh](#){MCXref .xref}

## tsm licenses activate

---

Activates a [Tableau Server] product key.

If the computer where you are running Tableau Server has been configured to connect to the internet through a forward proxy, follow the procedure in the topic, [Configure Product Key Operations with Forward Proxy](#), before running this command.

### Synopsis

```
tsm licenses activate --license-key <product-key> [global options]
```

### Options

-f, --license-file <file.tlf>

Required if doing offline activation.

Specifies the license file (<file>.tlf) used for offline activation.

-k, --license-key <product-key>

Required if activating a valid product key.

Specifies the product key to use for online activation.

-t, --trial

Required if activating a trial license.

Activate a trial license.

## tsm licenses deactivate

---

Deactivates a [Tableau Server] product key either online or offline.

If the computer where you are running Tableau Server has been configured to connect to the internet through a forward proxy, follow the procedure in the topic, [Configure Product Key Operations with Forward Proxy](#), before running this command.

### Synopsis

```
tsm licenses deactivate --license-key <product-key> [global options]
```

### Options

-f, --license-file <return\_file.tlr>

Required if doing offline deactivation.

Specifies the license file (<file>.tlf) used for offline deactivation.

-k, --license-key <product-key>

Required if deactivating a product key.

Specifies the product key to use for online deactivation.

### **tsm licenses get-offline-activation-file**

---

Generate an offline activate file to use for activating [Tableau Server] offline. To learn more, see [Activate Tableau Server Offline - Adding a License](#).

#### **Synopsis**

```
tsm licenses get-offline-activation-file --license-key <product-key> --output-dir  
<path> [global options]
```

#### **Options**

-k, --license-key <product-key>

Required.

Specifies the product key to use for offline activation.

-o, --output-dir <path>

Required.

The location where the offline activation file should be saved. This location must exist.

### **tsm licenses get-offline-deactivation-file**

---

Generate an offline deactivation file to use for deactivating [Tableau Server] offline. To learn more, see [Deactivate Tableau Server Offline](#).

#### **Synopsis**

```
tsm licenses get-offline-deactivation-file --license-key <product-key> --output-dir  
<path> [global options]
```

#### **Options**

-k, --license-key <product-key>

Required.

Specifies the product key to use for offline deactivation.

-o, --output-dir <path>

Required.

The existing location where the offline deactivation file should be saved.

### **tsm licenses list**

---

Lists licenses that are activated on the Tableau Server deployment.

For example, a server with five Creator licenses, five Explorer licenses, 100 Viewer licenses, and a Data Management Add-on would provide command output similar to the following:

```
C:\Windows\system32>tsm licenses list
Number of product keys: 4
The following license keys will expire soon. Access renewal resources including information on how to renew your software or change your billing preferences here https://www.tableau.com/support/renew
KEY          TYPE      CREATOR  EXPLORER  VIEWER    DATA MANAGEMENT ADD-ON  GUEST ACCESS  LIC EXP  MAINT EXP  UPDATABLE  LBLM  SERVER MANAGEMENT ADD-ON
TS9D-86E2-BF8E-89EA-36EE Term      0         0        100      false      false    11/30/20  N/A       false     false   false
TS9R-86E2-BF8E-89EA-36EE Term      0         0         0        true       false    11/30/20  N/A       false     false   false
TS4D-86E2-BF8E-89EA-36EE Term      0         5         0        false      false    11/30/20  N/A       false     false   false
TSQJ-86E2-BF8E-89EA-36EE Term      5         0         0        false      false    11/30/20  N/A       false     false   false
```

The following fields are returned:

- **KEY:** A globally unique 16-character string that identifies the license.
- **TYPE:** Describes the type of license
  - Term: Term licenses map to a subscription schedule and must be renewed. The expiration date is listed under the LIC EXP field.
  - Perpetual: Perpetual licenses are purchased once and do not need to be renewed but must be refreshed to update the MAINT EXP or maintenance expiration date.
  - Cores: Core licenses are licenses that map to the number of cores on the computers running specific Tableau Server services. Core licensing allows for a guest user access to views on the server or embedded on other web servers. Core licenses also allow for unlimited Explorer and Viewer users.
- **CREATOR:** The number of Creator licenses issued to the Tableau Server deployment.
- **EXPLORER:** The number of Explorer licenses issued to the Tableau Server deployment.
- **VIEWER:** The number of Viewer licenses issued to the Tableau Server deployment.
- **DATA MANAGEMENT ADD-ON:** Tableau Server is licensed for the Data Management Add-on ( True / False ). See [About Data Management Add-on](#)
- **GUEST ACCESS:** Tableau Server is licensed for a Guest User. See [Guest User](#) The ability to leverage a Guest User requires Core licensing. See TYPE field.
- **LIC EXP:** The date that the license expires and Tableau Server will stop working. Term licenses expire. See TYPE field. Visit the Tableau [Customer Portal](#)[\(Link opens in a new window\)](#) to refresh licenses.
- **MAINT EXP:** Applies only to legacy perpetual licenses (TYPE = Perpetual). For Term licenses, this field will output, N/A . MAINT EXP displays the date that the maintenance contract for the Tableau Server deployment expires. To update the license maintenance key see [Refresh Expiration Date for the Product Key](#). Visit the Tableau [Customer Portal](#)[\(Link opens in a new window\)](#) to view maintenance purchase history and to purchase additional maintenance.
- **UPDATABLE:** Specifies whether the license is an updatable subscription license ( True / False ).
- **LBLM:** Specifies if login-based license management (LBLM) is enabled for the Tableau Server deployment ( True / False ). When enabled, LBLM allows users to log into Tableau Server to license their instance of Tableau Desktop or Prep, rather than entering a product key. For more information about LBLM, see [Login-based License Management](#)
- **SERVER MANAGEMENT ADD-ON:** Tableau Server is licensed for the Server Management Add-on ( True / False ). For more information about the Server Management Add-on, see [About Tableau Server Management Add-on](#)

## Synopsis

```
tsm licenses list [global options]
```

## tsm licenses refresh

Update the maintenance expiration date of all product keys on Tableau Server.

If the computer where you are running Tableau Server has been configured to connect to the internet through a forward proxy, follow the procedure in the topic, [Configure Product Key Operations with Forward Proxy](#), before running this command.

## Synopsis

```
tsm licenses refresh [global options]
```

## Global options

---

-h, --help

Optional.

Show the command help.

-p, --password <password>

Required, along with `-u` or `--username` if no session is active.

Specify the password for the user specified in `-u` or `--username`.

If the password includes spaces or special characters, enclose it in quotes:

```
--password "my password"
```

-s, --server https://<hostname>:8850

Optional.

Use the specified address for Tableau Services Manager. The URL must start with `https`, include port 8850, and use the server name not the IP address. For example `https://<tsm_hostname>:8850`. If no server is specified, `https://<localhost | dnsname>:8850` is assumed.

--trust-admin-controller-cert

Optional.

Use this flag to trust the self-signed certificate on the TSM controller. For more information about certificate trust and CLI connections, see [Connecting TSM clients](#).

-u, --username <user>

Required if no session is active, along with `-p` or `--password`.

Specify a user account. If you do not include this option, the command is run using credentials you signed in with.