


ⓘ We're no longer updating this content regularly. Check the [Microsoft Product Lifecycle](#) for information about how this product, service, technology, or API is supported.

Recommended Version

✕

-  Filter by title
- > Dsget

> Dsmgmt

> Dsmod

Dsmove

> Dsquery

Dsrn

Echo

Edit

Endlocal

Erase

> Esentutl

Eventcreate

Eventquery.vbs

Eventtriggers

Evtncmd

Exit

Expand

Extract

Fc

> Filescrn

Find

Findstr

Finger

Flattemp

Fondue

For

Forfiles

Format

Freedisk

> Fsutil

> Ftp

Ftype

Fveupdate

Getmac

Gettype

Goto

Gpfixup

Gpresult

Gpupdate

Graftabl

Hashgen

⋯ / [Management and Tools](#) / [Command-Line Reference](#) / [Dsdbutil](#) / ⊕ ⋮

snapshot

Article • 08/31/2016

In this article

- [Syntax](#)
- [Parameters](#)
- [Remarks](#)
- [Examples](#)
- [Additional references](#)

Applies To: Windows Server 2008, Windows Server 2012, Windows 8

Manages snapshots of the volumes that contain the Active Directory database and log files, which you can view on a domain controller without starting in Directory Services Restore Mode (DSRM). You can also run the snapshot subcommand on an Active Directory Lightweight Directory Services (AD LDS) server.


In the command-line tool Ntdsutil.exe, you can use the snapshot subcommand to manage the snapshots, but you must use Dsamain.exe to expose the snapshot as a Lightweight Directory Access Protocol (LDAP) server. For more information about using Dsamain, see [Dsamain](#).

This is a subcommand of Ntdsutil and Dsdbutil. Ntdsutil and Dsdbutil are command-line tools that are built into Windows Server 2008 and Windows Server 2008 R2. Ntdsutil is available if you have the Active Directory Domain Services (AD DS) or AD LDS server role installed. Dsdbutil is available if you have the AD LDS server role installed. These tools are also available if you install the Active Directory Domain Services Tools that are part of the Remote Server Administration Tools (RSAT). For more information, see [How to Administer Microsoft Windows Client and Server Computers Locally and Remotely](#) [↗] (<https://go.microsoft.com/fwlink/?LinkID=177813> [↗]).

To use either of these tools, you must run them from an elevated command prompt. To open an elevated command prompt, click **Start**, right-click **Command Prompt**, and then click **Run as administrator**.

For examples of how to use this command, see [Examples](#).

Syntax

 Copy

```
activate instance %s [create] [delete %s] [unmount %s] [list all] [list mounted
```

Parameters

 Expand table

Parameter	Description
-----------	-------------

activate instance %s	Sets an active instance for the command. You can either specify "ntds" to set AD DS as the active instance or you can specify the name of an AD LDS instance.
create	Creates a snapshot.
delete %s	Deletes a snapshot with globally unique identifier (GUID) %s. Use * to delete all snapshots.
list all	Lists all mounted snapshots. You can run this command to obtain an index number for a mounted snapshot. You can then use the index number, instead of a GUID, to mount or unmount a snapshot.
list mounted	Lists mounted snapshots. You can run this command to obtain an index number for a mounted snapshot. You can then use the index number instead of a GUID to mount or unmount a snapshot.
mount %s	Mounts a snapshot with GUID %s. You can refer to an index number of any mounted snapshot instead of its GUID.
unmount %s	Unmounts a snapshot with GUID %s. Use * to unmount all mounted snapshots.
quit	Returns to the prior menu.
Help	Displays Help for this command.
?	Displays Help for this command.

Remarks

- Before you can run the **snapshot** subcommand, you must run the **activate instance** subcommand in Ntdsutil to set an active instance. For examples of how to set an active instance, see [Examples](#).
- You are not required to run the **snapshot** subcommand to use Dsmain.exe. Instead, you can use a backup of the AD DS or AD LDS database or another domain controller or AD LDS server. Running the **snapshot** subcommand simply provides convenient data input for Dsmain.exe.
- You should protect snapshots in a manner that is similar to how you protect domain controller backups. For example, use encryption or other data security precautions with AD DS snapshots to help mitigate the chance of unauthorized access to them.
- When you use Dsmain.exe to expose the data that is contained in a snapshot:
 - All permissions that apply to the data in the snapshot are enforced.
 - By default, only members of the Domain Admins group and the Enterprise Admins group are allowed to view a snapshot because it can contain sensitive AD DS data.
- Ntdsutil does not correctly handle special characters, such as the apostrophe character ('), that you can enter at the **ntdsutil:** prompt at the command line. In some situations, there may be an alternative workaround. For more information, see [local roles](#).

Examples

The following example sets NTDS as the active instance:

Copy

```
ntdsutil: activate instance ntds
```

The following example is another way to set NTDS as the active instance:

Copy

```
ntdsutil: ac in ntds
```

The following example mounts a snapshot that has the GUID 8ec8ff74-c0d7-435a-b6b1-54ef185926be:

```
snapshot: mount {8ec8ff74-c0d7-435a-b6b1-54ef185926be}
```

 Copy

The following example unmounts the same snapshot:

```
snapshot: unmount {8ec8ff74-c0d7-435a-b6b1-54ef185926be}
```

 Copy

The following example lists the mounted snapshots:

```
snapshot: list mounted
```

 Copy

Additional references

[Command-Line Syntax Key](#)

[Dsamain](#)

[Dsdbutil](#)

[Ntdsutil](#)

[authoritative restore](#)

[configurable settings](#)

[DS behavior](#)

[files](#)

[group membership evaluation](#)

[ifm](#)

[LDAP policies](#)

[local roles](#)

[metadata cleanup](#)

[partition management](#)

[roles](#)

[security account management](#)

[semantic database analysis](#)

[set DSRM password](#)

