



---

≡ Messaging platforms > **Signal**

---

## Messaging platforms

# Signal

Status: external CLI integration. Gateway talks to `signal-cli` over HTTP JSON-RPC + SSE.

## Prerequisites

OpenClaw installed on your server (Linux flow below tested on Ubuntu 24).

`signal-cli` available on the host where the gateway runs.

A phone number that can receive one verification SMS (for SMS registration path).

Browser access for Signal captcha ( [signalcaptchas.org](https://signalcaptcha.org) ) during registration.

## Quick setup (beginner)

1. Use a **separate Signal number** for the bot (recommended).
2. Install `signal-cli` (Java required if you use the JVM build).
3. Choose one setup path:

**Path A (QR link):** `signal-cli link -n "OpenClaw"` and scan with Signal.

**Path B (SMS register):** register a dedicated number with captcha + SMS verification.

4. Configure OpenClaw and restart the gateway.
5. Send a first DM and approve pairing ( `openclaw pairing approve signal <CODE>`  ).

Minimal config:

```
{
  channels: {
    signal: {
      enabled: true,
      account: "+15551234567",
      cliPath: "signal-cli",
      dmPolicy: "pairing",
      allowFrom: ["+15557654321"],
    },
  },
}
```

Field reference:

Field	Description
account	Bot phone number in E.164 format ( +15551234567 )
cliPath	Path to <code>signal-cli</code> ( <code>signal-cli</code> if on <code>PATH</code> )
dmPolicy	DM access policy ( <code>pairing</code> recommended)
allowFrom	Phone numbers or <code>uuid:&lt;id&gt;</code> values allowed to DM

## What it is

- Signal channel via `signal-cli` (not embedded `libsignal`).
- Deterministic routing: replies always go back to Signal.
- DMs share the agent’s main session; groups are isolated ( `agent: <agentId>:signal:group:<groupId>`  ).

## Config writes



By default, Signal is allowed to write config updates triggered by `/config set|unset` (requires `commands.config: true`).

Disable with:

```
{
  channels: { signal: { configWrites: false } },
}
```

## The number model (important)

The gateway connects to a **Signal device** (the `signal-cli` account).

If you run the bot on **your personal Signal account**, it will ignore your own messages (loop protection).

For “I text the bot and it replies,” use a **separate bot number**.

## Setup path A: link existing Signal account (QR)

1. Install `signal-cli` (JVM or native build).
2. Link a bot account:

```
signal-cli link -n "OpenClaw" then scan the QR in Signal.
```

3. Configure Signal and start the gateway.

Example:



```
channels: {
  signal: {
    enabled: true,
    account: "+15551234567",
    cliPath: "signal-cli",
    dmPolicy: "pairing",
    allowFrom: ["+15557654321"],
  },
},
}
```

Multi-account support: use `channels.signal.accounts` with per-account config and optional `name`. See [Signal CLI](#) for the shared pattern.

## Setup path B: register dedicated bot number (SMS, Linux)

Use this when you want a dedicated bot number instead of linking an existing Signal app account.

1. Get a number that can receive SMS (or voice verification for landlines).

Use a dedicated bot number to avoid account/session conflicts.

2. Install `signal-cli` on the gateway host:

```
VERSION=$(curl -Ls -o /dev/null -w %{{url_effective}} https://github.com
curl -L -O "https://github.com/AsamK/signal-cli/releases/download/v${VERSION}/sig
sudo tar xf "signal-cli-${VERSION}-Linux-native.tar.gz" -C /opt
sudo ln -sf /opt/signal-cli /usr/local/bin/
signal-cli --version
```

If you use the JVM build ( `signal-cli-${VERSION}.tar.gz` ), install JRE 25+ first. Keep `signal-cli` updated; upstream notes that old releases can break as Signal server APIs change.

&gt;

### 3. Register and verify the number:

```
signal-cli -a +<BOT_PHONE_NUMBER> register
```

If captcha is required:

1. Open <https://signalcaptchas.org/registration/generate.html> .
2. Complete captcha, copy the `signalcaptcha://...` link target from “Open Signal”.
3. Run from the same external IP as the browser session when possible.
4. Run registration again immediately (captcha tokens expire quickly):

```
signal-cli -a +<BOT_PHONE_NUMBER> register --captcha '<SIGNALCAPTCHA_LINK>'
signal-cli -a +<BOT_PHONE_NUMBER> verify <VERIFICATION_CODE>
```

### 4. Configure OpenClaw, restart gateway, verify channel:

```
# If you run the gateway as a user systemd service:
systemctl --user restart openclaw-gateway

# Then verify:
openclaw doctor
openclaw channels status --probe
```

### 5. Pair your DM sender:

Send any message to the bot number.



```
Approve code on the server:  openclaw pairing approve signal
<PAIRING_CODE> .
```

```
Save the bot number as a contact on your phone to avoid
>
“Unknown contact”.
```

Important: registering a phone number account with `signal-cli` can de-authenticate the main Signal app session for that number. Prefer a dedicated bot number, or use QR link mode if you need to keep your existing phone app setup.

Upstream references:

`signal-cli` README: <https://github.com/AsamK/signal-cli>

Captcha flow: <https://github.com/AsamK/signal-cli/wiki/Registration-with-captcha>

Linking flow: [https://github.com/AsamK/signal-cli/wiki/Linking-other-devices-\(Provisioning\)](https://github.com/AsamK/signal-cli/wiki/Linking-other-devices-(Provisioning))

## External daemon mode (httpUrl)

If you want to manage `signal-cli` yourself (slow JVM cold starts, container init, or shared CPUs), run the daemon separately and point OpenClaw at it:

```
{
  channels: {
    signal: {
      httpUrl: "http://127.0.0.1:8080",
      autoStart: false,
    },
  },
}
```

This skips auto-spawn and the startup wait inside OpenClaw. For slow starts when auto-spawning, set `channels.signal.startupTimeoutMs` .

&gt;

## Access control (DMs + groups)

DMs:

Default: `channels.signal.dmPolicy = "pairing"` .

Unknown senders receive a pairing code; messages are ignored until approved (codes expire after 1 hour).

Approve via:

```
openclaw pairing list signal
```

```
openclaw pairing approve signal <CODE>
```

Pairing is the default token exchange for Signal DMs. Details:

### Pairing

UUID-only senders (from `sourceUuid` ) are stored as `uuid:<id>` in `channels.signal.allowFrom` .

Groups:

```
channels.signal.groupPolicy = open | allowlist | disabled .
```

`channels.signal.groupAllowFrom` controls who can trigger in groups when `allowlist` is set.

## How it works (behavior)

`signal-cli` runs as a daemon; the gateway reads events via SSE.

Inbound messages are normalized into the shared channel envelope.

Replies always route back to the same number or group.

## Media + limits



Outbound text is chunked to `channels.signal.textChunkLimit` (default 4000).

Optional newline chunking: set `channels.signal.chunkMode="newline"` to split on blank lines (paragraph boundaries) before length chunking.

Attachments supported (base64 fetched from `signal-cli`).

Default media cap: `channels.signal.mediaMaxMb` (default 8).

Use `channels.signal.ignoreAttachments` to skip downloading media.

Group history context uses `channels.signal.historyLimit` (or `channels.signal.accounts.*.historyLimit`), falling back to `messages.groupChat.historyLimit`. Set 0 to disable (default 50).

## Typing + read receipts

**Typing indicators:** OpenClaw sends typing signals via `signal-cli sendTyping` and refreshes them while a reply is running.

**Read receipts:** when `channels.signal.sendReadReceipts` is true, OpenClaw forwards read receipts for allowed DMs.

Signal-cli does not expose read receipts for groups.

## Reactions (message tool)

Use `message action=react` with `channel=signal`.

Targets: sender E.164 or UUID (use `uuid:<id>` from pairing output; bare UUID works too).

`messageId` is the Signal timestamp for the message you're reacting to.

Group reactions require `targetAuthor` or `targetAuthorUuid`.

Examples:



```

message action=react channel=signal target=uuid:123e4567-e89b-12d3-a4f
message action=react channel=signal target="+15551234567" messageId=1737630212345 en
message action=react channel=signal target="signal:group:<groupId>" targetAuthor=uu
>

```

## Config:

`channels.signal.actions.reactions` : enable/disable reaction actions (default true).

`channels.signal.reactionLevel` : `off` | `ack` | `minimal` | `extensive` .

`off` / `ack` disables agent reactions (message tool `react` will error).

`minimal` / `extensive` enables agent reactions and sets the guidance level.

Per-account overrides: `channels.signal.accounts.<id>.actions.reactions` , `channels.signal.accounts.<id>.reactionLevel` .

## Delivery targets (CLI/cron)

DMs: `signal:+15551234567` (or plain E.164).

UUID DMs: `uuid:<id>` (or bare UUID).

Groups: `signal:group:<groupId>` .

Usernames: `username:<name>` (if supported by your Signal account).

## Troubleshooting

Run this ladder first:

```
🤖 openclaw status
openclaw gateway status
openclaw logs --follow
openclaw doctor
openclaw channels status --probe
```

Then confirm DM pairing state if needed:

```
openclaw pairing list signal
```

Common failures:

Daemon reachable but no replies: verify account/daemon settings ( `httpUrl` , `account` ) and receive mode.

DMs ignored: sender is pending pairing approval.

Group messages ignored: group sender/mention gating blocks delivery.

Config validation errors after edits: run `openclaw doctor --fix` .

Signal missing from diagnostics: confirm `channels.signal.enabled: true` .

Extra checks:

```
openclaw pairing list signal
pgrep -af signal-cli
grep -i "signal" "/tmp/openclaw/openclaw-$(date +%Y-%m-%d).log" | tail -20
```

For triage flow:

## Security notes



`signal-cli` stores account keys locally (typically  
~/.local/share/signal-cli/data/ ).

Back up Signal account state before server migration or rebuild.

Keep `channels.signal.dmPolicy`: "pairing" unless you explicitly want broader DM access.

SMS verification is only needed for registration or recovery flows, but losing control of the number/account can complicate re-registration.

## Configuration reference (Signal)

Full configuration: [Configuration](#)

Provider options:

`channels.signal.enabled` : enable/disable channel startup.

`channels.signal.account` : E.164 for the bot account.

`channels.signal.cliPath` : path to `signal-cli` .

`channels.signal.httpUrl` : full daemon URL (overrides host/port).

`channels.signal.httpHost` , `channels.signal.httpPort` : daemon bind (default 127.0.0.1:8080).

`channels.signal.autoStart` : auto-spawn daemon (default true if `httpUrl` unset).

`channels.signal.startupTimeoutMs` : startup wait timeout in ms (cap 120000).

`channels.signal.receiveMode` : on-start | manual .

`channels.signal.ignoreAttachments` : skip attachment downloads.

`channels.signal.ignoreStories` : ignore stories from the daemon.

`channels.signal.sendReadReceipts` : forward read receipts.

`channels.signal.dmPolicy` : pairing | allowlist | open | disabled (default: pairing).



`channels.signal.allowFrom` : DM allowlist (E.164 or `uuid:<id>` ). `open` requires `"*"` . Signal has no usernames; use phone/UUID ids.

`channels.signal.groupPolicy` : `open` | `allowlist` | `disabled` (default: `allowlist`).

`channels.signal.groupAllowFrom` : group sender allowlist.

`channels.signal.historyLimit` : max group messages to include as context (`0` disables).

`channels.signal.dmHistoryLimit` : DM history limit in user turns. Per-user overrides: `channels.signal.dms["<phone_or_uuid>"].historyLimit` .

`channels.signal.textChunkLimit` : outbound chunk size (chars).

`channels.signal.chunkMode` : `length` (default) or `newline` to split on blank lines (paragraph boundaries) before length chunking.

`channels.signal.mediaMaxMb` : inbound/outbound media cap (MB).

#### Related global options:

`agents.list[].groupChat.mentionPatterns` (Signal does not support native mentions).

`messages.groupChat.mentionPatterns` (global fallback).

`messages.responsePrefix` .

[< Mattermost](#)

[iMessage >](#)

Powered by [mintlify](#)