



≡ Built-in tools > Elevated Mode

Built-in tools

Elevated Mode

What it does

`/elevated on` runs on the gateway host and keeps exec approvals (same as `/elevated ask`).

`/elevated full` runs on the gateway host **and** auto-approves exec (skips exec approvals).

`/elevated ask` runs on the gateway host but keeps exec approvals (same as `/elevated on`).

`on / ask` do **not** force `exec.security=full` ; configured security/ask policy still applies.

Only changes behavior when the agent is **sandboxed** (otherwise exec already runs on the host).

Directive forms: `/elevated on|off|ask|full` , `/elev on|off|ask|full` .

Only `on|off|ask|full` are accepted; anything else returns a hint and does not change state.

What it controls (and what it doesn't)

Availability gates: `tools.elevated` is the global baseline.

`agents.list[].tools.elevated` can further restrict elevated per agent (both must allow).

Per-session state: `/elevated on|off|ask|full` sets the elevated level for the current session key.



Inline directive: `/elevated on|ask|full` inside a message applies to that message only.

Groups: In group chats, elevated directives are only honored when the agent is mentioned. Command-only messages that bypass mention requirements are treated as mentioned.

Host execution: `elevated` forces `exec` onto the gateway host; `full` also sets `security=full`.

Approvals: `full` skips exec approvals; `on / ask` honor them when allowlist/ask rules require.

Unsandboxed agents: no-op for location; only affects gating, logging, and status.

Tool policy still applies: if `exec` is denied by tool policy, `elevated` cannot be used.

Separate from `/exec`: `/exec` adjusts per-session defaults for authorized senders and does not require `elevated`.

Resolution order

1. Inline directive on the message (applies only to that message).
2. Session override (set by sending a directive-only message).
3. Global default (`agents.defaults.elevatedDefault` in config).

Setting a session default

Send a message that is **only** the directive (whitespace allowed), e.g. `/elevated full`.

Confirmation reply is sent (`Elevated mode set to full... / Elevated mode disabled.`).

If elevated access is disabled or the sender is not on the approved allowlist, the directive replies with an actionable error and does not change session state.



Send `/elevated` (or `/elevated:`) with no argument to see the current elevated level.

>

Availability + allowlists

Feature gate: `tools.elevated.enabled` (default can be off via config even if the code supports it).

Sender allowlist: `tools.elevated.allowFrom` with per-provider allowlists (e.g. `discord` , `whatsapp`).

Per-agent gate: `agents.list[].tools.elevated.enabled` (optional; can only further restrict).

Per-agent allowlist: `agents.list[].tools.elevated.allowFrom` (optional; when set, the sender must match **both** global + per-agent allowlists).

Discord fallback: if `tools.elevated.allowFrom.discord` is omitted, the `channels.discord.allowFrom` list is used as a fallback (legacy: `channels.discord.dm.allowFrom`). Set `tools.elevated.allowFrom.discord` (even `[]`) to override. Per-agent allowlists do **not** use the fallback.

All gates must pass; otherwise elevated is treated as unavailable.

Logging + status

Elevated exec calls are logged at info level.

Session status includes elevated mode (e.g. `elevated=ask` , `elevated=full`).

< `apply_patch` Tool

Thinking Levels >



Powered by mintlify

>