

Geoprocessing the UAS data

Modified from Course Materials by Helena Mitsova, and Justyna Jeziorska at NC State University, Shared under a Creative Commons License

In completing this assignment you will generate an orthomosaic and Digital Surface Model (DSM) using pictures taken from Rocky Mountain Biological Laboratory in June 2018 using a DJI Phantom 4 Pro.

The process can be very time consuming (depending on computational power of your device and desired quality)

In order to minimize the processing time, we will process only fraction of the data collected and we will use imagery downsampled by 50%. It will allow us to generate outputs in the classroom. The resolution of orthophoto and DSM will be lower, but the high quality and full extent output of the processing are provided [here](#)

General workflow (with GCPs):

- Preparation
- Stage 1: Building simple geometry (in order to place GCPs)
- Stage 2: Placing GCPs
- Stage 3: Building complex geometry
- Stage 4: Exporting results

Preparation

Data

- **OPTION 1: RECOMMENDED IN THE CLASSROOM** - small area, photos downsampled to accelerate processing (but lower the resolution of the outputs)
 - [download data](#) - photos, log and coordinates of 6 GCPs
- **OPTION 2:** Small area, but photos not downsampled (to obtain the highest resolution of the outputs)
 - [download data](#) - photos, log and coordinates of 6 GCPs
- **OPTION 3:** You can use your own data

Software

- Agisoft Metashape Professional ([installer](#))

Preferences

When launching Metashape for the first time, some settings need to be adjusted to optimize performance. These settings need to be done only once, at the first use of Metashape, and are loaded by default in subsequent sessions.

Menu > Tools > Preferences

General tab:

- Leave default (optional – write log to file: enabled, if you want to save the txt log file)

GPU tab:


- Check on any Graphics Processing Unit (GPU) devices detected by Metashape in the dialog.

Network Tab:

- Leave default

Appearance Tab:

- Leave default (or adjust to personal taste)



Stage 1: Aligning photos in low quality (in order to place GCPs)

In order to localize the GCPs first a preliminary simple model needs to be build.


Adding photos

Menu > Workflow > Add Photos

Indicate the path to the folder (downloaded data) containing photos and select them all.

In the Reference pane, you can see that the photos has been loaded, but the coordinate system indicates local coordinates. It can be changed in the Settings.


Click the settings icon  > change coordinate system to WGS 84 (EPSG:4326)



The image shows a 'Reference Settings' dialog box with a red title bar and a close button. It contains several sections: 'Coordinate System' with a dropdown menu set to 'WGS 84 (EPSG::4326)'; 'Rotation angles' with a dropdown menu set to 'Yaw, Pitch, Roll'; 'Measurement accuracy' with four input fields: 'Camera accuracy (m):' (10), 'Camera accuracy (deg):' (2), 'Marker accuracy (m):' (0.005), and 'Scale bar accuracy (m):' (0.001); 'Image coordinates accuracy' with two input fields: 'Marker accuracy (pix):' (0.1) and 'Tie point accuracy (pix):' (1); and 'Miscellaneous' with a 'Ground altitude (m):' input field. At the bottom are 'OK' and 'Cancel' buttons.

Section	Parameter	Value
Coordinate System	Coordinate System	WGS 84 (EPSG::4326)
	Rotation angles	Yaw, Pitch, Roll
Measurement accuracy	Camera accuracy (m):	10
	Camera accuracy (deg):	2
	Marker accuracy (m):	0.005
	Scale bar accuracy (m):	0.001
Image coordinates accuracy	Marker accuracy (pix):	0.1
	Tie point accuracy (pix):	1
Miscellaneous	Ground altitude (m):	

Loading camera positions

Click Import button  on the Reference pane toolbar > select file containing camera positions information (log file*) in the Open dialog.

Import CSV

Coordinate System: WGS 84 (EPSG::4326)

Rotation angles: Yaw, Pitch, Roll

Delimiter: ☒ Comma

Columns:

- Label: 1 ☐ Accuracy ☒ Rotation ☐ Accuracy
- Longitude: 3 8 Yaw: 5 9
- Latitude: 2 8 Pitch: 6 9
- Altitude: 4 8 Roll: 7 9
- Enabled flag: 10

Start import at row: 2

Label	Latitude	Longitude	Altitude	Yaw	Pitch	Roll
name	latitude	longitude	height	yaw	pitch	roll
DSC00338.JPG	35.72656324	-78.70361460	190.16	0.0621343	-0.117557	-2.04895
DSC00339.JPG	35.72554529	-78.70120397	196.45	0.0901325	-0.11187	-2.04336
DSC00340.JPG	35.72489546	-78.69876628	200.64	-0.0103275	-0.341259	-5.17255
DSC00341.JPG	35.72498760	-78.69898812	200.08	0.0110497	-0.214092	-5.20963
DSC00342.JPG	35.72509566	-78.69922216	199.87	-0.177936	0.145896	-5.24168

OK Cancel


*Agisoft support the camera orientation files in 5 formats: .csv, .txt, .tel, .xml and .log. The default format of the Trimble Aerial Imaging log is .jxl. In order to convert the Trimble .jxl log file please run [script by Vaclav Petras](#) or use **provided already converted log in .txt format**

Make sure that the columns are named properly – you can adjust their placement by indicating column number (top right of dialog box)

Aligning photos

- Accuracy: Low
- Check: Reference preselection
- Key point limit: default
- Tie point limit: default
- Adaptive camera model fitting: enabled


Menu > Workflow > Align Photos



Click Save  in the toolbar

Stage 2: Placing GCPs

Loading the GCPs coordinates

Click Import button  on the Reference pane toolbar > select file containing Ground Control Points coordinates in the Open dialog

Coordinate System: WGS 84 (EPSG::4326)

Rotation angles: Yaw, Pitch, Roll

Delimiter: ☒ Tab

Columns:

Label	1	Accuracy	Rotation	Accuracy
Longitude	6	8	Yaw	5
Latitude	5	8	Pitch	6
Altitude	4	8	Roll	7

Start import at row: 2

Label	Easting	Northing	Altitude	Latitude	Longitude
GCP			ASL	latitude	longitude
UAV 3	637194.845	219378.379	111.888	35.7272189	-78.69497878
UAV 6	637096.603	219361.049	112.526	35.7270654	-78.69606533
UAV 8	636960.473	219401.592	111.069	35.7274346	-78.69756874

OK Cancel

Make sure that the columns are named properly – you can adjust their placement by indicating column number (top right of dialog box).

This time you uncheck the *Rotation* box since GCPs are stationary and do not need determining yaw pitch and roll angles.

The window with the message: *Can't find match for 'UAV 3' entry. Create new marker?* will pop up.

Agisoft PhotoScan

Can't find match for 'UAV 1' entry. Create new marker?


Yes Yes to All No No to All

Choose 'Yes to All' – it will create new marker for each of the named GCPs from the file. They will be listed in Reference pane under the list of photos.


Indicating GCPs on the pictures

Now you need to find each of the GCPs and indicate its localization on all photos depicting it. You can also see the process on the [instructional video](#)

The Model pane shows approximate positions of GCPs, it is better visible if the ‘Show cameras’ option is disabled (Menu > View > Show/Hide Items > Show cameras)




Choose in the context menu of the selected point on the list (right click) > Filter Photos by Marker.




In the Photos pane appear only the images in which the currently selected GCP is probably* visible.

** This is possible because our pictures are geotagged (log indicates the position of each photo), if you will be working with the pictures that are not geotagged or in the area that you don't know and are not able to "guess" which photo depicts which GCP, it is useful to build the dense point cloud or even mesh and texture (see the following steps) to see the preliminary model of the area in the Model pane, not just a sparse cloud (this is depicted on the figures above)*

Open an image by double clicking the thumbnail. It will open in a tab next to the Model pane.



The GCP will appear as a grey icon . This icon needs to be moved to the middle of GCP visible on the photo



Drag the marker to the correct measurement position. At that point, the marker will appear as a green flag, meaning it is enabled and will be used for further processing.


Double click on the next photo and repeat the steps. As soon as the GCP marker position has already been indicated on at two images, the proposed position will almost exactly match the point of measurement. You can now slightly drag the marker to enable it (turning it into a green flag) or leave it unchanged (gray marker icon) to exclude it from processing.

Filter photos by each marker again. Agisoft adjusts the GCPs positions on the run, so you can locate the GCP on additional images that will appear in the Photos pane.

In this sample processing we will include 4 GCPs. Mathematically, you need to indicate marker positions for at least 3 GCPs. Accurate error estimates can be calculated with at least 4 GCPs, while often at least 5 are needed to cover the center of the project as well, which reduces the chance of error propagation and resulting terrain distortions especially on flat or undulating terrain types.

Click Save  in the toolbar

Optimizing alignment

You can see the errors by clicking on the View Errors icon 


Best results are obtained when the alignment is first optimized based on the camera coordinates only, and a second time based on the GCP only.

Click Optimize icon  in the Ground Control toolbar (check all the boxes)

Optimizing based on the GCP Markers

In the Ground Control pane:

- disable all the camera coordinates (select one > press Ctrl+A > right-click > choose Uncheck).
- enable all the GCP Marker coordinates (select one > press Ctrl+A > right-click > choose Check).

Click Settings icon  in the Ground Control toolbar:

- leave the default values (Marker accuracy (m) = 0.005 m)

click Optimize icon  in the Ground Control toolbar (leave all options at the default)

Click Save  in the toolbar



You can now see how much the errors were reduced through optimization by clicking on the

View Errors icon




Stage 3: Building complex geometry (for quality processing)

Before starting the Build Dense Cloud step it is recommended to check the bounding box of the reconstruction (to make sure that it includes the whole region of interest, in all dimensions). The bounding box should also not be too large (increased processing time and memory requirements).

The bounding box can be adjusted using the Resize Region  and the Rotate Region  tool from the toolbar. Make sure that the base (red plane) is at the bottom.






The next steps will be time consuming (depending on the desired quality and number of pictures). You can execute them one step at the time, what would be explained below. You can also set a batch processing that does not require user interaction until the end of geoprocessing (especially useful in case of Ultra High quality that requires even several days of processing). The batch processing will be explained at the end of this section.

Menu > Workflow > Build Dense Cloud

- Quality = Medium*
 - Medium (will downsample the images to get a 3D coordinate every 4 pixels)
 - High (will downsample the images to get a 3D coordinate every 2 pixels; typically takes several hours but will give acceptable results for most cases), typically takes >10-20 hours) or
 - Ultra high (will calculate a 3D coordinate for every pixel in original imagery; may take more than a day or several days)
- Depth filtering = Aggressive

*When working with large datasets take into consideration the RAM size requirements for the different target qualities with respect to the number of images (in appendix in the [manual](#) or in [lecture slides](#)).




Click Save  in the toolbar

Menu > Workflow > Build Mesh

- Surface type: Height field
- Source data: Dense cloud
- Face count: Medium
- Advanced options: leave default


*Face count set at “0” means that Metashape will determine an optimum number of faces (but this may not be enough to describe all the features on terrain)



Menu > Workflow > Build Texture

- Mapping mode: Orthophoto
- Blending mode: Mosaic (default)
- Texture size/count: 4096
- Enable color correction: disabled (unchecked)

Click Save  in the toolbar




Editing geometry

Sometimes it is necessary to edit geometry before building texture atlas and exporting the model.

If the overlap of the original images was not sufficient, the model can contain holes. In this case to obtain holeless model use Close Holes command. It is crucial if you want to perform any volume calculations - in this case, 100% holes need to be closed

Menu > Tools > Mesh > Close Holes

In Close Holes dialog select the size of the largest hole to be closed (in percentage of the total model size). **DO NOT CHOOSE 100% unless you are calculating volumes (then you have to close 100% holes)**



This does not apply to our data, since we have sufficient image overlap. But due to strong dependency on weather conditions, the holes in data are common with UAS.

Building DEM

Menu > Workflow > Build DEM

In this step the parameters of the exported DEM are determined. In order to work in the commonly used in NC reference system, we will won't keep the porject's WGS84 system, but change it to NC State Plane (ESPG:3358)

Build DEM

▼ Projection

Type: ☐ Planar ☒ Geographic

NAD83(HARN) / North Carolina (EPSG::3358) ▼

Parameters

Source data: Dense cloud ▼

Interpolation: Enabled (default) ▼

Point classes: All

Region

☐ Setup boundaries: 636830.916 - 637387.361 X

219249.486 - 219542.874 Y


Resolution (m): 0.251453

Total size (pix): 2213 x 1166

Building Orthophoto

Menu > Workflow > Build Orthophoto

Orthophoto can be build only in the same coordinate system that the DEM




Batch processing

Menu > Workflow > Batch process > Add

Batch processing allows to set multiple process in the preset order and execute it one after another without user intervention. All the parameters should be set the same as explained above.

1. Optimize Alignment (if the GCPs were placed but the optimization not performed, otherwise:skip)
2. Build Dense Cloud
3. Build Mesh
4. Build Texture
5. Build Build DEM
6. Build Build Orthophoto



Stage 4: Exporting results

This option will be disabled if you are working in the demo version

Orthomosaic

File > Export Orthophoto > Export JPEG/TIFF/PNG...

- Projection Type = geographic (default);
- Datum = WGS 1984,
- Write KML file (footprint) and World file (.tfw) = check if desired (if left unchecked, georeferencing information will still be contained in the GeoTIFF .tif file);
- Blending mode = Mosaic (default)
- Pixel size: leave default

Export Orthomosaic

Coordinate System
 NAD83(HARN) / North Carolina (EPSG::3358)

Raster
☒ Pixel size (m): 0.0628574 X
 Metres... 0.0628574 Y
☐ Max. dimension (pix): 4096
☐ Split in blocks (pix): 1024 x 1024
 Raster transform: None
 Background color: White

Region
☐ Setup boundaries: 636832.174 - 637349.867 X
 Reset 219253.258 - 219512.733 Y
 Total size (pix): 8236 x 4128
☐ Write KML file ☐ Write World file
☐ Write tile scheme

Compression
 Image description:
 TIFF compression: LZW
 JPEG quality: 90
☐ Write BigTIFF file ☒ Write alpha channel

Export... Cancel

Leave default values. Fill out the desired name and save as type TIFF/GeoTIFF (*.tif)

Digital surface model

Menu > File > Export DEM...

Export DEM

Coordinate System
 NAD83(HARN) / North Carolina (EPSG::3358)

Raster
☒ Pixel size (m): 0.25143 X
 Metres... 0.25143 Y
☐ Max. dimension (pix): 4096
☐ Split in blocks (pix): 1024 x 1024
 Raster transform: None
 No-data value: -32767

Region
☐ Setup boundaries: 636830.916 - 637387.331 X
 Reset 219249.486 - 219542.653 Y
 Total size (pix): 2212 x 1165
☐ Write KML file ☐ Write World file
☐ Write tile scheme

Compression
 Image description:
☐ Write BigTIFF file

Export... Cancel

Leave default values. Fill out the desired name and save as type TIFF/GeoTIFF (*.tif)

Generating report

Menu > File > Generate report

Indicate the name and path for the PDF file

Processing outputs from the OPTION 1 (downsampled images) are provided [here](#)

The following export steps are optional.

Model

Menu > File > Export model > OBJ/FBX/KMZ...

Indicate the name, path and format of the output model

Metashape supports model export in the following formats: Wavefront OBJ, 3DS file format, VRML, COLLADA, Stanford PLY, STL models, Autodesk FBX, Autodesk DXF, Google Earth KMZ, U3D, Adobe PDF. Some file formats (OBJ, 3DS, VRML, COLLADA, PLY, FBX) save texture image in a separate file. The texture file should be kept in the same directory as the main file describing the geometry.

3D Models are a great visualization tool. [Model generated by following the assignment instructions](#) as well as [model from full flight processing](#) can be viewed on sketchfab

Point cloud

Menu > File > Export points...

Indicate the name, path and format of the output file

Metashape supports point cloud export in the following formats: Wavefront OBJ, Stanford PLY, XYZ text file format, ASPRS LAS, ASTM E57, U3D, Potree, Metashape OC3, PDF,

Camera calibration and orientation data

Menu > Tools > Export > Export Cameras

Indicate the name, path and format of the output file

Metashape supports camera data export in the following formats: Metashape structure file format (XML based), Bundler OUT file format, CHAN file format, Boujou TXT file format, Omega phi Kappa text file format, PATB Exterior orientation, BINGO Exterior orientation, AeroSys Exterior orientation, Inpho project file.