



Subscribe ▼

TRENDING

Diablo 4

Microsoft Surface

Best Laptops

Xbox Series X

Best College Laptops

Best

When you purchase through links on our site, we may earn an affiliate commission. [Here's how it works.](#)


[Home](#) > [Software Apps](#) > [Windows 10](#)

Advertisement

How to convert MBR to GPT drive to switch BIOS to UEFI on Windows 10

By [Mauro Huculak](#) published March 16, 2022

A PC with UEFI is more secure and faster than the legacy one using BIOS, and here's how to switch.



Convert MBR to GPT on Windows 10 (Image credit: Windows Central)

When you want to switch firmware type from the Basic Input/Output System (BIOS) to Unified Extensible Firmware Interface (UEFI) without

modifying the current installation or deleting the data stored on the drive, or you plan to [upgrade Windows 10 to Windows 11](#), you can convert the drive using a Master Boot Record (MBR) to a GUID Partition Table (GPT) partition style using the "MBR2GPT" tool.

BIOS is a piece of code that resides on the motherboard that connects the hardware and software. This code has been around for a long time, and while it worked well, it was never designed for modern hardware, and it had many limitations, including limitations to partitions smaller than 2TB.

UEFI is the new firmware type designed to replace the old BIOS style. It introduces additional features, including support for partitions larger than 2TB and faster startup, sleep, resume, and shutdown times. Also, it unlocks new security features available on [Windows 11](#) and Windows 10. For instance, "Secure Boot" is a feature that can protect a device's startup process from malicious programs, and now it's a prerequisite to install Windows 11. "Device Guard" gives you more advanced controls for app access, and "Credential Guard" can help prevent pass-the-hash attacks.

In this Windows 10 guide, we will walk you through the steps and information to use the Microsoft MBR2GPT command-line tool to convert a drive from MBR to GPT partition style, to switch from BIOS to UEFI mode on your device, and enable Secure Boot correctly.

RECOMMENDED VIDEOS FOR YOU...

How To Find System Info

How to view system information using the System Information App

PLAY SOUND

00:00 / 00:00

- [How to convert a drive from MBR to GPT on Windows 10](#)
- [How to change the firmware mode from BIOS to UEFI](#)

Warning: This is a non-destructive process, but it's still recommended to make a full backup of your PC before proceeding in case something goes wrong and you need to recover your setup.

How to convert a drive from MBR to GPT on Windows 10

Unlike older methods requiring a backup of your data and reinstalling Windows, the MBR2GPT tool makes it easy to change the partition style quickly. When using this tool, the conversion process adds the GPT components to the MBR partition without modifying the existing partition and maintaining the data untouched.

Advertisement

MOST READ



1 [NVIDIA Studio makes life easier for students in creative fields](#)

2 [Don't waste your money on a Samsung Galaxy Z Fold 5](#)

3 [Alienware 34 Curved QD-OLED Gaming Monitor \(AW3423DWF\) review: Does it all with ease](#)

4 [Remnant 2: All possible choices for Meidre, and how to obtain Sorrow](#)

5 [Hey, Square Enix, now bring the](#)

The best approach is switching to UEFI and performing a clean install of Windows 11. However, if you already have a Windows 10 installation that you want to upgrade, you can convert the drive to change the system firmware settings properly. Otherwise, the device will no longer start correctly.


Mana games to Xbox

Advertisement

Check MBR or GPT partition style

Before making system changes, check the current settings to see whether the system is set to MBR or GPT using these steps:


1. Open **Start**.
2. Search for **Disk Management** and click the top result to open the experience.
3. Right-click the drive (where Windows 10 resides) and select the **Properties** option.



Source: Windows Central (Image credit: Source: Windows Central)

Advertisement

4. Click on the **Volumes** tab.
5. Under the "Partition style" field, if the field reads **GUID Partition Table (GPT)**, the drive does not need conversion, but if you see the **Master Boot Record (MBR)** label, you will need to use the conversion tool.



Source: Windows Central (Image credit: Source: Windows Central)

6. Click the **Cancel** button.


Once you complete the steps, you can change the partition style on the computer.

Also, if you need to change the partition, check your device manufacturer's support website to find out whether the hardware includes support for UEFI before using these instructions.

Convert MBR to GPT partition style (offline)

To convert a drive using MBR to GPT on Windows 10, use these steps:


1. Open **Settings**.
2. Click on **Update & Security**.
3. Click on **Recovery**.
4. Under the "Advanced startup" section, click the **Restart now** button.



Source: Windows Central (Image credit: Source: Windows Central)


Advertisement

5. Click the **Troubleshoot** option.




Source: Windows Central (Image credit: Source: Windows Central)

6. Click on **Advanced options**.



Source: Windows Central (Image credit: Source: Windows Central)

7. Click the **Command Prompt** option.



Advertisement

Source: Windows Central (Image credit: Source: Windows Central)

8. Select your administrator account and sign in (if applicable).

9. Type the following command to validate the drive's requirements and press **Enter**: `mbr2gpt /validate` **Quick tip:** The `mbr2gpt.exe` is located in the "System32" folder inside the "Windows" folder. If you want to see all the available options, use the `mbr2gpt /?` command.

The image shows a Windows Command Prompt window titled 'Administration: X:\windows\system32\cmd.exe'. The text inside the window shows the command 'X:\windows\system32>mbr2gpt /validate' being entered and executed. The output shows the command successfully validating the disk layout. The command prompt is highlighted with a red rectangle.


```
Administration: X:\windows\system32\cmd.exe
Microsoft Windows [Version 10.0.17763.1]
(c) 2018 Microsoft Corporation. All rights reserved.

X:\windows\system32>mbr2gpt /validate
MBR2GPT: Attempting to validate disk 0
MBR2GPT: Retrieving layout of disk
MBR2GPT: Validating layout, disk sector size is: 512 bytes
MBR2GPT: Validation completed successfully

X:\windows\system32>
```

Source: Windows Central (Image credit: Source: Windows Central)

10. Type the following command to convert the drive from MBR to GPT and press **Enter**: `mbr2gpt /convert`



```
Administrator: Windows\system32\cmd.exe
X:\Windows\system32>mbr2gpt /convert
MBR2GPT will now attempt to convert the default boot disk.
If conversion is successful the disk can only be booted in GPT mode.
These changes cannot be undone!

MBR2GPT: Attempting to convert disk 0
MBR2GPT: Retrieving layout of disk
MBR2GPT: Validating layout, disk sector size is: 512 bytes
MBR2GPT: Backing up the system partition
MBR2GPT: Creating the EFI system partition
MBR2GPT: Installing the new boot files
MBR2GPT: Performing the layout conversion
MBR2GPT: Migrating default boot entry
MBR2GPT: Adding recovery boot entry
MBR2GPT: Fixing drive letter mapping
MBR2GPT: Conversion completed successfully
MBR2GPT: Before the new system can boot properly you need to switch the firmware to boot to UEFI mode!

X:\Windows\system32>
```

Source: Windows Central (Image credit: Source: Windows Central)

11. Click the **Close** button.
12. Click the **Turn off your PC** option.

After you complete the steps, the tool will validate the drive and create an EFI system partition (ESP). The process will also insert the UEFI boot files and GPT components into the partition. The tool will update the Boot Configuration Data (BCD), and the previous drive letter will be added to the drive.


Advertisement

Convert MBR to GPT partition style (online)

It's always recommended to use the MBR2GPT tool offline to avoid potential problems. However, you can also run it when the system is operational.

To convert a drive from MBR to GPT on Windows 10, use these steps:

1. Open **Start**.
2. Search for **Command Prompt**, right-click the top result, and select the **Run as administrator** option.
3. Type the following command to validate the drive and press **Enter**:
`mbr2gpt /validate /allowFullIOS`




```
Administrator: Command Prompt
Microsoft Windows [Version 10.0.17763.379]
(c) 2018 Microsoft Corporation. All rights reserved.

C:\Windows\system32>mbr2gpt /validate /allowFullIOS
MBR2GPT: Attempting to validate disk 0
MBR2GPT: Retrieving layout of disk
MBR2GPT: Validating layout, disk sector size is: 512 bytes
MBR2GPT: Validation completed successfully

C:\Windows\system32>
C:\Windows\system32>
```

Source: Windows Central (Image credit: Source: Windows Central)

4. Type the following command to convert the drive to GPT and press **Enter**:
`mbr2gpt /convert /allowFullIOS`



Source: Windows Central (Image credit: Source: Windows Central)

Once you complete the steps, the command-line tool will reduce the size of the primary partition and change it from MBR to GPT.

Advertisement

MBR2GPT return codes

If the processes are completed successfully, the return code would be "0," but if the process fails, you may see one of the 11 error codes:

Swipe to scroll horizontally



Return code	Description
1	User canceled the conversion.
2	Internal error.
3	Initialization error.
4	Invalid command-line parameters.
5	Error on the geometry and layout of the selected disk.
6	One or more volumes on the disk are encrypted.
7	Geometry and layout of the disk don't meet requirements.
8	Error while creating the EFI system partition.
9	Error installing boot files.
10	Error while applying GPT layout.
100	Successful conversion, but some boot configuration data didn't restore.

MBR2GPT important details

You can use the MBR2GPT tool on a traditional hard drive (HDD), solid-state drive (SSD), or an M.2 drive with virtually any version of Windows 10, but you must run the tool from a Windows 10 (version 1703 or later) installation.

When dealing with a [drive using file encryption with BitLocker](#), you must

first suspend the encryption before following the outlined instructions.

While MBR-style drives can have up to four primary partitions, the drive you want to convert can't have more than three partitions because one additional allocation is required to create the UEFI partition.

Finally, Microsoft designed the tool to convert drives running Windows 8.1, 7, or from an older version, but you can always upgrade the installation to the latest release of Windows 10 and then use the tool to convert from MBR to GPT.

How to change the firmware mode from BIOS to UEFI

After converting the drive to the GPT style, the computer will no longer start until you change the firmware type from BIOS to UEFI in the motherboard.

Typically, this process requires hitting one of the function keys (F1, F2, F3, F10, or F12), Esc, or Delete key as soon as you start the device. However, since these options are always different, it's best to check your device manufacturer's support website for more specific details.


On the firmware interface, find the "Boot" menu, enable the UEFI option, save the changes, and then the computer should start normally.

Also, if you plan to upgrade the device to Windows 11 while in the UEFI settings, open the boot or security settings page, make sure to enable the "Secure Boot" option, and exit the firmware saving the changes.

Check GPT partition style


To confirm the device is using a GPT partition style, use these steps:

1. Open **Start**.
2. Search for **Disk Management** and click the top result to open the app.
3. Right-click the main drive and select the **Properties** option.



Source: Windows Central (Image credit: Source: Windows Central)

4. Click on the **Volumes** tab.
5. Under the "Partition style" field, the information should now read **GUID Partition Table (GPT)**.




Source: Windows Central (Image credit: Source: Windows Central)

After you complete the steps, if the partition is running using the correct partition style, you only need to check whether the device uses the UEFI firmware mode.

Check UEFI firmware

To confirm the computer is in UEFI mode and Secure Boot is turned on, use these steps:

1. Open **Start**.
2. Search for **msinfo32** and click the top result to open the **System Information** app.
3. Click on **System Summary** on the left pane.
4. Check the "BIOS Mode," which now should read **UEFI**.



Source: Windows Central (Image credit: Source: Windows Central)

5. Check the "Secure Boot State" information, which now should read **On**.

Once you complete the steps, if the System Information displays the mode as "UEFI," you have successfully switched the firmware type.

More Windows resources

For more helpful articles, coverage, and answers to common questions about Windows 10 and Windows 11, visit the following resources:

- [Windows 11 on Windows Central — All you need to know](#)

- Windows 11 help, tips, and tricks
- [Windows 10 on Windows Central — All you need to know](#)

Get the Windows Central Newsletter

All the latest news, reviews, and guides for Windows and Xbox diehards.

SIGN ME UP

- ☐ Contact me with news and offers from other Future brands
- ☐ Receive email from us on behalf of our trusted partners or sponsors

By submitting your information you agree to the [Terms & Conditions](#) and [Privacy Policy](#) and are aged 16 or over.



Mauro Huculak

Mauro Huculak is technical writer for WindowsCentral.com. His primary focus is to write comprehensive how-tos to help users get the most out of Windows 10 and its many related technologies. He has an IT background with professional certifications from Microsoft, Cisco, and CompTIA, and he's a recognized member of the Microsoft MVP community.

TOPICS

WINDOWS 10 HELP

CATEGORIES

WINDOWS 10 SOFTWARE APPS

Windows Central is part of Future US Inc, an international media group and leading digital publisher. **Visit our corporate site.**

- | | | | |
|---|--|--------------------------------|--------------------------------|
| Terms and conditions | Contact Future's experts | Privacy policy | Cookies policy |
| Accessibility statement | Careers | Licensing | About us |
| Newsletter | Advertising inquiries | | |

© Future US, Inc. Full 7th Floor, 130 West 42nd Street, New York, NY 10036.